

-
-
-
-
-

Chapter 1

Maintenance



Warehouse Configuration

Warehousing provides location control for items managed by Inventory Management. This can operate for some or all of the stockrooms and you can select and control each stockroom independently.

If you use Inventory Management without Warehousing, you can set up a number of stockrooms to create a logical or physical differentiation of stock. When you install Warehousing you need to re-evaluate the best use of the stockrooms or warehouses.

The most significant definition for a warehouse is the area which contains all of the stock that Warehousing considers to meet the pick requirements of a single despatch.

Before using Warehousing, you must define the map of the warehouse and the relationships that Warehousing uses to identify what items are at which locations.

To set up a warehouse you must set up the required data in a logical order. This is because some data is a pre-requisite for other data. For example, you must define packaging types before you can define the items package.

To set up and maintain a warehouse, enter the following in this order:

1. Warehouse descriptions in Inventory.
2. Inventory interface profiles.
3. Warehouse profile.
4. Area profile.
5. Area dimensions.
6. Resources.
7. Packaging types.
8. Location types.
9. Warehouse map.
10. Location check digits.
11. Location rules.
12. Item and warehouse profile.
13. Warehouse list profile.
14. Access points.
15. Authorise warehouse users.

For more information on each of these, see the following sections.

Warehouse Descriptions in Inventory

Before you can set up and use warehousing, you need to define the following description identities. You set these up in Inventory Management, for more information see the Description File section in the Inventory Management product information.



Tip: The following list only includes the minimum codes you require.

DIRE

Direction to Move in Warehousing.

Code length - 1.

- 1 - Ascending.
- 2 - Descending.

Use the literals when defining the location rules by item.

ORTP

Order Type.

Code length - 1.

- 1 - Sales.
- 2 - Production.

WHCS

Warehousing Commitment List Sequence.

Code length - 1.

- 1 - Order.
- 2 - Customer.
- 3 - Journey.
- 4 - Despatch date.
- 5 - Operation start date.

WHIS

Warehousing Item Sequence.

Code length - 1.

- 1 - Item.
- 2 - Alternative location.
- 3 - Location.

WHLS

Warehouse / List Type.

Code length - 2.

- 01 - Put away list.
- 02 - Move list.

03 - Pick list.
04 - Count list.

WHML

Move List By Sequence.

Code length - 1.

- 1 - Warehouse.
- 2 - Area.
- 3 - Access point for dimension 1.

WHMS

Move List Sequence.

Code length - 1.

- 1 - Item.
- 2 - Arrival.

WHMT

Warehousing Movement Type.

Code length - 1.

- 1 - Put-away.
- 2 - Pick.
- 3 - Sundry movement planned.
- 4 - Sundry movement not planned.
- 5 - Adjust committed to sales.
- 6 - Count reconciliation.
- 7 - Sundry frozen movement.

WHNL

Number of Locations to Create.

Code length - 3.

MAX - Maximum number of locations.

WHPS

Warehousing Pick List Sequence.

Code length - 1.

- 1 - Warehouse.
- 2 - Area.
- 3 - Access point for dimension 1.

WHRS

Warehousing Reason Codes.

Code Length - 2.

- #C - Production order completion.
- #P - Production order partial issue.
- #1 - Put-away found in error.
- #2 - Commit found in error.
- #3 - Replenishment error.

- #4 - Instruction Overridden.
- #5 - Item/pack profiles missing.
- #6 - Item/Warehouse profiles missing.
- #7 - Planned movement.
- #9 - Count Reconciliation.

For meaningful information when there is a variation from an instruction, you need extra user-defined reason codes.

If the variation from an instruction is relating to stock in the marshalling area, the parameter limit defined for the reason code determines what happens to the stock. A limit of zero freezes the stock and a limit of 1 leaves the stock committed.

WHSE

Warehouse Miscellaneous Parameters.

Code Length - 4.

CDID - Confirm dispatch identifier.

DTAQ - Data Queue Wait Time in Seconds.

EOFD - End of File Delay in Seconds.

The parameter limit against DTAQ and EOFD sets the data file polling delay in seconds, for example, 120.

Inventory Interface Profiles

To record transactions affecting the total stock position in Inventory accurately, you must define certain Inventory Interface Profiles, using the Processing Profiles option. For more information see the Inventory Management Product Information.

<u>Code</u>	<u>Description</u>
001	Adjust physical stock.
002	Customer order issue.
003	Adjust frozen stock.
014	Adjust back order quantity.
015	Adjust allocated.
018	Production order issue.

Warehouse Profile

You must define a Warehouse Profile for each Inventory stockroom which requires Warehouse level processing.

Before creating the warehouse profile consider the following:

- Is processing interactive or batch?
- What are the special receiving and marshalling locations?
- What are the default put-away and commit rules?
- Are check digits used to check instructions are carried out correctly?

You use the warehouse profile to maintain warehouse policies, such as the special receiving and marshalling locations, and item/warehouse profile defaults. Because you cannot set up the details relating to the receiving and marshalling locations until a later stage, you must set up the basic details for the warehouse, and then return to Warehouse Profile when you have defined the required data.

You activate the warehouse after you define all the data for the application. To do this you must access the Warehouse Profile function a third time.

Area Profile

You must define area profiles for the receiving and marshalling locations and other areas needed for the warehouse to function as required.

For each area you must specify the dimensions for the structure of that area. For example, you could have three dimensions Aisle, Bay and Row. Warehousing uses the dimensions to build up the codes for the locations in the area.

Before setting up the area profiles, consider the following:

- How to structure the warehouse for general operation.
- How to divide the warehouse into logical areas, for example, floor area, main store area, bulk store area.
- What is the structure of locations in the area, for example, racking, block stacker?
- What kind of location code structure do you require for each area?

Area Dimensions

You must define the range of codes for each area dimension. Warehousing produces the overall location code by the concatenation of the dimension codes for the area.

For example, if a floor area has two dimensions, length and breadth, and the range of codes for each is AA to AC and 01 to 20, then a location code could be AB12, or AC01.

Resource Codes

You must define at least one resource code. A resource code refers to the resource required to move a particular pack type into or out of a specific type of location. For example, Fork Lift Truck.

Warehousing does not consider resources as separate entities, but you can use them for memorandum purposes.

Packaging Types

Packaging types define the storage units related to items processed by Warehousing. For example, pallets, and cartons.

Warehousing uses packaging types to calculate the quantity of stock that fits in individual locations. You need to define each different packaging type.



Note: You must define at least one packaging type.

Location Types

The Location Type defines the characteristics of a group of common locations. You also define the relationship between locations and packs. Warehousing uses this information, together with the packs and location relationship, to decide whether to put a pack away in a location.



Note: You must define at least one location type, with at least one pack type.

Warehouse Map

The warehouse map provides the layout of the warehouse with all specified locations. You can define zones, or parts of areas, where you need to identify the type of location. For example, to restrict where you store items by weight, access, or temperature.



Note: You may need to use this option several times to cover all areas and locations and produce the complete map.

Location Check Digits

You only require location check digits if you confirm move instructions by entering codes which quickly identify if the item is in the correct location.

If you want check digits, you can use the default, based on modulus 23, or you can define your own location check digit codes.

You can define and apply these check digits at any time before you activate the warehouse. You must display the codes at the physical locations.

Location Rules

You can create two types of rules to suggest storage locations for a product received into Warehousing.



Note: You can use the same rules for committing and picking stock, if you are not using rotation date control.

You can create item and area rules. When you define an item (using the Item/Warehouse Profile option) you can link the rule to that item.

A product can have one item and one area rule for whole packs, and the same or different rules for split packs.



Tip: If you require location rules, define them before the item/warehouse profiles to minimise updates. However, you can define the rules at a later stage.

Item Rule

The item rule defines a sequence of locations to test for receiving and committing stock, based around a specific location. This can be a fixed location, or, more usually, a defined preferential pick location for the item.

One item rule can have a variable start point which depends on the item's preferential pick location. This helps to make sure that if the preferential pick location requires replenishment, the stock is nearby.

Area Rules

Area Rules are based on a fixed (or datum) location and cover a range of locations in an area. Thus, you can link similar products which you want to store in the same locality to the same area rule. Area rules provide similar functionality to item rules, but select locations on different criteria, such as proximity to a location or usage of locations.

Warehousing first looks for an item rule, then for an area rule.

Item/Warehouse Profile

You must define all items that you use in the warehouse at this level. If you have defined the item in Inventory at item/stockroom level, you must also define the following:

- Date for stock rotation, if applicable.
- Default pack type.
- Relationship between pack types and quantities per pack.
- Fixed Locations - if you store an item at a specific locations.
- Pick Location - If you pick the item from a specific picking location, you must also define the pick and replenishment details.
- Put Away Processing - For Warehousing to recommend locations to use for a receipt, you must specify the rules and restrictions which apply. These rules provide the basis for the effective organisation of the warehouse.
- Commit Processing - For Warehousing to identify the next stock to use, you must specify the rules and restrictions which apply.

Warehouse List Profile

You use the warehouse list profiles to define where, when and how many work documents to print. (Work documents are pick, move and put-away lists.)


There are four reserved codes:

- 01 - Put-away List.
- 02 - Pick List.
- 03 - Move List.
- 04 - Count List.

Determine Access Points

This sets the relative access point for locations based upon the area proximity details.

For example, if you define warehouse dimension 1 as aisles, then this associates each location with the appropriate physical point of access for the aisle.



Authorise Warehouse Users

You cannot perform processing functions within a warehouse unless you are specifically authorised to the warehouse. You must define appropriate authorisation before you activate the warehouse.

You can nominate a default warehouse for each user. This is the warehouse accessed each time the user enters Warehousing. You can change the warehouse currently assigned to another authorised warehouse.

Warehouse Profile Maintenance



1/WHM

You use the warehouse profile to maintain warehouse policies for each stockroom requiring warehouse level processing.

You must enter the Warehouse Profile Defaults before you can enter the area profiles and dimensions. However you need to set up the area profiles and area dimensions before you can enter the standard receiving and marshalling points and set up key messages. Therefore you must set up the basic details for the warehouse, and then return to Warehouse Profile when you have defined the required data.

You activate the warehouse after you define all the data for the application. To do this you must access the Warehouse Profile function a third time.



Note: Activating or de-activating a warehouse has critical implications for stock levels, order processing and so on, therefore restrict its use.

It is possible to change all of the data for a warehouse before it is activated.

Maintain Warehouse Profiles Selection Screen



Select Warehouse Profile.

Use this screen to select the warehouse you want to maintain, or stockroom you want to define as a warehouse.

WH010	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
-------	----------------------------	----------	----------------------

Maintain Warehouse Profiles

Stockroom...?.. WH

F3=Exit F4=Prompt

Fields:

Stockroom

To maintain a warehouse or define a stockroom as a warehouse, select a stockroom.



Tip: Stockrooms already activated as warehouses are highlighted.



To display the Maintain Warehouse Profiles Defaults screen, press **Enter**.

Maintain Warehouse Profiles Defaults Screen



To display this screen, select a stockroom on the Maintain Warehouse Profiles Selection screen and press **Enter**.

You use this screen to maintain Warehouse defaults. When you first create a warehouse ****INACTIVE**** displays. You can only activate the warehouse when you have created certain minimum definitions.

You can change all of the data for a warehouse before you activate it.

WH010	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
Maintain Warehouse Profiles			
Stockroom.... WH Central Warehouse			
Default Sequence for Picking List.. 1		1=Order 2=Account Code	
Putting away.. 1		3=Journey 4=Despatch date	
Moving..... 1		5=Op start date 6=Consignment	
Default date for committing..... 1		1=Receipt at warehouse	
		2=Receipt at location	
		3=Expiry	
System to generate locations..... 1		0=No, 1=Yes	
Are location check digits to be entered at confirmation..... 0		0=No, 1=Yes	
Are confirmation updates to be performed interactively..... 1		0=No, 1=Yes	
Allow default confirmation..... 0		0=No, 1=Yes	
F3=Exit F5=Refresh F11=Delete F12=Previous F14=Deactivate warehouse			

Fields:

Default Sequence For

For future development.



Tip: You can set the picking list sequence when you produce Pick Lists.

Default Date For Committing

Enter one of the following to define the date used for stock rotation:

- 1 - Receipt at the warehouse, this is when you confirm the item is in the receiving area.
- 2 - Receipt at the location, this is when you put-away stock.
- 3 - Expiry, this is the expiry date of the stock.

You can override this default using the Item/Warehouse profile.



Note: If you use expiry date and have a shelf life in Inventory, the system adds the number of days to the current date. Otherwise the rotation date is the date the stock enters the warehouse.

System To Generate Locations

Enter one of the following:

- 0 - If you want to allocate a location manually.
- 1 - If you want the system to suggest a location when you perform put away.

Are Location Check Digits To Be Entered At Confirmation

Enter one of the following:

- 0 - If you do not want to control the warehouse with check digits.
- 1 - If you want to control the warehouse with check digits. When you confirm actions you must enter a check digit corresponding to a location. You should display these digits at the physical location within the warehouse.



Note: You cannot use this and Allow Default Confirmation.

Are Confirmation Updates To Be Performed Interactively

Enter one of the following:

- 0 - To confirm updates by continuous operation. This means that the program is always in the background, which slows down the confirmation process.
- 1 - To confirm updates interactively. It is quicker to enter the updates to confirm.

Allow Default Confirmation

Enter one of the following:

- 0 - Not to use default confirmation.
- 1 - To automatically confirm Put-Away, Move or Pick Lists. You must un-confirm the lines where the operation failed. This option is preferable.



Note: You cannot use this and Location Check Digits.

Functions:

F11

Delete. Use this function to delete the warehouse functionality. This does not delete the stockroom.

F14

Activate/De-Activate Warehouse. Use this function to activate or de-activate a warehouse.



Tip: To exit Warehouse Profile without losing any data, select **F3=Exit** on this screen.



To display the Maintain Warehouse Profiles Locations screen, press **Enter**.

Maintain Warehouse Profiles Locations Screen



To display this screen, on the Maintain Warehouse Profiles Defaults screen press **Enter**.



Note: Use this screen when you access Warehouse Profiles for the second time.

You use this screen to define the standard receiving and marshalling points and set up key messages. Before you can enter these locations, you must set up area profiles and area dimensions.



Tip: To exit Warehouse Profile without losing any data, select **F3=Exit** on the Maintain Warehouse Profiles Default screen.

WH010	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
Maintain Warehouse Profiles			
Stockroom..... WH Central Warehouse			
Maintain receiving and marshalling locations.			
After the warehouse areas have been created, special locations must be set up. These are for the receiving and marshalling. It may be appropriate to set up areas specifically for this purpose.			
Receiving location.....?		A1	
Marshalling location for production.....?		C1	
Marshalling location for sales.....?		B1	
Serious error monitoring			
Message to show if a location is not recommended....		No Location	
User to receive error messages.....		SP1	
Work station to receive error messages.....		QPADEV0003	
F3=Exit F4=Prompt F5=Refresh F12=Previous			



Warning: Take care when you establish the marshalling and receiving locations, you should not change them once you have activated the warehouse.

Fields:

Maintain Receiving and Marshalling Locations:

Receiving Location

Enter the receiving location. All actions resulting in an Inventory receipt locate the items in the receiving location. You can choose any location in the warehouse as the receiving location. We recommend that you prepare an area for receiving.

Marshalling Location For Production

Enter the production marshalling location. When picking for production, Warehousing recommends that you move the stock required into the marshalling area prior to issue. You can choose any location in the warehouse. We recommend that you set up an area especially for the marshalling location.

Marshalling Location For Sales

Enter the sales marshalling location. When picking for sales, Warehousing recommends that you move the stock required into the marshalling area prior to despatch. You can choose any location in the warehouse. We recommend that you set up an area especially for this marshalling location.

Serious Error Monitoring:

If Warehousing cannot recommend a location for putting away or for picking, it prints a user defined message on the list, instead of a location. The message also displays on screen. It is possible to have the message directed to a specific user, for example: the warehouse manager.



Note: If you do not wish to use this facility for displaying messages on screen, do not start the Serious Error.

Message To Show If Location Is Not Recommended

Enter a message to display, using 12 characters, if Warehousing cannot recommend a location.



Note: Do not change this whilst there are outstanding actions in the warehouse.

User To Receive Error Messages

Not Used.



Note: The summary of errors automatically displays when the nominated user for the warehouse accesses any warehouse option.

Work Station To Receive Error Messages

Enter the terminal to receive the message, if the user set to receive messages is not signed on. This is not used by the current system.



Press **Enter** to check and save the information.
Press **Enter** again to display the Maintain Warehouse Profiles Item Defaults screen.

Maintain Warehouse Profiles Item Defaults Screen



To display this screen, complete the Maintain Warehouse Profiles Locations screen and press **Enter**.

Each item managed by Warehousing requires an item/warehouse profile. You can set up defaults to minimise the amount of data entry required when creating item/warehouse profiles.

This screen displays the default values to use for any new Item/Warehouse profiles. You can edit these defaults in Item/Warehouse Profile.



Tip: Refer to the section on setting up item/warehouse profiles, and consider how you want to define the majority of items before you use this screen to set up the defaults.

WH010	Z1 - UK Demonstration Company	USER	GBJBANB4	3/03/98 12:59:34
Warehouse Profile Maintenance				
The following values will be used to default the corresponding entries on the item/warehouse profile.				
	Whole packs (0=No, 1=Yes, 2=Consume split packs ONLY)	Split packs		
Fixed locations	1	1		
Putting away (0=No, 1=Yes)				
Multiple rotation dates.....	1	0		
Multiple LOTS.....	0	0		
Picking location.....	0	0		
Committing (0=No, 1=Yes, 2=Consume split packs ONLY)				
Rotation date.....	0	0		
Minimise LOTS.....	0	0		
Picking location.....	0	0		
F3=Exit F5=Refresh F12=Previous				

Fields:



Note: You can define all of the following fields separately for Whole and Split packs.

Fixed Locations

Enter one of the following:

- 0 - If you do not use fixed locations for an item.
- 1 - If you do use fixed locations for an item.
- 2 - To consume split packs only. Only valid for split packs.

Putting away:

Multiple Rotation Dates

Enter one of the following:

- 0 - If you cannot put away items with mixed rotation dates at a single location.
- 1 - If you can put away items with mixed rotation dates at a single location.

Multiple Lots

Enter one of the following:

- 0 - If you cannot put away items with mixed lots at a single location.
- 1 - If you can put away items with mixed lots at a single location.

Picking Location

Enter one of the following:

- 0 - If you cannot put away items at the picking location.
- 1 - If you can put away items at the picking location.

Committing:

Rotation Date

Enter one of the following:

- 0 - If you do not commit the item in rotation date order.
- 1 - If you do commit the item in rotation date order.
- 2 - Consume split packs only. Only valid for split packs.

Minimise Lots

Enter one of the following:

- 0 - If you do not want to minimise lots when committing lot controlled items.
- 1 - If you do want to minimise lots when committing lot controlled items.
Warehousing commits all of a lot in the warehouse before starting another lot.
- 2 - Consume split packs only. Only valid for split packs.

Picking Location

Enter one of the following:

- 0 - If you do not check the item's pick location when committing.
- 1 - If you do check the item's pick location when committing.
- 2 - Consume split packs only. Only valid for split packs.



To save the information, press **Enter**.

Area Profile Maintenance

1... **2/WHM**

You use this option to create and maintain the data which defines the areas required.

You set up a warehouse to record and manage the locations of items at the appropriate level. Before you can do this, you must define the shape and structure of the warehouse.

Warehousing treats the warehouse as a series of areas, divided into a number of locations. For example, to reflect the physical nature of a warehouse you could define three areas. One called Floor, set up to contain locations for receiving and marshalling, another called Main Store representing most of the aisles and bays, and a third called Bulk, used to store very large items. The definition and naming of areas is very flexible and therefore you should consider carefully how you want to represent your warehouse before you set up the areas.

Area Dimensions

After you have set up an area, you can divide it into a number of locations, using up to four dimensions. For example Aisle, Bay, Row and Front/Back. You can set the area to five units in the length dimension and two units in the width dimension, making a total of ten locations.

After you have divided an area into a set number of locations, you must give each location a type. The location type specifies what types of packs and how many of each pack type fit into the location. For example, a location type RA - Standard racking can accept one pallet or ten boxes. For more details see the Location Types section in this Product Guide.

Proximity Rules

Warehousing uses proximity rules to generate recommendations for putting away, letting down or picking, based on how near items are to the location. In order to do this you must generate a physical map of relationships and create some measure of proximity, one location to another. To simplify the definition use the following generalisations:

1. The distance between access points in any dimension need not be physical distance. What is important is the relative difficulty of changing access points in each dimension. This might be the time to change access points or the amount of work.
2. Any distance moved is the average for the area; For example, the average distance between column centres or level centres.

An access point is a point of reference in the dimension being defined. For example, the access point between aisles A and B provide access to two positions, while a truck positioned in front of column Q can only access this column.

Maintain Area Profiles Selection Screen



Select Area Profile.

Use this screen to select the warehouse and area you want to maintain.

WH020	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
Maintain Area Profiles			
Warehouse...?.. <u>WH</u>			
Area.....?.. <u>MS</u>			
F3=Exit F4=Prompt			

Fields:

Warehouse

Select a warehouse.



Note: You cannot define areas for a stockroom until you define the stockroom to Warehousing. You can select active or inactive warehouses.

Area

Enter a new or existing area code.



To display the Area Profiles Details screen, press **Enter**.

Maintain Area Profiles Details Screen



To display this screen, select a warehouse and area on the Maintain Area Profiles Selection screen, and press **Enter**.

Use this screen to define the dimensions of the area and the format of the location code.

The location code is a unique code, up to twelve characters, that identifies a particular location within an area. Warehousing produces the code from the dimensions set up for the area. For example, for a floor area with two dimensions, Length and Width, three units long, A to C and twelve units wide, 01 to 12. The location codes are three characters in length, A01, A02, A03 ... C12.

The code, built from the dimensions, can have up to six characters for each dimension, but no more than twelve characters in total.

WH020	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
Maintain Area Profiles			
Warehouse.....	WH	Central Warehouse	
Area.....	MS	Main Store	
Unit of Measure -	to define maximum capacities of the locations in the Area		
- Length...?..	—		
- Weight...?..	—		
- Volume...?..	—		
Dimension	Name	Code Length	
1	Aisle	1	
2	Bay	1	
3	Row	1	
4		—	
Control data for Proximity rules.....		0	0 = No, 1 = Yes
F3=Exit F4=Prompt F5=Refresh F11=Delete F12=Previous			

Fields:

Area

Enter a description for the area.

Units Of Measure

These are the default units of measure for memorandum purposes only.

Length

Select a unit of measure from the descriptions file.

Weight

Select a unit of measure from the descriptions file.

Volume

Select a unit of measure from the descriptions file.

Name

Enter a description for the dimension.



Note: You must define at least one dimension.

Code Length

Enter the number of characters, between 1 and 6, to use for the location code.



Note: The sum of the code lengths must not exceed 12.

Control Data For Proximity Rules

Enter one of the following:

0 - No. If you do not want proximity data.

1 - Yes. If you want to set up proximity data for the area.

For further details on the proximity rules field see Maintain Area Profiles - Proximity Rules.



Warehousing prevents you changing code lengths when this would produce unpredictable results, for example, if you have already generated locations.



Press **Enter**. Press **Enter** again to either return to the selection screen or, if you set the proximity rules field to 1, display the Maintain Area Proximity Rules screen.

Maintain Area Profiles Proximity Rules Screen



To display this screen, set the proximity rules to 1, on the Area Profiles Maintenance screen and press **Enter**.

Use this screen to define the control data for proximity rules.

This screen displays the answers to three questions for each dimension set up for the area. The questions are asked in turn for each dimension and should only be answered in relation to that dimension.



Tip: An access point is a point of reference in the dimension. For example, the access point between aisles A and B can access two positions, while a truck positioned in front of column Q can only access this column.

WH020	ZM - Multi-Currency Demo Company	USER QUSER	2/04/91 14:56:53
Maintain Area Profiles			
Warehouse..... WH Warehouse			
Area..... ST MAIN STORE AREA			
Control data for proximity putting away and committing rules			
Dimension:	1	2	3
Name.....	AISLE	BAY	HEIGHT
Distance to be moved between access points in the dimension.	10	1	5
The number of positions that can be accessed from access point.	2	1	1
Number of positions at the first access point.	1	1	1
F3=Exit F5=Refresh F12=Previous			

Fields:

Name

For each dimension, the text descriptions entered in the Name field on the Maintain Area Profiles screen are displayed.

Distance To Be Moved Between Access Points In The Dimension

Enter the distance between access points. This does not need to be physical distance, it might be time or relative work. You should define relative effort of changing access points by dimension.

The Number Of Positions That Can Be Accessed From An Access Point

Enter the number of positions which you can access in the dimension without incurring the penalty of a move in the dimension.

For example:

(1) Number of positions = 1

Access Points

Aisle

|A ▼ A|B ▼ B|C ▼ C|

(2) Number of positions = 2

Access Points

Aisle

|A ▼ B|C ▼ D|E ▼ F|

(3) Number of positions = 4 (Double Deep)

Access Points

Aisle

|AB ▼ CD|EF ▼ GH|

Number Of Positions At The First Access Point

Enter the number of positions at the first access point. This is necessary to define precisely what the warehouse looks like.

For Example:

Number of positions = 1

Access Points

Aisle

A|B ▼ C|D ▼ E|

Number of positions = 2

Access Points

Aisle

|A ▼ B|C ▼ D|E ▼ F|



Note: If you change the parameters after you have set up a rule, then you must regenerate it to reflect the latest changes.



Press **Enter** to save the data and display the Maintain Area Profiles Selection screen.

Area Dimensions Maintenance



3/WHM

Once you have defined an areas dimensions and location codes from the Area Profile option, you can set up the dimension sizes and hence the allowable codes for each of the locations. If you want the codes to be continuous, such as A-Z, 1 - 9, you only need to nominate the start and end of a range of codes.

Once you have set the size of each dimension, Warehousing can calculate and label the locations for that area. You can then allocate types to the locations which define what pack types can be in the location and how many of each pack type fit.

Maintain Area Dimensions Location Code Screen



To display this screen, enter a warehouse and area on the Maintain Area Dimensions Select Area screen and press **Enter**.

Use this screen to set the size of the dimensions for an area by specifying the characters to use in the code. For example, if you specify codes A to C for a dimension, this sets the size of that dimension to 3 units, and labels those units A, B and C.

You can enter the characters and code ranges for each dimension, and a batch process generates the codes, or you can select a single dimension for interactive maintenance.

The dimension names and the code lengths defined in the Area Profile option are displayed.

WH025	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
Maintain Area Dimensions			
Warehouse.....	WH Central Warehouse		
Area.....	MS Main Store		
Control information to automatically generate dimension codes			
Dimensions	Name	Length	Allowable characters Lowest Highest
			0 1-9 A-Z
1	Aisle	1	- - - _____
2	Bay	1	- - - _____
3	Row	1	- - - _____
 OR Select Dimension... _ (to enter codes individually)			
F3=Exit F4=Prompt F5=Refresh F11=Delete F12=Previous			

Fields:

Allowable Characters

Enter one of the following for each of the three fields:

0 - No. The character or range of characters cannot feature in the code.

1 - Yes. The character or range of characters can feature in the code.

Lowest

Enter the lowest code in the range of codes. The code must conform to the allowable characters specified.

Highest

Enter the highest code in the range of codes. The code must conform to the allowable characters specified.



Note: Warehousing generates the codes within the allowable character sets according to the standard IBM collating sequence, this is A to Z, Zero, and One to Nine. A low of AA and a high of CC with only the characters A to Z allowed generates 55 codes not 3, for example: AA, AB, AC, AD.....BA, BB.....CA, CB, CC.



Note: If there is only one code in the range you must enter it in both the Lowest and Highest fields.

OR

Select Dimension

Enter the dimension number to maintain individual codes. The dimension number is displayed in the left hand column.



Note: This process produces a list of location codes. To convert location codes to usable locations, assign location types to them.



Press **Enter** to make sure that the range limits specified comply with the constraints. If this finds no errors, Warehousing starts a batch job to generate the location codes for each dimension.

Maintain Area Dimensions Individual Codes Screen



To display this screen, enter the number of the required dimension in the Select Dimension field on the Maintain Area Dimensions Location Code screen.

You use this screen to maintain the location codes for any selected dimension.

To change a code, either enter the line number and the new code then press **Enter**, or enter the line number, press **Enter**, change the code in the dimension code field, then press **Enter** again.

To delete a code, enter the line number of the code and select **F11=Delete**. Select **F11=Delete** a second time to confirm.

To add a new code, enter it in the dimension code field, with no line number. Press **Enter** to insert the new code into the sequence.

WH025	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
-------	----------------------------	----------	----------------------

Maintain Area Dimensions

Warehouse..... WH Central Warehouse
Area..... MS Main Store
Dimension..... 1 Aisle Code length... 1

Line	Code	Dlt	Line	Code	Dlt	Line	Code	Dlt	Line	Code	Dlt
0001	A										
0002	B										
0003	C										
0004	D										
0005	E										
0006	F										

Line	Dimension code
—	—

F3=Exit F5=Refresh F8=Update F11=Delete F12=Previous

Fields:

Line

Enter the line number of the code to change or delete.

Code

Enter the dimension code you want to add or edit.

Dlt

This field displays a delete flag for codes which have been marked for deletion using **F11=Delete**.



Select **F8=Update** to remove codes flagged for deletion, insert new codes in the correct collating sequence, and renumber the whole list.

Item/Warehouse Profile Maintenance

4/WHM

You must associate each item you want to keep in a warehouse with a location.

If you use Warehousing to the fullest extent, it makes certain recommendations concerning where to put items, when and where you should replenish and from where you should pick items.

You can vary the way you manage items between warehouses in the same company. You therefore define the parameters for each item and warehouse combination.

Picking Location

You set up a pick face so that you can pick quantities less than the normal pack size without splitting packs in other parts of the warehouse.

You must define, for each pick face, the maximum pick quantity, the minimum quantity at the location and the replenishment quantity.

If, for example, the normal pack size contains one hundred items then:

- Set the maximum quantity to 99, any more would be a whole pack.
- Set the minimum quantity to 10, so when the quantity at the pick location drops below 10 you replenish the location.
- Set the replacement quantity to 100, a whole pack.

The minimum quantity at the picking location depends on when it is appropriate to trigger replenishment of the pick face. You must make sure there is enough space at the pick location to take any replenishment.

If the pick quantity does not exceed the defined maximum pick quantity, then Warehousing goes to the pick face even if there is not enough stock. This is termed over committing the pick face.

The pick face should hold enough stock to cover a working period, such as a shift or a day. You would then replenish the face at the end of the shift.

You can set up pick faces without running the automatic replenishment.

The Confirm Pick option updates stock and therefore it is this operation that triggers possible replenishment. Confirm pick updates a data queue which is read by the replenishment monitor. Moving stock from a pick face also updates the replenishment data queue.



Tip: If you use pick faces but not replenishment, the queue builds up. If, at some later stage, you switch on replenishment, contact your DP department to clear the data queue.

Automatic replenishment looks for stock to move to the pick face using the normal committing rules for the item. Automatic replenishment commits stock at specific locations to move to the pick face, therefore this stock is not available for any other reason, such as sales. You must run the Move List option to produce the actual replenishment move list. You can separate ordinary move lists from replenishment

move lists. You must then confirm these replenishment lists, with overrides if necessary, to make this stock available again. During this procedure the stock has always been available in Inventory.

Put-Away

When you receive stock into Inventory it is moved into the Receiving location set up in the Warehouse profile.

Put-away defines the steps Warehousing takes when recommending where to put an item. You can define different rules for whole packs and split packs.

You can change the pack type displayed when you receive goods, however this can affect the put-away recommendations. Warehousing does not recommend mixing different packaging types in a single location.

The decision whether you can have multiple products per location is a function of the location type. The decision whether you can have multiple rotation dates of the same product is a function of the item.

Items received into Purchase Management with status G (Goods) or I (Inspection) are not held in Inventory Management. Therefore, Warehousing does not select these items for put away recommendations. Put-away only happens when you receive items into Purchase Order Management with a status of S (Stores).

Warehousing determines the put-away location by following the steps:

1. Is this a whole or split pack? Is the quantity greater then or equal to the quantity defined for the pack?
2. Test defined pick locations.
3. Test defined fixed locations.
4. Test defined item rules.
5. Test defined area rule.

Once Warehousing finds a location, it performs various checks to make sure you can place the item there. The checks are:

1. Is the pack type defined for this location.
2. Rotation dates check. Can different rotation dates for an item be stored in the same location?
3. Lots check. Can different lots for an item be stored in the same location?
4. Will it fit? Does the number of packs exceed the permitted limit.



Note: Warehousing only performs this check when you store only one pack type in a location.

If Warehousing cannot place an item in that location, it repeats the steps to find another location. If it cannot find another locations, it logs a serious error and the serious error message set up in the warehouse profile prints on the put-away list.

Committing

Committing is the warehouse equivalent of allocation in Inventory Management. When you run a Pick List option in Warehousing, it commits specific elements of stock in the warehouse locations to sales, which reduces the available stock in these locations.

You can define the processing steps taken by Warehousing when recommending where you should pick an item from. Warehousing commits items using four overriding principles:

- Rotation dates.
- Minimise lots.
- Picking locations.
- Physical position.

Maintain Item/Warehouse Details Selection Screen



Select Item/Warehouse Profile (Maintenance).

Use this screen to select an item and warehouse for which you want to enter location details.

WH030	Z1 - Demonstration Company	User SP1	01/09/94 12:00:00
Maintain Item/Warehouse Details			
Item?.. 5006			
Warehouse ...?.. <u>WH</u>			
F3=Exit F4=Prompt			

Fields:

Item

Enter an item that is on the Item Master record.

Warehouse

Enter a warehouse. Active warehouses display in high intensity in the prompt window.



Press **Enter** to display the Maintain Item/Warehouse Details Packaging screen.

Maintain Item/Warehouse Details Packaging Screen



To display this screen, enter an item and warehouse on the Maintain Item/Warehouse Details Selection screen and press **Enter**.

Or select **F19=Packaging** from any other Item/Warehouse screen.

Use this screen to maintain the relationship between the item and the warehousing packing types, and define the stock rotation rules.

Use the upper part of the screen to define the minimum information required for the warehouse to recognise the item. Use the lower part to define the pack types the item is stored in and the item default pack type.

WH030	Z1 - Demonstration Company	User SP1	01/09/94 12:00:00
Maintain Item/Warehouse Details			
Item	5006	Organic Hair Tonic 18x215ml	
Warehouse	WH	Central Warehouse	
Date to be used for stock rotation ... 0		0 = None	1 = Receipt W/H
		2 = Receipt Loc	3 = Expiry
Warehouse activity, stocking and packaging units of measure			
Conversion factor to measure warehousing activity		1.00000	
Unit of measure	BX	Boxes of	
Default pack	PAL	Pallet	
Line	Warehouse pack	Description	Quantity/pack
0001	BOX	Box	1.000
0002	CSE	Case	4.000
0003	PAL	Pallet	16.000
Line	Warehouse pack(?)		Quantity/pack
F3=Exit F4=Prompt F5=Refresh F8=Update F11=Delete F12=Previous F15=Fixed Locs F16=Putaway F17=Commit F18=Picking F20=Restart			

Fields:

Date To Be Used For Stock Rotation

Enter one of the following:

0 - None. If this item is not date controlled.

1 - Receipt W/H. To use the date you received the item into the warehouse as the stock rotation date.

2 - Receipt Loc. To use the date you confirmed put-away at the location as the stock rotation date.

3 - Expiry. To use the expiry date as the stock rotation date. If you set up a shelf life for the item in Inventory Management, then when you receive a product, the rotation date is today's date plus the shelf life days. You can override the rotation date when you receive stock.

Warehouse activity, stocking and packaging units of measure:

Conversion Factor To Measure Warehouse Activity

This field is not currently used.

Unit Of Measure

Enter the unit of measure for the item. This field is not currently used.

Default Pack

Select the pack type to use as the default when you make inventory receipts.

Line

Enter the number of the line you want to change.

If you are entering a new pack type, leave this field blank.

Warehouse Pack

Select the pack type.

Quantity/Pack

Enter the number of items that fit in the pack, based on the Inventory Management item and stockroom issue units of measure.



Note: If the item does not have a standard pack type, use standard units of volume or weight. You can then define the number of items that this unit of volume or weight can contain.



Note: You can define different pack types for an item for different storage methods.

Functions:

F15

Fixed locations. Use this function to define the fixed locations used for this item.

F16

Put-away. Use this function to define the put-away profile for the item.

F17

Commit. Use this function to define the commit profile for the item.

F18

Picking. Use this function to define the picking location for the item.

F20

Restart. Use this function to return to the Maintain Item/Warehouse Details Selection screen.



Select **F8=Update** to save the information. Then select **F3=Exit** to leave the screen.

Maintain Item/Warehouse Details Fixed Locations Screen (F15)



To display this screen, select **F15=Fixed Locations** on any other Item/Warehouse screen.

Use this screen to maintain an individual fixed location or create a fixed location.

To maintain a location enter the line number at the bottom and press **Enter** then amend the data.

To add a fixed location, enter the data at the bottom of the screen and press **Enter**.

WH030	Z1 - Demonstration Company	User SP1	01/09/94 12:00:00
Maintain Item/Warehouse Details - Fixed Locations			
Item	5006	Organic Hair Tonic 18x215ml	
Warehouse	WH	Central Warehouse	
Line	Location	Whole packs	Split packs
0001	FE1	1	1
.			
Line	Location(?)	Whole packs	Split packs
_____	_____	0	0 (0 = No, 1 = Yes)
F3=Exit F4=Prompt F5=Refresh F8=Update F11=Delete F12=Previous F16=Putaway F17=Commit F18=Picking F19=Packaging F20=Restart			

Fields:

Line

Enter the number of the line you want to maintain.

Leave this field blank when you add a new location.

Location

Select the location to use as a fixed location for this item.

Whole Packs

Enter one of the following:

0 - No. Not to store whole packs at the location.

1 - Yes. To store whole packs at the location.

Split Packs

Enter one of the following:

0 - No. You do not allow split packs in this location.

1 - Yes. To allow the storage of split packs in the location.

Functions:

F16

Put-away. Use this function to define the put-away profile for the item.

F17

Commit. Use this function to define the commit profile for the item.

F18

Picking. Use this function to define the picking location for the item.

F19

Packaging. Use this function to define the packaging profiles for the item.

F20

Restart. Use this function to return to the Maintain Item/Warehouse Details Selection screen.



Select **F8=Update** to save the information. Then select **F3=Exit** to leave the screen.

Maintain Item/Warehouse Details Put Away Screen (F16)



To display this screen, select **F16=Put Away** on any other Item/Warehouse screen .

Use this screen to set the put-away conditions for whole and split packs of this item.

This screen displays either the current data for the item or, if this is a new item profile, the defaults set up in the Warehouse profile.

WH030	Z1 - Demonstration Company	User SP1	01/09/94 12:00:00
Maintain Item/Warehouse Details			
Item	5006	Organic Hair Tonic 18x215ml	
Warehouse	WH	Central Warehouse	
Putting away:		Whole packs	Split packs
Multiple rotation dates	1	1	0 = No;1 = Yes
Multiple LOTS per location ...	0	0	0 = No;1 = Yes
Picking location	0	1	0 = No;1 = Yes
Putting away rules:			
Whole packs			
Rule 1 - Item	?.. I01	Item Rule 1	
Rule 2 - Area	?.. A01	Area Rule 1	
Split packs			
Rule 1 - Item	?.. I01	Item Rule 1	
Rule 2 - Area	?.. A01	Area Rule 1	
F3=Exit F4=Prompt F5=Refresh F12=Previous F15=Fixed Tocs F17=Commit F18=Picking F19=Packaging F20=Restart			

Fields:



Tip: You need to enter all of this information for both split and whole packs.

Putting Away:

Multiple Rotation Dates

Enter one of the following:

0 - No. Not to allow items with different rotation dates in one location.

1 - Yes. To allow items with different rotation dates in one location.



Note: This is only relevant if you use stock rotation by date.

Multiple Lots Per Location

Enter one of the following:

0 - No. Not to allow items with different lot numbers in the same location.

1 - Yes. To allow items with different lot numbers in the same location.



Note: This is only relevant if you use lot numbering.

Picking Location

Enter one of the following:

0 - No. Not to test and use picking locations in preference.

1 - Yes. To test and put-away items in picking locations by preference.



Note: This is only relevant if you use picking locations.

Putting Away Rules:

Item

Enter the item rule to use.

Area

Enter the area rule to use.

Functions:

F15

Fixed locs. Use this function to define the fixed locations for the item.

F17

Commit. Use this function to define the commit profile for the item.

F18

Picking. Use this function to define the picking location for the item.

F19

Packaging. Use this function to define the packaging profiles for the item.

F20

Restart. Use this function to return to the Maintain Item/Warehouse Details Selection screen.



Press **Enter** to save the information. Then select **F3=Exit** to leave the screen.

Maintain Item/Warehouse Details Commit Screen (F17)



To display this screen, select **F17=Committing** on any Item/Warehouse screen.

Use this screen to define the principles and, if appropriate, the specific rules to use for committing.

This screen displays the current data for the item or if it is a new item, the defaults set up in the Warehouse profile.

WH030	Z1 - UK Demonstration Company	User GBJBAMSA	28/05/98 15:28:19
Maintain Item/Warehouse Details			
Item	5006	Organic Hair Tonic 18x215ml	
Warehouse	WH	Central Warehouse	
Committing stock		Whole packs	Split packs
By rotation date	0	0	0 = No;1 = Yes
Minimise LOTS	0	0	0 = No;1 = Yes
Picking location	0	0	0 = No;1 = Yes
Commit reserved lots.....	0	0	0 = No;1 = Yes
Committing rules			
Whole packs			
Rule 1 - Item	?.. I01	Item Rule 1	
Rule 2 - Area	?.. A01	Area Rule 1	
Split packs			
Rule 1 - Item	?.. I01	Item Rule 1	
Rule 2 - Area	?.. A01	Area Rule 1	
Allow commit at any location..		1	0 = No;1 = Yes
F3=Exit F4=Prompt F5=Refresh F12=Previous F15=Fixed Locs F16=Putaway F18=Picking F19=Packaging F20=Restart			

Fields:



Tip: You need to enter all of this information for both split and whole packs.

Committing Stock:

By Rotation Date

Enter one of the following:

0 - No. Not to commit in date order.

1 - Yes. To commit in date order, oldest date first.



Note: This is only relevant if you use stock rotation.

Picking Location

Enter one of the following:

0 - No. Not to test and use picking locations in preference.

1 - Yes. To test and put-away items in picking locations by preference.



Note: This is only relevant if you use picking locations.

Minimise Lots

Enter one of the following:

0 - No. Not to minimise use of lots.

1 - Yes. To use all of a lot before moving to another lot. This only applies in a single commit action.



Note: This is only relevant if you use lot numbering.

Commit Reserved Lots

Enter one of the following:

0 - No. Not to commit reserved lots.

1 - Yes. To commit reserved lots if they are allocated to a specific lot or batch number.

Committing Rules:

Item

Enter the item rule to use for committing.

Area

Enter the area rule to use for committing.

Allow Commit At Any Location

Enter one of the following:

0 - No. Not to commit anywhere if all other rules fail.

1 - Yes. To commit the item anywhere in the warehouse if all other rules fail.



Note: Warehousing only uses the pick location when the required quantity is less than the maximum quantity to pick.

Functions:

F15

Fixed locs. Use this function to define the fixed locations for the item.

F16

Putaway. Use this function to define the put away profile for the item.

F18

Picking. Use this function to define the picking location for the item.

F19

Packaging. Use this function to define the packaging profiles for the item.

F20

Restart. Use this function to return to the Maintain Item/Warehouse Details Selection screen.



Press **Enter** to save the information, then select **F3=Exit** to leave the screen.

Maintain Item/Warehouse Details Picking Location Screen (F18)



To display this screen, select **F18=Picking** on any Item/Warehouse screen.

Use this screen to enter the picking face and replenishment of picking face details.

This screen displays two types of data, the picking location details and the replenishment details.

WH030	Z1 - Demonstration Company	User SP1	01/09/94 12:00:00
Maintain Item/Warehouse Details			
Item	5006	Organic Hair Tonic 18x215ml	
Warehouse	WH	Central Warehouse	
Picking face details			
Picking location	?	BC3	
Maximum quantity to be picked from picking location		15.000	
Replenishment of picking face			
Minimum quantity at picking location		3.000	
Replacement quantity for picking location..		16.000	
Default resource code at picking location			
	?	TR	
F3=Exit F4=Prompt F5=Refresh F12=Previous F15=Fixed locs F16=Putaway F17=Commit F19=Packaging F20=Restart			

Fields:

Picking Face Details:

Picking Location

Enter a location.

Maximum Quantity To Be Picked From Picking Location

Enter the maximum quantity you can pick from this location.

Replenishment Of Picking Face:

Minimum Quantity At Location

Enter the minimum quantity you allow at the location. When the quantity falls below this level, replenishment is actioned.

Replacement Quantity For Picking Location

Enter the quantity required to replenish the pick location.

Default Resource Code At Picking Location

Enter the resource normally used to move items from the picking location.

Functions:

F15

Fixed locs. Use this function to define the fixed locations for the item.

F16

Putaway. Use this function to define the putaway profile for the item.

F17

Commit. Use this function to define the commit profile for the item.

F19

Packaging. Use this function to define the packaging profiles for the item.

F20

Restart. Use this function to return to the Maintain Item/Warehouse Details Selection screen.



Press **Enter** to update.

Packaging Types Maintenance

1... **2...** 5/WHM

Use this procedure to set up standard packaging specifications.

Many of the movements in a warehouse are done on pallets or containers. Warehousing uses the information you enter using this option to decide whether to put the pack in a particular location.

Maintain Packaging Code Specification Selection Screen



Select Packaging Types.

Use this screen to select an existing packaging type to maintain or enter a new type to create.

WH035	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
-------	----------------------------	----------	----------------------

Maintain Packaging Code Specification

Packaging code...?.. PAL

F3=Exit F4=Prompt

Fields:

Packaging Code

To amend packaging details, select the packaging type.

To add a pack type, enter the new code using up to 3 alphanumeric characters.



Enter a packaging type and press **Enter** to display the Maintain Packaging Code Specification Details screen.

Maintain Packaging Code Specification Details Screen



To display this screen enter a packaging type, on the Maintain Packaging Code Specification Selection screen, and press **Enter**.

Use this screen to maintain the data for the packaging type.



Note: Warehousing does not check weight or volume to test if the pack fits in the location.

WH035	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
Maintain Packaging Code Specification			
Packaging code.....	PAL	Pallet	
Unit of measure for check against			
Location size.....	Weight..?	Length..?	Volume..?
	---	---	---
Packaging capacity...	Weight.....	Volume.....	
	---	---	
Packaging specification and sizes			
Tare Weight.....	Length.....	Height.....	Depth.....
	---	---	---
Processing by label number..... 0 0 = No;1 = Yes			
F3=Exit F4=Prompt F5=Refresh F11=Delete F12=Previous			

Fields:

Packaging Code

Enter the description of the packaging type.

Unit Of Measure For Check Against Location Size

Specify the default weight, length and volume units of measure for this packaging type.

This is for memorandum purposes only.

Packaging Capacity

Specify the volume and weight of items that this packaging type can contain.

This is for memorandum purposes only.

Packaging specification and sizes:

Enter the tare weight, length, height and depth of the packaging types, in the appropriate unit of measure.

Processing By Label Number

Enter one of the following:

0 - No. You do not want to process this packaging type by label number.

1 - Yes. You do want to process this packaging type by label number. Warehousing calculates the number of packs and prints a label for each pack. Warehousing considers each label separately for processing. Warehousing generates label numbers during the receiving process. Use this to double-check that the pack is in the right location.



Note: You should not set this to 1 if any stock already exists in the warehouse under this packaging code.



Press **Enter** to save the information and return to the Maintain Packaging Code Specification Selection screen.

Location Types Maintenance



6/WHM

Use this option to set up the location type in the warehouse.

Depending on the function of the warehouse, there are a number of types of location. Choose the size, shape and use of the locations to meet the particular storage requirements and the number and distribution of the pack types.

Warehousing uses this information, together with the packs/location, to decide whether a pack should be put away in a location.

For each location type you need to:

- Set up the maximum storage length, weight, height, depth and volume for the location. Warehousing does not require these, but they are needed for clarification.
- Enter a cost of storage. This is for memorandum purposes only.
- Enter the packaging allowed at this location.

Maintain Location Types Selection Screen



Select Location Types (Maintenance).

Use this screen to maintain existing location types for a warehouse or to add new location types.

WH015	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
-------	----------------------------	----------	----------------------

Maintain Location Types

Warehouse.....?.. MH
Location type..?.. RA

F3=Exit F4=Prompt

Fields:

Warehouse

Enter any warehouse.

Location Type

To maintain a location type, select a location type.

To add a location type, enter the location type code, using 2 alphanumeric characters.



Press **Enter** to display the Maintain Location Types Details screen.

Maintain Location Types Details Screen



To display this screen, enter a warehouse and location type, on the Maintain Location Types Selection screen, and press **Enter**.

Use this screen to enter the storage constraints, and the packing allowed at the selected location.

WH015	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
Maintain Location Types			
Warehouse.....	WH Central Warehouse		
Location type.....	RA Standard Racking		
Maximum storage constraints		Length..	
	Volume..	Height..	
	Weight..	Depth..	
Cost of storage.....			
Allowed warehouse packing			
Line	W/house pack	Description	Packs/location Resource
0001	BOX	Box	16 WORK
0002	CSE	Case	4 TR
0003	PAL	Pallet	1 FLT
Line	W/hse pck(?)	Description	Packs/location Rsrce(?)
F3=Exit F4=Prompt F5=Refresh F8=Update F11=Delete F12=Previous			

Fields:

Location Type

If you are creating a new location type, enter the description.

Maximum Storage Constraints

Enter the maximum storage volume, weight, length, height and depth for this location. Warehousing does not require this information, but you can enter it for clarification.

Cost Of Storage

Enter the cost of storing items at this location. This field is for use in reporting. It is not used in any predefined calculations.

Line



Tip: If you are entering a new pack type, leave this blank.

To amend a pack type, enter the line number and press **Enter**. The details display in the other fields on this line, for you to amend.

W/Hse Pck

Enter an existing packaging type.

Packs/Location

Enter the number of the packaging type which is normally stored in this location type.

Rsrce

Enter the normal resource, for example, trolley, used to move the packaging type into or out of the location.



Press **Enter** to save the details and add them to the list of allowed packaging types.

Select **F8=Update** to update the database, then select **F3=Exit** to return.

Warehouse Map



7/WHM

Use this option to produce the complete warehouse layout.

An area of a warehouse is rarely uniform. You often have requirements to restrict where you store items, because of weight or access. You need to define these zones or parts of an area and identify the type of location. You can do this on a location by location basis, or by a range of locations.



Tip: To produce the complete map you have to go through this procedure a number of times.

Maintain Warehouse Map Selection Screen



Select Warehouse Map.

Use this screen to select an area within a warehouse.

You can enter three levels of data, warehouses, areas and locations, to directly access the part of the area you want to maintain. If you do not select a location, the display starts at the first location.



Note: Make sure there are no batch jobs running, because you cannot make any changes until the batch job is finished. If a batch job is running an error message is displayed.

WH040	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
-------	----------------------------	----------	----------------------

Maintain Warehouse Map

Warehouse .?.. WH
Area?.. MS

Start display at .?.. _____ (Blank for first location)

F3=Exit F4=Prompt

Fields:

Warehouse

Enter a warehouse.

Area

Enter the area you want to maintain.

Start Display At

Enter the first location to display.

Leave this field blank to start the display at the first location.



Press **Enter** to display the Maintain Warehouse Map Location screen.

If the location is not used, Warehousing does not:

- Recommend put-away.
- Commit any stock for picking.
- Replenish from the location (move).

But allows:

- Move to.
- Move from.
- Put away or pick with override.

Multi-Item

Enter one of the following:

0 - No. If you do not want Warehousing to recommend that you put different items in the same location.

1 - Yes. If you allow Warehousing to recommend that you put different items in the location, if all of the other tests are met, that is the pack types are the same and there is sufficient space.

Type

Enter a location type.

Functions:

F11

Delete. Use this function to delete the selected line. Select **F11=Delete** again to confirm deletion. The line is marked as pending deletion and is deleted when you select **F8=Update**.

F15

Maintain Range. Use this function to access the Maintain Warehouse Map By Range screen.



Press **Enter** to accept any line changes, then select **F8=Update** to save the changes.

Maintain Warehouse Map By Range Screen (F15)



To display this screen, select **F15=Maintain Range** on the Maintain Warehouse Map Location screen.

Use this screen to enter ranges of codes to limit the scope of the amendment, define the characteristics of the locations, and define how the characteristics are applied.

WH040	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
Maintain Warehouse Map			
Warehouse	WH	Central Warehouse	
Area	MS	Main Store	
Location Definition:			
Length	Dimension	Minimum(?)	Maximum(?)
1	Aisle	A	D
1	Bay	A	E
1	Row	I	5
Location status 1 (0=Void; 1=Active)			
Multiple items 0 (0=No; 1=Yes)			
Maximum no. of locations to be created ... 300			
Location type RA			
Maintenance Constraints: (0=No; 1=Yes)			
Create new locations	1	Amend location status	1
Amend existing locations ..	1	Amend multiple items	1
		Amend location type	1
F3=Exit F4=Prompt F5=Refresh F11=Delete F12=Previous			
F16=Number of locations			

Fields:

Minimum

Select the lowest (minimum) position for the displayed dimension.

Maximum

Select the highest (maximum) position for the displayed dimension.

Location Status

Enter one of the following:

0 - Void. Do not recommend this location for put-away, pick or replenishment.

1 - Active. Warehousing can use this location for put-away, pick or replenishment.

Multiple Items

Enter one of the following:

0 - No. Warehousing does not recommend you put two different items in the same location.

1 - Yes. Warehousing can recommend that you put different items away, if the pack types is the same and there is sufficient space.

Maximum No. Of Locations To Be Created

Enter the maximum number of locations. Use this to make sure Warehousing does not create an unreasonable number of locations.



Tip: Select **F16=Number Of Locations** to calculate and display the number of possible locations in the specified range.

Location Type

Enter a location type.

Create New Locations

Enter one of the following:

0 - Not to create any locations within the requested range that do not exist.

1 - To create any locations in the requested range that do not exist.

Amend Existing Locations

Enter one of the following:

0 - Not to amend any existing locations.

1 - To amend any existing locations. Select the characteristics you want to amend in the remaining fields.

Amend Location Status

Enter one of the following:

0 - Not to amend the status of existing locations.

1 - To amend the status of the locations, if you set Amend Existing Locations field to 1.

Amend Multiple Items

Enter one of the following:

0 - Not to change whether you allow multiple items.

1 - To amend whether you allow multiple items, if you set the Amend Existing Locations field to 1.

Amend Location Type

Enter one of the following:

0 - Not to amend the locations type.

1 - To amend the location type, if you set the Amend Existing Locations field to 1.

Functions:

F16

Number of locations. Use this function to calculate and display the number of locations defined by the specified range. Press **Enter** to remove the window from the screen.



*Note: Use **F16=Number Of Locations** to check the number of locations that you want to create is*

not too great, before you submit the batch job.



Press **Enter** to submit job to the batch queue.
Only one job for each area can be active at a time.

Location Rules By Item



8/WHM

Use this procedure to reproduce a line of sight check for an empty location for a specified item.

You can define rules to specify the order Warehousing checks locations when searching for the best location to pick from.

Maintain Location Rules Item Selection Screen



Select Location Rules By Item.

Use this screen to select the rule to amend or enter a number to create a new rule.

WH045	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
-------	----------------------------	----------	----------------------

Maintain Location Rules - Item

Warehouse...?.. WH

Rule no....?.. I01

F3=Exit F4=Prompt

Fields:

Warehouse

Enter a warehouse. Active warehouses display in high intensity in the prompt window.

Rule No.

To amend an item rule, select the rule number.

To add a rule, enter a new rule number.



Press **Enter** to display the Maintain Location Rules Item Details screen.

Maintain Location Rules Item Details Screen



To display this screen, enter a warehouse and rule number, on the Maintain Location Rules Item Selection screen, and then press **Enter**.

When you define an area, you also define the dimensions for the area. This type of rule tests a series of locations in a defined sequence. You must therefore define the first location and which dimension and how many positions to move before performing the next test.

The upper part of the screen displays the area, and dimensions. The lower part displays a list of the moves defined. A new step number starts from the datum location, a new sequence number starts from the previously tested location.

WH045		Z1 - Demonstration Company		USER SP1		01/09/94 12:00:00	
Maintain Location Rules - Item							
Warehouse..... WH		Central Warehouse		Dimensions			
				1 Aisle			
				2 Bay			
				3 Row			
				4			
Rule no..... I01		Item Rule 1					
Area.....?.. MS		Main Store					
Picking location =		Datum location...		1		(1=Yes; 0=No)	
OR		Datum location..?..					
Line	Step No	Sequence	Dimension	Direction	Step size		
0001	5	5	3 Row	2 Descending	1		
0002	5	10	2 Bay	2 Descending	1		
0003	5	15	3 Row	1 Ascending	1		
0004	5	20	3 Row	1 Ascending	1		
0005	10	5	3 Row	1 Ascending	1		
0006	10	10	2 Bay	1 Ascending	1		
0007	15	5	2 Bay	1 Ascending	1		
0008	15	10	3 Row	2 Descending	1		
Line	Step No	Sequence	Dimension	Direction(?)	Step size		
—	—	—	—	1	1		
F3=Exit F4=Prompt F5=Refresh F8=Update F11=Delete F12=Previous							

Fields:

Rule No

Enter the rule description.

Area

Select the area for which you want to set up the rule.

Picking Location - Datum Location

Enter one of the following:

0 - No. To search from a specific point. Enter the location in the field below.

1 - Yes. To start the search from the picking location individually defined for the items.

Line

Enter the number of the line you want to maintain or delete.



Tip: If you are defining a new rule, leave this field blank.

Step No

Enter a step number. Increase the step number in 10s so you can insert more lines later.

When you specify a new step, the search returns to the datum location to start in a different direction

Sequence

Enter a sequence number. Increase the sequence number in 10s so you can insert more lines later.

When you specify a new sequence number, the search starts from the last point searched.

Dimension

Enter the dimension in which the move is made.

Direction

Enter one of the following:

- 1 - Ascending. To move up the dimension.
- 2 - Descending. To move down the dimension.

Step Size

Enter the number of codes to move in the defined dimension.



Select **F8=Update** to re-order the instructions in sequence within step number and save the changes. Select **F3=Exit** to leave the screen.

Location Rules by Area



9/WHM

Use this option to define the rules that reproduce the review of a large number of locations. You can define rules to answer questions such as:

- Find the location with space, in this area, which is closest to the receiving bay.
- Select a not-full location randomly.

The rule only operates within an area.

An Area Rule specifies the sequence Warehousing tests a range of locations, either for put-away or committing.

There are a number of sequences:

- Proximity - The shortest distance to move from a datum or search anchor point. The distances between location are derived from the proximity data entered for the area. For more information see Determine Access Points.
- Random - The locations are accessed in a random sequence. When you first generate a random rule, the locations within the parameter set are randomised, this is the set sequence until you re-generate the rule.
- Utilisation - The location is accessed in order of the locations with the least number of movements. This, like random, tries to make sure of a uniform distribution throughout the warehouse and therefore should minimise congestion. You must recreate these rules to reflect changes in Warehouse Location Utilisation.

Maintain Location Rules Area Selection Screen



Select Location Rules By Area.

Use this screen to select the area rules you want to maintain or enter a number to create a new area rule.

WH050	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
-------	----------------------------	----------	----------------------

Maintain Location Rules - Area

Warehouse...?.. WH
Rule.....?.. A01
Area.....?.. — (For new rules)

F3=Exit F4=Prompt

Fields:

Warehouse

Select a warehouse. Active warehouses are highlighted in the prompt window.

Rule

To amend a rule, enter the rule number and leave the area field blank.

To add a new rule, enter a new rule number.

Area

If you are creating a new rule, select an area in the selected warehouse.



Press **Enter** to display the Maintain Location Rules Area Details screen.

Maintain Location Rules Area Details Screen



To display this screen, select a rule on the Maintain Location Rules Area Selection screen and press **Enter**.

Use this screen to define or amend the selected area location rule.

The upper section of the screen displays the rule, the area and the type of rule. The lower section displays the range of locations in the area to which the rule applies.

WH050	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
Maintain Location Rules - Area			
Warehouse.....	WH	Central Warehouse	
Rule no.....	A01	Area Rule 1	
Area.....	MS	Main Store	
Rule class....	1	(1=Proximity; 2=Utilisation; 3=Random)	
Datum location...?	AA1		
Dimension	Name	Code Length	Range of locations From(?) To(?)
1	Aisle	1	A D
2	Bay	1	A D
3	Row	1	2 5
F3=Exit F4=Prompt F5=Refresh F8=Update F11=Delete F12=Previous			

Fields:

Rule No

Enter the rule description.

Area

Enter the area in which the rule operates.

Rule Class

Enter one of the following to define the rule class.

- 1 - Proximity.
- 2 - Utilisation.
- 3 - Random.

Datum Location

If you select proximity in the Rule Class field, enter a fixed location. This is the search anchor point for the rule.

Range Of Locations

For each dimension, enter the upper and lower limits of the scope of the rule.



Select **F8=Update** to save the rule details and submit a batch job to build the new rule sequence.

Resource Codes



10/WHM

Use this option to set-up and maintain resource codes.

A resource code refers to the resource required to move a particular pack type into or out of a specific type of location. For example, the resource required to move a pallet from a standard racking location could be a fork lift truck, whereas the resource required to move a pallet from a floor location need only be a trolley.

You can associate resource codes with location and pack types using the Location Types option.

Maintain Resource Codes Selection Screen

 Select Resource Codes.

Use this screen to select the resource and warehouse combination you want to maintain or create.

WH055	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
Maintain Resource Code			
Warehouse.....?.. <u>WH</u>			
Resource code...?.. <u>FLT</u>			
F3=Exit F4=Prompt			

Fields:

Warehouse

Enter any warehouse. Active warehouses are highlighted in the prompt window.

Resource Code

To maintain a resource, select any resource already set up in the warehouse.

To add a resource, enter a resource code using 4 alphanumeric characters.

 Press **Enter** to display the maintain Resource Codes Details screen.

Maintain Resource Codes Details Screen



To display this screen, enter a resource code on the Maintain Resource Codes Selection screen and press **Enter**.

You use this screen to maintain the resource details. At present data is for information only.

WH055	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
Maintain Resource Code			
Warehouse..... WH Central Warehouse			
Resource code..... FLT			
Description..... Fork Lift Truck			
Cost.....			
F3=Exit F5=Refresh F11=Delete F12=Previous			

Fields:

Description

Enter a text description of the resource. This is a mandatory field.

Cost

Enter a cost rate. This is for memorandum purposes only.



Press **Enter** to save the changes.

Location Check Digit Codes



11/WHM

You can use check digits or return codes to make sure that warehouse staff visit the defined location.

You confirm that an action is complete by entering a check digit that is only displayed at the physical location.

To use check digits you need to:

1. Specify whether the Warehouse uses check digits.
2. Define a set of default check digits for the warehouse. You can override these for an area.



Note: If you specify that the warehouse uses check digits but do not set them up, Warehousing determines a check digit based on Modulus 23.

Maintain Check Digits Selection Screen



Select Location Check Digit Codes.

Use this screen to select the warehouse and, if required, area for which you want to maintain location check digits.

WH060	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
Maintain Check Digits			
Warehouse...?.. <u>WH</u>			
Area.....?.. <u>MS</u>			
F3=Exit F4=Prompt			

Fields:

Warehouse

Select the warehouse required. Active warehouses are highlighted in the prompt window.

Area

If required, select an area.

Leave this field blank to maintain check digits for the whole warehouse.



Note: If you select an area and warehouse that you have not set up to use check digits, an error displays, and you cannot maintain the check digits.



Press **Enter** to display the Maintain Check Digits Details screen.

Warehouse List Profiles



13/WHM

If you manage your warehouse by instruction documents, that is pick, move and put-away lists, you must define where and when they print, and how many print at a time.

Maintain Warehouse/List Profiles Selection Screen



Select Warehouse List Profile.

Use this screen to select the list type and warehouse you want to maintain.

WH070	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
Maintain Warehouse/List Profiles			
Warehouse...?.. <u>WH</u>			
List type...?.. <u>02</u>			
F3=Exit F4=Prompt			

Fields:

Warehouse

Enter the warehouse. Active warehouses are highlighted in the prompt window.

List Type

Select the list type to maintain.



Press **Enter** to display the Maintain Warehouse/List Profiles Details screen.

Maintain Warehouse/List Profiles Details Screen



To display this screen, select the warehouse and list type on the Maintain Warehouse/List Profiles Selection screen and press **Enter**.

Use this screen to maintain the defaults for the warehouse instruction documents.

WH070	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
-------	----------------------------	----------	----------------------

Maintain Warehouse/List Profiles

Warehouse..... WH Central Warehouse

List..... 02 Move List

No of instructions per list..... 15

Maximum lists per run..... 100

Allow continuous processing..... 0 (0=No,1=Yes)

Output queue for continuous
processing..... QPRINT

Library for output queue..... QGPL

F3=Exit F5=Refresh F11=Delete F12=Previous

Fields:

No Of Instructions Per List

Enter the default number of lines to print on the list. You can change this at run time.

Maximum Lists Per Run

Enter the number of lists to print in the run, to reduce the work output at run time.

Allow Continuous Processing

This is not currently used.

Output Queue For Continuous Processing

This is not currently used. However, you must enter an output queue, for example, QPRINT.

Library For Output Queue

This is not currently used. However, you must enter the library to use for the output queue, for example QGPL.



Press **Enter** to save the changes, then select **F3=Exit** to leave the screen.

Determine Access Points



21/WHM

Use this option to set the relative access point for locations, based upon the area proximity details.

You need to run this option if you use area proximity rules in the warehouse and you produce pick lists based on warehouse dimension 1.

You determine the correct access point for each warehouse location.



Note: This procedure runs for your default warehouse. To run this for another warehouse, use the Change Warehouse option to change your default warehouse.



Note: You must run this batch job every time you alter the structure of the warehouse.

Determine Access Points Screen



Select Determine Access Points.

Use this screen to select the area for which you want to determine access points.

WH409	Z1 - Demonstration Company Central Warehouse	USER SP1	01/09/94 12:00:00
Determine Access Points			
Area.....?.. <u>MS</u> (Leave blank for ALL areas)			
F3=Exit F4=Prompt F8=Submit			

Fields:

Area

To determine access points for a single area, enter the area.

Leave this field blank to determine access points for all areas.



Note: You must run this batch job every time you alter the structure of the warehouse.



Select **F8=Submit** to submit the batch job for processing.

Create Location Check Digits



22/WHM

Use this option to sequentially apply the check digits, defined using the Location Check Digits Codes option, to the warehouse locations.

This procedure also prints a report detailing the check digits assigned to the warehouse and area.

The batch job processes all of the locations for the nominated area in turn. For each location it selects the next non-blank pair of check digits and assigns it to the location. When it has used all of the check digits, the sequence is repeated.

If check digits are not present for the area, it uses the check digits for the warehouse. If they are not present, the batch job generates a single check digit based on modulus 23.



Note: This batch job runs for the default warehouse. To run this job for another warehouse, you must change your default warehouse, using the Change Warehouse option.

Create Location Check Digits Screen



To display this screen, select the Create Location Check Digits option.

Use this screen to select the area, in the default warehouse, for which you want to create location check digits.

WH420	Z1 - Demonstration Company Central Warehouse	USER SP1	01/09/94 12:00:00
Create Location Check Digits			
Area.....?.. <u>MS</u>			
Update locations.. <u>1</u>		(0=No,1=Yes)	
Print..... <u>1</u>		(0=No,1=Yes)	
F3=Exit F4=Prompt F5=Refresh			

Fields:

Area

Select the area required.

Update Locations

Enter one of the following:

0 - No. If you do not want to apply check digits to the locations.

1 - Yes. If you want to apply check digits to the locations.

Print

Enter one of the following:

0 - No. If you do not want to print a report.

1 - Yes. If you want to produce a report showing the location and check digit relationship.



Note: You must generate and print the check digits before fixing them at the physical location.



Press **Enter** to submit the batch job.

Warehouse Profile Enquiry



31/WHM

This enquiry displays the warehouse profile of the users' default warehouse. It includes details of the warehouse policies, such as check digit usage, the locations defined for marshalling and receiving, and the defaults set for item/warehouse profiles.

Warehouse Profile Enquiry Selection Screen



Select Warehouse Profile (Enquiries).

Use this screen to select the warehouse for which you want to display the profile.

Fields:

Stockroom

Select the warehouse you require.



Press **Enter** to display the Warehouse Profile Enquiry Defaults screen.

Warehouse Profile Enquiry Defaults Screen

-  To display this screen, select a warehouse on the Warehouse Profile Enquiry Selection screen and press **Enter**.

This screen displays:

- The default picking, put away and movement sequence.
- Default commitment date.
- Location and check digit defaults.

WH200	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
Warehouse Profile Enquiry			
Stockroom..... WH Central Warehouse			
Default sequence for Picking list..... 1		1=Order 2=Account code	
Putting away..... 1		3=Journey 4=Despatch date	
Moving..... 1		5=Oper'n start date 6=Consignment	
Default date for committing..... 1		1=Receipt at warehouse	
		2=Receipt at location	
		3=Expiry	
System to generate locations..... 1		0=No, 1=Yes	
Are location check digits to be entered at confirmation..... 1		0=No, 1=Yes	
Are confirmation updates to be performed interactively..... 1		0=No, 1=Yes	
Allow default confirmation..... 0		0=No, 1=Yes	
F3=Exit F12=Previous			

For more details on the individual fields see the Warehouse Profile Maintenance section of this product information.

-  Press **Enter** to display the Warehouse Profile Enquiry Locations screen.

Warehouse Profile Enquiry Locations Screen



To display this screen, press **Enter** on the Warehouse Profile Enquiry Defaults screen.

This screen shows the receiving location and the marshalling location for production and sales. It also displays the details for serious error monitoring.

WH200	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
-------	----------------------------	----------	----------------------

Warehouse Profile Enquiry

Stockroom..... WH Central Warehouse

Receiving location.....	A1
Marshalling location for production.....	C1
Marshalling location for sales.....	B1

Serious error monitoring

Message to show if a location is not recommended... No Location

User to receive error messages..... SP1

Work station to receive error messages..... QPADEV0003

F3=Exit F12=Previous

For more details on the individual fields see the Warehouse Profile Maintenance section of this product information.



Press **Enter** to display the Warehouse Profile Enquiry Item Defaults screen.

Warehouse Profile Enquiry Item Defaults Screen



To display this screen, press **Enter** on the Warehouse Profile Enquiry Locations screen.

This screen displays the commit and put-away rules for split and whole packs.

WH200	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
Warehouse Profile Enquiry			
Stockroom..... WH Central Warehouse			
The following values are used to default the corresponding entries on the item/warehouse profile.			
	Whole packs	Split packs	(0=No, 1=Yes)
Fixed locations	0	0	
Putting away			
Multiple rotation dates.....	1	1	
Multiple LOTS.....	0	0	
Picking location.....	0	0	
Committing			
Rotation date.....	1	1	
Minimise LOTS.....	0	0	
Picking location.....	0	1	
F3=Exit F12=Previous			

For more details on the individual fields see the Warehouse Profile Maintenance section of this product information.



Select **F3=Exit** to leave the enquiry.

Area Profile/Dimensions Enquiry



32/WHM

This enquiry displays the area definition, the proximity variables, the location code structure and dimension values.

Area Profile Enquiry Selection Screen

 Select Area/Profile Dimensions (Enquiry).

Use this screen to select the area for which you want to display the details.

WH205	Z1 - Demonstration Company Central Warehouse	USER SP1	01/09/94 12:00:00
-------	---	----------	----------------------

Area Profile Enquiry

Area.....?.. MS

F3=Exit F4=Prompt

Fields:

Area

Enter the area to enquire upon.

 Press **Enter** to display the Area Profile Enquiry Dimensions screen.

Area Profile Enquiry Dimensions Screen



To display this screen, on the Area Profile Enquiry Selection screen, enter an area and press **Enter**.

This screen displays the defined dimensions for the selected area.

WH205	Z1 - Demonstration Company Central Warehouse	USER SP1	01/09/94 12:00:00
-------	---	----------	----------------------

Area Profile Enquiry

Area..... MS Main Store

Unit of Measure - to define maximum capacities of the locations in the Area

- Length.....
- Weight.....
- Volume.....

Dimension	Name	Code	Length
1	Aisle		1
2	Bay		1
3	Row		1
4			

F3=Exit F12=Previous F14=Proximity details F15=Area dimensions

For further details of individual fields, refer to the Area Profiles Maintenance section.

Functions:

F14

Proximity Details. Use this function to display the proximity details set up for the area.

F15

Area Dimensions. Use this function to display the area dimension information.



Select **F3=Exit** to leave the enquiry.

Area Profile Enquiry Proximity Details Screen (F14)



To display this screen select **F14=Proximity Details** on the Area Profile Enquiry Dimensions screen

This screen displays the measures of proximity used to determine the relative distance between locations in the selected area.

WH205	Z1 - Demonstration Company	USER SP1	01/09/94
	Central Warehouse		12:00:00
Area Profile Enquiry			
Area..... MS Main Store			
Control data for proximity putting away and committing rules			
Dimension:	1	2	3
Name.....	Aisle	Bay	Row
Distance to be moved between access points in the dimension.	10	1	5
The number of positions that can be accessed from access point.	2	1	1
Number of positions at the first access point.	1	1	1
F3=Exit F12=Previous			

For further details of individual fields, refer to the Area Profiles Maintenance section.



Select **F3=Exit** to leave the enquiry.

Enquire On Area Dimensions Screen (F15)



To display this screen select **F15=Area Dimensions** on the Area Profile Enquiry Dimensions screen

Use this screen to select the dimension for which you want to see the area dimensions.

WH205	Z1 - Demonstration Company Central Warehouse	USER SP1	01/09/94 12:00:00
-------	---	----------	----------------------

Enquire on Area Dimensions

Area..... MS Main Store

Select Dimension..... 1 (to review codes individually)

F3=Exit F12=Previous

Fields:

Select Dimension

Enter the number of the dimension to display. For example, to display the codes used in the first dimension enter 1 and press **Enter**.



Press **Enter** to display the Area Profile Enquiry Area Dimensions screen.

Item/Warehouse Profile Enquiry



33/WHM

This enquiry displays the parameters that have been set up for an item so you can process it in the warehouse.

These details include packaging information, locations, put away details, commitment details and picking information.

Item/Warehouse Profile Enquiry Packaging Screen



To display this screen, select the Item/Warehouse Profile (Enquiries) option, enter an item and press **Enter**.

OR. Select **F19=Packaging Information** from any Item/Warehouse Profile Enquiry screen.

This screen displays the stock rotation rules and the packaging types for this item.

WH210	Z1 - Demonstration Company	USER SP1	01/09/94
	Central Warehouse		12:00:00
Item/Warehouse Profile Enquiry			
Item.....	5006	Organic Hair Tonic 18x215ml	
Date to be used for stock rotation....	0	(0=None; 1=Receipt into W/H; 2=Receipt into loc; 3=Expiry)	
Warehouse activity, stocking and packaging units of measure			
Conversion factor to measure			
warehousing activity.....		1.00000	
Unit of measure.....	BX	Boxes of	
Default pack.....	PAL	Pallet	
Line	Warehouse pack	Description	Quantity/pack
0001	BOX	Box	1.000
0002	CSE	Case	4.000
0003	PAL	Pallet	16.000
F3=Exit F12=Previous F15=Fixed locations F16=Put away details			
F17=Commitment details F18=Picking information			

For further details of individual fields, refer to the Item/Warehouse Profiles Maintenance section.

Functions:

F15

Fixed Locations. Use this function to display the fixed locations for the item.

F16

Put Away Details. Use this function to display the put away details for the item.

F17

Commitment Details. Use this function to display the commit details for the item.

F18

Picking Information. Use this function to display the picking details for the item.



To leave the enquiry, select **F3=Exit**.

Item/Warehouse Profile Enquiry Locations Screen (F15)



To display this screen, select **F15=Fixed Locations Details** on any of the Item/Warehouse Profile Enquiry screens.

This screen displays the fixed locations set up for an item, and whether you allow whole and split packs in the location.

WH210	Z1 - Demonstration Company	USER SP1	01/09/94
	Central Warehouse		12:00:00
Item/Warehouse Profile Enquiry - Fixed Locations			
Item.....	5006	Organic Hair Tonic 18x215ml	
Line	Location	Whole packs	Split packs
0001	FE1	1	1
F3=Exit F12=Previous F16=Put away details F17=Commitment details			
F18=Picking information F19=Packaging information			

For further details of individual fields, refer to the Item/Warehouse Profiles Maintenance section.

Functions:

F16

Put Away Details. Use this function to display the put away details for the item.

F17

Commitment Details. Use this function to display the commit details for the item.

F18

Picking Information. Use this function to display the picking details for the item.

F19

Packaging Information. Use this function to display the packaging details for the item.



To leave the enquiry, select **F3=Exit**.

Item/Warehouse Profile Enquiry Put Away Screen (F16)



To display this screen, select **F16=Put Away Details** on any of the Item/Warehouse Profile Enquiry screens.

This screen displays the put-away rules set up for an item. These rules are for both split and whole packs.

WH210	Z1 - Demonstration Company Central Warehouse	USER SP1	01/09/94 12:00:00
Item/Warehouse Profile Enquiry			
Item.....	5006	Organic Hair Tonic 18x215ml	
Putting away		Whole packs	Split packs
Multiple rotation dates.....	1	1	0 = No;1 = Yes
Multiple LOTS per location....	0	0	0 = No;1 = Yes
Picking location.....	0	1	0 = No;1 = Yes
Putting away rules			
Whole packs			
Rule 1 - Item.....	I01	Item Rule 1	
Rule 2 - Area.....	A01	Area Rule 1	
Split packs			
Rule 1 - Item.....	I01	Item Rule 1	
Rule 2 - Area.....	A01	Area Rule 1	
F3=Exit F12=Previous F15=Fixed locations F17=Commitment details F18=Picking information F19=Packaging information			

For further details of individual fields, refer to the Item/Warehouse Profiles Maintenance section.

Functions:

F15

Fixed Locations. Use this function to display the fixed locations for the item.

F17

Commitment Details. Use this function to display the commit details for the item.

F18

Picking Information. Use this function to display the picking details for the item.

F19

Packaging Information. Use this function to display the packaging details for the item.



To leave the enquiry, select **F3=Exit**.

Item/Warehouse Profile Enquiry Commitment Screen (F17)



To display this screen, select **F17=Commitment Details** on any of the Item/Warehouse Profile Enquiry screens.

This screens displays the committing rules set up for both split and whole packs of the item.

WH210	Z1 - UK Demonstration Company	USER	GBJBANB4	2/03/98
	Central Warehouse			8:35:11
Item/Warehouse Profile Enquiry				
Item.....	5006	Organic Hair Tonic 18x215ml		
Committing stock				
By rotation date.....	0	Whole packs	Split packs	0 (0 = No,
Minimise LOTS.....	0	(0 = No,	0	1 = Yes,
Picking location.....	0	1 = Yes)	0	2 = Consume split
Commit reserved lots.....				packs ONLY)
Committing rules				
Whole packs				
Rule 1 - Item.....	I01	Item Rule 1		
Rule 2 - Area.....	A01	Area Rule 1		
Split packs				
Rule 1 - Item.....	I01	Item Rule 1		
Rule 2 - Area.....	A01	Area Rule 1		
Allow commit at any location..		1	0 = No;1 = Yes	
F3=Exit F12=Previous F15=Fixed locations F16=Put away details				
F18=Picking information F19=Packaging information				

For further details of individual fields, refer to the Item/Warehouse Profiles Maintenance section.

Functions:

F15

Fixed Locations. Use this function to display the fixed locations for the item.

F16

Put Away Details. Use this function to display the put away details for the item.

F18

Picking Information. Use this function to display the picking details for the item.

F19

Packaging Information. Use this function to display the packaging details for the item.



To leave the enquiry, select **F3=Exit**.

Item/Warehouse Profile Enquiry Picking Screen (F18)



To display this screen, select **F18=Picking Information** from any of the Item/Warehouse Profile Enquiry screens.

This screen displays the picking details set up for an item, including location, maximum quantity, minimum quantity and replacement quantity.

WH210	Z1 - Demonstration Company	USER SP1	01/09/94
	Central Warehouse		12:00:00
Item/Warehouse Profile Enquiry			
Item.....	5006	Organic Hair Tonic 18x215ml	
Picking face details			
Picking location.....	BC3		
Maximum quantity to be picked from			
picking location.....		15.000	
Replenishment of picking face			
Minimum quantity at picking location.....		3.000	
Replacement quantity for picking location..		16.000	
Default resource code at			
picking location.....	TR		
F3=Exit	F12=Previous	F15=Fixed Locations	F16=Put away details
F17=Commitment details		F19=Packaging information	

For further details of individual fields, refer to the Item/Warehouse Profiles Maintenance section.

Functions:

F15

Fixed Locations. Use this function to display the fixed locations for the item.

F16

Put Away Details. Use this function to display the put away details for the item.

F17

Commitment Details. Use this function to display the commit details for the item.

F19

Packaging Information. Use this function to display the packaging details for the item.



To leave the enquiry, select **F3=Exit**.

Packaging Types Enquiry



34/WHM

This enquiry displays the characteristics set up for a packaging type. These characteristics include the location and packaging capacities.

Packaging Types Enquiry Details Screen

- ➔ Select Packaging Types, select a packaging type on the Packaging Types Selection screen and press **Enter**.

This screen displays the location size, packaging capacity, and packaging specifications for the selected packaging type.

For further details of individual fields, refer to the Packaging Types Maintenance section.

WH215	Z1 - Demonstration Company	USER SP1	01/09/94 12:00:00
Packaging Code Specification Enquiry			
Packaging code..... PAL Pallet			
Unit of measure for check against			
Location size.....	Weight.....	Length.....	Volume.....
Packaging capacity...	Weight.....	Volume.....	
Packaging specification and sizes			
	Tare Weight.....	Length.....	Height.....
		Height.....	Depth.....
Processing by label number..... 0 (1=Yes; 0=No)			
F3=Exit F12=Previous			

- ➔ Select **F3=Exit** to leave the enquiry.

Location Types Enquiry



35/WHM

This enquiry displays the location type characteristics and the relationships between the location type and the packaging types.

Location Type Enquiry Selection Screen



Select Location Types (Enquiries).

Use this screen to select the location type to display.

WH220	Z1 - Demonstration Company Central Warehouse	USER SP1	25/10/94 11:06:14
Location Type Enquiry			
Location type...?.. <u>RA</u>			
F3=Exit F4=Prompt			

Fields:

Location Type

Select the location type.



Press **Enter** to display the Location Type Enquiry Details screen.

Location Type Enquiry Details Screen



To display this screen, on the Location Type Enquiry Selection screen, enter a location type and press **Enter**.

This screen displays a list of package types allowed for this location type, with the maximum number of packs you can store at one time and the resource used to move the pack.

WH220	Z1 - Demonstration Company Central Warehouse	USER SP1	01/09/94 12:00:00
Location Type Enquiry			
Location type..... RA Standard Racking			
Maximum storage constraints		Length..	
	Volume..	Height..	
	Weight..	Depth...	
Cost of storage.....			
Allowed warehouse packing			
Line	W/house pack	Description	Packs/location Resource
0001	BOX	Box	16 WORK
0002	CSE	Case	4 TR
0003	PAL	Pallet	1 FLT
F3=Exit F12=Previous			

For further details of individual fields, refer to the Location Types Maintenance section.



Select **F3=Exit** to leave the enquiry.