

-
-
-
-
-

Chapter 2

Production Scheduling



Production Scheduling Overview

Master production scheduling comprises the following sequence of activities:

- Run MPS.
- Review MPS.
- Review capacity.
- Confirm suggested orders.

Run MPS

Use the Run Production Scheduling option to examine all current supplies and demands against MPS items.

This option generates suggestions for actions that need to be carried out in order to satisfy the plan.

Review MPS

Use the Review Production Schedule option to examine the results from the MPS run and determine whether the correct orders are in place to meet the plan.

Optionally, action any suggestions related to adding, changing, or cancelling orders.

Review Capacity

Use the Capacity Review option to examine the results from the MPS run and determine whether the level of resource necessary to meet the plan is available.

Confirm Suggested Orders

You can confirm suggested orders in two ways:

- Individual orders. Use the Suggested Order Maintenance window under the Review Production Schedule option.
- En masse. Use the Confirm Suggested Orders option.

Run MPS



Warning: MPS and MRP are widely-used manufacturing control terms which are used in many different environments.

These terms in Style Production differ from many other uses of the terms in the following way. In Style Production, all manufactured items should be designated MPS items; and all purchased items should be designated MRP items.

Style does not prevent you from contravening this rule. If you do break the rule, the effect is that the production load imposed by wrongly coded items is not reflected in the Capacity Review and the recommendations for actions on wrongly coded purchased items are generated during the MPS run rather than the MRP run.

MPS is a process whose main functions are common to MRP. In summary, MPS:

- Takes the top-level demand of sales orders and forecasts against finished products.
- Compares the demand against the available supply and generates additional suggested demand where appropriate.
- Explodes the supplies into lower level demands.
- Compares the demands against supplies for lower level items.
- And continues down the structures in a similar manner.

At the end of the run, you can review and action the suggestions that have been made.

Run MPS in one of the following ways:

- As a single run which carries out all of the common processes without interruption.
- As a run which is interrupted after the consumption of forecasts. At this point, you can review and amend the net effects of the latest forecasts against the latest firm demand. After this review, you can restart the job which then proceeds to completion.

Review MPS

The system enables you to save the original and amended version(s) of the master production schedule; and assigns a user-defined revision level code to each version in order to identify it. The original version has a revision level of blank.

A range of selection parameters allow you to select which items to review by entering one or more of the following:

- Planning model & revision level.
- Style.
- Planner.

Entry of a planning model and revision level is mandatory (although a blank revision level indicates the generated level); following which the entry of a style and/or planner code is optional. Entry or absence of an entry has the following effect on the presentation of data within the review:

- If no style or planner code is entered, the system will display the first item in the planning model, and display subsequent items in item code sequence.
- If you enter a style, (no planner), the system will display the selected style and then subsequent items in item code sequence.
- If there is no data for the style entered, the system will display an item with the nearest item code.
- If you enter a planner, (no style), the system will display the first style associated with the planner, and subsequent styles in item code sequence.
- If there is no data for the planner entered, the system will display an item for the nearest planner code.


On selection, the system displays all supply and demand details associated with each item within the review; together with their corresponding recommendations and the time-projected inventory balances.



Note: If there is no detail available, then the Summary screen will be presented.

For purchase items, the system will not display the option to amend suggested orders.


Production order suggestions which offend the maximum order quantity defined for an item are highlighted by being displayed in reverse video.



This figure provides a route map to the various screens and windows available within MPS Review. The boxes indicate the relevant function. Fn indicates a numbered function key available on the calling screen. Enter indicates that the **Enter** key needs to be pressed. N on a line indicates the Option number which may be entered against a displayed line.

Review Capacity

From the reviews, suggested production orders can be maintained and can be converted to 'Confirmed' orders. Changes to capacity loads are calculated interactively, and immediately update the master production schedule; with the changed schedule being saved as a new revision level.



This figure provides a route map to the various screens and windows available within Capacity Review. The boxes indicate the relevant function. Fn indicates a numbered function key available on the calling screen. Enter indicates that the **Enter** key needs to be pressed. N on a line indicates the Option number which may be entered against a displayed line.

Confirm Suggested Orders

When the master production schedule has been reviewed to an extent that it will be used for actual production, there are two possible courses of action:

- Confirm all or selected suggested orders; individual orders may have been confirmed by the review procedures.
- Take no further action and run MRP using the MPS suggested orders as a base. To do this, set the Include Suggested MPS field on the MRP Run Selection Parameters screen to 1 (yes).



Note: These options are only available for the 'live' planning models

If the former option is required, then the following procedure should be adopted to confirm selected or all suggested orders. Once confirmed, the order will be taken into account by any future MPS runs.

Maintain Model Stockrooms



1/P2M

Use this option to create and subsequently maintain MPS/MRP planning models in terms of the stockrooms to be considered.

The review process takes the demand and supplies within the stockrooms you select as a basis for its planning.

Next, you should use the Maintain Reporting Profile option to set up a reporting profile for the planning model.



Tip: A control model should include all active stockrooms; and exclude any obsolete and seconds/irregulars stockrooms. Ensure all demand and supply for the whole company is included.



Note: This option also appears under Style Material Planning.

MPS Stockroom Model Maintenance

Screen 1



To display this screen, select Maintain Model Stockrooms from the menu.

Use this screen to enter a planning model.

Fields:

Model

Enter a maximum 2 alphanumeric character code to create or maintain.

If you are creating a new model, select **F8=Add New Model** either immediately after specifying a code here, or at the OR All Stockrooms prompt.

Based On Model

If creating a model, and details are to be based on an existing model, enter the code of the existing model here. The existing model details will be copied to the new code, and can be maintained here. Leave blank to create a model from scratch, or maintain an existing model.

Or All Stockrooms

This prompt is only effective when creating a new model. If maintaining a model it is necessary to specify each stockroom. To specify stockrooms manually, accept the default. To include all stockrooms, enter 1 (all stockroom codes are retrieved and displayed automatically).

Functions:

F8

Add New Model. Create a new planning model.



To display MPS Stockroom Model Maintenance screen 2, press **Enter**.

Additional Parameters. For MPS models only, further define the planning model by opening the Additional Parameters window.

Additional Parameters Window (F18)



To open this window, select **F18=Additional Parameters** on MPS Stockroom Model Maintenance screen 2.

Use this window to further define the planning model.

```

MP015          SH - Steves Manufacturing Company  USER GBJBASAW  19/09/96
                                           14:26:00

MPS Stockroom Model Maintenance

Model.....?.. M1      Based On Model.?..  OR  All Stockrooms.. @ (1=Yes)
Model Description.. Single Plant/Multi-line
..... Stockrooms To Be Included .....
C1      C2      C3      -      -      -      -
-      -      -      -      -      -      -
-      -      -      -      -      -      -

Additional Parameters
Model Type.....?.. 1 Multi-Plant
Live Plant.....  (1=Yes)
Primary Stockroom.?..
Business Unit Code?..
Site Code.....?..

F4=Prompt  F12=Previous  F15=Item/Plant Primary Stockroom Maint.

-      -      -      -      -      -      -
F3=Exit    F4=Prompt    F8=Update/Add  F11=Delete  F12=Previous
F18=Additional Parameters
13-34      S2      MW      KS      IM      II  KENB20A  PET166S2
  
```

Fields:

Model Type

Three different model types can be defined. Enter one of the following:

0 or Blank - Centralised. Standard, non multi-plant model.

1 - Multi-plant. Control model used to view the whole organisation.

2 - Plant. Single plant or line. You should also enter a primary stockroom for the model in the Primary Stockroom field on this screen.

Codes are defined on the parameter file, against type MTYP.

Live Plant

This flag is used to indicate whether or not suggestions made against this model can be confirmed.

If you entered 2 in the Model Type field on this screen, enter one of the following:

0 - No. Do not confirm suggestions made against this model.

1 - Yes. This is a live plant. Therefore, confirm suggestions made against this model.

Primary Stockroom

If you entered 2 in the Model Type field on this screen, enter a default stockroom. A valid style/stockroom relationship must exist.

This stockroom identifies which overrides are used in a multi-plant run.



Tip: To change the primary stockroom for specific styles, select **F15=Item/Plant Primary Stockroom Maint.**

Business Unit Code

This is an optional entry.

Codes are defined on the parameter file, against type BUCS.

Site Code

This is an optional entry.

Codes are defined on the parameter file, against type STES.

Functions:

F15

Item/plant primary stockroom maint. Select this function if you entered 2 (plant) in the Model Type field on this screen.

This function displays the Style/Plant Primary Stockroom Maintenance screen, from which you can select stockrooms for individual styles.

Style/Plant Primary Stockroom Maintenance Screen (F15)



To display this screen, select **F15=Item/plant primary stockroom maint.** from the Additional Parameters window

Use this screen to define stockroom exceptions for specific styles.

To access this screen, set the Model Type to 2 (plant) on the Additional Parameters window.

MP014	SH - Steves Manufacturing Company	USER GBJBASAW	19/09/96
Style/Plant Primary Stockroom Maintenance			15:15:11
Plant.....: M1 Single Plant/Multi-line			
0 Style ?	Primary Stockroom ?		
_____	_____		
_____	_____		
_____	_____		
_____	_____		
_____	_____		
_____	_____		
_____	_____		
_____	_____		
_____	_____		
4=Delete			
F3=Exit F8=Update/Add F12=Previous			
09-05	SA	MW	KS IM II KENB20A PET166S2

Fields:

O

Option. Enter 4 to remove the style/stockroom relationship.

Style

Enter a style.

Primary Stockroom

Enter the primary stockroom for this style in this planning model.

Functions:

F8

Update/Add. Save your changes.

Maintain Reporting Profile



2/P2M

For every model that you define, you can specify the way the planning functions summarise supply and demand information for enquiries and reports.

For example, details of the first week of the schedule may require reporting on a daily basis, the following three weeks consolidated into weekly summaries, and the rest of the review shown in monthly terms. The function is flexible in this, and you can define up to 46 time 'buckets' (entered as periods of consecutive days) of different length.

This description also applies to the following options:

- The Maintain Reporting Profile option in Style Material Planning.
- The Maintain Model Stockrooms option under Forecasting in Style Production Definition Management.



Note: The planning process balancing of supply and demand information is 'bucketless', that is, the supply and demand situation is analysed and reconciled on a daily basis.

MPS and MRP reviews will stop at the end date defined on the Run Parameters screen, irrespective of the number and length of summary reporting buckets defined here.

Prerequisites

Before you use this option, you must have set up stockrooms for the planning model already. For more information, refer to the Maintain Model Stockrooms option.

Master Production Schedule Maintain MPS Reporting Profile Screen



To display this screen, select the Maintain Reporting Profile option.

Use this screen to enter a planning model.

Fields:

Model

Enter the relevant planning model.



To display the Maintain MPS Reporting Profile screen, press **Enter**.

Maintain MPS Reporting Profile



To display this screen, press **Enter** on the Master Production Schedule Maintain MPS Reporting Profile screen.

Use this screen to nominate a calendar and set up the reporting profile. Initially, the screen is a read-only screen.



Warning: Before you can enter data on this screen, you must select F18=Update Details. This takes you into Update mode.

MP001		ZS - Style Demonstration Co.				USER GBJBAMS		15/04/96			
								9:52:29			
Maintain MPS Reporting Profile (in days)											
Model ZS The Live Planning Model					Calendar Code.. 01						
1	2	3	4	5	6	7	8	9	10	11	12
28	28	28	28	28	28	28	28	28			
13	14	15	16	17	18	19	20	21	22	23	24
25	26	27	28	29	30	31	32	33	34	35	36
37	38	39	40	41	42	43	44	45	46		
F3=Exit F12=Previous F18=Update Details											
01-02		SF		MW		KS		IM		II KENB20A PET166S2	

Fields:

Calendar Code

Enter the calendar that you wish to use for planning with the current model. Planning routines use this calendar to validate suggested due dates for production and purchase orders. Enter a calendar defined via the Calendar Maintenance option.

To use the Company Profile default calendar, leave this field blank..

You must ensure that production calendars are set up for the years for which you wish to establish a plan, including all forecasting data.

That is, if you are using planning model 01, production calendar 02, and want to forecast to 1999, then a production calendar 02, 1999 calendar must exist.

It is the week numbers associated with this calendar that are prompted for when forecasting periods; however, it is the Company Profile, Calendar Details screen, Number of Periods Per year field which determines the number of periods within any year.

(Untitled)

Days Per Period. Enter the length, in days, of the consolidation periods for supply and demand on enquiries and reports. The periods you enter must be continuous, and commence at the current date of the planning runs. The maximum period length is 999 days.

It is not necessary to make an entry in all fields. Entries should relate to the time buckets required for the results of the planning process.

To update any of these fields, select **F18=Update Details**.

Functions:

F18

Update Details / Review. Displays this window in UPDATE mode, allowing you to make changes to the days in each period.

Maintain Supply Sourcing Rules



3/P2M

Use this option to enable multi-sourcing to take place during an MPS run. If any styles are not defined, then multi-sourcing is not actioned.

Sourcing rules may be defined at both the control (multi-plant) and the plant model.

If at the control (multi-plant) level, then either a default rule or separate rules per each plant model can be defined. This allows for different sourcing methods dependent upon where the demand, sales orders and forecasts, comes from; that is, control model or plant specific model.



Tip: This must be maintained for all styles otherwise any suggestions generated within the MPS run will remain at a status of MP (unsourced multi-plant requirement).



Tip: In a multi-plant MPS run, forecast is for the control model only.

Sourcing Rule Maintenance Screen 1



To display this screen, select Maintain Supply Sourcing Rules from the menu.

DB092	SH - Style Demonstration Co.	USER GBJBASAW	26/09/96 16:11:46
Sourcing Rule Maintenance			
Control Model.....: M1 Single Plant/Multi-line			
Style.....?: F100 CS0			
Demand Model/Plant...: _			
Rule Number.....?: _			
Effective From..... 0/00/00 To 99/99/99			
F3=Exit F4=Prompt F8=Update F12=Previous F16=Review Rules			
07-25 SF MK KS IM II KENB20A PET166S2			

Fields:

Control Model/Plant

Enter a control or plant model.

Style

Enter a style code.

Demand Model/Plant

Only displayed if a control model has been entered.

If left blank it enables default rules to be defined for all plants attached to the control model; otherwise different sourcing rules for each plant can be defined.

Rule Number

This must be set to 1 (critical resource).

Effective Date Range

For each style, the rule number is linked to an effectivity date range.

Functions:

F8

Update. Update a sourcing rule

F16

Review Rules. Enables display and optional selection of existing sourcing rules

Sourcing Rule Maintenance Screen 2 (F8)



To display this screen, select **F8=Update** from Sourcing Rules Maintenance screen 1.

Use this screen to maintain the sourcing rules for a particular style.

Either a preferred route or a sequence of routes can be recorded. These routes are linked to effectivity dates.

```

DB092                SH - Style Demonstration Co.        USER GBJBASAW  19/09/96
                                                           16:54:14

Sourcing Rule Maintenance      Rule...: 1 - Critical Resource
                               Effective From: 0/00/00 To: 99/99/99
Control Model.....: M1  Single Plant/Multi-line
Style.....: MP/A1          assembly
Demand Model/Plant....:

Preferred Route.....?: █

Seq Route ?              Capacity Policy  Inter Plant Lead Time  Effective From To
-----
 1 B                     1              .00          1/10/96 31/10/96
 2 A                     1              20.00         1/01/96 31/12/96
 3 C                     -              .00          1/01/96 31/12/96

Blank out sequence number to delete a line
F3=Exit  F4=Prompt  F8=Update  F10=Add  F12=Previous

10-29  S2  MW  KS  IM  II  KENB20A  PET166S2
  
```

Fields:

Preferred Route

The preferred route may optionally be recorded.

Seq

Sequence. This field works in conjunction with the Route and Preferred Route fields.

The alternative to a preferred route is the listing in the required sequence of numerous routes, each of which may be linked with effectivity dates.

If there is no spare capacity on the route defined to the first sequence then routes are interrogated in sequence order. If there is still not enough capacity, the route entered in the Preferred Route field will be used, if it doesn't exist, then the planning route on the item definition will be used.

Route

Enter the route applicable to the sequence and effectivity date range.

Capacity Policy

This field is used to define whether or not a suggested order should be split over two routes if the available capacity of the critical resources on the first route are insufficient.

Enter one of the following:

0 - Whole order only.

1 - Can be split.

Inter Plant Lead Time

This field is for memorandum purposes only.

Effective Date Range

Enter the date range for which the definition is effective.

Functions:

F10

Add. Create new sequences.

Run Production Scheduling



11/P2M

This option produces a high level production plan for manufactured items.

The system then matches the projected demand for designated products to the ability to supply based on user-defined planning models and planning horizons.



Tip: Ensure that you have defined your calendars to cover the duration of the review.



Note: As part of standard processing, the system generates an MPS Reporting Profile report, detailing the run dates and the reporting periods associated with the planning model

Master Production Schedule Run Selection Screen



To display this screen, select Run Production Scheduling from the menu.

Use this screen to enter a planning model.

Fields:

Model

Enter the planning model to run. To confirm any planning suggestions, enter the planning model defined on Maintain Company Profile Screen 3 in Style Production Definition Management.

The stockrooms defined to the selected model determine the scope of the master production schedule produced; and the associated reporting profile defines how information will be presented ('bucketed') on reports and enquiries. Only items with defined item/stockroom relationships within the selected model are extracted for planning.



To display the MPS Run Options screen, press **Enter**.

MPS Run Options Screen



To display this screen, press **Enter** on the Master Production Schedule Run Selection Screen.

This screen displays the date parameters set the last time an MPS was generated for the model, together with a selection of run parameters.

Critical Fields

The following fields on this screen are the most critical:

- Lowest Level To Review.
- Current Date.



Warning. In multi-plant planning, when you run MPS for the first time on the control model, make sure that the Suppress Low Level Code Generation field is set to 0. This setting ensures that MPS looks at all routes to determine the low level codes.

MP002	SH - Style Demonstration Co.	USER GBJBASAW	20/09/96 10:45:45
MPS Run Options	MPS Model : M1 Single Plant/Multi-line	Production Calendar : 01	
Details shown are from the last run selection.			
Start Date	140796	Overdue Days	
Current Date	150796		
Time Fence Date	150796	Time Fence Days	
End Date	311297		
Enter: Lowest Level To Review.....	<u>10</u>		
Current Date.....	<u>150796</u>		
Overdue Days.....	—		
Time Fence Days.....	—		
Safety Horizon Days.....	—		
End Date.....	<u>311297</u>		
Suppress low level code generation.. (1=Yes)			
*** Changes made in structure currently exist ***			
F3=Exit	F5=Refresh	F12=Previous	F16=Display New Run Dates
F17=Start Run	F18=Additional Parameters	F22=Print Details	
13-42	<u>SC</u>	<u>ML</u>	KS IM II KENB20A PET166S2

Fields:

Production Calendar

System maintained field; displays the calendar associated with the reporting profile for the selected planning model.

Run Dates

Initially the system displays date details pertaining to the last time the run was initiated. These details can be updated to the dates pertinent to the next run, based on entered parameters, by pressing **F16=Display New Run Dates**. The

following field descriptions refer to fields which can be entered directly against each run; or are calculated as a consequence of the parameters entered.

Start Date

System maintained field; displays the first date which is considered for the run. Orders prior to this date are ignored. This is calculated as:

- Current date less overdue days.

Lowest Level To Review

Enter the lowest level of item within the product structures to include in the planning process. To only schedule parent items, leave this field blank or enter zero (0).

However, lower level items such as spares, or items which are on the critical path, may be defined as MPS items. Such items may never be reviewed by MPS unless a subsequent run or alternative model specifies a lower level.

Current Date

This is the live date for the plan. The start date and frozen period (Time Fence Days) are calculated from this date.

Overdue Days

Indicates the number of days of overdue supply and demand you wish to consider.

Accumulated supply and demand in this period is displayed in the OVERDUE column on the MPS Summary Review and Capacity Review screens.

Time Fence Days

The period between the current date and the time fence date is regarded as fixed; that is, a frozen period (schedule) in which no recommendations can be made. This may be:

- Entered directly.
- Production lead time for each style.

The second option is actioned by setting the Use Item Time Fence parameter to 1 (yes)

Safety Horizon Days

This ensures that the end date is extended so that all generated demand is included in the lower level analysis.

End Date

Enter the last date that the MPS run should consider. To extend the end date to include a safety lead time, enter a value in the Safety Horizon Days field.

Alternatively, to incorporate a cumulative lead time for each style plus safety lead time, set the Use Item End Date field on the Additional Parameters window to 1.



Note: For non-production items, the purchasing lead time is used for production and cumulative lead times

Suppress Low Level Code Generation

This field has a default setting dependent on whether or not the system has detected any changes to planning routes. If it has, the field will default to 0 and display the message 'changes made in structure currently exist' If it has not, the field will display 1.

The routine may also be suppressed if the independent Generate Low Level Codes routine is destined to be run prior to running MPS.



Warning: The decision to suppress must only be taken if you are sure that the planning process will not be compromised by the lack of up-to-date data regarding planning routes.

Functions:

F16

Display New Run Dates. Recalculates and displays run dates to be associated with the parameters entered; rather than the dates from the previous run.

F17

Start Run. Start the MPS run; this will be submitted as a batch job. The system automatically produces a report detailing the parameters set for the run.

F18

Additional Parameters. Display additional parameters for review.

F22

Print Details. Print the run parameters without initiating a run.

Additional Parameters Window (F18)



To display this window, select **F18=Additional Parameters** from the MPS Run Options screen.

Use this screen to enter additional, static parameters.

```
MP002          SH - Style Demonstration Co.          USER GBJBASAW    20/09/96
                                                    10:59:18
MPS Run Options      MPS Model      : M5 M5 - control model
                    Production Calendar : 01

Additional Parameters
D      are from the last run selection.
  Planning Basis..... 1      0 = Centralised
                                   1 = Multi-Plant
                                   2 = Multi-Sourcing

  Review Demand..... -      (1=Yes)
  Use Item Time Fence..... 0      (1=Yes)
E      Use Item End Date..... 0      (1=Yes)
  Include Capacity..... 1      (1=Yes)
  Capacity Route..... -
  OR
  Planning Route..... 0      (1=Yes)
  Critical Resource Review..... 1      (1=Yes)

F      F12=Previous
F17=Start Run      F18=Additional Parameters      F22=Print Details
07-40      SA      MK      KS      IM      II      KENB20A      PET166S2
```

Fields:

Planning Basis

Indicates the planning basis for the run. Enter one of the following:

- 0 - Centralised.
- 1 - Multi-plant.
- 2 - Multi-sourcing

Review Demand

This enables a review of the calculated demand before it is translated to the production schedule.

Enter one of the following:

- 0 or blank - Do not interrupt the MPS run, run to completion.
- 1 - Interrupt the run to allow review and maintenance of the calculated demand at item level. Following review, you should use the Resume Production Scheduling option to resume the process.

Use Item Time Fence

The Production Lead Time is held on the Production Details screen under the Style/Material Details option. The Production Lead Time is the 'this level' lead time in days required to produce an item from its immediate components.

If no time has been entered or calculated, the run uses the global, default Time Fence Days setting.

Enter one of the following:

0 or blank - Use the global date.

1 - Use this date.

Use Item End Date

The cumulative lead time is held on the Production Details screen under the Style/Material Details option.

The cumulative lead time is the total lead time in days required to produce an item based on a full explosion of its planning route, including any low level production items included on the route; together with the purchasing lead time of materials and bought out components.

If no time has been entered or calculated, the run will use the global, default end date.

0 - Use the global date (default).

1 - Use this date.

Include Capacity

Enter one of the following:

0 - Exclude capacity planning.

1 - Include capacity planning (default). Since you can base capacity planning on specifically defined capacity routes or standard planning routes, you should indicate which you intend to use in the Planning Route field.

Capacity Route

If you have set the Include Capacity field to 1 and the Planning Route field to 0, enter a capacity route code.

Planning Route

If you enter 1 in the Include Capacity field, use this field to indicate whether you intend to use the planning route or a capacity route for capacity planning.

Enter one of the following:

0 - Base capacity planning on the capacity route entered in the Capacity route field on this window.

1 - Base capacity planning on the planning route defined for each style under the Style Route/Bill Of Material option.

Critical Resource Review

This indicator is used to save the end result of all critical resources (that is, capacity available and capacity unused) for each reporting profile period. This could be used to determine why the system suggested manufacturing particular products on particular routes.

Review Demand



12/P2M

Use this option to examine adjusted, calculated demand before it is translated into a master production schedule. It is calculated for production items and will not consider dependent demand.

Calculated demand is determined by the demand policy in for the item, and the method of consumption of forecast employed; that is, discrete or cumulative comparisons. The sales, forecast and calculated net demand for each style or variant forecast period can be displayed, and may be maintained.



Note: The updated quantity is recorded and the demand flagged against a status code of MA (manual adjustment); and associated with the operator/user making the change.

To enable this function, the Run Parameters, Review Demand field must have been set to 1 (yes) when running the Run Production Scheduling option. Otherwise, this step in the process is bypassed.

MPS Demand Review Screen 1



To display this screen, select Review Demand on the menu.

Use this screen to enter a planning model and a style variant.

Fields:

Enter Model

Enter the planning model to review.

Item

Enter a style variant to review.



To display MPS Demand Review screen 2, press **Enter**.

MPS Demand Review Screen 2



To display this screen, press **Enter** from MPS Demand Review screen 1.

MP150	ZS - Style Demonstration Co.	USER GJBAMS	15/04/96
MPS Demand Review	Demand Policy	Gtr of F/C or Sales	13:37:05
Model	ZS	The Live Planning Model	
Item	ELF_BOOTS	Elfin Boots	
Period			
Start	End	Forecast	Sales
21/03/96		26.000	
22/03/96		33.000	25.00
23/03/96		33.000	
24/03/96		65.000	
25/03/96		13.000	
26/03/96		20.000	
27/03/96		26.000	
28/03/96		26.000	
29/03/96		33.000	
30/03/96		33.000	
			Net Demand
			26.000
			33.000
			33.000
			65.000
			13.000
			20.000
			26.000
			26.000
			33.000
			33.000
			+
F3=Exit F8=Update F12=Previous			
10-54	SA	MW	KS IM II KENB20A PET166S2

Fields:

Demand Policy

This field displays, for your information only, the demand policy for the chosen style variant. If the policy considers dependent demand, it will not be calculated.

Start/End

These 2 fields display, for your information only, the start and end dates of the demand comparison period. These are determined by the forecast start and end dates. If no forecasts exist, the sales orders are passed unchanged to MPS.

Forecast

This field displays, for your information only, the forecast quantity for the period.

Sales

This field displays, for your information only, the sales order quantity for the period.

Net Demand

The adjusted consumed demand for the period. This value depends on the forecast consumption method employed. This quantity may be adjusted.

Resume Production Scheduling



13/P2M



To display the MPS Run Options screen, select Resume Production Scheduling from the menu.

If the Review Demand option on the Run Parameters has been taken; then this facility must be used to restart the process; irrespective of whether or not any adjustments have been made to the demand quantities via the Review Demand function.

Although this option is not usually applicable if no demand review was requested, it is possible to re-invoke a previously processed MPS plan. You can then review demand, run the full MPS, re-adjust the demand using the Review Demand function; then run MPS against the revised demand.



*Note: On entry following a partial MPS run, the system displays the message 'Previous run was not full MPS, **F8** to continue'.*

It is possible to start a new MPS run without resuming the previous run.

```

MP130          ZS - Style Demonstration Co.          USER GBJBAMS    15/04/96
                                                    13:37:32

MPS Run Options

                Production Model      ZS The Live Planning Model
                Production Calendar

Details shown are from initiating run selection.

Lowest level to Review      1

Run Dates      Start Date      27/12/95      Overdue Days      5
                Current Date     1/01/96
                Time Fence Date  11/01/96      Time Fence Days    10
                End Date         1/09/96      Safety Lead Time   5

                Use Item End Date  1
                Use Item Time Fence 0

-----
F3=Exit  F12=Previous  F17=Continue Run

01-02    SF      MW      KS      IM      II  KENB20A  PET166S2
  
```

Fields:

Model

Enter the planning model to resume processing. The system displays the parameters associated with the run.

Functions:

F17

Continue Run.

Confirm Suggested Orders



14/P2M

Use this option to confirm the orders suggested by an MPS run.



Note: If you have set the Allocation Of Materials At field to 1 (ie allocate at order confirmation) on Maintain Company Profile screen 4, then material for the production orders is allocated automatically upon confirmation.

Confirm MPS Suggested Orders Screen



To display this screen, select Confirm Suggested Orders on the menu.

Use this screen to enter a planning model.

Fields:

Model

Enter a live planning model from which you wish to confirm suggested orders.



To display the MPS Confirmation Of Suggested Orders Screen, press **Enter**.

MPS Confirmation Of Suggested Orders Screen



To display this screen, press **Enter** from the Confirm MPS Suggested Orders screen.

Use this screen to choose which orders you wish to confirm.

MP052	ZS - Style Demonstration Co.	USER GBJBAMS	15/04/96
			15:24:34
MPS - Confirmation of Suggested Orders			
Model... ZS The Live Planning Model			
From Start Date.. <u>27/12/95</u>		To Start Date.. <u>1/09/96</u>	
From Planner..?.. <u> </u>		To Planner..?.. <u> </u>	
F3=Exit F4=Prompt			
09-37	SP	MW	KS IM II KENB20A PET166S2

Fields:

From/To Start Date

Enter a range of dates to only include production orders with a start date within the selected range; or leave blank to include all orders. Any dates entered must be within the date range of the last MPS run.

From/To Plant

If the last run of the MPS model selected was multi-plant, then a plant range may be specified.

From/To Planner

Enter a range of planners to select only orders associated with items defined with the entered planner codes, or leave blank to include all planners.



To display the Order Creation screen, press **Enter**.

Order Creation Screen



To display this screen, press **Enter** from the
MPS Confirmation Of Suggested Orders screen.

Use this screen to control which suggested orders to confirm, and then to submit a batch job to carry out the confirmation.

This screen displays all suggested production orders which comply with the selection parameters entered. The orders have an associated flag which defaults to 1 (create order). You may omit orders from the confirmation process by changing this flag to 0 (do not create order).

If a plant range has been entered then only production orders pertinent to those plants will be displayed. If plants are selected, the plant code will be displayed for reference.

Confirmed orders for the suggested due dates and quantities are generated. Style uses the designated planning route entered on the item definition, Production Details screen to generate operation and material requirement details.

MP052		SH - Style Demonstration Co.		USER GBJBASAW		20/09/96 13:00:13	
Order Creation		Model... SH Steve Model					
Start Date Range...		1/06/96 To 30/09/96 MPS Start. 1/06/96 MPS End 30/09/96					
0	Start	Quantity	Item	Description	Route		
1	2/09/96	200	FCSTC-FCC	Col/---/Fcast col			
1	2/09/96	90	FCSTC-FS	col/---/Fcast St			
1	2/09/96	102	FCSTCSFS	COL/SIZE/FCST ST			
1	1/07/96	699	FCSTSCCOL	col/siz/fcast col			
1	29/07/96	48	F100 CS0	FCAST/C/S STY			
1	29/07/96	5	F100 CS2	FCAST/C/S SKU	1		
1	1/07/96	120	MP006	MP - STYLE 006	1		
1	1/07/96	60	MP010	MP - STYLE 010	1		
1	13/06/96	100	ROGER/C/S	rogers test			
1	27/06/96	100	ROGER/C/S				
1	11/07/96	100	ROGER/C/S				
1	25/07/96	100	ROGER/C/S				
1=Create Order Blank/0=Do Not Create Order F3=Exit F8=Update and Submit Job F12=Previous							
06-02		SE	MK	KS	IM	II	KENB20A PET166S2

Fields:

0

Option. Enter one of the following:

0 - Do not create order. Prevent the suggested production order from being processed.

1 - Create order. Select an order for processing (default).

Functions:

F8

Update And Submit Job. Confirm all selected production orders.

Review Production Schedule



15/P2M

Use this option to review the results of the MPS run and, for the 'live' planning model, to create and maintain actual supply.

Sequence

Data can be displayed in either of two sequences:

- MPS recommended due date. These are dates incorporating any suggested changes made by MPS
- Current due date. These are the dates which currently exist and which the MPS run may have recommended for change.

The **F21** function enables you to toggle between the two sequences.



Note: All status and action codes are described in detail in a previous section

Stock Forecasts

Stock forecasts are not subtracted as demand but there may be a corresponding supply order which is scheduled to provision the stock level defined in the forecast. This stock is additional to safety stock, so the quantity available will reflect stock forecast demand.

Stock forecasts should be viewed as an additional hedging technique, with the flexibility to amend the desired stock level by week. Additional stock forecasts will cause an additional level of stock to be planned.

Production Schedule Review Screen



To display this screen, select Review Production Schedule from the menu.

From this screen, select a planning model to review.

```
MP350          RK - Style Production Company      USER GBJBARK      15/10/96
                                                    14:51:22

Production Schedule Review

Base Model.... .....?. CM
Revision Level .....?. ____

F3=Exit  F4=Prompt

06-34  SP  MK  KS  IM  II  KENB20A  PET166S3
```

Fields:

Base Model

Enter the planning model you wish to review.

Revision Level

To review a revised version of the master production schedule, enter the appropriate revision level.

To save all subsequent changes to a new revision, enter a new revision level.

To review an unrevised master production schedule, leave this field blank. It is worth noting that, since it is possible to alter the original schedule without adding a revision level, this may not be the original master production schedule.



Warning: If you do not enter a new revision level, any changes that you make are implemented in the existing master production schedule.

Description

Enter a description for a new revision level. This field displays only if you enter a new revision level in the Revision Level field.



To display the Enquiry screen, press **Enter**.

Enquiry Screen



To display this screen, press **Enter** on the Production Schedule Review screen.

Use this screen to select a specific style, plant or planner.

MP350	RK - Style Production Company	USER GBJBARK	15/10/96 14:55:48
Enquiry			
Base Model....		CM Central Model	
Revision Level		02 Central Model	
Select Style		?	
Plant Model.....		?	
OR Planner.....		?	
F3=Exit F4=Prompt F12=Previous			
08-37	SP	MK	KS IM II KENB20A PET166S3

Fields:

Select Style

Optionally enter a style item code.

Plant Model

This field is only prompted if the Planning Basis flag on the MPS Run Parameters, Additional Parameters screen was set to 1 (multi-plant). Enter a plant model if required.

Or Planner

Optionally, enter a planner code.



Press **Enter** to display Review Detail screen 1.

Review Detail Screen 1



To display this screen, press **Enter** on the Enquiry screen.

This screen allows you to view all of the anticipated stock movements of an item in chronological sequence along with the resulting inventory level. From this screen it is possible to move to lower level screens where you can see greater detail or comply with suggested actions.



Warning: To retain your updates, select F8=Save.

MP350	RK - Style Production Company				USER GBJBARK	15/10/96
Review - Detail	Base Model....	Central Model	Start 17/06/96			
Style	874NC	Revision Level	Central Model	Plan Type 1		
		Col W-D Workwear				
Planning Basis:						
MPS	<----	Demand	----->	<-----	Supply	----->
0	Date	Order	Quantity	St	Order	Quantity
	1/07					13000 YW
	1/07					12000 MP
	1/07					72150 SW
-	19/08	100000	FC		100100	SW
-	23/08				99970	SW
-	26/08	100000	FC			
-	2/09	100000	FC		99970	SW
-	9/09	100000	FC		99905	SW
-	16/09	100000	FC		100035	SW
-	99/99			W000003	105	IW CA
-	99/99			W000004	105	IW CA
						Available
						13000
						25000
						97150
						97250
						197220
						97220
						97190
						97095
						97130
						97130
						97130
Bottom						
3=Maintain Suggestions S=Maintain Order 6=Peg Demand 7=Supply Detail						
F3=Exit F5=Refresh F8=Save F12=Previous F15=Capacity F23=More Options						
F16=Previous Style F17=Summary F18=Header F19=Next Style F24=More Keys						
10-02 SP MK KS IM II KENB20A PET166S3						

Fields:

Plan Type

Planning Type. System maintained field; displays the value of the Planning Type flag on the item definition. This is 1 (MPS) or 0 (MRP).

Plant

System maintained field; displays the plant code and description if a plant has been selected.

Planning Basis

System maintained field; displays centralised, multi-plant or multi-sourcing depending on the type of plan being enquired on.

O

Option. If a line does not have this option field, this indicates an accumulated demand/supply on the first item.

Enter one of the following:

3 - Maintain Suggestions. Use this option to do one or more of the following:

- Change the production route.
- Split the quantity onto two separate orders.
- Change the quantity.
- Change the due date.



Note: To make your changes permanent, select option 5 (Maintain Order) against the order to update the status to confirmed. Otherwise, further MPS runs will reschedule the demand.

5 - Maintain Order. Use this option to do any of the following:

- Amend details on an existing production order.
- Change a suggested order to planned or confirmed.
- Amend a suggested purchase order.



Note: The standalone Confirm Suggested Orders facility may be used to confirm multiple orders rather than selecting individually via this review screen.

6 - Peg Demand. Display the parent that generated a particular demand against a material requirement on a production style. The material requirement must be a material requirement on a production style and have a low level code of 1 or greater.

After viewing any number of levels of parent details, **F12** will return to a display of the originating item in a chain of pegging requests.



Note: This option is only available for material items.

7 - Supply Detail. Open the Select Colour window, from which you can review the variant breakdown of the style. No changes can be made to the quantities displayed. This option is available for:

- An existing production order.
- A suggested production order.
- An existing purchase order.
- A suggested purchase order.

8 - Display plant supply details.



Note: This option is only available when enquiring on a plant model within a control model.

9 - Display plant demand details.



Note: This option is only available when enquiring on a plant model within a control model.

Date

System maintained field; displays one of the following:

- For dependent demand, this is the required date of the item, and reflects a higher level MPS demand.
- For independent demand, this is the forecast due date, or sales order shipment date.
- For a supply, depending on the presentation sequence selected (F21), it is either:
 - MPS recommended due date.
 - Current date of the order.
- For supplies with no recommended date change the sequence remains the same.
- If the date is shown as 99/99 then this indicates a zero demand, with an existing supply.

St

Demand Status. The following status codes can be displayed:

Demand Status Codes	
CA	Cancelled
CD	Cumulative demand, if cumulative consumption of forecast
CW	Confirmed production order
FC	Sales forecast
FS	Stock forecast
FX	Forecast (excluded)
IW	Active production order
MA	[MPS] Manual adjustment
MX	[MPS] Manual adjustment (excluded)
PW	Planned production order
PX	Suggested purchase order (excluded)
RW	Released production order
SO	Sales order
SP	Suggested purchase order
SW	Suggested production order
SX	Sales order (excluded)
WX	Production order (excluded)
YF	STYLE sales forecast
YP	STYLE suggested purchase order
YS	STYLE stock forecast
YW	STYLE suggested production order

St

Supply Status. The following status codes can be displayed:

Supply Status Codes

CN	Cancelled
CO	Complete production order
CP	Confirmed purchase
CW	Confirmed production order
GI	Goods inwards
IS	In inspection
IW	Active production order
PW	Planned production order
RW	Released production order
SP	Suggested purchase order
SW	Suggested production order
YW	STYLE suggested production order
YP	STYLE suggested purchase order

Action

Action Code. The following action codes can be displayed:

Action Codes	
CA	Cancel order
CQ	Change quantity (mix)
EF	Check effectivity
EI	Reschedule 'in' and check effectivity
EICQ	Reschedule 'in' and change quantity and check effectivity
EO	Reschedule 'out' and check effectivity
EOCQ	Reschedule 'out' and change quantity and check effectivity
EQCQ	Change quantity and check effectivity
RI	Reschedule 'in'
RICQ	Reschedule 'in' and change quantity
RO	Reschedule 'out'
ROCQ	Reschedule 'out' and change quantity

Available

System maintained field; displays one of the following:

- MPS recommended due date sequence. This indicates the planned available stock, and reflects MPS supply recommendations to meet demand. The balance normally shows a quantity equivalent to safety stock, because MPS aims to protect the defined safety stock level of the item. Calculated as:
 - Physical stock (first detail line only) or quantity available on previous date less demand for that date less safety stock plus supplies recommended on that date
- Current date sequence. Indicates the current supply schedule in terms of quantities and due dates and the resultant availability against demand. It is calculated for each day that a demand or supply line is present and represents the style phased projected inventory level. Calculated as:

- Physical stock (first detail line only) or quantity available on previous day less demand for date less safety stock plus supplies currently due on date



Note: Dependent demand for a given date is always generated from higher level recommendations and represents the MPS suggested schedule, and does not change when the supply sequence is changed

Functions:

F8

Save. Saves as a new revision level if required.

F15

Capacity. Display Capacity Review Screen 1, giving you direct access to the Capacity Review option.

F16

Previous Style. Display previous style.

F17

Summary. Display a Summary screen.

F18

Header. Display a Header screen.

F19

Next Style. Display the next style.

F20

Next Planner. Display the next item for the next planner in sequence.

F21

Change Sequence. Toggle between displaying details in MPS recommended due date and current due date.

F22

Detail. Shows additional demand information for each supply and demand line:

- Supply Line. Shows the current due date of the order and the earliest and latest start date.
- Demand Line. Shows the parent item causing a particular generated demand.

For purchased orders, the receipt date may be the due date, promised date or expected date, whichever is the greatest.

F23

More Options. Toggle display of options.

F24

More Keys. Toggle display of functions.

Suggested Order Maintenance Window (Option 3)



To display this window, enter 3 against a suggested order in the Option field on Review Detail screen 1.

Use this window to make manual adjustments to a single suggested production order.



Note: Once you have made the adjustments, the status of the order remains at suggested. To confirm the order, select option 5 (Maintain Order) from Review Detail screen 1.

MP350	SH - Style Demonstration Co.	USER GJBASAW	20/09/96
Review - Detail	Base Model....	Single Plant/Multi-line	Start 14/07/96
Style	MP/A1	assembly	Plan Type 1
MPS	<--- Demand --->	<--- Supply --->	Planning Basis:
0	Date Order	Quantity St Order	Quantity St Action
10/09		318 SW	318-
3	26/09		8-
7/10			8-
4/11			8-

Suggested Order Maintenance			
Style	MP/A1	assembly	
Plant.....	M1	Single Plant/Multi-line	
Route ...?..	A	Current	Change or Split
Due Date....	26/09/96	0/00/00	0/00/00
Quantity....	438		
Filter...?..			

3=Maintain Su	F4=Prompt	F12=Previous	F20=Qty Breakdown
F3=Exit	F5=Refresh	F8=Save	F12=Previous
F15=Capacity	F23=More Options	F16=Previous Style	F17=Summary
F18=Header	F19=Next Style	F24=More Keys	
16-47	SA	MA	KS
		IM	II
		KENB20A	PET166S2

Fields:

Route

The system displays the default planning route for the style for a new suggestion; or the amended route if the supply has been manually updated. Any route entered must be a fully defined route.

Due Date

This is the due date suggested by the MPS run.

Quantity

Displays the current suggested quantity.

Planning Filter

This field displays the Planning Filter for the current style and route.



Note: This filter is only effective if MPS is re-run

following confirmation of the order.

Functions:

F20

Qty Breakdown. Updates the master production schedule with the entered details and displays the Select Colour window, from which you can override quantities across the variants.

Select Colour Window (Option 7, F20)

-  To display this window, enter 7 in the Option field against a production order or purchase order from Review Detail screen 1.
-  To display this window, select **F20=Qty Breakdown** from the Suggested Order Maintenance window.

From this window, select the colour for which you wish to view the variant quantities on the order.

```

MP350                      DS - DS GLAD RAGS                      USER GBJBASPD  27/05/98
                                                                10:40:26
Review - Detail  Base Model.... Planning Model 1                Start 20/05/98
Revision Level  Planning Model 1
Style    DS_79003  Trousers

MPS <---- Demand ----> <----- Supply ----->
0 Date Order  Quantity St Order  Quantity St Action          Available
3 5  Select Colour                                     200
7  Style: DS_79003                                     0
17 Trousers                                           0
31 Seq Sel Code Description      Quantity          s
001 - BLK Black                  20          g Model 1
002 - BRN Brown                  20          ge or Split
003 - NAV Navy                    20          6/98  0/00/00
                                     20          -
                                     om

3=Ma
F3=E
F16=

1=Select      Position to Sequence
F12=Previous  F13=Select All

s F20=Qty Breakdown
apacity
le F24=More Keys

MA b MW 13/014
  
```

Fields:

Sel

Select. If you accessed this window using option 7, enter 1 against a colour to open the Variant Quantities window, from which you can review the variant breakdown of the style.

If you accessed this window using **F20=Qty Breakdown**, enter 1 against a colour to open the Suggested W/O window, from which you can enter quantities for colour variants.

Functions:

F13

Select All. Opens the Variant Quantities window for each colour in turn.

Variant Quantities Window (Option 1)



To display this window, enter 1 against a colour on the Select Colour window, having already entered 7 in the Option field against a production order or purchase order from Review Detail screen 1.

Use this window to enter the quantities you require of each variant.

MP350		DS - DS GLAD RAGS		USER GBJBASPD		27/05/98	
Review - Detail		Base Model....		Planning Model 1		10:40:26	
		Revision Level		Planning Model 1		Start 20/05/98	
Style		DS_79003 Trousers					
Planning Basis:							
MPS <---- Demand ----->				<----- Supply ----->			
Variant Quantities		Ord qty: 200		Entered Qty: 20			
DS_79003	Black	Fit	More:				
Size	Short	Mediu	Long				
26in	_____	_____	_____				
28in	_____	_____	_____				
30in	_____	_____	_____				
32in	_____	_____	_____				
34in	_____	_____	_____				
36in	_____	_____	_____				
38in	_____	_____	_____				
40in	_____	_____	_____				
42in	_____	_____	_____				
F10=Change matrix F12=Previous F24=More keys							
b		MW		12/019			

Fields:

Untitled

Quantity. Enter the quantity you wish to make on this production order.

Functions:

F10

Change matrix. Delete all quantities already entered and start again.

Suggested W/O Window



To display this window, enter 1 against a colour on the Select Colour window, having already selected **F20=Qty Breakdown** from the Suggested Order Maintenance window.

This window displays, for information only, the variant style/colour or style/colour/size distribution of an order.

MP350	ZS - Style Demonstration Co.				USER GBJBAMS	15/04/96
						13:54:51
Review - Detail		Base Model....		The Live Planning Model		
		Revision Level				Start 27/12/95
Style		ELF_BOOTS Elfin Boots		Plan Type 1		End 31/03/96
						Time Fence 11/01/96
MPS <---- Demand -----> <----- Supply ----->						
0	Date Order	Quantity	St	Order	Quantity	St Action Available
Suggested W/O						161
ELF_BOOTS		Elfin Boots		Size		More:
Colour	6	6 1/2	7	7 1/2	8	
Beige	21		10		10	
Black	10		10		10	
Blue	10		10		10	
Brown	10		10		10	
Burgundy	10		10		10	
F12=Previous F24=More keys						
12-19	SF	MW	KS	IM	11	KENB20A PET166S2

Production Order Maintenance Screen (Option 5)



To display this screen, enter 5 in the Option field against a suggested or existing production order on Review Detail screen 1.

Use this screen to create or maintain a production order. In particular, you can convert a suggested order to a planned order. Other changes of status and detail are also possible.

From this screen, you can maintain production orders at suggested, planned, confirmed or released status. However, within the context of planning, you are more likely to change the status of the order either from suggested to planned, or from planned to confirmed.

This screen is described in more detail in Style Production Control. For more details, refer to Production Order Maintenance screen 2 under the Maintain Orders option.



Note: This option is only available for the 'live' planning models.

PC151	ZS - Style Demonstration Co.	USER GBJBAMS	15/04/96
			13:46:48
Production Order Maintenance			Week: 16 96
Production Order : _____		* Enter new order details.	
Order Type.....:	1		
Style	BLF_BOOTS		
Route Code....?..:	2		
Quantity.....:	6219	UOM.....:	
Due Date.....:	110196	Stockroom:	
Start Date.....:		Due Week.....:	
		Start Week.....:	
Calendar Code...?.	01	Production Stage.: _	
Planning Filter.?.		Reference 1	
Print Order.....:	0 (1=Yes)	Reference 2	
F3=Exit	F4=Prompt	F8=Add new order	F12=Previous
F16=Item search		F19=Confirm	
08-22	SA	MW	KS IM II KENB20A PET166S2

Purchase Order Maintenance Window (Option 5)



To display this window, enter 5 in the Option field against a suggested purchase order on Review Detail screen 1.

Use this window to maintain the due date and/or quantity against a suggested purchase order.



Note: Plant details are displayed where applicable.



Warning: If you have coded your items as recommended, you should not need to use this screen from within MPS. We recommend that you set the Planning Type on the Production Details screen to 1(MPS) for manufactured items and to 0 (MRP) for purchased items.



Note: This option is only available for the 'live' planning model.

MP350	ZS - Style Demonstration Co.	USER GBJBAMS	15/04/96
Review - Detail Base Model.... The Live Planning Model			13:47:27
Revision Level		Start	27/12/95
Style MAT002 Suede		Plan Type 1	End 11/01/96
MPS <---- Demand -----> <-----		Purchase Order Maintenance	96
0 Date Order Quantity St Order		Item: MAT002	e
26/06 102657 SW		Suede	7-
11/01		Due Date: 11/01/96	0
		Quantity: 102656.630	
		F5=Refresh F12=Previous	

S=Display Supply	6=Peg Demand	2=Schedule Maintenance
F3=Exit	F8=Save	F12=Previous
F17=Summary	F18=Header	F23=Capacity
F19/F20=Next Item/Planner	F16=Prev.Item	F21=Change Sequence
F22=Detail Line		
11-51	SW	MW KS IM II KENB20A PET166S2

Fields:

Due Date

Maintain due date.

Quantity

Maintain quantity.

Functions:

F5

Refresh. To restore the date and quantity to the values displayed when the order was selected.

Review Detail Screen 2 (Option 6)



To display this screen, enter 6 against a demand item in the Option field on Review Detail screen 1.

From this screen, you can view the detailed production schedule for the parent item causing a generated demand on a lower level item. The demand is shown together with its own MPS supply/demand details.



Note: This screen only applies to materials.

MP350	ZS - Style Demonstration Co.	USER GBJBAMS	15/04/96
			13:53:56
Review - Detail	Base Model....	The Live Planning Model	
	Revision Level		Start 27/12/95
Style MS0001	Outrider	Plan Type 0	End 1/09/96
		Time Fence	11/01/96
MPS	<---- Demand -----> <----- Supply ----->		
0	Date Order	Quantity St Order	Quantity St Action Available
11/01			560 YW 560
11/01			13440 SW 14000
3=Suggest Maint S=Supply Order 6=Peg Demand 7=SupplyDetail			
F3=Exit F8=Save F12=Previous F17=Summary F18=Header F23=Capacity			
F19/F20=Next Item/Planner F16=Prev.Item F21=Change Sequence F22=Detail Line			
09-02	Sf	MW	KS IM II KENB20A PET166S2

Supply Detail Window (Option 8)



To display this window, enter 8 in the Option field against a relevant supply line on Review Detail screen 1.



Note: This window is only available if the MPS run was multi-plant or multi-sourcing.

Demand Detail Window (Option 9)



To display this window, enter 9 in the Option field against a relevant demand line on Review Detail screen 1.



Note: This window is only available if the MPS run was multi-plant or multi-sourcing.

Save Changes Window (F8)



To display this window, select **F8=Save** from Review Detail screen 1.

Use this window to save any changes made to the master production schedule to a new revision level, or to the base model.



Note: This window is also accessible from the Review Capacity function when changes are made to the plan from within capacity planning.

This function does not just save details of the current style. It saves all of the supply information and the changed demand information for the current model.

MP350	SH - Style Demonstration Co.	USER GBJBASAW	20/09/96	
Review - Detail	Base Model....	Single Plant/Multi-line	Start 14/07/96	
Style	MP/A1	assembly	Plan Type 1	
MPS <--- Demand --->		<----- Supply ----->		
0	Date Order	Quantity St Order	Quantity St Action Available	
-	10/09	318 SW		318-
-	26/09	438		8-
-	7/10	18		8-
-	4/11	102		8-

Save Changes

Base Model.....: M1

Single Plant/Multi-line

Revision Level.:

Save New Level.:

F12=Previous

Bottom

3=Maintain Suggestions	5=Maintain Order	6=Peg Demand	7=Supply Detail
F3=Exit	F5=Refresh	F8=Save	F12=Previous
F15=Capacity	F23=More Options	F16=Previous Style	F17=Summary
F18=Header	F19=Next Style	F24=More Keys	
17-47	SA	MM	KS IM II KENB20A PET166S2

Fields:

Save New Level

Enter a 2 character, code to identify the latest revision level of the plan. The details of the revision level may subsequently be maintained, or used to drive capacity review and reports. Leave blank to save to the original base model or current revision level - as displayed above the Save New Level field.

Untitled

Enter a description to identify the code. This will be displayed or printed alongside the revision level on enquiries and reports.

Review Summary Screen (F17)



To display this screen, select **F17=Summary** from Review Detail screen 1.

This screen displays a summary of the item supply and demand schedule, using the reporting periods defined for the planning model via the Maintain Reporting Profile function. All fields are system maintained.

MP350	ZS - Style Demonstration Co.	USER GBJBAMS	15/04/96
			13:57:59
Review - Summary	Base Model....	The Live Planning Model	
	Revision Level		
Style	ELF_BOOTS Elfin Boots	Plan Type 1	Start 27/12/95
		End 31/03/96	
		Time Fence 11/01/96	
Opening Stock.	564.000		
	<u>OVERDUE</u>	<u>01/01/96</u>	<u>29/01/96</u>
Actual Dem.			<u>25/02/96</u>
Forecast...			<u>25/03/96</u>
Adj.Demand.	1081	1081	25
Supply.....	1081	1081	216
Available..	6923	1073	865
Net Reqmt..	564	6398	874
Plan Recpt.	308-	6407	223
Plan Avail.	6150-	6151-	6414
	7079	1073	6158-
	564	6562	874
		6554	223
		6563	6570 +
F3=Exit	F12=Previous	F17=Detail	F19=Next Style
F8=Update	F18=Header	F16=Previous Style	F20=Next Planner
20-02	SE	MW	KS
		IM	II
		KENB20A	PET166S2

Fields:

Opening Stock

Displays the current inventory stocking level. Calculated as:

- Physical stock less frozen stock.

Overdue

First column. Displays demand and supply falling in the overdue period defined by the Overdue Days field on the MPS Run Parameters screen. The period is defined as:

- Current date less overdue days.

Actual Dem.

Actual demand. Calculated as:

- Total sales demand plus Dependent demand due in period.

Dependent demand is material requirements for orders offset by the lead time from the parent order due date.

Forecast

Displays the sales forecast in the period.

Adj. Demand

Adjusted demand. Displays the calculated demand due in the period. This quantity is potentially determined by three factors:

- Demand policy for the item, set on the Production Details screen.
- Forecast consumption method defined on the Company Profile, Planning Options screen.
- Manual adjustments made to demand via the Review Demand facility.

Supply

Displays the total of existing supplies in the period.

Available

Displays the available quantity in the period. Calculated as:

- Prior period quantity available plus Supply less Adjusted demand.

In the first period, prior available is equal to Opening Stock balance.

Net Reqmt

Net requirement. Calculated as:

- Adjusted demand plus safety stock plus largest stock forecast in period less prior period available less existing supplies.

Plan Recpt

Planned receipt. Displays the total of all MPS recommended supplies (production and purchase orders) due in the period.

Plan Avail

Planned available. Calculated as:

- Prior period planned available plus planned receipts less adjusted demand.

In the first period, previous period planned available is equal to the Opening Stock balance.

Total

Last column. Displays the sum of all periods for each of the rows except Available, Net Requirement, and Planned Available.

Functions:

<PgUp>, <PgDn>

Use the PageUp and PageDown (or equivalent) keys to display next and previous period details when all period details cannot be displayed on one screen.

Header Details Window (F18)



To display this window, select **F18=Header** from Review Detail screen 1.

This window displays, for information only, inventory and production details pertaining to the parent style selected.

MP350	SH - Style Demonstration Co.	USER GBJBASAW	20/09/96
			12:13:20
Review - Detail	Base Model.... Steve Model	Start	1/06/96
	Revision Level		
Style	SCC/S01	Style c/s	
Planning Basis: Suggested W/O			
MPS	<---- Demand ----->	<----- Supply ----->	
0	Date Order	Quantity St Order	Quantity St Action Available
Header Details			
Planner.....	Item Group.....	Date Last Planned...	23/07/96
UOM..... EA	Phy. Stk..	.000 Fixed Qty..	.000
Order Policy A	Safety Stk	.000 Min. Qty...	.000
Item Type... M	Lead Time. .14	Max. Qty...	.000
Supplier....	Value/Usage Class.. 0	Multiples..	.000
GT Family...	0	Lead Time Policy...	
F12=Previous			
Bottom			
3=Maintain Suggestions 5=Maintain Order 6=Peg Demand 7=Supply Detail			
F3=Exit F5=Refresh F8=Save F12=Previous F15=Capacity F23=More Options			
F16=Previous Style F17=Summary F18=Header F19=Next Style F24=More Keys			
10-02	SA	ML	KS IM II KENB20A PET166S2

Review Detail Screen 3 (F22)



To display this screen, select **F22=Detail** from Review Detail screen 1.

This screen displays an additional line of information beneath each supply/demand detail.

The Order column displays the order line number of the purchase order. If the purchase order is a blanket order, the order line number is followed by / and the blanket sequence number.

Options and functions are the same as Review Detail screen 1.

MP350	SH - Style Demonstration Co.	USER GBJBASAW	20/09/96				
Review - Detail	Base Model....	Single Plant/Multi-line	12:15:47				
	Revision Level		Start 14/07/96				
Style	MP/A1	assembly	Plan Type 1				
Planning Basis:							
MPS	<--- Demand	<--- Supply	<--->				
0	Date Order	Quantity St Order	Quantity St Action Available				
10/09		318 SW		318-			
96	MP/S2	style colour					
26/09		438 SW	438 SW	318-			
96	MP/S2	style colour	Due 26/09/96 Es 0/00/00 Ls 0/00/00				
7/10		18 FC	18 SW	318-			
96			Due 7/10/96				
4/11		102 FC	102 SW	318-			
96			Due 4/11/96				
Bottom							
3=Maintain Suggestions 5=Maintain Order 6=Peq Demand 7=Supply Detail							
F3=Exit F5=Refresh F8=Save F12=Previous F15=Capacity F23=More Options							
F16=Previous Style F17=Summary F18=Header F19=Next Style F24=More Keys							
10-02	SP	MK	KS	IM	II	KENB20A	PET166S2

Fields:

(Item Code & Description)

For dependent demand, the system displays the parent item (code) and description originating the demand.

Due

Current date for supply.

Es

Earliest start date.

Ls

Latest start date.

(Receipt Date)

For purchase orders, the receipt date is the latest of due date, promised date or expected date.

Maintain Capacity Bill



21/P2M

This option is the same as the Style Route/Bill Of Material option described under Style Production Definition Management.

Capacity Review



22/P2M

Use this option to review loading and capacity generated by the last MPS run. This enables you to compare factory capacity to anticipated, calculated load.

You can review load in terms of work centres, machines, labour departments or labour skills. The review commences from the start date of the MPS run.



Note: For an MPS run to consider capacity loading, you must enter 1 in the Include Capacity field on the Additional Parameters window under the Run Production Scheduling option. Otherwise, the MPS run does not produce any data to review in a Capacity Review. In addition, use the Additional Parameters window to determine whether capacity details are based on a capacity route or a planning route.

Barcharts Explained

The barchart screens show capacity load comparisons bucketed in accordance with the periods defined for the planning model via the Maintain Reporting Profile function. Loading appears as a series of coloured bars (vertical columns) on a day by day, or machine by machine, or labour department by labour department etc basis. The degree of loading is reflected by the characters which comprise the bar:

- LD (green). Indicates load is equal to capacity.
- UL (yellow/silver). Indicates capacity exceeds load.
- OV (red). Indicates load exceeds capacity.

The characters displayed are user-definable.

Capacity Review Screen 1



To display this screen, select Capacity Review from the menu or press **F23** from the MPS Review screen.

```

MP410                ZS - Style Demonstration Co.        USER GBJBAMS    15/04/96
                                                    14:00:07

Capacity Review

Base Model.... .....?.. _   Revision Level .....?.. _

Capacity Basis..... 1 (1 - Standard)
                        (2 - Standard x Efficiency)

Enquiry of.:

Work Centre .....?.. ____
OR
Machine .....?.. ____
OR
Labour Department ...?.. ____
OR
Labour Skill .....?.. _

F3=Exit  F4=Prompt

05-31  S2  MW  KS  IM  II  KENB20A  PET166S2
  
```

Fields:

Base Model

Enter the planning model to review. This is defaulted if called from the MPS Review screen.

Revision Level

If the entered planning model has been saved with one or more revision levels; then enter the particular level to review. This is defaulted if called from the MPS Review screen.

Description

If entering/creating a new revision level, enter a description.

Capacity Basis

Machine capacity is derived from one of the following sources held on the machine definition:

1 - Standard capacity.

2 - Standard effective capacity. This is the standard capacity multiplied by the standard efficiency factor.

Work Centre

Enter a work centre or leave blank.

(Or) Machine

Enter a machine or leave blank.

(Or) Labour Department

Enter a labour department or leave.

(Or) Labour Skill

Enter a labour skill or leave blank.

Common Functions

There are several functions common to the subsequent screens:

- Save revision level. An **F8** function is available to save any changes to the master production schedule to a new revision level.
- Load maintenance. Options which enable changes to be made to the work load at work centre, machine, labour department or labour skill level provide the same maintenance facilities.
 - For a specific period for a specific work centre, machine, labour department or skill - actioned by entering 1 against a date on a display.
 - For all periods for a specific work centre, machine, labour department or skill - actioned by pressing **F17** on a display.

Save Revision Level



Each time changes are made to the master production schedule, **F8** can be used to save the changes to a new revision level if required. This may be effected from any of the maintenance screens.

MP411		ZS - Style Demonstration Co.		USER GBJBAMS		15/04/96	
Capacity Review		Base Model.... ZS Work Centre		ELFIN Cal. 01		14:23:50	
Hours	Var	27389	91828	91744	91790	91939	91956
192000.000		UL	UL	UL	UL	UL	UL
		UL	UL	UL	UL	UL	UL
		UL	UL	UL	UL	UL	UL
128000.000		UL	UL	UL	UL	UL	UL
		UL	UL	UL	UL	UL	UL
		UL	UL	UL	UL	UL	UL
64000.000		UL	UL	UL	UL	UL	UL
		UL	UL	UL	UL	UL	UL
		UL	UL	UL	UL	UL	UL
0		UL	UL	UL	UL	UL	UL
Sel(1/5)		UL	UL	UL	UL	UL	UL
Period		27/12	17/01	29/01	26/02	25/03	22/04
Start		95	96	96	96	96	96
F3=Exit		F5=Refresh	F8=Save	F12=Previous	F17=Detail		
17-47		Se	MW	KS	IM	II	KENB20A
							PET166S2

Save Changes

Base Model.....: ZS

The Live Planning Model

Revision Level.: _____

Save New Level.: _____

F12=Previous

Fields:

Save New Level

Enter a new revision level or press Enter to retain the current level.

Untitled

If a new revision level has been entered, a description can entered.

Load Maintenance



F17 and Option 1 at appropriate screens provide maintenance facilities. For example:

```

MP412                ZS - Style Demonstration Co.        USER GBJBAMS    15/04/96
                                                           14:24:55
Capacity Review   Base Model....   .... ZS   The Live Planning Model
                  Revision Level   ....
Machine          . ELF01   Elfin preliminary work group   Period Start.. 27/12/95
Capacity.....    160.00 Load...    51.84 Under    108.16
Loading Details
S Str.Date Order  Opcode Dur(Hrs) S Fabric      Quantity UM Style
■ 27/12/95 SUGGEST LAYOUT    51.84 1 LEATH        6219 EA Elfin Boots

                                                           Bottom

1=Style Schedule 3=Suggest Main 5=Supply Order
F3=Exit  F8=save  F12=Previous  F17=Bar Chart

09-02   S2   MW   KS   IM   II  KENB20A  PET166S2
  
```

Fields:

S(Elect)

These functions are described in detail in the Review MPS section.

- 1 - Access MPS or MRP Review facilities appropriate to the item selected.
- 3 - Change the detail of a suggested production order.
- 5 - Amend an existing production order; create a planned or confirmed suggested production order; or modify a suggested purchase order

S(Tatus)

Indicates the status of the order, this may be:

- 1 - Suggested
- 2 - Confirmed

Fabric

Where displayed, shows the entry made in the fabric Type field on the relevant item definition.

Work Centre Load Barchart




This screen is displayed if a capacity review, by work centre has been requested on the Capacity Review Selection screen.

This enquiry displays in barchart format a multi-period review of the master production schedule for a selected work centre.



Note: The review will commence from the start date of the MPS run.



Fields:

Cal.

System maintained field; displays the production calendar entered against the reporting profile for the planning model selected.

Sel

1 - Display the Work Centre Period Load Details screen showing the individual operations which make up the load within the selected period.

5 - Display the Work Centre Machine Load Barchart displaying the capacity and load of individual machines within the work centre within the selected period.

Functions:

F8

To save the current changes to a new revision level by calling the Save Revision Level screen

F17

To display the Work Centre Total Load Detail screen showing all of the individual operations due to be carried out in the work centre.

<PgUp>, <PgDn>

Use the PageUp and PageDown (or equivalent) keys to display following and previous details when all periods cannot be displayed on one screen.

Work Centre Period Load Detail (Option 1)



Option 1 against a date on the Work Centre Load Barchart displays this screen.

This screen displays a detailed breakdown of the loading in the selected period.



Note: Quantities to be made, and times to be taken, relate to the events in the chosen period only. In the case where the operation continues over a period boundary, to see the total quantity to be processed and the full operation time, see the Work Centre Total Load Detail screen.

MP412	ZS - Style Demonstration Co.				USER GBJBAMS	15/04/96
						14:28:16
Capacity Review	Base Model....		ZS	The Live Planning Model		
	Revision Level					
Work Centre	. ELFIN					Period Start.. 27/12/95
Capacity.....	28814.50	Load...	1425.25	Under	27389.25	
Loading Details						
S	Str.Date	Order	Opcode	Dur(Hrs)	S Machine	Quantity UM Style
-	27/12/95	SUGGEST	LAYOUT	51.84	1	6219 EA Elfin Boots
-	27/12/95	SUGGEST		1373.41	1	6219 EA Elfin Boots
Bottom						
1=Style Schedule 3=Suggest Main 5=Supply Order						
F3=Exit F8=save F12=Previous F17=Bar Chart F18=Machines						
09-02	SF	MW	KS	IM	II	KENB20A PET166S2

Fields:

S

Selection. These functions are described in detail in the Review MPS section.

1 - Access MPS or MRP Review facilities appropriate to the item selected.

3 - Change the detail of a suggested production order.

5 - Amend an existing production order; create a 'Planned' or 'Confirmed' suggested production order.

S

Status. This field is system maintained.

1 - Suggested

2 - Confirmed

Machine

System maintained; where displayed, shows the entry made in the Machine field in the relevant item definition.

Functions:

F8

To save the current changes to a new revision level by calling the Save Revision Level screen.

F17

To display the Work Centre Load Barchart.

F18

To open a window showing a list of the machines within the current work centre.

Work Centre Machine Load Barchart (Option 5)




Option 5 against a date on the Work Centre Load Barchart displays this screen.

This screen shows the capacity and load for each machine within a work centre, for a single period.



Note: The review will commence from the start date of the MPS run.



Functions:

F8

To save the current changes to a new revision level by calling the Save Revision Level screen.

F17

To display the Work Centre Load Barchart screen showing all of the individual operations due to be carried out in the work centre.

Work Centre Total Detail (F17)



F17=Detail on the Work Centre Load Barchart screen displays this screen.

This screen shows the work load for the work centre in all periods.

MP412	ZS - Style Demonstration Co.	USER GBJBAMS	15/04/96
			14:30:20
Capacity Review	Base Model....	 ZS	The Live Planning Model
	Revision Level		
Work Centre	. ELFIN		
Loading Details			
S	Str.Date	Order	Opcode Dur(Hrs) S Machine Quantity UM Style
-	22/07/96	W000770	.65 25 EA Elfin Boots
-	27/12/95	SUGGEST LAYOUT	51.84 1 6219 EA Elfin Boots
-	4/01/96	SUGGEST LAYOUT	1.35 1 161 EA Elfin Boots
-	11/01/96	SUGGEST LAYOUT	1.46 1 174 EA Elfin Boots
-	15/01/96	SUGGEST LAYOUT	.14 1 16 EA Elfin Boots
-	16/01/96	SUGGEST LAYOUT	.15 1 17 EA Elfin Boots
-	16/01/96	SUGGEST LAYOUT	.20 1 32 EA Elfin Boots
-	17/01/96	SUGGEST LAYOUT	.20 1 32 EA Elfin Boots
-	18/01/96	SUGGEST LAYOUT	1.46 1 174 EA Elfin Boots
-	22/01/96	SUGGEST LAYOUT	.14 1 16 EA Elfin Boots
-	23/01/96	SUGGEST LAYOUT	.16 1 18 EA Elfin Boots
			More...
1=Style Schedule 3=Suggest Main 5=Supply Order			
F3=Exit F8=save F12=Previous F17=Bar Chart F18=Machines			
09-02	S2	MW	KS IM II KENB20A PET166S2

Fields:

S

Selection. These functions are described in detail in the Review MPS section.

1 - Access MPS or MRP Review facilities appropriate to the item selected.

3 - Change the detail of a suggested production order.

5 - Amend an existing production order; create a planned or confirmed suggested production order.

S

Status. System maintained field; indicates the status of the order.

1 - Suggested

2 - Confirmed

Machine

System maintained; where displayed, shows the entry made in the Machine field in the relevant item definition.

Functions:

F8

To save the current changes to a new revision level by calling the Save Revision Level screen

F17

To display the Work Centre Load Barchart

F18

To open a window showing a list of the machines within the current work centre

Machine Load Barchart




This screen is displayed if a capacity review, by machine has been requested on the Capacity Review Selection screen.

This enquiry displays in barchart format, a multi-period review of the master production schedule.



Note: The review will commence from the start date of the MPS run.



Fields:

Cal.

System maintained field; displays the production calendar entered against the reporting profile for the planning model.

Sel

Enter 1 at a date to display the Period Machine Detail Display screen showing the individual operations which make up the load within the selected period.

Functions:

F8

To save the current changes to a new revision level by calling the Save Revision Level screen

F17

To display the Machine Total Load Detail screen showing all operations due at the machine

Machine Period Load Detail (Option 1)



Option 1 against a date on the Machine Load Barchart screen displays this screen.

This function enables you to amend the loading at a machine within a single period.



Note: Quantities to be made, and times to be taken, relate to the events within the chosen period only. In the case where the operation continues over a period boundary, to see the total quantity to be processed and the full operation time, see the Machine Total Load Detail display.

MP412	ZS - Style Demonstration Co.		USER GBJBAMS	15/04/96
				14:35:13
Capacity Review	Base Model....	 ZS	The Live Planning Model	
	Revision Level			
Machine	. ELF02	Cut, form and assemble	Period Start..	27/12/95
Capacity.....	24.00	Load...	1373.41	Over 1349.41
Loading Details				
S Str.Date	Order	Opcode	Dur(Hrs)	S Fabric
27/12/95	SUGGEST		1373.41	1 LEATH
			Quantity	UM Style
			6219	EA Elfin Boots
Bottom				
1=Style Schedule 3=Suggest Main 5=Supply Order				
F3=Exit F8=save F12=Previous F17=Bar Chart				
09-02	SA	MW	KS	IM II KENB20A PET166S2

Fields:

S

Selection. These functions are described in detail in the Review MPS section.

1 - Access MPS or MRP Review facilities appropriate to the item selected.

3 - Change the detail of a suggested production order.

5 - Amend an existing production order; create a planned or confirmed suggested production order.

S

Status. System maintained field; indicates the status of the order. This may be 1 (suggested) or 2 (confirmed)

Fabric

System maintained; where displayed, shows the entry made in the Fabric Type field in the relevant item definition.

Functions:

F8

To save the current changes to a new revision level by calling the Save Revision Level screen

F17

To display the Machine Load Barchart

Machine Total Load Detail (F17)



F17 on the Machine Load Barchart screen displays this screen.

This screen shows the work load for the machine in all periods.

MP412	ZS - Style Demonstration Co.	USER GBJBAMS	15/04/96
			15:08:55
Capacity Review	Base Model....	 ZS	The Live Planning Model
	Revision Level		
Machine	. ELF02	Cut, form and assemble	
Loading Details			
S	Str.Date	Order	Opcode Dur(Hrs) S Fabric Quantity UM Style
-	17/05/96	W000785	30.35 2 25 EA Elfin Boots
-	27/05/96	W000784	30.35 2 25 EA Elfin Boots
-	24/06/96	W000780	29.50 2 25 EA Elfin Boots
-	22/07/96	W000778	30.35 2 25 EA Elfin Boots
-	27/12/95	SUGGEST	1373.41 1 LEATH 6219 EA Elfin Boots
-	5/01/96	SUGGEST	35.59 1 LEATH 161 EA Elfin Boots
-	12/01/96	SUGGEST	1.31 1 LEATH 174 EA Elfin Boots
-	15/01/96	SUGGEST	3.58 1 LEATH 16 EA Elfin Boots
-	15/01/96	SUGGEST CUT	5.10 1 LEATH 174 EA Elfin Boots
-	16/01/96	SUGGEST	3.79 1 LEATH 17 EA Elfin Boots
-	16/01/96	SUGGEST	7.10 1 LEATH 32 EA Elfin Boots
More...			
1=Style Schedule 3=Suggest Main 5=Supply Order			
F3=Exit F8=save F12=Previous F17=Bar Chart			
09-02	S2	MW	K3 IM II KENB20A PET166S2

Fields:

S

Selection.

- 1 - Access MPS or MRP Review facilities appropriate to the item selected.
- 3 - Change the detail of a suggested production order.
- 5 - Amend an existing production order; create a 'Planned' or 'Confirmed' suggested production order.

S

Status. System maintained field; indicates the status of the order.

- 1 - Suggested
- 2 - Confirmed

Fabric

System maintained; where displayed, shows the entry made in the Fabric Type field in the relevant item definition.

Functions:

F8

To save the current changes to a new revision level by calling the Save Revision Level screen

F17

To display the Machine Load Barchart

Labour Department Load Barchart




This screen is displayed if a capacity review, by labour department has been requested on the Review Capacity Selection screen.

This enquiry displays in barchart format, a multi-period review of the master production schedule.



Note: The review will commence from the start date of the MPS run



Fields:

Cal

System maintained field; displays the production calendar entered against the reporting profile for the planning model selected.

Sel

1 - Display the Labour Department Period Load Detail screen showing the individual operations which make up the load within the selected period.

5 - Display the Labour Department Skill Barchart showing the capacity and load of individual skills within the department within the selected period.

Functions:

F8

To save the current changes to a new revision level by calling the Save Revision Level screen

F17

To display the Labour Department Total Load Detail screen showing all of the individual operations due to be carried out in the work centre

Labour Department Period Detail Load (Option 1)



Option 1 against a date on the labour
Department Load Barchart screen displays this
screen.

This function enables you to amend the load on a department within the selected
period.



*Note: Quantities to be made, and times to be
taken, relate to the events within the chosen
period only. In the case where the operation
continues over a period boundary, to see the
total quantity to be processed and the full
operation time, see the labour Department Total
Load Detail display.*

MP412	ZS - Style Demonstration Co.	USER GBJBAMS	15/04/96
			15:12:35
Capacity Review	Base Model....	 ZS	The Live Planning Model
	Revision Level		
Department...	ELFIN	Elfin boot group	Period Start.. 1/01/96
Capacity.....	Load...	12803.64	Over 12803.64
Loading Details			
S	Str.Date	Order	Opcode Dur(Hrs) S Skill Quantity UM Style
-	12/01/96	SUGGEST	2648.64 1 161 EA Elfin Boots
-	15/01/96	SUGGEST	1923.28 1 174 EA Elfin Boots
-	15/01/96	SUGGEST	265.68 1 16 EA Elfin Boots
-	17/01/96	SUGGEST FORM	475.04 1 174 EA Elfin Boots
-	16/01/96	SUGGEST	282.16 1 17 EA Elfin Boots
-	17/01/96	SUGGEST	528.64 1 32 EA Elfin Boots
-	18/01/96	SUGGEST	355.60 1 32 EA Elfin Boots
-	19/01/96	SUGGEST ASSEM	463.92 1 174 EA Elfin Boots
-	18/01/96	SUGGEST	173.04 1 32 EA Elfin Boots
-	22/01/96	SUGGEST	1923.28 1 174 EA Elfin Boots
-	22/01/96	SUGGEST	265.68 1 16 EA Elfin Boots
More...			
1=Style Schedule 3=Suggest Main 5=Supply Order			
F3=Exit F8=save F12=Previous F17=Bar Chart			
09-02	SA	MW	KS IM II KENB20A PET166S2

Fields:

S

Selection. These functions are described in detail in the Review MPS section.

1 - Access MPS or MRP Review facilities appropriate to the item selected.

3 - Change the detail of a suggested production order.

5 - Amend an existing production order; create a 'Planned' or 'Confirmed'
suggested production order.

S

Status. System maintained field; indicates the status of the order.

1 - Suggested

2 - Confirmed

Skill

System maintained; where displayed, shows the skill attached to a labour profile specified against the operation.

Functions:

F8

Save the current changes to a new revision level by calling the Save Revision Level screen.


F17

Display the Labour Department Load Barchart.

Labour Department Skill Load Barchart (Option 5)



Option 5 against a date on the Labour
Department Load Barchart screen displays this
screen.



Functions:

F8

To save the current changes to a new revision level by calling the Save Revision Level screen

F17

To display the Labour Department Load Barchart

Labour Department Total Load Detail (F17)



F17 on the labour Department Load Barchart screen displays this screen.

This screen shows the work load for the labour department in all periods.

MP412	ZS - Style Demonstration Co.	USER GBJBAMS	15/04/96
			15:15:20
Capacity Review	Base Model....	 ZS	The Live Planning Model
	Revision Level		
Department...	ELFIN	Elfin boot group	
Loading Details			
S	Str.Date	Order	Opcode Dur(Hrs) S Skill
■	12/01/96	SUGGEST	2648.64 1
-	15/01/96	SUGGEST	1923.28 1
-	15/01/96	SUGGEST	265.68 1
-	17/01/96	SUGGEST FORM	475.04 1
-	16/01/96	SUGGEST	282.16 1
-	17/01/96	SUGGEST	528.64 1
-	18/01/96	SUGGEST	355.60 1
-	19/01/96	SUGGEST ASSEM	463.92 1
-	18/01/96	SUGGEST	173.04 1
-	22/01/96	SUGGEST	1923.28 1
-	22/01/96	SUGGEST	265.68 1
			More...
1=Style Schedule 3=Suggest Main 5=Supply Order			
F3=Exit F8=save F12=Previous F17=Bar Chart			
09-02	S2	MW	KS IM II KENB20A PET166S2

Fields:

S

Selection. These functions are described in detail in the Review MPS section.

1 - Access MPS or MRP Review facilities appropriate to the item selected.

3 - Change the detail of a suggested production order.

5 - Amend an existing production order; create a planned or confirmed suggested production order.

S

Status. System maintained field; indicates the status of the order.

1 - Suggested

2 - Confirmed

Skill

System maintained; where displayed, shows the skill attached to a labour profile specified against the operation.

Functions:

F8

To save the current changes to a new revision level by calling the Save Revision Level screen

F17

To display the Labour Department Load Barchart

Labour Skill Load Barchart




This screen is displayed if a capacity review, by labour skill has been requested on the Review Capacity Selection screen.

This enquiry displays in barchart format, a multi-period review of the master production schedule.



Note: The review will commence from the start date of the MPS run



Fields:

Cal.

System maintained field; displays the production calendar entered against the reporting profile for the planning model.

Sel

1 - Display the Skill Load Detail screen showing the individual skills which make up the load in the selected period.

Functions:

F8

To save the current changes to a new revision level by calling the Save Revision Level screen

F17

To display the Labour Skill Load Barchart

Skill Period Load Detail (Option 1)



Option 1 against a date on the Labour Skill Load Barchart screen displays this screen.

This function enables you to amend the load on a skill.



Note: Quantities to be made, and times to be taken, relate to the events within the chosen period only. In the case where the operation continues over a period boundary, to see the total quantity to be processed and the full operation time, see the labour Department Total Load Detail display.

MP412	ZS - Style Demonstration Co.				USER GBJBAMS	15/04/96
						15:18:23
Capacity Review	Base Model....	 ZS	The Live Planning Model			
	Revision Level					
Labour Skill . E1	Engineer			Period Start..	1/01/96	
Capacity.....	Load...	3200.91	Over	3200.91		
Loading Details						
S	Str.Date	Order	Opcode	Dur(Hrs)	S Fabric	Quantity UM Style
-	12/01/96	SUGGEST		662.16	1 LEATH	161 EA Elfin Boots
-	15/01/96	SUGGEST		480.82	1 LEATH	174 EA Elfin Boots
-	15/01/96	SUGGEST		66.42	1 LEATH	16 EA Elfin Boots
-	17/01/96	SUGGEST	FORM	118.76	1 LEATH	174 EA Elfin Boots
-	16/01/96	SUGGEST		70.54	1 LEATH	17 EA Elfin Boots
-	17/01/96	SUGGEST		132.16	1 LEATH	32 EA Elfin Boots
-	18/01/96	SUGGEST		88.90	1 LEATH	32 EA Elfin Boots
-	19/01/96	SUGGEST	ASSEM	115.98	1 LEATH	174 EA Elfin Boots
-	18/01/96	SUGGEST		43.26	1 LEATH	32 EA Elfin Boots
-	22/01/96	SUGGEST		480.82	1 LEATH	174 EA Elfin Boots
-	22/01/96	SUGGEST		66.42	1 LEATH	16 EA Elfin Boots
						More...
1=Style Schedule 3=Suggest Main 5=Supply Order						
F3=Exit F8=save F12=Previous F17=Bar Chart						
10-02	SP	MW	KS	IM	II	KENB20A PET166S2

Fields:

S

Selection.

- 1 - Access MPS or MRP Review facilities appropriate to the item selected.
- 3 - Change the detail of a suggested production order.
- 5 - Amend an existing production order; create a 'Planned' or 'Confirmed' suggested production order.

S

Status. System maintained field; indicates the status of the order.

- 1 - Suggested
- 2 - Confirmed

Fabric

System maintained; where displayed, shows the entry made in the Fabric Type field on the relevant item definition.

Functions:

F8

To save the current changes to a new revision level by calling the Save Revision Level screen

F17

To display the Labour Skill Load Barchart

Skill Total Load Detail (F17)



F17 on the Labour Skill Load Barchart screen displays this screen.

This screen shows the work load for the skill in all periods.

MP412	ZS - Style Demonstration Co.	USER GBJBAMS	15/04/96
			15:19:26
Capacity Review	Base Model....	 ZS	The Live Planning Model
	Revision Level		
Labour Skill . E1	Engineer		
Loading Details			
S Str.Date	Order	Opcode	Dur(Hrs) S Fabric
- 12/01/96	SUGGEST		662.16 1 LEATH
- 15/01/96	SUGGEST		400.82 1 LEATH
- 15/01/96	SUGGEST		66.42 1 LEATH
- 17/01/96	SUGGEST	FORM	118.76 1 LEATH
- 16/01/96	SUGGEST		70.54 1 LEATH
- 17/01/96	SUGGEST		132.16 1 LEATH
- 18/01/96	SUGGEST		00.90 1 LEATH
- 19/01/96	SUGGEST	ASSEM	115.90 1 LEATH
- 18/01/96	SUGGEST		43.26 1 LEATH
- 22/01/96	SUGGEST		400.82 1 LEATH
- 22/01/96	SUGGEST		66.42 1 LEATH
			More...
1=Style Schedule 3=Suggest Main 5=Supply Order			
F3=Exit F8=save F12=Previous F17=Bar Chart			
09-02	S2	MW	K3
IM	II	KENB20A	PET166S2

Fields:

S

Selection. These functions are described in detail in the Review MPS section.

1 - Access MPS or MRP Review facilities appropriate to the item selected.

3 - Change the detail of a suggested production order.

5 - Amend an existing production order; create a 'Planned' or 'Confirmed' suggested production order.

S

Status. System maintained field; indicates the status of the order. This may be 1 (suggested) or 2 (confirmed)

Fabric

System maintained; where displayed, shows the entry made in the Fabric Type field on the relevant item definition.

Functions:

F8

To save the current changes to a new revision level by calling the Save Revision Level screen.

F17

To display the Labour Skill Load Barchart screen showing all the individual operations due to be carried out in the work centre.

Capacity Summary Report



23/P2M



To display the Multi Period Capacity Report screen, select Capacity Summary Report from the menu.

This report identifies those areas of the capacity plan that need to be reviewed in more detail. The report shows the workload, by style, over twelve periods from an entered start date. The total workload is compared to the overall capacity of the resource with the periodic and cumulative over and under loads shown.

MP417

ZS - Style Demonstration Co.

USER GBJBAMS

15/04/96
15:45:29

Multi period Capacity Report

Base Model.....?.. ☐ Revision Level?.. ☐

Capacity Basis..... 1 (1 - Standard)
(2 - Standard + Efficiency)

Period Start Date..... 0/00/00

Report of.:

Work Centre?.. ☐ To ☐

OR

Machine?.. ☐ To ☐

OR

Labour Department ...?.. ☐ To ☐

OR

Labour Skill?.. ☐ To ☐

F3=Exit F4=Prompt

05-31 ☐ MW ☐ IM II KENB20A PET166S2

Fields:

Base Model

Enter the planning model to report.

Revision Level

If the entered planning model has been saved with one or more revision levels; then enter the particular level to review.

Capacity Basis

Capacity for machines and work centres may be derived from one of the following sources:

- 1 - Standard capacity, from the machine definition.
- 2 - Standard effective capacity. This is defined as the standard capacity multiplied by the standard efficiency factor; again entered on the machine definition.

Period Start Date

Enter the date from which to commence the report.

Work Centre Range

Enter a range of work centres or leave blank to include all work centres.

(Or) Machine Range

Enter a range of machines or leave blank to include all machines.

(Or) Labour Department Range

Enter a range of labour departments or leave blank to include all labour departments.

(Or) Labour Skill

Enter a range of labour skills or leave blank to include all labour skills.



To generate the Capacity Summary report, press
Enter.

Capacity Period Report



24/P2M



To display the Single Period Capacity Report screen, select Capacity Period Report from the menu.

Use this report to:

- Determine those areas you need to review in more detail.
- View the workload, by style, over twelve months from an entered start date.

The total workload is compared to the available capacity of the resource with the periodic and cumulative under and over loads shown.

MP420	ZS - Style Demonstration Co.	USER GBJBAMS	15/04/96
			15:45:50
Single Period Capacity Report			
Base Model....?.. __ Revision Level?.. __			
Capacity Basis..... 1 (1=Std, 2=Std + Efficiency)			
Time Basis..... 1 (1=Mins, 2=0s, 3=00s, 4=000s)			
Period Start Date..... 0/00/00			
Work Centre?.. ____ To ____			
OR			
Labour Department?.. ____ To ____			
F3=Exit F4=Prompt			
05-31	SF	MM	KS IM II KENB20A PET166S2

Fields:

Base Model

Enter the planning model to report.

Revision Level

If the entered planning model has been saved with one or more revision levels; then enter the particular level to review.

Capacity Basis

Capacity for machines and work centres may be derived from one of the following sources:

- 1 - Standard capacity from the machine definition.
- 2 - Standard effective capacity. This is defined as the standard capacity multiplied by the standard efficiency factor; again entered on the machine definition.

Time Basis

Enter the units in which to report time.

Period Start Date

Enter the date from which to commence the report.

Work Centre Range

Enter a range of work centres or leave blank to include all work centres.

(Or) Labour Department Range

Enter a range of labour departments or leave blank to include all labour departments.



Press **Enter** on the Single Period Capacity
Report screen to generate the report.

Demand Report



31/P2M



To display the MPS Demand Report screen,
select Demand Report from the menu.

This report produces a detailed listing of demand derived from the last MPS run for a selected planning model. The report may be tailored to generate details for a specific range of items or planners, or as an audit report of changes made to the demand plan.

```
MP100                ZS - Style Demonstration Co.      USER GBJBAMS    15/04/96
                                                            15:44:04
MPS Demand Report

Enter  Model .....?..  █
      Planner ....?...  ____ to ____
      Item .....?...   _____ to _____
      Changes only....  _ (1=Yes)

F3=Exit  F4=Prompt

08-40    S2      MW      KS      IM      II  KENB20A  PET166S2
```

Fields:

Model

Enter the planning model to be reported.

Planner Range

Enter a range of planners or leave blank to include all planners.

Item Range

Enter a range of items or leave blank to include all items.

Changes Only

You can enter the following options:

0 - No. Report on the whole of the production schedule.

1 - Yes. Produce an audit report of all manual changes made to demand details via the Review Demand and Review Production Schedule functions.



To generate the Demand Report, press **Enter**.

Recommendations Report



32/P2M

This report produces a summarised action list of recommended changes to supply in the planning model. The report can also identify overdue supplies, that is, production orders with a due date earlier than the current date.

MPS Planner Action Report Screen



To display this screen, select Recommendations Report from the menu.

MP344	ZS - Style Demonstration Co.	USER GBJBAMS	15/04/96
MPS Planner Action Report			15:44:16
Model...?... █			
Planner Action Start..... 15/04/96 To 15/04/96			
Include Overdue Orders..... _ (1=Yes)			
Detail Level 1 (1=Style / Material Group)			
(2=Full Product)			
F3=Exit F4=Prompt F14=Additional Selection			
06-31	SP	MW	KS IM II KENB20A PET166S2

Fields:

Model

Enter the planning model to be reported.

Planner Action Start

This is established by review period. Enter the earliest and latest start dates to consider for MPS supply exceptions.

Include Overdue Orders

You can enter the following options:

- 0 - No. Exclude details of orders with a due date earlier than the current date.
- 1 - Yes. Include details of orders with a due date earlier than the current date.

Detail Level

You can enter the following options:

- 1 - Style/Material Group. Report at style/material group level
- 2 - Full Product. Report at full product detail level. A matrix is prompted beneath the order header information to show the breakdown into the variants.

Functions:

F14

Additional Selection. Display the Enter Selection Criteria window, from which you can select a range of styles on which to report.



To generate the Recommendations Report, press **Enter**.

Enter Selection Criteria Window (F14)



To display this window, select **F14=Additional Selection** from the following screens:

- MPS Planner Action Report screen
- Master Production Scheduling Report screen

Use this window to select a range of styles, rather than including all styles. The window offers further selection options based on parameters set on the style's definition, including planner code, preferred supplier etc.

Enter ranges of items to include on the report. The report only prints an item if the item matches all the selection parameters you enter. If you make no selections, then the report lists all items.

All selection parameters excluding value/usage class are defined for an item via the Style/Material Details option in Production Definition Management. Value/usage classes are defined within the Style Inventory Management application, and relate to specific stockrooms.

Style.....?..	_____ to _____	Report Sequence
Planner.....?..	_____ to _____	-
Style Group.....?..	_____ to _____	-
Value/Usage Class.....	_____ to _____	-
Preferred Supplier....	_____ to _____	-
Fabric Type.....	_____ to _____	-

F4=Prompt F12=Previous

11-30 SF MW KS IM II KENB20A PET16SS2

Fields:

You can sequence your report by entering up to three sequence fields. Enter 1 against the primary report sequence, 2 and 3 against the minor sequences.

For example, you can produce a report showing items in value/usage class sequence within planner responsibility.

Style

Enter a range of item codes or leave blank to include all items.

Planner

Enter a range of planners or leave blank to include all planners.

Style Group

Enter a range of product group minor codes or leave blank to include all product group minor codes.

Product group minor codes are used to group styles into product families for sales and stock forecasting; but could be used for other purposes if product families are not required.

Value/Usage Class

Enter a range of value/usage classes to include or leave blank to include all value/usage classes.

Preferred Supplier

Enter a range of preferred suppliers or leave blank to include all preferred suppliers.

Fabric Type

Enter a range of fabric types or leave blank to include all fabric types.



To return to the previous screen, press **Enter**.

Valuation Report



33/P2M

Use this option to produce a Valuation Report.

The report assesses the inventory and purchase order commitment of a proposed production schedule in standard or current cost terms. The selected schedule is translated from a quantitative plan by extending quantities by the unit cost of items.

You can select which elements of cost are to be included to build the unit cost; and may be set to include cost elements which are excluded from the normal cost by the Company Profile default cost presentation definition. In addition, any cost element can be incremented by a user-defined percentage increase (uplift).

MPS Valuation Report Screen



To display this screen, select Valuation Report from the menu.

MP022	ZS - Style Demonstration Co.	USER GBJBAMS	15/04/96
MPS - Valuation Report			15:44:28
Model.?..	Start	Current	Time Fence
0/00/00	0/00/00	0/00/00	0/00/00
End			
0/00/00			
Basis.....?			
1=Units 2=Hundreds 3=One Thousands 4=Ten Thousands			
5=Hundred Thousands 6=Millions			
MPS Item From.....?.. To			
Planner From.....?.. To			
Reporting Level.....?			
1=Summary 2=Detail			
1=Std Cost 2=Cost Set.....			
Cost Set.....			
Select MPS Item Types.....			
1=Manufactured 2=Purchased 3=Both			
Revision Level.....?..			
F3=Exit F4=Prompt F8=Submit Job F18=Cost Presentation F19=Cost Uplift			
05-12	SP	MW	KS
IM	II	KENB20A	PET166S2

Fields:

Model

Enter the planning model to be reported.

Basis

This indicates the basis for 'rounding' cost values. Detail calculations will take place prior to rounding on the report.

MPS Item From/To

Enter an item range or leave blank to include all items.

Planner From/To

Enter a planner range or leave blank to include all planners.

Reporting Level

The option is given to limit the report to a single level; that is, bill of material low level code.

This option is intended for use in the summary report, since the cost of an item is the full rolled-up cost. If more than one level is included in the summary, then the costs of a child item will be included twice, once in the child's cost, and once in its parent's cost.

To produce a detailed report showing more than one level, leave this field blank.

To produce a summary report for a single level, enter a low level code in the range 0-9. This will usually be 0.

Summary Or Detail

You can enter the following options:

- 1 - Summary. Print calculated total model information only.
- 2 - Detail. Include detail item values.

Standard Cost Or Cost Set

You can enter the following options:

- 1 - Std Cost. Carry out costing using standard costs from the specified cost set.
- 2 - Cost Set. Carry out costing using non-standard costs from the specified cost set.

Cost Set

If 2 (cost set) was selected in the above field, enter the cost set on which calculations are to be based.

Select MPS Item Types

You can enter the following options:

- 1 - Manufactured. Include production items only, item type M (production).
- 2 - Purchased. Include purchased items only, item types P (purchased materials), B (bought out components) and C (consumable tools).
- 3 - Both. Include all items.

Revision Level

Enter the MPS planning model revision level. To report on the original plan, leave this field blank.

Functions:

F8

Submit Job. Generate the report.

F18

Cost Presentation. Select this function to display the Cost Presentation window.

F19

Cost Uplift. Specify cost uplift. Select this function to display the Cost Uplift window.

Cost Presentation Window (F18)



To display this window, select **F18=Cost Presentation** from the MPS Valuation Report screen.

Use this window to change the presentation format of costing information on the report. You can redefine :

- Which cost elements to include in the report.
- The order in which to print cost elements.
- How cost elements are calculated.

The Company Profile holds the default format and definitions of cost elements. Changing the presentation characteristics for this report does not change either the Company Profile defaults or the defaults for this report.

It is possible to retain a modified cost presentation to use with subsequent enquiries and reports; or to return to the default format when the enquiry or report is next used.

MP022	ZS - Style Demonstration Co.	USER GBJBAMS	15/04/96
MPS - Valuation Report			15:43:04
Model.?.. ZS	Start	Current	Time Fence
	0/00/00	0/00/00	0/00/00
End			
0/00/00			

Basis..... _			
1=Units	2=Hundreds	3=One Thousands	4=Ten Thousands
5=Hundred Thousands	6=Millions		

Cost Presentation			
Cost Element	Order	Add to	Roll to
1 Not Used			
2 Main Material	1		
3 Trim	2		
4 Packaging	3		
5 Labour	4		
6 Set-up	5		
7 Machine	6		
8 Sub-Contract	7		

Fixed	Description
	Fabric
	Trim
	Packaging
	Labour
	Set Up
	Machine
	Subcontract

1=Fixed cost

F5=Refresh F12=Previous F15=Save F16=Restore

14-27 SF MW KS IM II KENB20A PET166S2

Fields:

Order

This field controls the order in which the individual elements are presented on the report.

Add To

By entering a cost element number (for example: 02 for material cost, or 05 for labour cost) an element may be accumulated in the total for another element. The element selected to be added to must have a sequence number defined in

the Order field. One cost element cannot have both an order sequence and an 'add to' element defined; they are mutually exclusive.

Roll To

The 'Roll to' column displays for reference purposes only; the field cannot be maintained. However, an element referred to by a 'roll to' element cannot be excluded unless the 'roll to' element itself is excluded.

Fixed

The 'Fixed' column displays for reference purposes only; the field cannot be maintained.

Description

The descriptions entered will appear in the output from all cost-related functions.

Functions:

F15

Save. Save the current presentation format and use on a subsequent enquiry or report.

F16

Restore. Return to the default presentation format.



To return to the MPS Valuation Report screen, press **Enter**.

Cost Uplift Window (F19)



To display this window, select **F19=Cost Uplift** from the MPS Valuation Report screen.

Any element of cost that is either defined via the Company Profile, Cost Element Maintenance screen, or has been selected using the Cost Presentation function may be increased by a percentage entered here. Every item which has a cost for the element will undergo the uplift.

MP022	ZS - Style Demonstration Co.	USER GBJBAMS	15/04/96																											
MPS - Valuation Report		Start	Current																											
Model.?.. ZS		0/00/00	0/00/00																											
Basis..... -		Time Fence	End																											
1=Units 2=Hundreds 3=One Thousands 4=Ten Thousands		0/00/00	0/00/00																											
5=Hundred Thousands 6=Millions																														
MPS Item From.....?.. -	Cost Uplift <table> <thead> <tr> <th>Cost Element</th> <th>Percentage Uplift</th> <th>More: +</th> </tr> </thead> <tbody> <tr><td>Main Material</td><td>_.00</td><td></td></tr> <tr><td>Trim</td><td>_.00</td><td></td></tr> <tr><td>Packaging</td><td>_.00</td><td></td></tr> <tr><td>Labour</td><td>_.00</td><td></td></tr> <tr><td>Set-up</td><td>_.00</td><td></td></tr> <tr><td>Machine</td><td>_.00</td><td></td></tr> <tr><td>Sub-Contract</td><td>_.00</td><td></td></tr> <tr><td>Overhead 1</td><td>_.00</td><td></td></tr> </tbody> </table>			Cost Element	Percentage Uplift	More: +	Main Material	_.00		Trim	_.00		Packaging	_.00		Labour	_.00		Set-up	_.00		Machine	_.00		Sub-Contract	_.00		Overhead 1	_.00	
Cost Element				Percentage Uplift	More: +																									
Main Material				_.00																										
Trim				_.00																										
Packaging				_.00																										
Labour				_.00																										
Set-up				_.00																										
Machine				_.00																										
Sub-Contract				_.00																										
Overhead 1				_.00																										
Planner From.....?.. -																														
Reporting Level..... -																														
1=Summary 2=Detail -																														
1=Std Cost 2=Cost Set..... -																														
Cost Set..... -																														
Select MPS Item Types..... -																														
1=Manufactured 2=Purchase																														
Revision Level.....?.. -																														
F3=Exit F4=Prompt F8=Submit Jo	F8=Update F12=Previous																													
14-68	SF	MW	KS																											
		IM	II																											
		KENB20A	PET166S2																											

Fields:

Percentage Uplift

For each element, enter a percentage by which to uplift all costs for this element for all items that are to be included in the report.

Reporting Profile Report



34/P2M



To display the Master Production Schedule Print MPS Reporting Profile screen, select Reporting Profile Report from the menu.

This report lists the actual dates represented by the periods defined for a specific planning model.



Note: This description also applies to the Reporting Profile option in Style Material Planning.



Note: This report is also produced automatically as part of the MPS and MRP runs

MP003P	ZS - Style Demonstration Co.	USER GBJBAMS	15/04/96
			9:59:57
Master Production Schedule - Print MPS Reporting Profile			
Model...?... ZS			
Model ZS The Live Planning Model was printed successfully.			
Select another model, or press F3 to return to the menu			
F3=Exit F4=Prompt			
06-27	SF	MW	KS IM II KENB20A PET166S2

Fields:

Model

Enter the planning model whose reporting profile you wish to list.

Schedule Report



35/P2M



To display the Master Production Scheduling Report screen, select Schedule Report from the menu.

This report produces a full listing of the master production schedule for review and evaluation.

MP321P	ZS - Style Demonstration Co.	USER GBJBAMS	15/04/96
Master Production Scheduling Report			15:43:45
Model...?.. __			
Print Items With No Details.. @ (1=Yes)			
Exclude Dependent MRP..... @ (1=Yes)			
F3=Exit F4=Prompt F14=Additional Selection			
06-30	SE	MW	KS IM II KENB20A PET166S2

Fields:

Model

Enter the planning model to be reported.

Print Items With No Details

You can decide whether to include styles for which there are no supply and/or demand details. Enter one of the following:

0 - No.

1 - Yes. Include styles for which there are no supply and/or demand details

Exclude Dependent MRP

Dependent MRP demand can result from MPS items existing at a lower level than an MRP style on route/BOMs. You can decide whether to include any MRP dependent demand details.

Enter the following options:

0 - No.

1 - Yes.

Functions:

F14

Additional Selection. Display the Enter Selection Criteria window, from which you can select a range of styles on which to report. This window is described under the Recommendations Report option.



To generate the Schedule Report, press **Enter**.