

-
-
-
-
-

Chapter 1

Maintenance



Inventory Maintenance Functions

Use the maintenance functions to create and amend Master files, and the parameters that are fundamental to Style Inventory Management's operation.



Note: Take care when you maintain files, particularly Description file maintenance, as errors will have far reaching effects. A proper procedure of authorisation and post maintenance checking should be introduced as a matter of company policy.

The master file enquiries are output-only versions of the maintenance transactions and are therefore not separately described.

Inventory Maintenance lists the following functions:

- Descriptions.
- Colours.
- Sizes.
- Size Masks.
- Styles.
- Alternative Parts.
- VAT Codes At Full Product.
- Calendars.
- Period/Week End Control.
- Search Family Codes.
- Carton Maintenance.
- Default Size Distribution.
- Colour Type Master File Maintenance.
- FIFO Costs.
- Bar Codes/Alternative References.
- Full Product Stockroom Details.
- Divisional Information Maintenance.
- Full Product Item Details.
- Article Numbering Maintenance.
- Item Article Number Maintenance.

You can assess all of the above functions from Maintenance except Company Profile Maintenance. The Company Profile can be accessed from the Inventory Management Company Profile option within Utilities.

Company Profile Maintenance

This procedure has three purposes:

- To maintain company details and defaults for the Style Inventory application.
- To create and maintain stockrooms for a company.
- To create and maintain usage profiles for a company.



Warning: If there is a Copy Company option within Utilities, JBA strongly recommend that you use this option to create a new company. You can use the Copy Company option to copy existing parameters and miscellaneous codes to your new company. You can amend these details using your maintenance and utility options.

Company Selection Screen



Select the Inventory Management Company Profile. Once the function has been accessed an initial screen is displayed.

Use this screen to select the company to be maintained.

IN010	User	GBJBARW2	8/11/95
			12:24:57
Maintain Company Profile			
Sel Company			
-	AC	Acceptance test - Process	
-	BJ	BJ	
-	CP	Z1 QA company V3.2	
-	JW	JW - Jeff's Company	
-	JW	JW - Jeff's Company	
-	MA	Mathews Company	
-	MD	Repetitive Production	
-	PM	Process Manufacturing Test Com	
-	RP	JBA Production Company	
-	RW	ROBS COMPANY	
-	SF	Simon Fishers Test Company	
-	SH	Steves Manufacturing Company	
-	SS	Steve Hughes Test Company	
-	ST	Style	
-	S1	System Test One	
-	TE	TE Base Test Company	
-	TS	TESTPRO - TEST COMPANY	+
1=Select			
F3=Exit			
14-03	SF	ML	KS IM II KENB20A PET178S2

Fields:

Sel

Select. Enter 1 against the company to be maintained.



Select a company to display the Company profile
Select Action screen.

Company Profile Select Action Screen



This screen is displayed when a Company has been selected on the Company Selection screen.

Use this screen to select the aspect of the Company Profile Maintenance action required.

IN010	ROBS COMPANY	GBJBARW2	8/11/95 12:25:42
Maintain Company Profile			
Press ENTER to process Company OR enter			
Stockroom code.....?.. _ OR enter			
Usage profile code...?.. _			
F3=Exit F4=Prompt F12=Previous			
07-27 SF MW KS IM II KENB20A PET178S2			

Fields:

Stockroom Code

Enter the code of the Stockroom to be maintained; an existing code for amendment, or a new code for addition. Press **Enter** to maintain the Stockroom Profile. See the Stockroom Details screen for more information.

Usage Profile Code

Enter the code of the Usage Profile you want to maintain. You can either enter an existing code for amendment, or a new code for addition.

Style Inventory Management uses the Usage Profile Code to nominate which historical data, by week or month, is to be used to calculate average usage.

Style Inventory Management uses the code to make reorder recommendations. You can define different usage profiles to reflect differing trends of usage. For more information see the Usage Profile Maintenance screen.



Enter a Stockroom code and press **Enter** to maintain the Stockroom profile.



Enter a Usage Profile code and press **Enter** to maintain the Usage Profile.



Leave the Stockroom and Usage Profile codes blank and press **Enter** to maintain Company

Profile data for the selected company.

Company Profile Maintenance Screen



This screen is displayed if the Stockroom and Usage Profile code are left blank on the Select Action screen when you press **Enter**.

Use this screen to maintain the default parameters for the company.

IN010 JBA System Test Company		GBJBARW2	10/03/97 8:38:27
Maintain Company Profile			
Company name	JBA System Test Company		
Costing method (S,L,A,F) ...	S	Size System .?..	_
Specification 1 description.	Packing		
Specification 2 description.		Memo Fields	Decs
Specification 3 description.			
General ledger account	355000		-
Sales GL account	370000		-
Cost of sales GL account ...	601100		-
Price variance GL account ..	766000		-
Usage cycle	M		-
Default reorder policy	1 Upto MAX		-
Reorder quantity factor % ..	0		-
Stock carrying rate %			-
Order placement cost			-
Purchasing in use	1 (0=No,1=Yes)		-
SOP in use	1 (0=No,1=Yes)		-
Excise Duty %	.00	Default item search ...	1
		Date last changed..	14/02/97
F4=Prompt F11=Delete F12=Previous F13=Additional Details			
16-46	SP	MW	KS IM II EDN400A PE9106S2

Fields:

Company Name

You cannot maintain the company name from within Style Inventory Management. Use System Manager to amend the company name if required.

Costing Method

Enter one character to specify the company's default costing method. The costing method can also be changed at Style level; codes are:

L - Latest costing. This costing method will be the default method for each product within this company. It may be changed for individual products.

A - Average costing. The movement is valued at the average cost of the Out stockroom, causing a re-calculation of average cost at the In stockroom.

S - Standard costing. The movement out is valued at the standard cost of Out stockroom. The movement in is valued at standard cost of the In stockroom.

Any difference is written as an A type (value only) movement.

F - FIFO costing. The movement out is valued at the FIFO cost of the Out stockroom. The movement in is at the same value and creates a new FIFO record.

Specification N Description

Where N is 1 to 3. You can define three numeric specifications for each product, using up to 15 alphanumeric characters.

The description for each specification will appear alongside the specification on the Product Maintenance screen.

Typically you would use these specifications to define some dimension of a product not provided in the standard data. Standard Processing makes no use of the specifications.

General Ledger Account

Enter up to 12 alphanumeric characters. This is the default account number in the General Ledger to which purchase invoices are posted if the Style Purchase Management application is in use.

Sales GL Account

Enter up to 12 alphanumeric characters. This is the default account number in the General Ledger to which stock transaction values are posted.

Cost Of Sales GL Account

Enter up to 12 alphanumeric characters. This is the default account number in the General Ledger to which cost of sales transaction values are posted if the Style Sales Order Processing application is in use.

Price Variance GL Account

Enter up to 12 alphanumeric characters. This is the default account number in the General Ledger to which accruals are posted if the Style Purchase Management application is in use.

Usage Cycle

Enter one of the following to define the basis for Style Inventory Management to calculate average usage.

M - To maintain usage figures by month, and to express average usage as average/month.

W - To maintain usage figures by week, and to express average usage as average/week.

The system automatically records the usage of all items at both stockroom and company level.



Note: The usage figure is based on all types of issue movements and transfers out. Four of the Reorder Policies make use of an average usage figure. To set the system to calculate this, you need to define Usage Profile codes.

Default Reorder Policy

Enter one of the following to specify the company's normal reorder policy:

1 - Up To Max. When expected stock drops below the reorder point the system suggests that an order be placed of sufficient size to take the stock level up to the maximum.

2 - Reorder Quantity (ROQ). When expected stock drops below the reorder point the application suggests that the reorder quantity be ordered.

You can set this quantity yourself, or it can be determined by the application. You can hold a Reorder Quantity Factor at stockroom level or as a default on the

Company Profile. If the reorder quantity factor was 30%, the application recommends action to reorder enough stock to last through 30% of the lead time. If the factor was 200% the application recommends action to reorder enough stock to last through twice the lead time.

3 - Up To ROP. When expected stock drops below the reorder point the application suggests that you order enough to take the level up to the reorder point again. For example, if you set the reorder point to zero, this rule would re-order goods when there is demand for them, for example, from a customer or manufacturing order.

4 - Up To Min. When expected stock drops below the reorder point the system suggests that you order enough stock to take the balance back up to the minimum level.

5 - EOQ. When expected stock drops below the reorder point the system suggests that you place an order for the calculated or maintained economic order quantity.

This re-order policy is then the default for all products in all stockrooms; you can, however, change it for a particular product or stockroom.

Reorder Quantity Factor %

Define, as a percentage, the number of lead times worth of average usage to be reordered.

For example 100% is one lead times worth, 150% is one and a half lead times worth.

This is used to calculate reorder quantity for those item/stockroom combinations where the reorder policy is ROP and no reorder quantity has been specified.

Stock Carrying Rate %

Enter five numeric characters with two decimals, to specify the percentage cost of carrying a stock item for a year. This rate is used in the economic order quantity calculations.

Order Placement Cost

Enter five numeric characters with two decimals, to specify the cost in base currency of placing and processing a purchase order. This cost is used in the economic order quantity calculations.

Purchasing In Use

Enter one of the following:

0 - No, Style Purchase Management is not in use.

1 - Yes, Style Purchase Management is in use.

SOP In Use

Enter one of the following:

0 - No, Style Sales Order Processing is not in use.

1 - Yes, Style Sales Order Processing is in use.

Excise Duty %

Enter the default duty percentage that will be applied to goods when they are recovered from a designated bonded warehouse. This is a memorandum field.

Size System

Enter the default size system to be applied to the colour/size matrix processing.

For example B indicates that all sizes will be displayed in base values, that is UK. If other systems are to be considered, that is, E-European or U-USA, then these must be set up on the size file.

Memo Fields

These are ten optional user defined numeric fields. Decimal position can be 0, 2 or 4. If used, these fields will appear on the Product Maintenance screen. The system does no processing with these memo only fields. These fields are particularly useful when designing reports.

Default Item Search Option

Enter one of the following to specify the default item search.

- 1 - Search by item.
- 2 - Search by Inventory description.
- 3 - Search by Purchase description.

Date Last Changed

This displays the last date when changes were made.

Functions:

F11

Delete. To delete Company Profile.

F13

Additional details. To define Generate Article Number details for this company.



Press **Enter** to update the Company Profile.

Maintain Company Profile Additional Details Screen (F13)



This screen is displayed when **F13=Additional Details** is selected from the Company Profile Maintenance screen.

Use this screen to set up UPC/UEN codes; a number will be generated for every item. You can set specific parameters required for article numbering processing.

```

IN010                JBA System Test Company                GBJBARW2    10/03/97
                                                8:38:27

Maintain Company Profile

Company name ..... JBA System Test Company
Cos Additional Details
Spe
Spe  Gen.article no..... 1    (0=No,1=Yes)                ecs
Spe
Gen  Article no. flag... 0    (0=Company Level)
Sal                                  (1=Division Level)
Cos                                  (2=Brand Level)
Pri
Usa  Rule.....? BW1
Def
Reo  F4=Prompt F12=Previous
Stock carrying rate % .....
Order placement cost .....
Purchasing in use ..... 1    (0=No,1=Yes)
SOP in use ..... 1    (0=No,1=Yes)                Default item search ... 1
Excise Duty % ..... .00                Date last changed.. 14/02/97

F4=Prompt F11=Delete F12=Previous F13=Additional Details

08-29  SF  MW  KS  IM  II  EDN400A  PE9106S2
  
```

Fields:

Gen Article No

Generate Article Numbers. Enter one of the following:

- 0 - No. Suppress article number generation.
- 1 - Yes. Generate article numbers for items.

Article No Flag

Article Number Flag. Enter one of the following to define the level at which article numbers will be generated:

- 0 - Company Level. The rule defined to the company.
- 1 - Division Level. The rule defined to the division of an item.
- 2 - Brand Level. This field entry is for future development.

Rule

If you have decided to activate the Generate Article Number at Company level, by setting both of the previous fields to 1, enter the rule that you want as the company default using up to three alphanumeric characters.

This rule is used to determine how items will be numbered. These are set up within the Article Numbering Maintenance option.



Press **Enter** to display the Stockroom Details screen.

Stockroom Details Screen



This screen is displayed after you have selected the Maintain Stockroom Profile option from the Company Maintenance Action selection screen.

Use this screen to create and maintain stockroom profiles.

IN010	ROBS COMPANY	GBJBARW2	8/11/95 12:25:42
Maintain Company Profile			
Stockroom	02		
Include in valuation	1	{0=No,1=Yes}	
Stockroom usage code?	-		
Department	?		
Transaction allowed {0=No,1=Yes}			
Receipts	1		
Issues	1		
Adjustments	1		
Transfers	1		
Supplier orders	1		
Sales orders	1		
F4=Prompt F12=Previous			
05-36	SF	ML	KS IM II KENB20A PET178S2

Fields:

Stockroom

Enter up to 25 alphanumeric characters for the stockroom name.

Include In Valuation

Enter one of the following:

0 - To exclude the stockroom from the valuation. You could do this if the stockroom was set up to hold incidentals such as stationery.

1 - To include the stockroom in the valuation.

Stockroom Usage Code

Enter the usage code associated with this stockroom. This code is used for information only by the standard application. Stockroom Usage codes are defined in the Descriptions file against major type STKU.

Department

Enter a department code to be associated with this stockroom. This data is used for information only by the standard application. Department codes are defined on the Descriptions file against major type DEPT.

Transaction Allowed

Receipts

Enter one of the following:

- 0 - To not receive goods at this stockroom.
- 1 - To receive goods at this stockroom.

Issues

Enter one of the following:

- 0 - To not issue goods from this stockroom.
- 1 - To issue from this stockroom.

Adjustments

Enter one of the following:

- 0 - To not allow adjustments at this stockroom.
- 1 - To allow adjustments to be made at this stockroom.

Transfers

Enter one of the following:

- 0 - To not initiate transfers at this stockroom.
- 1 - To initiate transfers at this stockroom.

Supplier Orders

Enter one of the following:

- 0 - To not initiate supplier orders at this stockroom.
- 1 - To initiate supplier orders at this stockroom.

Sales Orders

Enter one of the following:

- 0 - To not take sales orders against this stockroom.
- 1 - To take sales orders against this stockroom.



Press **Enter** to update the Stockroom profile and to display the stock weeks matrix associated with this stockroom.

Stock Weeks Matrix



This screen is displayed when you press **Enter** on the Stockroom Details screen.



Note: This would normally be used for stockrooms which cater for manufacturing, rather than for stockrooms that hold finished goods to cater for sales.

You can set up ABC classifications which can then be attributed to a style. It enables the maintenance of parameters which are used to classify products into one of nine value/usage categories.

The minimum and maximum required stockholding can be specified for each category.

A three by three matrix is displayed on the screen. The Y axis is value and the X axis is usage. Value is the unit cost of the product and the usage is the most recently calculated average usage for any product in the stockroom.

The minimum and maximum stock holdings are expressed in a number of weeks of average usage. The date the matrix was last changed is displayed on the screen.

You can enter the following details for each cell in the matrix.

```

IN010          ROBS COMPANY          GBJBARW2    9/11/95
                                           9:41:29

Maintain Company Profile

Stockroom ..... 01   robs depot
V
A 0.000          +--- 1 ---+--- 2 ---+--- 3 ---+   Stock weeks code
L          | Class | Class | Class |   1 Low val/low usg.
U          | Min  | Min  | Min  |   2 /med usg.
E          | Max  | Max  | Max  |   3 /hi usg.
          +--- 4 ---+--- 5 ---+--- 6 ---+
          | Class | Class | Class |   4 Med val/low usg.
          | Min  | Min  | Min  |   5 /med usg.
          | Max  | Max  | Max  |   6 /hi usg.
          +--- 7 ---+--- 8 ---+--- 9 ---+
          | Class | Class | Class |   7 Hi val /low usg.
          | Min  | Min  | Min  |   8 /med usg.
          | Max  | Max  | Max  |   9 /hi usg.
          +---+---+---+
          0.0 to .000 to .000 USAGE Last change 0/00/00

F11=Delete F12=Previous

00-29  SA  MW  KS  IM  11 KENB20A PET178S2
  
```

Fields:

Min

Enter three numeric characters, one decimal, to specify the minimum weeks stock to hold for the category.

Max

Enter three numeric characters, one decimal, to specify the maximum weeks stock to hold for the category.

Class

Enter A, B, C or Z to assign a classification to all products that fall within this value or usage category. Historically A class products are high value or high usage. Whereas C class products are low value or low usage.

You can request stock counting by ABC Classification and define a profile so that higher value or usage products are counted more frequently than lower value or usage ones.

If you enter the classification Z for products, ABC Count Creation will ignore them.

To define the Y axis:

Value 1

Enter 15 numeric characters, five decimal, to specify the first value de-limiter. Any items with a unit cost less than or equal to this value will fall into categories 1, 2 or 3.

Value 2

Enter 15 numeric characters, five decimals, to specify the second value de-limiter.

Items with a unit cost between this value and value 1 will fall into category 4, 5 or 6. Items with a unit cost over this value will fall into category 7, 8 or 9.

To define the X axis:

Usage Qty 1

Enter 11 numeric characters, three decimals, to specify the first usage de-limiter.

Items with an average usage up to this quantity will fall into category 1, 4 or 7.

Usage Qty 2

Enter 11 numeric characters, three decimals, to specify the second usage de-limiter.

Items with an average usage between quantity 1 and this quantity will fall into category 2, 5, or 8. Items with an average usage over this quantity will fall into category 3, 6, or 9. During the Ad-hoc Update, for each included item, the system reviews the item's cost and average usage, thus identifying an appropriate square and then selecting the number of minimum and maximum weeks.

The system then calculates:

Reorder Point $(\text{Minimum Stock Weeks} + \text{Lead Time in Weeks}) \times \text{Average Usage}$

Maximum Stock $\text{Minimum Stock Weeks} \times \text{Average Usage}$

Economic Order Quantity

$$\sqrt{\frac{(2 \times \text{order placement cost} \times \text{annual usage})}{\text{inventory holding cost per year}}}$$



Note: Any stockroom balance records found without an associated Item Master or Stockroom Detail record are written to an exception report.

The Stockroom Details record would now include the calculated figures. (In other words, as seen on the Inventory Maintenance screen.)

Functions:

F11

Delete. To delete the matrix.



Press **Enter** to update the stockroom weeks matrix.

Usage Profile Maintenance



This screen is displayed when you press **Enter** on the Stock Weeks Matrix screen.



Note: This would normally be used for stockrooms which cater for manufacturing, rather than for stockrooms that hold finished goods to cater for sales.

Use this screen to create and maintain a set of profiles which can be used to define which historical periods are used in the calculation of average weekly or period usage.

```

IN010                ROBS COMPANY                GBJBARW2    9/11/95
                                           9:41:29

Maintain Company Profile

Usage profile code .. 01
Indicate with a '1' the weeks/months to be included in the calculation of
average usage
This week/
month  -1  -2  -3  -4  -5  -6  -7  -8  -9 -10 -11 -12 -13 -14 -15
      0  0  0  0  0  0  0  0  0  0  0  0  0  0  0
      -16 -17 -18 -19 -20 -21 -22 -23 -24 -25 -26 -27 -28 -29 -30
      0  0  0  0  0  0  0  0  0  0  0  0  0  0  0
      -31 -32 -33 -34 -35 -36 -37 -38 -39 -40 -41 -42 -43 -44 -45
      0  0  0  0  0  0  0  0  0  0  0  0  0  0  0
      -46 -47 -48 -49 -50 -51 -52 -53 -54 -55 -56 -57 -58 -59
      0  0  0  0  0  0  0  0  0  0  0  0  0  0  0

Date last changed    0/00/00

F11=Delete F12=Previous

10-04    SF    MW    KS    IM    II  KENB20A  PET178S2
  
```

Fields:

This Week/Month

Enter 1 against each period (the current and previous 59) you wish to include in the calculation of average usage. Each period may be a week or a month depending on your definition of usage period (see Company Profile). As a result the history may go back one and a quarter years or five years.



Tip: The usage cycle parameter which determines whether the usage is expressed in weeks or months is set on the Company Profile screen.

Date Last Changed

The date last changed is displayed.



Press **Enter** to update the Usage Profile.

Descriptions File



1/STINM

The Descriptions file is used by Style Inventory Management to define valid parameter values for the application.

The system uses parameter files for a number of reasons, for example at data entry time instead of using long repetitive data.

Once set up and checked, parameter files help to ensure that data input is both accurate and acceptable to the system.

An example of the use of the Descriptions file is for the usage cycle. When you set up an Inventory Company Profile you must also set up a Usage Cycle code; this field establishes whether the stock history records should be summarised at a weekly or monthly level.

Description codes are used within Style Production applications to:

- Add user defined reason codes, which indicate why manual adjustments to WIP inventory have been made; why quantities of WIP have been scrapped or held; identifying machine status.
- Define issuing, stocking, purchasing and bundle ticket units of measure. This is an inventory function but codes are required when defining items and bundle ticket types. At minimum a stocking UOM is required.

Descriptions File Maintain Description IDs Screen

 This screen is accessed by selecting the Descriptions option within Inventory Maintenance.

The screen enables the addition and maintenance of the definitions of Major Types. A list of the current Major Types is displayed.

IN037		ST - JBA System Test Company		USER GBJBARW2	8/11/95
					12:28:33
Descriptions File Maintenance					
Description type	TYPE				
Description I.D.	_____				
Low Level Code	_____				
Desc'n. I.D.	Description	Limit			
BUDG	Budget types	30			
CALT	Calendar Type	30			
CANC	Cancellation code	30			
CARC	Carrier Codes	30			
CCCC	Customer class	30			
CDSC	Cash settlement discount	30			
CSTP	Credit stop flags	30			
CTRE	Count Reason Code	30			
DAGL	Discount Account	30			
DAYS	P.notes O/due by X days -limit	30 +			
F3=Exit F15=Lower Level Details					
06-30 SF MW KS IM II KENB20A PET178S2					

Fields:

Description ID

Enter a Major Type to create or maintain.

Low Level Code

Optionally enter a Low Level Code to create or maintain.



Tip: Use page up and page down to display subsequent screens when appropriate.



To display details about a specific Major Type, enter the Major Type and press **Enter**.

Description File Maintenance Codes

To enable the entry and use of parameters, codes which relate to a single function are grouped together. The identifier for a group of codes is called the Major Type. The members of any group are the Descriptions codes. Some of the more regularly used codes are:

ANTP

Article number type.

CANC

Cancellation code. This is a two character reason code used to cancel an order.

CHBN

Charge back number code. This is used to tailor the charge back or debit note field on credit notes. The description should be no more than 20 characters in length. The description is defaulted to Charge back number.

COLS

Colour status. This enables you to link the colour to a style and Sales Analysis.

COLT

Colour type. (Groups of colours.) This is used in Sales Analysis as a report criterion.

CSTP

Credit stop. These are reason codes for customer credit stop.

DCOL

Default matrix colour description. These are no longer used by Style.

DFIT

Default matrix fit description. These are no longer used by Style.

DSIZ

Default matrix size description. These are no longer used by Style.

EMPN

Employee number.



Note: If you choose to confirm picking, you must apply an employee number in Confirm Despatch.

FRGT

Freight terms. These are attached to your supplier using the Vendor Details Maintenance option.

GRAC

Number of days grace. These codes define a customer's grace period with payments.

MISC

Miscellaneous. This holds other major types.

MSKS

Size masks. These are groups of sizes.

MTYP

Movement types. The following have relevance particularly if Style Production is installed:

M - Production Issue.

N - Production Receipt.

O - Transfer Out.

W - Production Adjustment.

MOVR

Movement reason codes. These are required when Style Production is installed and are relevant when booking scrap and held quantities during order and operator booking routines in Production Control. Quantities may be allocated to more than one code during a single session. A default scrap and held reason code are entered on the Organisation Model.

ORTP

Only items that have a line order method of either 0 (Normal) or 4 (Reservation order) will be processed by batch allocation. The items order method is defaulted from the Item Master file to the order line but can be changed at line level at order entry time. If order method is normal, enhanced allocations are determined by the order type. If the order type is set on the Descriptions file not to perform enhanced allocations, the line will be allocated from stock.

Distribution orders will not be able to make use of the back-to-back purchase and works orders and direct delivery. A distribution order will be treated as a normal order (0). In batch allocation only, you may use enhanced allocations for distribution orders by setting the order type (ORTP) in the descriptions file as 0, 1, 2 or 3.

Order types, P/V.

P/V Indicator	Order Entry	Batch Allocation
0	No allocation	Allocate from stock
1	Allocate from stock	Allocate from stock
2	No allocation	Enhanced allocation
3	Allocate from stock	Enhanced allocation
4	Reserve against existing Purchase order	
5	Enterprise order	Enhanced allocation
6	Direct delivery Enterprise order	
7	Rush order	Forces allocation (if stock is available)
8	Special	No allocation

9	Direct Delivery (Not compatible with Enterprise orders)	
B	Blanket order	(Not compatible with Enterprise Direct delivery orders)

If the P/V indicator in the allocation field is set to 2, 3, 5 or 6 enhanced allocations are enabled.



Tip: If you leave the P/V field blank it will default to 1.

Parameter limit = 1

Enhanced allocations reserve against the oldest POs or WOs, starting at the sales order date and reserving against supply orders working up to the sales order due date.

Parameter limit = 0

Enhanced allocations reserve against the newest POs or WOs starting at the sales order due date and reserving against supply orders working backwards to the sales order date.



Note: If a sales order line is deallocated using manual deallocation the change will be reported on the demand exception file.

PACS

Pack status code. If you are using Packaging, this then forms an internal memo on the status.

PATN

Pattern type.

ROUC

Routing codes. These are attached to your supplier using the Vendor Details Maintenance option.

SESN

Season. This is viewed on the Sales Order and Purchase Order Header.

SIZS

Size systems code. These are attached to products to determine which size system they use. For example, British, European, American.

SPTS

Special tasking codes. Set to customers' and orders special pick/pack instructions.

SRCE

Order source. Used in sales analysis only for bespoke queries. It is not used by the system.

SRC1

Source supply types. You can define codes to record how you received a customer's order, these can be reported on using Query.

SUNC

Small order charge. This is used for extended credit checking (in Sales Order Processing).

TASK

Payment method. Optional tasks. This is an override payment code, which can only be used via Application Manager, by authorised users.

VAT

Value Added Tax. You will need to set up the values used in the General Ledger.

WOTF

Works order time fence.

Description File Major Type ID Screen



This screen is displayed if a specific Major Type is selected for maintenance on the Descriptions ID screen and you press **Enter**.

The screen enables the amendment of the major type description and the description limit.

IN037

ST - JBA System Test Company

USER GBJBARW2

8/11/95
12:29:41

Descriptions File Maintenance

Description Type

TYPE

Description I.D.

DIVN

Description

Inventory product division

Description Limit

30

Desc'n I.D.	Description	Limit
BUDG	Budget types	30
CALT	Calendar Type	30
CANC	Cancellation code	30
CARC	Carrier Codes	30
CCCC	Customer class	30
CDSC	Cash settlement discount	30
CSTP	Credit stop flags	30
CTRE	Count Reason Code	30
DAGL	Discount Account	30
DAYS	P.notes 0/due by X days -limit	30

F3=Exit

F12=Previous

F15=Lower Level Details

07-30

SF

MM

KS

IM

II

KENB20A

PET178S2

Fields:

Description

Enter up to 30 alphanumeric characters to describe the Major Type.



Tip: The maximum length is determined by the limit field.

Description Limit

Enter up to two numeric characters which specify how long the descriptions associated with this Major Type will be (maximum value 30).

Functions:

F15

Lower Level Details. Select to add or maintain low level codes for a specific major type.

Descriptions File Low Level Codes (F15) Screen



To display this screen, either select **F15=Lower Level Details** on the Major Type ID screen, or on the Description File Maintain Description IDs screen.

This screen enables the maintenance of valid Low Level Codes for a Major Type. The upper part of the screen contains the details of the Description Code being maintained, the lower part, a list of the current Description Codes for the selected Major Type.

IN037		ST - JBA System Test Company		USER GBJBARW2		8/11/95	
						12:30:00	
Descriptions File Maintenance							
Description Type		DIVN		Inventory product division		Limit 30	
Description I.D.							
1	Desc'n I.D.	Description	Limit	Vat	PV	Rate	
-	A	Clothing				.00	
-	B	Equipment				.00	
-	C	Footwear				.00	
-	D	Apparel				.00	
-	E	Accessories				.00	
-	H	Handbags				.00	
-	M	Mens Shoes				.00	
-	S	Socks				.00	
-	T	Tights				.00	+
F3=Exit F12=Previous							
06-25 SF MK KS IM II KENB20A PET178S2							



Tip: To amend a Description Code enter 1 against the item to be changed.



Tip: To add details, enter a new code and press **Enter** to continue.

Fields:

Description

Enter (up to the limit value as specified for the Major Type) the description associated with the Low Level Code.

Parameter Limit

Enter up to seven numeric characters. This field is for information purposes only within Style Inventory Management.

Rate

Enter up to five numeric characters, two decimals. The rate is used for certain description types, such as extra charges, to define a rate associated with the Major

Type. The nature of the rate is defined by the percentage/value flag specified for this Major Type.

P/V

Enter one of the following:

P - Where the rate is a percentage basis.

V - Where the rate is a value basis.

Vat Code

Enter one character to specify the VAT code, if required. This would typically be used to define VAT codes associated with extra charges.

Functions:

F11

Delete. To delete the Low Level Code.



*Note: The code to be deleted must be selected prior to selecting the **F11-Delete** key. This marks the code for deletion. When the list is reviewed the deleted codes are no longer displayed.*



Press **Enter** to update the Description Code details.

Colour File Maintenance



2/STINM

This procedure creates and maintains all the colour and pattern codes and descriptions that can be attributed to any style that the company may sell.

Colour Master File Maintenance Screen

 This screen is displayed when the Colour File Maintenance option is selected.

It enables you to select the colour code to be maintained.

AP010 ST - JBA System Test Company USER GBJBARW2 8/11/95
12:31:11

Colour Master File Maintenance

Colour code.....?. ?

Colour Code Selection

More +

Code	Description
- A71	Azure/Status
- BLK	Black
- BLU	Bluey
- C&A	C & A
- C38	Cherry/Azure
- C55	Cherry/Thunder
- C76	Cyclamen
- DEB	Debenhams
- F08	Almondish
- F25	Turquoise

1=Select Position to:

F5=Refresh F12=Previous

F3=Exit F4=Prompt

10-46 **SA** **MA** KS IM II KENB20A PET178S2

Fields:

Colour Code

Enter a valid three digit alphanumeric colour code or use the prompt facility to list the codes available and enter 1 against the one you wish to maintain.

You can then amend an existing description, or enter a new description for a new code.

 Press **Enter** to update the details held on the system.

Size File Maintenance



3/STINM

This procedure creates and maintains all the sizes and descriptions across the companies entire style range.



Note: JBA recommend that you take care creating size files. Size files cannot be deleted if they are created with the wrong code length for your style matrix.

Size Master File Maintenance Screen 1



This is the initial screen displayed when the Size File Maintenance option is selected.

It enables the selection of a size to be maintained, within a particular size system. The size system is set up on the company profile and indicates whether the sizes refer to base sizes (UK) or European sizes and so on.

```
AP015                ST - JBA System Test Company      USER GBJBARW2      8/11/95
                                                           12:32:52

Size Master File Maintenance

Size code.....?._
Size system.....?._

F3=Exit  F4=Prompt

06-26  SF  ML  KS  IM  II  KENB20A  PET178S2
```

Fields:

Size Code

Enter a valid alphanumeric size code which can be either one, two, or three characters, or use the prompt facility.



Note: The length of the Size Code you use will depend on the dimension of the Styles you will attach these codes to. Consider the construction of these codes carefully before you add them to the system.

Size System

Enter a valid one digit alphanumeric code. These are defined within Description Codes against SIZS.

Three of the defaults are:

B - Base (UK).

E - European.

U - USA.



Press **Enter** to display the Size Master File Description screen.

Size Master File Maintenance Screen 2



This screen is displayed when **Enter** is pressed once a size file has been selected from the Size Master File Maintenance screen 1.

The screen enables the size description to be maintained.

AP015	ST - JBA System Test Company	USER GBJBARW2	8/11/95 12:33:54
Size Master File Maintenance			
Size code.....	A12	*Add	
Size system.....	B		
Size Code Description..	a12		
F3=Exit F5=Redisplay F8=Update F11=Delete F12=Previous			
08-29	SA	ML	KS IM II KENB20A PET178S2

Fields:

Size Description

Enter up to five alphanumeric characters for the size description.



Tip: Consider setting up size descriptions with leading blanks rather than trailing blanks so that size descriptions line up with quantities within the Style matrix.

Functions:

F5

Redisplay. To redisplay original description.

F11

Delete. To delete the description.

Size Mask File Maintenance



4/STINM

This procedure creates and maintains a size mask that is attached to a style or styles. A size mask is a collection of individual sizes which can be naturally linked together in some way. For example, ladies' dress sizes, men's collar sizes and so on.



Note: A size can be used in many size masks if appropriate. If a particular style has four dimensions (that is. a fitting is included in the product style), then two size masks are used.

Size Mask File Maintenance Screen 1



This screen is displayed when the Size Mask File option is selected.

It enables the selection of the size mask to be maintained.

```
AP020          ST - JBA System Test Company    User GBJBARW2    8/11/95
                                           12:35:36

Size Mask File Maintenance

Size mask code.....?. ?

F3=Exit  F4=Prompt

10-39  SA  MW  KS  IM  II  KENB20A  PET178S2
```

Size Mask Selection

Code	Description	More	+
#1	2 fits		
#2	3 sizes		
AAA	test		
AM1	All Mask 1		
AM2	All Mask 2 - sequenced		
BED	Bed Linen		
BRG	Berghaus Products		
BT1	Bottom Diameter range 1		
CH1	Childrens Age range 1		
CH2	Childrens Age range 2		

1=Select 2=Enquire Position to:
F5=Refresh F12=Previous

The following data is entered:

Fields:

Size Mask Code

Enter a valid three digit alphanumeric or use the prompt facility. These are defined in Descriptions within Style Inventory Management under code MSKS.



Press **Enter** to display the Size Mask Description screen.

Size Mask File Maintenance Screen 2



This screen is displayed when **Enter** is pressed from the initial screen.

It enables the size mask description to be maintained.

```
AP020          ST - Style Test & QA Company      User GBJBARW2      1/06/98
                                           13:37:00

Size Mask File Maintenance

Size mask code..... CH1          Size mask length.....(1,2,3) _
Inclusion type..... _ (0=Same length 1=Upto the length)
Description..... _____

F3=Exit F12=Previous

MA a                                           06/072
```

The following data is entered.

Fields:

Inclusion type

Enter one of the following to limit the search for other size masks to:

0 - Codes of the same length.

1 - Codes of up to the length.

Description

You must enter up to 30 alphanumeric characters for the Size Mask description.

Size Mask Length

If creating a new size mask, the prompt will be displayed for a size mask. Enter a value of 1, 2 or 3.



Note: The value entered will determine which sizes are available for selection. For example, specifying a size mask length of 1 will display 1 character codes such as; S, M, L. A size mask length of 2 will display 2 character codes, such as SM, MD, LG. This is particularly important when defining styles as either 3 or 4 dimensional.

This is explained further in the section on Style Maintenance, Size Selection.



Press **Enter** to display the Size Mask File
Maintenance screen 3.

Size Mask File Maintenance Screen 3

 This screen is displayed when **Enter** is pressed from the Size Mask File Maintenance screen 2.

It enables the selection of sizes (and the sequence they will appear in the matrix) that will be attached to this size matrix. All the sizes and descriptions for all styles that have been created within the system are displayed.

AP020			ST - JBA System Test Company			User GBJBARW2			8/11/95		
Size Mask File Maintenance						*Update			12:37:24		
Size mask CH1 Description Childrens Age range 1											
Seq.	Size	Desc.	Seq.	Size	Desc.	Seq.	Size	Desc.			
<u>10</u>	A02	3-6	---	B04	15MM	---	C10	56DEN			
<u>20</u>	A03	6-12	---	B05	20MM	---	DBL	DBL			
<u>30</u>	A04	12-18	---	B06	25MM	---	D01	1.0MM			
<u>40</u>	A05	18-24	---	B07	30MM	---	D02	1.5MM			
<u>50</u>	A06	2-3	---	C01	50	---	D03	2.0MM			
<u>60</u>	A07	3-5	---	C02	60	---	F01	50/50			
<u>70</u>	A08	5-7	---	C03	75	---	F02	WOOL			
<u>80</u>	A09	7-9	---	C04	2/28	---	F03	100%			
<u>90</u>	A10	9-11	---	C05	1/24	---	HL1	2			
<u>100</u>	A11	11-13	---	C06	1/36	---	HL2	2.5			
---	B01	2MM	---	C07	2816	---	HL3	3			
---	B02	9MM	---	C08	276	---	HL4	3.5			
---	B03	12MM	---	C09	2/72	---	HL5	4	+		

F3=Exit F5=Display F8=Size system F12=Previous

09-02 **SF** **MM** KS IM II KENB20A PET178S2

Fields:

Seq

Sequence Number. Enter up to a three digit number to indicate selection of the size within the size mask. You can select up to 30 sizes.



*Note: The system will re-sequence the selected sizes within the Size Mask when you press **Enter**.*



Press **Enter** to display the Size Mask File Maintenance screen 4.

Size Mask File Maintenance Screen 4



This screen is displayed when **Enter** is pressed from the Size Mask File Maintenance screen 3.

It enables the choice of sizes selected within the size mask to be amended in sequence, or confirmed. The selected sizes and descriptions are displayed in the sequence they were selected.

AP020		ST - JBA System Test Company		User GBJBARW2		8/11/95	
						12:41:50	
Size Mask File Maintenance				*Update			
Size mask AAA Description test							
Seq.	Size	Desc.	Seq.	Size	Desc.	Seq.	Size
<u>10</u>	LG	LONG					
<u>20</u>	MD	MED'M					
<u>30</u>	SH	SHORT					
<u>40</u>	PT	Petit					
F3=Exit F5=Display F8=Size system F12=Previous							
09-02		SF	MM	KS	IM	II	KENB20A PET178S2

The following data may be entered.

Fields:

Sequence

You can blank out the sequence number that is displayed to delete the selected size or the number changed in order to resequence the selected sizes.

Functions:

F5

Display. To display size screen.



Select **F8=Size System** to continue and display Size Mask File Maintenance screen 5.

Size Mask File Maintenance Screen 5 (F8)

 This screen is displayed when you select **F8=Size system** on the Size Mask File Maintenance screen 4.

Use this screen to select multiple size systems.

The sizes that have been selected within the size mask must have been set up (with the same size code) under different size systems with a different description. At order entry time the user can then choose which size system to use when displaying size descriptions within the matrix.

For example:

Size system B (base UK)

Sizes 001 002 003

Desc. 5 6 7

Size system E (European)

Sizes 001 002 003

Desc. 38 39 40

The size systems and descriptions that have been created on the system are displayed. The default size system, as set up on the company profile, is indicated with 1.

AP020		ST - JBA System Test Company		User GBJBARW2	8/11/95
Size Mask File Maintenance				*Update	12:42:25
Select	Size system	Description			
1	B	Base Size System (UK)			
-	E	European Size System			
-	U	US Size System			
1=Select					
F3=Exit F8=Update F11=Delete F12=Previous					
10-04		SA	MA	KS	IM II KENB20A PET178S2

Fields:

Select

Enter 1 against the size systems that are to be attached to the size mask.

Style/Part/Product Maintenance



5/STINM

Use this option to create and maintain styles and materials.



Note: This option is the same option as the Style/Material Details option in Style Production.



Warning: This option behaves differently, according to whether you are creating a new style/material or updating an existing style/material.

Create a new style/material

The option takes you through each screen of fields in turn.

Update an existing style/material

When you have entered the style or material code, a menu gives you access to the screens of fields. See Product Maintenance screen 3 for details.



Note: Warehouse details are only maintained when the Warehouse product is installed. Production Details are only maintained when Style Production is installed.

Prerequisites

When adding a new style or material, you need to set up the following items beforehand:

Set Up The Following Beforehand:	Option	Exceptions
Search Family	Search Family Codes option	Mandatory if using the Style Production module.
One or more colours	Colours option	Materials where the colour is irrelevant, such as hangers and pins.
A size mask to cover the range of sizes	Size Masks option	Styles where the size is irrelevant, such as ties and scarves. Many materials.
A size mask to cover the range of fits	Size Masks option	Styles where the fit is irrelevant, such as ties and scarves and all materials.

Product Maintenance Screen 1

-  To display Product Maintenance screen 1, select Styles from the Style Inventory menu.
-  To display Product Maintenance screen 1, select Style/Material Details from the Style Production Definition Management menu.

Use this screen to enter the style or material that you are adding or updating.

AP035	ST - Style Test & QA Company	User QASTYLE	22/12/97 9:06:52
Product Maintenance			
Style.....?..			
Based on.....?..			
Copy from Company?..			
Source stockroom.?..			
Stockrooms.....?..			
Order method.....?..			
F3=Exit F4=Prompt			
6-22 SA MM KS CL IM DM IT STUD140 KB PED201S1			

Fields:

Style

To maintain an existing style or material, enter the appropriate code. You can search for the style you require by using the prompt facility to access the Item Master Scan window.

To add a new style or material, enter a new code. The Style code provides a unique identifier to each style product and each material. The Style code is a 15 character code and breaks down into the following:

- Style or material. Enter up to nine characters to specify a unique identifier for the style or material (mandatory). This is sufficient for one-dimensional styles and materials where colour and size is irrelevant, such as coat hangers and pins.
- Colour. Up to three characters.
- Size/Fit. Up to three characters. If you are using size only, you can use all three of these characters to describe the size (for example, XXL to describe Extra Large). Otherwise, you need to break down the three characters into size and fit (for example 14L to describe size 14 long).

Enter a unique identifier, together with, where applicable, a colour, size and fit. Style concatenates these code elements to give a full style or material definition.

Based On

To save time when adding similar styles or materials, you can copy from a style or material that Style already recognises.

Use this field to enter a code for the style or material you wish to copy across.

If you are maintaining an existing style/material, leave this field blank.



Warning: Use the Based On field only if you are not going to change the Search Family for the new style or material.

Order method

This field controls the way you handle sales orders. Enter one of the following:

0 - Normal.

1 - Make to order.

2 - Purchase to order.

3 - Deliver direct.

4 - Reserve.

5 - Enterprise order.

6 - Direct delivery Enterprise order.



To display Product Maintenance screen 2, press **Enter** on Product Maintenance screen 1.

Product Maintenance Screen 2

 To display Product Maintenance screen 2, press **Enter** on Product Maintenance screen 1.

For an existing style or material, this screen allows you to modify the style/material description.

For a new style or material, this screen allows you to enter a description for the style/material.

AP035

ST - Style Test & QA Company

User QASTYLE

22/12/97
11:31:12

Product Maintenance

Style.....?. SKIRT01

Style Description.. Leated Skirt

F3=Exit

F12=Previous

F21=Text

F22=Purchase Text

6-57

SA

MM

KS

CL

IM

DM

II

STUD140

KB

PED201S1

Fields:

Style

This field displays the style that you either entered or selected on Product Maintenance screen 1.

Style Description

To help you identify the style/material, enter a meaningful description (up to 17 alphanumeric characters).

Functions:

F21

Text. Enter additional descriptive text. Opens the Maintain Text window.

F22

Purchase Text. If you are adding or updating a purchased style/material, enter any relevant text against purchased styles/materials. Displays Part Text window 3.

 If you are updating a material/style, press **Enter** on Product Maintenance screen 2 to display Product Maintenance screen 3.



If you are adding a new material/style, press **Enter** on Product Maintenance screen 2 to display Product Maintenance screen 4.

Maintain Text Window (F21)



To display the Maintain Text window, select **F21=Text** on Product Maintenance screen 2.

This window allows you to specify where to print and display text by selecting a Usage Code and a Language Code, or both.

AP035 ST - Style Test & QA Company User QASTYLE 22/12/97 13:05:27

Product Maintenance

Style.....?. SKIRT01 Style Description.. Pleated Skirt

Maintain Text
Text Type..... P Part text
Text Reference.. SKIRT01
Usage Code...?..
Language Code?... 00
F4=Prompt F12=previous F13=Select existing Text

F3=Exit F12=Previous F21=Text F22=Purchase Text

14-44 SA MW KS CL IM DM II STUD140 KB PED201S1

Fields:

Text Type

This field allows up to ten combinations of default text/default references to be defined. On this window, the field displays for your information only.

Text Reference

This field displays the reference number given to a text type, which in turn enables default text to be retrieved when no text exists for the usage/language code that you enter.

Usage Code

Enter a valid Usage Code to specify where text is displayed or printed. For more details, refer to the USGC code under the Descriptions option.

Language Code

If you intend to enter multi-lingual text, you can use this field to specify which language you are using.

Functions:

F13

Select existing text. Opens Part Text window 1.




Enter a valid usage code in the Usage Code field on the Maintain Text window to display Part Text window 2.

Part Text Window 1 (F13)

 Select **F13=Select Existing Text** on the Maintain Text window to display Part Text window 1.

This window lists all currently defined Usage/Language code combinations for the text type/text reference. Use the window to select the combination you want to use for entering multi-lingual text.



The screenshot shows a main window titled "AP035 ST - Style Test & QA Company User QASTYLE 22/12/97 13:22:02". Below the title bar, it says "Product Maintenance". The main area contains two fields: "Style.....?. SKIRT01" and "Style Description.. Pleated Skirt". A sub-window titled "Part text" is open, showing "Reference.. SKIRT01" and a table with columns "Sel", "Text Usage", and "Language". The sub-window also has a "1=Select" button and "F12=Previous" text. At the bottom of the main window, there is a line of text: "F3=Exit F12=Previous F21=Text F22=Purchase Text". The bottom status bar shows "1-1 SA MW KS CL IM DM II STUD140 KB PED201S1".

Fields:

Sel

Select. Enter 1 to select a Usage/Language code combination for the text type/text reference.

Part Text Window 2



Enter a valid usage code in the Usage Code field on the Maintain Text window to display Part Text window 2.

Use this window to enter multi-lingual text.

AP035 ST - Style Test & QA Company User QASTYLE 22/12/97 14:13:42

Product Maintenance

Style.....?. SKIRT01 Style Description.. Pleated Skirt

Maintain

- Text Typ
- Text Ref
- Usage Co
- Language
- F4=Prompt

Part text

Lin	Batch	Reference	Text
1			
2			
3			
4			
5			
6			

Position to ___ Insert ___ after ___
Delete ___ from ___

F5=Refresh F8=Update F12=Previous
F13=Change usage/language

F3=Exit F12=Previous F21=Text F22=Purchase Text

12-42 SA MW KS CL IM DM II STUD140 KB PED201S1

Fields:

Lin

Line. Type in the multi-lingual text.

Functions:

F13

Change usage/language. Reopens the Maintain Text window.

Part Text Window 3 (F22)


 Select **F22=Purchase Text** on Product Maintenance screen 2 to display Part Text window 3.

Use this window to enter descriptive text relating to purchasing. You can use this text as an alternative description for this style/material in Style Purchase Management.

This text can provide a more detailed specification of the style/material than is required for internal use.

You can review the text you enter here at order entry time within the Style Purchase Management module.

 *Note: This text entry option is only available if the Style Purchase Management application is installed and is linked to this Style Inventory company.*



The screenshot displays the 'PART TEXT' window. At the top, it shows 'AP035 ST - Style Test & QA Company User QASTYLE 22/12/97 13:29:18' and 'Product Maintenance'. Below this, 'Style.....?. FABRIC03' and 'Style Description.. Woolen fabric' are visible. The main area is titled 'PART TEXT' and contains 'PURCHASE TEXT FOR FABRIC03'. It lists six lines for text entry, with the first line containing 'Purchase monthly'. At the bottom of the window, there are controls: 'Position to ___ Insert ___ after ___', 'Delete ___ from ___', and a row of function keys: 'F3=Exit F12=Previous', 'F5=Refresh F8=Update F12=Previous'. The bottom status bar shows '14-33 SA MW KS CL IM DM II STUD140 KB PED201S1'.

Fields:

Purchase Text For

Type in purchasing text. You can enter up to 99 lines of text.

Product Maintenance Screen 3



If you are updating a material/style, press **Enter** on Product Maintenance screen 2 to display Product Maintenance screen 3.

This screen displays a menu containing up to nine options.

There are certain restrictions on which menu options are available from this screen:

- Colour Select. This option displays only if you have assigned at least one colour code to the style/material.
- Size Mask Select. This option displays only if you have assigned at least one size mask to the style/material.
- Warehouse Details. This option displays only if the Warehousing module is live in the current company.
- Production Details. This option displays only if you are running Style Production and you have defined production details for this style/material.



Warning: Making changes in an option does not save updated details automatically. To save the changes you make to details on a selected option, make sure you press F8=Update before you exit from Product Maintenance screen 3.

AP035	ST - Style Test & QA Company	User: QASTYLE	22/12/97 14:35:49
Product Maintenance			
Style Code..... SKIRT01		Pleated Skirt	
Option.. █	1. Static Part 2. Static Warehouse 3. Warehouse Select 4. Colour Select 5. Size Mask Select 6. Warehouse Details 7. Production Details 8. Maintain Item Search 9. Delete Style		
F3=Exit F8=Update F11=No Update			
7-12 SA MW KS CL IM DM II STUD140 KB PED201S1			

Fields:

Option

Enter one of the following:

1 - Static Part. Use Product Maintenance screen 4 to update Inventory details.

- 2 - Static Warehouse. Use the Stockroom Details Maintenance screen to update Inventory costing and provisioning details.
- 3 - Warehouse Select. Use the Product Code Maintenance Warehouse Selection screen to update stockrooms into which the style/material may be received, and from which it may be issued. Style only allows balances and transactions against the stockrooms you enter here.
- 4 - Colour Select. Use the Product Code Maintenance Colour Code Selection screen to add more colours to the style/material.
- 5 - Size Mask Select. Use the Product Code Maintenance Size Mask Selection screen to update the size masks to cover all the variations in size of the style/material.
- 6 - Warehouse Details. Use the Maintain Item/Warehouse Details screen to identify which warehouses, if any, stock the style/material. You can then issue from these warehouses and receive into these warehouses. This option is only available if you have installed Warehousing.
- 7 - Production Details. Use the Production Details screen to update production details for the style or material. This option is only available if you have installed Style Production.
- 8 - Maintain Item Search. Use the Inventory Item Search Words window to enter search words. This is an Inventory only function.
- 9 - Delete Style. Use the Style Deletion screen to delete the style/material.



Note: If you are entering a new style, the Styles option automatically steps you through these screens.

Functions:

F8

Update. If you have set up the Inventory Company Profile to generate article numbers, Style displays a window from which you can select the styles that numbers will be generated for.

F11

No Update. Exit from Product Maintenance screen 3 without saving your changes.

Product Maintenance Screen 4 (Option 1)

-  To display this screen, enter 1 in the Option field on Product Maintenance screen 3.
-  If you are adding a new style/material, press **Enter** on Product Maintenance screen 2 to display this screen.

Use this screen, together with Product Maintenance screen 5, to enter or update inventory details for the style or material. Inventory details are common to all sizes and colours.

Critical Fields

If you have installed Style Production, the following fields are critical:

- Prod Group Minor.
- Stock Unit (mandatory).
- VAT Code.



Note: In Style Inventory Management, you can request reports and stock counts by the information you enter here under Product Type, Product Class, Prod Group Major and Prod Group Minor.

AP035	ST - Style Test & QA Company	USER QASTYLE	10/03/98 09:58:49
Product Maintenance			
Style Code.....	6210/DS51	Silk skirt	
Spec 1		Effectivity start.....	7/01/98
Spec 2		end.....	0/00/00
Spec 3		Packaging Reporting Style.	0 (0=No 1=Yes)
Product type.....?	—		
Product class.....?	—		
Prod group major.....?	—		
Prod group minor.....?	Q	Clothing	
Division.....?	—		
Sub-division.....?	—		
Purchase pack.....	—	Pricing Level.....	1
Purchase unit.....?	EA	Weight per selling unit..	
Stock unit.....?	EA	Stock->purchase conv.....	1.00000
Issue unit.....?	EA	Issue->stock conv.....	1.00000
Individual Unit.....?	EA	Individual->issue conv...	1.00000
VAT code.....?	A 17.50 %	VAT at product level.....	0 (0=No,1=Yes)
Discount group.....?	—		
Inventory source.....?	—		
F3=Exit F4=Prompt F12=Previous			
7-67	SA	MW KS CL IM DM II	MARVIN KB PED201S1

Fields:

Specification (1 to 3)

These user defined details default through from Style Inventory Management Company Profile.

Effectivity Start/End

Enter an effectivity date range. This is the date that the Product is entered onto the system for the first time.

Packaging Reporting Style

Enter one of the following:

0 - To not report on the packaging usage.

1 - To report on the packaging usage for this company.

Product Type

Enter a product type from those defined under the Descriptions option in Style Inventory Management against Major Type PTYP.

Maximum field length is one character.

Product Class

Enter an item class from those defined under the Descriptions option in Style Inventory Management against Major Type PCLS.

Maximum field length is two characters.

Prod Group Major

Product Group Major. Enter a major item group from those defined under the Descriptions option in Style Inventory Management against Major Type PGMJ.

The maximum field length is three characters.

Prod Group Minor

Product Group Minor. Enter a minor item group from those defined under the Descriptions option in Style Inventory Management against Major Type PGMN. Use these codes to group similar styles into product families for use by Production forecasting. You can also classify like styles/materials for reporting purposes.

The maximum field length is three characters.

Division

Enter a division from those defined under the Descriptions option in Style Inventory Management against Major Type DIVN.

The maximum field length is two characters.



Note: Use the Division and Sub-Division codes to define which division of the company has responsibility for this particular product.

Sub-Division

Enter a sub-division from those defined under the Descriptions option in Style Inventory Management against Major Type SDIV.

The maximum field length is two characters.

Purchase Pack

Enter up to six alphanumeric characters to define the purchase pack of this style or material.

Pricing Level

This field applies to Sales Order Processing. Enter one of the following:

- 1 - Pricing is at style level only.
- 2 - Pricing is at style/colour level only.
- 3 - Pricing is at style/size level only.
- 4 - Pricing is at style/colour/size level only.



Note: For four dimensional styles, where fit is the fourth dimension then:

3 - Pricing is at the Style/Size/Fit level only.

4 - Pricing is at the Style/Colour/Size/Fit level only.

Purchase Unit

Enter a unit from those defined under the Descriptions option in Style Inventory Management against Major Type UNIT.

The purchase unit you enter here provides the default purchase unit at style/stockroom or material/stockroom level.

The maximum field length is two characters.

Weight Per Selling Unit

Enter 11 numeric characters, including four decimals, to specify the weight of a single selling unit.

Stock Unit

Enter a default stock unit from those defined under the Descriptions option in Style Inventory Management against type UNIT (mandatory). The stock unit provides the default purchase and issue units.



Note: The Stock Unit, together with the Purchase Unit and Issue Unit, provide the three valid units of measure for use with this style or material. You will use these units when ordering, moving, stocking and selling this product.

Stock->Purchase Conv

Stock To Purchase Conversion Factor. Enter up to nine numeric characters, including five decimals, to specify the relationship between the stock and purchase units. The default is 1.

For example, if you set Stock Unit to Each and Purchase Unit to packs of 10, then set this conversion factor to 10.

If stock and purchase units are the same, enter 1.

Issue Unit

Enter a purchase unit from those defined under the Descriptions option in Style Inventory Management against Major Type UNIT.

The maximum field length is two characters.

This issue unit you enter here:

- Provides the default issue unit at style/stockroom or material/stockroom level (the unit in which stockholding is expressed for the style/stockroom or material/stockroom).
- Is the common stock unit for this style or material in Purchase Management, which uses this unit to express orders for the same style/material in a common unit where many order units may be used.

Issue->Stock Conv

Issue To Stock Conversion Factor. Enter up to nine numeric characters, including five decimals, to specify the relationship between the issue and stock units.

For example, if you set Issue Unit to Each and Stock Unit to packs of 10, then enter a conversion factor of 10.

If issue and stock units are the same, enter 1.

Individual Unit

Enter the unit item, as defined on the descriptions file against Major Type UNIT, that is used to determine what constitutes an individual unit for an item, for example EA for Each.

VAT Code

Enter a VAT code from those defined under the Descriptions option in Style Inventory Management against Major Type VAT (mandatory).

VAT At Product Level

Enter one of the following:

0 - VAT is at style level only.

1 - VAT is at style/colour/size level.

Discount Group

Enter a discount group, using up to three alphanumeric characters, from those defined under the Descriptions option in Style Inventory Management against Major Type PGR.

If you intend to group this style/material with others for the purposes of discounting, enter the common discount group. You can then specify this discount group against a discount list for the group in the Sales Order Processing and Invoicing Application.

Inventory Source

Enter an inventory source code chosen from those defined under the Descriptions option in Style Inventory Management against Major Type INSC. This field is not currently used within this application.

The maximum field length is one character. The default is 1.



To validate the data, press **Enter**. To display Product Maintenance screen 5, press **Enter** again.

Product Maintenance Screen 5



To display this screen, press **Enter** from Product Maintenance screen 4.

Use this screen to enter more inventory details for the style or material.

Critical Fields

The following field is mandatory:

- Sourcing Warehouse.

If you have installed Style Production, the following field is mandatory:

- Search Family.

AP035		ST - Style Test & QA Company		USER QASTYLE		10/03/98 10:04:11	
Product Maintenance							
Style Code.....		6210/DS51		Silk skirt			
Superseded by.....							
Supersession date.....		0/00/00		Date last changed...		5/02/98	
Costing Method (S,L,A,F) ☒				GL A/C.....		811	
Standard cost.....				Sales GL A/C.....		822	
Latest cost.....				Cost of sales GL A/C		832	
Average cost.....				Price variance A/C..		842	
Base list price.....				Purchasing Officer..		00000	
Price regulator code..?		_ _ %		Sourcing Whse.....		FG	
Price list seq code....		_ _		Matrix type.....		2 (1,2,3,4,5)	
Warranty type.....?		_		Search family.....?		SMS	
Storage method.....?		_		Order Method.....?		0 Normal Ord	
Shelf life unit.....?		_		Cust shelf life.....		_	
Shelf life.....		_		Date..		0/00/00 Ref	
EEC tariff code.....?		_		Inspection reqd.....		0 (0=No,1=Yes)	
Duty %.....		_					
Batch Control (B/L/N).		N					
Sub contract product....		_ _					
F3=Exit F4=Prompt F12=Previous F13=Additional Product Details							
7-27 SA MW KS CL IM DM II MARVIN KB PED20131							

Fields:

Superseded By

Enter 15 alphanumeric characters to specify if the product on display has been or is to be superseded by another style/material. If the product has been superseded then enter the new product number and the supersession date.

Supersession Date

Enter the date on which the style/material was or is to be superseded. This field must be entered if superseded by is entered.

Date Last Changed

The date of the last amendment to the style/material's file.

Costing Method

Enter the default method used to cost styles/materials as received into inventory. You need enter this field only if the costing method for this style or material is not to be the same as the default costing method set up on the company profile. Although

the costing method remains the same in all stockrooms, each stockroom holds its own unique cost; costs may therefore vary between stockrooms.

Style Production does not use the default costs entered on this screen, but references those associated with specific stockrooms when copying material costs, and transferring production costs to inventory.

Enter one of the following:

S - Standard costing.

L - Latest costing.

A - Average costing.

F - FIFO costing.

GL A/C

General Ledger Account Codes. These codes will default to those specified on the company profile.

Standard Cost

[Not used]

Sales GL A/C

Sales General Ledger Account Codes. These codes will default to those specified on the company profile.

Latest Cost

[Not used]

Cost Of Sales GL A/C

Average Cost

[Not used]

Price Variance A/C

This value defaults to that specified on the company profile.

Base List Price

[Not used]

Purchasing Officer

The code of the purchasing officer responsible for the style/material details. If the sales order is for direct delivery or purchase to order the purchasing officer code must be valid. These are defined in Planner Maintenance within Style Purchase Management. This will be attached to sourced requisitions and purchase orders. If you have selected to have this as mandatory on the Style Purchase Management Company Profile, then you *must* enter a code here.

Price Regulator Code

[Not used]

Price List Seq Code

Price List Sequence Code. Enter a five alphanumeric character code for the sequence in which the price lists will be applied.

Sourcing W'hse

Sourcing Warehouse. Enter the warehouse where you store this style or material for issuing out. This field is mandatory.



Note: This warehouse becomes the default warehouse on sales orders placed for this style.

Warranty Type

Enter a warranty type code chosen from those defined on the descriptions file against Major Type WTYP. Examples of warranty types are 24 months guarantee against parts and labour or labour only warranties.

The maximum field length is one character.

Matrix Type

This field determines the validation rules imposed on entering and enquiring on variant quantities within all Style Distribution and Style Production applications.

Enter one of the following:

- 1 - Display 15 size columns and allow quantities of up to 999, without any decimal places.
- 2 - Display 10 size columns and allow quantities of up to 99999 without any decimal places (default).
- 3 - Display six size columns and allow quantities of up to 99999.999 (three decimal places).
- 4 - Numbers up to 999999999 with no decimal places.
- 5 - Numbers with decimal places up to 99999999999.999.

Storage Method

Select an item type from those held on the descriptions file in Style Sales Order Processing against major type PTYP.

Search Family



Warning: If you are using Style Production, this field is mandatory.



Note: To make a style or material one-dimensional (that is, with no colour or size), leave blank.

The field determines the number of dimensions associated with this style or material. Characteristics are related to the dimensions you define for a style or material. For example, if you define colour as a dimension, then red, black and blue might be characteristics of that dimension.

To be able to add style and colour characteristics to the style or material, enter an appropriate search family (that is, with the correct dimensions) set up under the Search Family Codes option in Style Inventory Management. Subsequently, this program prompts for colour codes and size masks according to the number of dimensions set up on the search family that you enter here.

This field defaults to the family set on the Inventory descriptions file, type MISC against subcode DSFC.



Warning: It is essential that you select the correct search family,; as it is not practical to change to a family with more or fewer dimensions once the style/material has been created.

Shelf Life Unit

Enter a shelf life unit code using up to three characters, chosen from those defined on the descriptions file Major Type SHLU. This would normally be days, months or years.

Order Method

Enter one of the following:

0 - Normal. This is the default method. It enables you to sell (that is, allocate) from stock. If there is a stock shortage for the order line you can use any of the other ordering methods.

1 - Make to order. This option enables you to create a back-to-back (make to order) production order which enables you to plan for the stages of manufacture. The lead time for the style/material is added to the time fence days. The time fence days for the stockroom is held on the descriptions file, major type WOFT, minor type set to line stockroom. The number of days is held in the limit field. If no record is held, assume zero days. This procedure calculates the number of working days that would be added to the current date. Non working days and holidays will be taken into account during the calculation. The date of the works order will be changed to be the last working day prior to the sales order due date. This calculation determines the date by which an style/material can be manufactured. A warning will be displayed if this date exceeds the sales order due date. You can override this manually if you wish.

2 - Purchase to order. This option enables you to create a back-to-back purchase order to satisfy a particular order line quantity. Check the style/supplier or material/supplier profile for the lead time and add it to the current date. If the date exceeds the sales order due date a warning will be displayed, which can be overridden manually, if necessary. Ensure that a valid supplier is set up against the style/material; the supplier is used to create requisitions for purchase orders. If no supplier is found for the style/material a warning will be displayed and the requisition, when created, will be available for manual intervention.

3 - Deliver direct. This creates a back-to-back purchase order for direct delivery from the supplier to the customer. It bypasses normal stock allocation for the order line. More than one purchase order may be created for a back-to-back sales order detail line if it is amended. If an order line is assigned a back-to-back order method a requisition will be raised for the order detail line. The requisition will be changed to a purchase order when the create purchase orders option is run in Requisitioning. If the quantity is increased on the sales order detail line, another requisition is created for the increased quantity which will subsequently be turned into another purchase order.

If the sales order detail line is increased or decreased while a requisition is still against the line, that is , before it is turned into a purchase order, the requisition itself will be amended. If the sales order detail line is reserved against only purchase

orders, then the decrease will be reported on the demand exception file but the purchase order will not be changed

4 - Reserve. This option enables you to reserve against an existing production or purchase order. If a manufactured style/material, it will be reserved against works orders. If unable to fully reserve against works orders it will then check for any purchase orders and reserve against those found. If it is not a manufactured style/material reservations will be made against purchase orders. If an order is set to method 0 it will be allocated according to the rules (P/V indicator on ORTP in Descriptions file). If the order method is changed to, for example, method 4, the line will be deallocated and the allocated or outstanding quantity is changed to reserved.

If an order line is to be reserved against purchase or works orders and can only be sourced by supply orders that are beyond its due date a message will be displayed to inform you that of the date that the order can actually be sourced by. This date can be accepted, in which case, the available due date will become the order line due date and the customer's requested due date will display on the sales line as the original due date.

If an order is amended to reduce quantities to lines with reservations, a record is written to the demand exceptions file which can be printed off to highlight differences between supply orders and sales orders as a result of the amendment. If an order is suspended all allocations and reservations will be deleted.

A record will be written to the demand exception file if a variant is amended within an order line that has a reservation against a works order. If the same line is amended but a different variant is changed, the original variant will against be reported on. This is because works order creation is at style level rather than variant level and all the variants on a line are processed for a style line amend.

For all order methods other than Normal (0), the reserved quantity will be set to the ordered quantity equivalent to the outstanding quantity. The reserved quantity will be used to update the customer's outstanding orders value as the line is treated as allocated to the customer if it is reserved which will affect the customer's credit rating and limit.

5 - Enterprise order. This allows you to source the style/material from an enterprise. An enterprise provides the ability to link sales orders to both purchase orders and works orders. This link allows the supplier to be another company within the same enterprise enabling goods to be sourced from that company. Enterprise is particularly useful in multi-company businesses where they operate on a number of physical sites and may have multiple processors and a distributed database. Enterprise orders can be used with enhanced allocation and back to back processing.

6 - Direct delivery Enterprise order. This enables direct delivery processing with the ability to source styles/materials using the Enterprise system.

Certain order method types are incompatible with certain order types, these are shown below:

<u>Order Type</u>	<u>Blanket - B</u>	<u>Rush - 7</u>	<u>Direct - 9</u>
Normal	yes	yes	yes
Make to Order	yes	no	no
Buy to Order	yes	no	no

Reservation	yes	no	no
Direct delivery	no	no	no
Enterprise	yes	yes	no
Enterprise direct delivery	no	yes	no

If the order method is incompatible with the order type, then the order method is set to 0 for normal orders.



Note: If a line is reserved it is not taken off outstanding quantity.

Shelf Life

Enter up to three numeric characters. This is the shelf life of the style/material defined in Shelf Life Units. This is the actual life of the product.

Cust Shelf Life

Customer shelf life is a portion of the total shelf life after which time some action should be taken, that is shelf life of a product may be fourteen days. If customer shelf life was 11 days then after that time you may consider reducing the price. Customer Shelf Life is again expressed in Shelf Life units.

EEC Tariff Code

Enter an EEC tariff code chosen from those defined on the descriptions file against Major Type TAR. If a tariff code has been entered then Duty % is retrieved from the description file entry for the tariff code.

Date

Enter the date on which the tariff classification was agreed.

Ref

References. Enter 12 alphanumeric characters to specify the reference number of the document confirming the EEC tariff classification.

Duty %

Duty is retrieved from the Descriptions file if an EEC tariff code has been entered.

Batch Control

Enter one alphanumeric character to specify the level of control for this style of material. This is particularly relevant to the production applications.

Enter one of the following:

L - Lot. Control stock by manufacturing lot number.

S - Serial Number. Not supported by Style.

B - Bin. Control stock by physical stockroom bin.

N - No batch control. Control of stock by total quantity recorded only.

With the exception of N these methods of batch control require the entry of the appropriate control number when making a stock movement.

Inspection Req'd

Inspection Required.

Enter one of the following:

0 - For this product to be subject to normal despatch procedures.

1 - For this product to be inspected before despatch.

This data is for information only.

Sub Contract Product

This field is only used if Style Inventory Management is linked to Purchase Order Management. Enter up to 15 alphanumeric characters to specify if the product on display is to be booked into stock under another part number. If a sub contract is specified, then any purchase receipts against the maintained product will be booked into stock against the sub contract product.



Note: Maintain bar codes through the Maintain Bar Codes/Alternative Item References option.



Functions:

F13

Additional Product Details. Opens Product Maintenance screen 6 from which you can enter data in additional fields.



To validate the data, press **Enter**. To display the Stockroom Details Maintenance screen, press **Enter** again.



Stockroom Details Maintenance Screen (Option 2)



To display this screen, press **Enter** from Product Maintenance screen 5.



To display this screen, enter 2 in the Option field on Product Maintenance screen 3.

Use this screen to maintain stockroom details for a style or material. Initially, the screen displays details of the stockroom selected on Product Maintenance screen 5, including information on stock control, costs and preferred suppliers for this style/stockroom combination.



Warning: It is not possible to maintain the following defaults once set: re-order point, maximum stock, re-order quantity, re-order factor %, EOQ, standard cost, latest cost, base list price, bin 1 and bin 2.

These values may however be re-set for individual style/colour/sizes in specific stockrooms by using the Style Inventory Management, Full Product Stockroom Details routine.

Fields which can be maintained via this screen are defaults and cannot be set specifically for individual stockrooms.



Note: The following fields defining stock replenishment policies are not used by Style Production: re-order policy, re-order point, maximum stock, re-order quantity, re-order factor %, EOQ.

(MPS) Production Scheduling and (MRP) Material Planning use Style Production's own style/material replenishment policies.

Mandatory Fields

The following field is mandatory:

- Standard Cost.

AP035	H1 - RELAY CLOTHING	User GBJBARUC	9/03/98 12:10:12
Stockroom Details Maintenance			
Product Code.....	SKIRT05	tweed skirt	
Purchase unit.....?	SA		
Issue unit.....?	EA		
Reorder policy (1/2/3).	1		
Profile code.....?	—		
Lead time.....	— .00		
Reorder point.....	— .000		
Maximum stock.....	— .000		
Reorder qty.....	— .000		
Reorder factor %.....	— 0		
E0Q.....	— .000	ABC class override.....	—
Calculate E0Q etc.....	1 (0=No,1=Yes)		
Standard cost.....	— .00000	Suppliers..?.	— —
Latest cost.....	— .00000		
Base list price.....	— .00000	Bins.....	— —
Date changed.....	0/00/00		
F3=Exit F4=Prompt F12=Previous F14=Landed Costs			
6-26	SA	HW	KS CL IM DM II MARVIN KB PED201S1

Fields:

Purchase Unit

Enter a purchase unit chosen from the units of measure on the Item Master Record. This defaults to the purchase unit defined for the style/material. This unit is then assumed as the default purchase ordering unit in the Purchase Order Management application.

Issue Unit

This field identifies the unit of measure (UoM) in which stock is issued. All stock balances and costs for this style/material will be expressed in this unit.

This is the default UoM used when defining a route header (style); and defining input quantities (materials).

Reorder Policy

Enter one alphanumeric character to specify the item's normal reorder policy in this stockroom. The valid codes are:

- 1 - Up To Max.
- 2 - ROQ.
- 3 - Up To ROP.

The code will default to that defined on the company profile.

Profile Code

Enter up to two alphanumeric characters to specify the usage code to be used to define the average usage calculation for this style/material in this stockroom.

Lead Time

Enter up to five numeric characters, including up to two decimals, to define the lead time in weeks for this style or material into this stockroom.

For non-production style/materials, this value is used as the purchasing lead time when calculating production and cumulative lead times. Non-production

style/materials are those style/materials with Style Production, item type codes of P (purchased), B (bought out), and T (consumable tools).

Reorder Point

Enter up to 13 numeric characters, three decimals. This is only required if you do not want the system to calculate this value automatically.

Maximum Stock

Enter up to 13 numeric characters, two decimals. This is only required if you do not want the system to calculate this value automatically.

Reorder Qty

Enter up to 13 numeric characters, three decimals, to specify the reorder quantity. If this value is left as zero, the system will calculate a reorder quantity based on Reorder Factor %. This only applies if Reorder policy -ROQ is specified.

Reorder Factor %

Enter up to three numeric characters, to specify the reorder factor %. This will default to the percentage defined on the company profile. See the sections on company profiles and Stock Movement for an explanation of this percentage.

EOQ

Enter up to 13 numeric characters, two decimals, to specify the Economic Order Quantity.

ABC Class Override

Enter A, B or C classification against the style. Enter Z to ignore classification.

Calculate EOQ Etc.

Enter one of the following:

0 or blank - No. Enter Economic Order Quantity, Reorder Point and Maximum Stock manually.

1 - Yes. Calculate Economic Order Quantity, Reorder Point and Maximum Stock automatically.

Standard Cost

This field is mandatory. Enter up to 15 numeric characters, including up to five decimals, to specify the unit standard cost of one issue unit of the style or material. If you entered S in the Costing Method field on Product Maintenance screen 5, Style uses the Standard Cost to value all stock movements.

This cost is forced on receipt for all purchased styles and materials (including bought out and consumable tools) and for styles and materials transferred from Style Production using this method of costing. To re-set the standard cost for a specific stockroom, use the Full Product Stockroom Details option.

Suppliers

Enter up to four, eight character supplier codes to specify the suppliers of this style/material for this stockroom. The first supplier is used by Requisitioning as the preferred supplier when generating recommended purchase orders.

Latest Cost

Enter up to 15 numeric characters, including up to five decimals, to specify the latest cost. The latest cost is maintained by Style Inventory as the unit cost associated with the last recorded receipt, but may be specified here when you first set up the style/stockroom or material/stockroom.

To set the latest cost for a specific stockroom, use the Full Product Stockroom Details option.

Base List Price

This price is used to value forecasts in Production Scheduling and Material Planning. This price can be re-set for a specific stockroom using the Full Product Stockroom Details routine. This information is also used within Sales Analysis as a report criterion.

Bins

Enter up to two sets of six alphanumeric characters to specify the bins where this style/material is stored in this stockroom. If you require full location management, install Warehousing.



Note: Bin number 1 prints on picking notes and picking notes may be sequenced by this number.

Date Changed

This field displays, for information only, the date the stockroom details were last changed.



Select **F14=Landed Costs** on the Stockroom Details Maintenance screen to display the Landed Costs Entry screen.

Functions:

F14

Landed Costs. For standard cost styles and materials only, displays the Landed Costs Entry screen from which you can select landed costs.



To validate the data, press **Enter**. To display the Product Code Maintenance Warehouse Selection screen, press **Enter** again.

Landed Costs Entry Screen (F14)



To display this screen, select **F14=Landed Costs** from the Stockroom Details Maintenance screen.

Use this screen to set up additional cost elements associated with receiving the goods into the finished goods warehouse. This function is only available for standard cost products.

To copy landed costs for all purchased materials to Style Production, use the Purchased Items Re-Cost option. Such costs are held in up to four user defined cost elements, defined on the Company Profile.



Note: These costs are only available for standard costed style/materials.

Landed Costs Entry		Standard	Perc/
Code	Description	Landed Cost	Value
(?)			(1/0)
FR	Freight	5.00000	1
---		---	-
---		---	-
---		---	-
---		---	-
---		---	-
---		---	-
---		---	-
---		---	-

F3=Exit F4=Prompt F8=Update F12=Previous

12-06 SF MW KS IM II KENB20A PET166S2

Fields:

Cost Code

Enter a valid landed cost code. The relevant description is displayed. A maximum of four costs can be copied to Style Production.

Standard Landed Cost

Enter the cost percentage or value associated with this element. The cost is entered for this additional cost element (five decimal places).

Perc/Value (1/0)

Percentage Values Indicator. Indicates how the landed cost is to impact on the overall cost. Enter one of the following:

0 - Value. Cost is a value to be added to the existing product cost.

1 - Percentage. Cost is a percentage to be added to the existing product cost.

Product Code Maintenance Warehouse Selection Screen (Option 3)

-  To display this screen, enter 3 in the Option field on Product Maintenance screen 3.
-  To display this screen, press **Enter** from the Stockroom Details Maintenance screen.

Use this screen to identify receiving and issuing stockrooms and warehouses. Enter all the valid warehouses that stock this particular style or material.

 **Warning: Once you have assigned a stockroom to a material or style, you cannot remove the stockroom.**

AP03B ZS - Style Demonstration Co. USER GBJBAMS 29/02/96
14:50:16

Product Code Maintenance - Warehouse Selection
Style ELF_B00TS Elfin Boots

Warehouse	Description
E1	Elfin WIP location
FG	Finished Goods Stockroom

Warehouse ..?. __

F3=Exit	F4=Prompt	F5=Refresh	F8=Accept	F11=Remove	F12=Previous	F15=All
21-18	SA	MW	KS	IM	II	KENB20A PET166S2

Fields:

Warehouse

Enter a stockroom set up under the Depot Maintenance option within Style Sales Order Processing. You must select at least one stockroom.

As a minimum, define the primary, sourcing and subcontractor (materials) stockrooms for the style or material. Any code entered must have been defined via the Style Inventory Management Company Profile Maintenance option.

Functions:

F8

Accept. Accept the stockrooms entered during this session and display the Product Code Maintenance Colour Code Selection screen.

F11

Remove. Remove the stockroom entered in the Warehouse field.



Warning: Once you have saved a stockroom, you cannot use this function to remove the stockroom.

F15

All. Allow issuing and stocking from/in all defined stockrooms.



To display the Product Code Maintenance Colour Code Selection screen, select **F8=Accept**.

Product Code Maintenance Colour Code Selection Screen (Option 4)

-  To display this screen, enter 4 in the Option field on Product Maintenance screen 3.
-  To display this screen, select **F8=Accept** from the Product Code Maintenance Warehouse Selection screen.

 *Note: This screen only displays if you enter a Search Family with 2 or more dimensions on Product Maintenance screen 5.*

Use this screen to associate colours with a style or material. You can select up to 300 colours per style.

At a later stage, Style displays the associated colours in matrices, allowing you to discriminate between variants of this style or material.

 **Warning: Once you have assigned and saved a colour, that colour is permanently associated with the style or material.**

AP037 ST - JBA System Test Company USER GBJBARW2 8/11/95
12:55:17

Product Code Maintenance - Colour Code Selection

Style LADYSH/1 Ladies Shoe 1

Seq	Colour	Description
5	001	ALPINE WHITE
10	002	BLUE
15	006	BLACK
20	021	Brown *
25	022	Red *

Colour Code ..?.  Sequence ____

F3=Exit F4=Prompt F5=Resequene F8=Accept F11=Remove F12=Previous

21-20   KS IM II KENB20A PET178S2

Fields:

Seq

Sequence. The sequence code assigned to the colour.

Colour

Enter codes referencing colours appropriate to the style/material. Any code entered must have been defined via the Colours Maintenance routine. A maximum of 20 colours can be specified.

Functions:

F5

Resequence.

F8




Accept. Accept the colours selected.

F11

Remove. Remove colour(s) entered this session. Enter the colour code to be removed in the colour code field and press this function. This function cannot be used once a colour has been saved.



To add a colour to the list, press **Enter**. When you have finished adding colours, select **F8=Accept**. If you entered a 3 or 4-dimensional Search Family on Product Maintenance screen 5, the Product Code Maintenance Size Mask Selection screen displays. Otherwise, the Maintain Item/Warehouse Details screen displays.



- 3-dimensional styles and materials. Associate one size mask with the style or material you are creating or maintaining.
- 4-dimensional styles and materials. Associate two size masks (for example, size and fit) with the style or material you are creating or maintaining.

```

AP035                ZS - Style Demonstration Co.        USER GBJBAMS        29/02/96
                                                                14:52:04

Product Code Maintenance - Size Mask Selection
Style Code..... ELF_BOOTS        Elfin Boots

Size Mask      Description
ELF            Elfin Leather Boot Sizes

Size Mask.?. █

F3=Exit  F4=Prompt  F8=Accept  F12=Previous

21-16    S█      MW      KS      IM      II  KENB20A  PET166S2

```

Size Mask

Note: Size masks contain sizes of up to three characters. If you are including two size masks, you can have a maximum of three characters in

total for the two sizes. Therefore, make sure that the sizes in one size mask are a maximum of two characters each and the sizes in the other size mask are one character each.



Note: You can change the size mask at a future date. However, the new size mask must be compatible with the previous size mask.



To add a size mask to the list, press **Enter**. When you have finished adding size masks, select **F8=Accept** to display the Maintain Item/Warehouse Details screen.

- Use this option to designate location details for warehouse controlled materials and styles, where appropriate.

- Maintain the relationship between inventory units of measure (Stock Keeping Units) and warehousing packing units.
- Define the stock rotation rules.

Tip: If you want to set these details up at a later date, select **F12=Previous**.

Note: This screen only displays when you have Warehousing installed.

Fields:

Date To Be Used For Stock Rotation

This field defaults from the warehouse details. Enter one of the following:

0 - None. No stock rotation.

1 - Receipt W/H. Date Receipt at warehouse.

2 - Receipt Loc. Receipt at location.

3 - Expiry. Expiry date as calculated or input.

Conversion Factor To Measure Warehouse Activity

In many industries there is a standard unit of work. This conversion unit can be used to convert Inventory units to Warehouse Work units.

Unit Of Measure

The unit in which the warehouse activity is measured.

Default Pack

When inventory receipts are made, this becomes the standard pack type.

This is followed by a sub-file display of the pack type relationships that have been set up for the style/material in the warehouse.

Line

The line number of the sub-file entry to be changed.

Warehouse Pack

The pack type which is being set up or maintained.

Quantity/Pack

The quantity of the style/material in the pack.

If the style/material does not have a standard pack type it is suggested that standard units of volume are used, for example pack type/Cubic Meter. The number of style/CM or material/CM can then be defined. The locations can then be set up in Numbers of CMs or Cubic Meters. A unit of weight can also be used.

Functions:

F5

Refresh to screen display or previous **F8** key.

F8

Update. Base records and sub-files.

F12

Returns to the Size Mask Selection screen.

F15

Fixed Locs. The Fixed Locations window opens.

F16

Putaway. The Putting Away window opens.

F17

Commit. The Committing window opens.

F18

Picking. The Picking Location window opens.

F20

Restart. Restart processing without update.

F21

Complete. All updates complete, return to style maintenance option screen.



To create/update the Warehouse record for the style/material, press **F8=Update**.

Fixed Locations Window (F15)

Despite the ability to locate styles/materials randomly it is sometimes desirable to store them in a fixed or a number of fixed locations. For example, engineering spares.

This screen displays a sub-file of fixed locations.

Line

The line number in the sub-file of the location to be amended.

Location

The location selected for use as a fixed location for the style/material. A prompt of locations is available.

Whole Packs

If Yes is displayed it means the application will recommend that whole packs are stored in the location shown.

Split Packs

If Yes is displayed this means the application will recommend that split packs are stored in the location shown.



*Note: When you select **F8=Update**, the changes you have made in the sub-file are written back to the database. If it is not pressed, changes are lost when a different option is selected.*

Putting Away Window(F16)

Use this window to define the processing steps to take when recommending where an style/material should be put. The rules can be defined for whole packs or split packs. The following steps are taken:

- Is it a whole pack or a split pack? (Is the quantity greater than or equal to the quantity defined for the pack?)
- Test Fixed Locations, if defined.
- Test Pick Locations, if required.
- Test Item Rule, if required.
- Test Area Rule, if required.
- Can it be put in the locations?
- Rotation Dates, check.
- Lots, check.
- Will it fit? Does the number of packs exceed the permitted limit? Note this check is valid when only one pack type is stored in a location.

The current data for the style/material is displayed on the screen. If this is an addition, the data from the default Style/material/s Warehouse profile will be displayed.

The conditions can be set for whole packs and for split packs.

Fields:

Multiple Rotation Dates

Are receipts with different rotation dates allowed in the same location?

Multiple Lots

Are receipts with different lot numbers allowed in the same location?

Picking Locations

Should the picking locations be tested?

Putting Away Rules: Item

Item rule to be used. May be selected from a prompt.

Area

The Area rule to be used. This may be selected from a prompt.



Press **Enter** to update the system.

Committing Window (F17)

To define the processing steps taken by the application when you recommend from where a style/material should be picked. Styles/materials are committed using four overriding principles which are:

- Rotation Dates.
- Minimise Lots.
- Picking Location.
- Physical Position.

The current data for the style/material is displayed on the screen. If this is an addition, the data from the default Item/Warehouse Profile is displayed.

Rotation Date

Commit in oldest date first, date can be receipt at warehouse, receipt at location or expiry date.

Minimise Lots

If the style/material is lot controlled, once a lot has been committed, use all of the lot before moving it to another. (This only applies to a single commit action.)

Picking Location

Commit from the picking location quantities up to the control limit.

Committing Rules: Item

The item rule to be used for committing.

Area

The area rule to be used for committing.

Allow Any Location

This is used if all other rules have failed to find the style/material anywhere in the warehouse.



Press **Enter** to update the system.

Picking Location Window (F18)

This function is used to maintain the control data for the picking location. This includes the setting of the trigger for replenishment. The replenishment monitor is triggered by confirmation of picking. If the quantity remaining is less than or equal to the minimum, the committing rules are then used to identify the next stock you require to be moved to the picking location.

In this screen there are two types of data shown, the first defines the picking location, the second sets the replenishment limits.

Picking Location

This can be any valid location in the warehouse.

Maximum quantity to be picked

If the quantity to be committed exceeds this quantity, the whole pack rules for committing are used.

Fields:

Minimum Quantity At Location

If after a confirmation of pick the quantity falls below this level, replenishment is actioned.

Replacement Quantity

The quantity required to replenish the pick location.

Default Resource Code

The resource normally used to move styles/materials from the picking location.



Press **Enter** to update the system.

Production Details Screen (Option 7)



To display this screen, enter 7 in the Option field on Product Maintenance screen 3.



To display this screen, select **F12=Previous** from the Maintain Item/Warehouse Details screen.

Use this screen to enter or maintain production details for the style or material.

The parameters on this screen provide the defaults for the style/material you are creating or maintaining. However, you can change the following fields for individual variants on specific process routes by using the Full Product Details option in Style Production:

- Minor sequence.
- Major sequence.

In addition, you can use the Full Product Details option to update material and user-defined costs 1-4 at the same level.



Note: This screen only displays if you have installed Style Production.

Critical Fields

The following fields are critical:

- Item Type.
- Planning Route.
- Costing Route.
- Planning Type.
- Demand Policy.
- Forecast Level.

DB033	ZS - Style Demonstration Co.	USER GBJBAMS	29/02/96 14:54:59
Item.....: ELF_BOOTS		Elfin Boots	
Item Type: <u>M</u> Manufactured		Specification Ref.... <u>SPEC:7979</u>	
Planner.....?.. <u> </u>		Planning Route..... <u>9</u> Costing Route .. <u>9</u>	
Planning Type..... <u>1</u> (1=MPS)		Demand Policy.....?.. <u>2</u> Gtr of Sales or F/C, +	
Fabric Type.. <u>LEATHER</u>		Smoothing Policy..?.. <u>0</u> No Levelling	
Forecast Level..?.. <u>1</u>		Planning Filter...?.. <u> </u>	
Minor Sequence..... <u>000200</u>		Seasonal Profile..?.. <u>02</u>	
Min Order Qty..... <u>150.000</u>		Max Order Qty..... <u>2000.000</u>	
Mult Order Qty.... <u>.000</u>		Fixed Order Qty..... <u>.000</u>	
Safety Stock..... <u>256.000</u>		No. of days Supply..... <u>0</u>	
Production Lead Time.... <u>.09</u>		Cumulative Lead Time..... <u>49.09</u>	
Primary Stockroom.....?.. <u>FG</u>		Mat'l Control Policy..?.. <u>0</u> Formal issue	
Finished Goods Stockroom			
Order Policy ..?.. <u>A</u> Discrete			
F4=Prompt F11=Delete F12=Cancel F18=Additional Parameters F19=Calc.Production Lead Time F20=Calc.Cumulative Lead Time F21=Text F22=Costs			
08-21	SF	MM	KS IM II KENB20A PET166S2

Fields:

Item Type

This parameter provides a general classification of style/material use. Enter one of the following:

M - Production styles/materials. These may be styles (finished goods) or intermediates used in the production of a style. That is, production styles/materials that appear on lower levels of a route/BOM.

P - Purchased styles/materials. For example: lace, leather, cotton, silk, nylon, linings and so on.

B - Bought out styles/materials. For example: buttons, zips, hangars, suit covers, and packaging materials such as: boxes, laces, labels and so on.

T - Consumable tools. For example: knitting needles, blades, pins and so on.

Codes are defined on the parameter file, against type PITP.



Note: There is no functional difference between item types P (purchased) and B (bought out) other than that the Indented Item Cost Simulation facility enables you to see the effect on a cost explosion of increasing or decreasing purchased and bought out costs; with independent percentages being able to be applied to either or both.

Item types B (bought out) and T (consumable tools) are both regarded by the Planning applications as purchased styles/materials.

This flag may be re-set at style/planning or material/planning route level via Route/BOM Maintenance.

Specification Ref

Enter your own or customer or supplier specification. A maximum of 15 alphanumeric characters may be entered.

Planner

Enter either a buyer or a planner as follows:

- Buyer. For a purchased material or style, enter the buyer responsible for buying the style or material.
- Planner. For a manufactured style or material, enter the planner responsible for planning production of the style or material.

You can use planners in Style Production Planning to sequence MPS and MRP outputs in reports. Also, you can select a planner on planning enquiries, giving you fast access to schedules for styles/materials under the planner's control.

Define planner codes against the PLAN system parameter under the Maintain Parameter File option.



Tip: To change the planner for an individual route, use the Style Route/Bill Of Material option.

Planning Route

For manufactured styles and materials only, enter a planning route to be used by MPS and MRP as a default planning route when suggesting production orders. When you create production orders for this style, Style Production Control nominates this route as the planning route by default. In addition, the Cumulative Lead Time and Production Lead Time fields on this screen use the planning route to calculate lead times when you select **F19=Calc. Production Lead Time** and **F20=Calc. Cumulative Lead Time**.

Cumulative Lead Time.

If you are using multiple plants rather than a centralised plant, leave this field blank. With MPS multi-plant planning, different plants can use different planning routes. Style determines which planning route to use for each plant by matching the Receiving Stockroom for a route on the Style Route Header Maintenance screen with the stockrooms set up for a plant's planning model via the Maintain Model Stockrooms option.



Note: Ensure that you create the Planning Route via the Style Route/Bill of Material Maintenance option.



Warning: If you leave this field blank, Style may recognise a valid planning route. This is because the Style Route/Bill Of Material option allows you to create a route with a blank code.

Costing Route

Enter the route code to use to roll up costs. This route may be used by Style Production re-cost functions to calculate standard and non-standard unit costs; and will be used when calculating the standard cost of an style/material in its primary stockroom. Ensure that this route is defined via Style Route/Bill of Material Maintenance.

Planning Type

This field indicates whether the style/material should be planned as a production style/material (MPS) or as a material requirement (MRP). Enter one of the following.

0 - Material Planning (MRP) style or material (Default).

1 - Production Scheduling (MPS) style or material.

Demand Policy

This field controls the method Style uses to compare the following types of demand in order to arrive at the adjusted or net demand that drives MPS and MRP:

- Sales demand.
- Forecast demand.
- Dependent demand.

The method used to calculate forecast demand is controlled by the Consume Forecast flag on the Company Profile, and affects those policies which utilise Planning or external forecasts. The Consume Forecast flag allows you to adopt either a discrete comparison or a cumulative consumption.

The demand policy set here will also affect what forecast level may be chosen.

Codes are defined on the parameter file, against type MPFF. Enter one of the following codes:

Demand Policies		
Code	Description	Demand Definition
0 or blank	Total actual demand	Sum of sales orders <i>plus</i> dependent demand; no forecast
1	Forecasts compared with independent demand	Greater of (forecast <i>or</i> sales orders) <i>plus</i> dependent demand
2	Forecasts compared with total demand	Greater of (sales orders <i>plus</i> dependent demand) or forecasts
3	Independent demand compared with dependent demand	Greater of sales orders <i>or</i> dependent demand; no forecast
5	Make to forecast	Equal to forecast only; no sales orders or dependent demand
6	Total demand	Total demand; sum of forecasts <i>plus</i> sales orders <i>plus</i> dependent demand



Note: MPS and MRP recognised demand may be excluded from the production schedule or material plan because it offends a demand policy set here. Such demands will be identified on review enquiries and reports by inclusion of an X in the associated supply status code. For

example, WX indicates an excluded production order.



Note: You can override this field for individual routes by using Style/Route Override Maintenance screen 2 under the Style Route/Bill of Material option.

Fabric Type

Use this code to group together styles and materials with the same fabric content, for example, 100% cotton, polycotton, velour and so on. The code is used in the Production Scheduling, Material Planning and Production Control applications for style/material selection and sequencing.

Smoothing Policy

This field contains the demand smoothing policy that MPS and MRP runs use. Enter one of the following:

0 - No smoothing. By default, buckets forecasts into weekly requirements.

1 - Forecast smoothing. Spreads forecasts evenly over each working-day in a week.

Codes are defined on the parameter file, against type FPOL.



This second option carries a substantial machine overhead in terms of disk space requirement and should only be set following careful review of its likely impact on system resources



This flag may be re-set at individual route level via the Route/Bill Of Material option.

Forecast Level

This field determines if the style/material has a forecast and at what level the forecast can be maintained. The code that you enter here must be compatible with the code that you enter in the Demand Policy field on this screen.

Forecasts can be directly maintained at one of the levels described below. Alternatively, they can be spread down to this level from a product family level forecast.

Enter one of the following:

Blank - No forecast required. This setting is only allowed if the style/material's Demand Policy is blank or 0 (total actual demand) or 3 (independent demand compared to dependent demand)

0 - Forecast is maintained at style level. Only allowed for styles/materials with sizes and/or colours.

1 - Forecast is maintained at the style/colour level. Only available for 2-dimensional styles/materials.

2 - Forecast is maintained at the variant level. Only available for 3-dimensional and 4-dimensional styles/materials.

Codes are defined on the parameter file, against type DEMP.



Note: If you set the Forecast level to 0 on your styles, then you can enter forecasts at the style

level rather than for each variant. Subsequently, use the Generate Variant Forecast option to spread the forecast down to variant level.

Planning Filter

This entry specifies the style/material's default rescheduling policy during MPS and MRP processing. These sensitivity policies determine whether or not production orders at a particular status can be rescheduled, or if the order quantity can be increased or decreased.

They also provide the facility to exclude recommendations for insignificant or unworkable changes to the quantity or due date of the supply (order).

Enter one of the following:

Blank - No special conditions apply.

Non-Blank - A parameter code is generated by utilising the filter character as a suffix to the order status. The status/filter combination refers to a particular set of processing rules which must be obeyed in preference to the default rules by MPS and MRP processing. Each filter character must be specifically defined against each order status.

Production order status codes are as follows:

41 - Planned.

42 - Confirmed.

43 - Released.

44 - Active.

For example: if a planning filter character of S is entered, when a production order is confirmed, it will have a status of 42S. The effect this will have on Planning recommendations will depend on how you have defined S. It may be, for example, confirmed, cannot cancel or no changes allowed.

Filters are specific to an order status, but may be applied to any style/material. If a filter is not defined via Parameter File Maintenance, entering a code here will have no effect on the planning process.

Codes are defined on the parameter file, against type WTYP.



Note: This filter can be reset for a specific production order when creating or maintaining an order, and via the Production Scheduling and Material Planning reviews.



Note: This flag may be re-set at individual route level via the Route/Bill Of Material option.

Minor Sequence

This field is used to determine the sequence in which styles/materials are processed at a machine.

This is useful if, for example, if you have a mixing process where products range in colour from light to dark, in order that light coloured styles/materials are sequenced ahead of dark; or to sequence styles/materials with a long set up time ahead or following those with short set up times; or sequence high quality output ahead of low.

This field may also be used in conjunction with the Major Sequence field prompted in the Additional Details window, which is used to group similar styles/materials so that they may be planned and scheduled together; with the processing of styles/materials within the group sequenced by the code entered here.

Enter one of the following:

Blank - Assume no special sequencing is required.

Sequence - Enter up to six characters to define the sequence number for this style/material.



Note: Although this is the default setting for a style, the sequence can be re-set at style/colour/size level for individual process routes via the Full Product Details routine.



Note: This flag may be re-set at individual route level via the Style Route/Bill Of Material option.

Seasonal Profile

Optionally, enter a default seasonal profile for the style/material for use in Production Scheduling and Material Planning forecasting routines. Profile codes are defined via the Maintain Seasonal Indices function within the Forecast Management application.

Min Order Qty

Minimum Order Quantity. This value is used at the variant level with ordering policies B (discrete above minimum) and H (multiples above minimum) in MPS and MRP to set the minimum quantity for a suggested supply order.



Note: This flag may be re-set at individual route level; and at the item variant/planning route level via Route/BOM Maintenance.

Max Order Qty

Maximum Order Quantity. This value is the maximum supply order quantity which should normally be provisioned. It is used at the variant level as an advisory field by MPS and MRP. If a suggested order quantity exceeds this value, the system will flag the order for the planner's attention by:

- Printing Above Max on the Material Planning, Recommendations Report.
- Printing an asterisk * against the production order on the Production Scheduling Schedule Report and the Material Planning Material Plan Report.
- Highlighting the production order on the Production Scheduling, Review Production Schedule and Material Planning, Review enquiries.



Note: This flag may be re-set at individual route level; and at the item variant/planning route level via Route/BOM Maintenance.

Mult Order Qty

Multiple Order Quantity. The value entered is used at the variant level in conjunction with order policy code H (multiples above minimum). The effect is to increase the suggested order value in increments of the multiple above minimum order quantity, to meet the demand.



Note: This flag may be re-set at individual route level; and at the item variant/planning route level via Route/BOM Maintenance.

Fixed Order Qty

Fixed Order Quantity. This is the quantity used at the variant level by MPS and MRP to generate suggested supply orders for each variant using order policy D (fixed quantity).

If the requirement is greater than the fixed quantity, additional batches of the fixed quantity will be generated until the requirement is met.



Note: This flag may be re-set at individual route level; and at the item variant/planning route level via Route/BOM Maintenance.

Safety Stock

Where there is a requirement to retain a safety or buffer stock, enter a quantity at variant level. This figure will be the target inventory level maintained by MPS and MRP.



Note: This flag may be re-set at individual route level; and at the item variant/planning route level via Route/BOM Maintenance.

No Of Days Supply

Number Of Days Supply (Period Cover). The system can look forward a number of days to determine the requirements to be covered by a suggested order. This is used in conjunction with order policy code G (number of days supply).



This flag may be re-set at individual route level; and at the item variant/planning route level via Route/BOM Maintenance

Production Lead Time

This is the production, or this level lead time for the style/material which represents the time *in days* required to produce it, from its components and/or raw materials.



Note: This flag may be re-set at individual route level; and at the item variant/planning route level via Route/BOM Maintenance.

The lead time may be entered manually, or calculated by the application from the designated planning route and standard lot size, by invoking **F19=Calc. Production Lead Time**; or from within Route/BOM maintenance when defining the style/material's planning route. If the Use Item Time Fence option is selected when running MPS and MRP, in preference to the default global option, the production lead time is used to establish the frozen schedule time fence for the style/material.

Cumulative Lead Time

This represents the total time required, *in days*, to produce the style/material based on a full explosion of its planning route, including any low level production styles/materials included on the route; and the purchasing lead time of materials and any bought out components.



Note: Purchasing lead times are taken from the Static Stockroom, Lead Time field defined for the style/material.



Note: This field may be re-set at individual route level via Route/BOM Maintenance.

The time is calculated from the longest leg or critical path of the production and procurement process. The lead time may be entered manually or calculated by the application from the designated planning route and standard lot size, by invoking **F20=Calc. Cumulative Lead Time**.

If the Use Item Time Fence option is selected when running MPS and MRP, in preference to the default global option, the production lead time is used to establish the planning horizon for the style/material. For non-production styles/materials, the calculation will return the purchasing lead time.

Primary Stockroom

Multiple stockrooms may be defined for an style/material. The primary stockroom will be used as the default in all issuing and receipt activities for this style/material. The default may be overridden during transaction processing and route definition, if required.

Mat'l Control Policy

Material Control Policy. This parameter defines the way this style/material will be issued to production. Enter one of the following:

0 - Formal issue against a production order.

1 - Backflushed. These styles/materials have stockroom balances reduced by standard requirement quantities when a quantity is booked at a route count point. This removes the need to record a formal issue transaction against a production order and is commonly used for bulk issue styles/materials. Lot controlled styles/materials cannot be backflushed. Subcontractor materials should be assigned this policy.

2 - Actual issue. These styles/materials must be formally issued.

3 - Issue to floor stock. Material issuing of such an style/material creates a reservation at a designated holding area (floor stock location) associated with the machine defined on the operation at which the material(s) is required; (entry of a floor stock location is mandatory when defining a machine). When floorstock material is used it must be recorded via a material usage window, opened automatically when booking work at an operation where such styles/materials are a standard input. Such styles/materials are generally lot controlled. Materials defined as key styles/materials (which must also be lot controlled) on a route should be assigned this policy.

Codes are defined on the parameter file, against type BLKI.

Order Policy

Supply order policies are used by MPS and MRP to govern suggested order replenishment quantities.

Enter one of the following:

A - Discrete (lot for lot). This policy will produce a suggested order quantity equal to the demand quantity (default).

B - Discrete above minimum. This policy will generate a suggested order quantity to meet the requirement that will be at least as large as the stipulated minimum order quantity. If the requirement is less than the minimum, the suggested order will be equal to the minimum quantity.

D - Fixed quantity. This policy creates one or more orders of a fixed quantity (same due date), until the requirement is met.

G - Number of days supply (period cover). This policy accumulates forward requirements over the specified number of days and generates a single order to satisfy the total demand.

H - Multiples above minimum. This policy considers two parameters. A minimum quantity will be generated and any unsatisfied requirement above the minimum will be met by increments of the defined multiple order quantity. Variants should be defined with this policy via Route Overrides Maintenance, if the standard style is defined with order policy I (multiples up to a maximum)

I - Multiples up to a maximum. For use at style level only. The total of the variants is compared to the multiple and maximum order quantities defined for the style. If the total exceeds the maximum, then an order will be split into two or more separate orders. If the total is not divisible by the multiple, then later supply will be brought back until the next multiple is reached. Variants should be defined with order policy H (multiples above minimum), with its multiple the same or a direct division of the style multiple, via Route Overrides Maintenance within the Route/BOM Maintenance option.

Codes are defined on the parameter file, against type POPC.



Note: This flag may be re-set at individual route level; and at the item variant/planning route level via Route/BOM Maintenance.

Functions:

F18

Display the Additional Parameters window.

F19

Calculate production lead time; the Production Lead Time field updates automatically.

F20

Calculate cumulative lead time; the Cumulative Lead Time field updates automatically.

F21

Text. Enter additional descriptive text.

F22

Costs. Display the Cost Set Selection window, listing style/material costs for review. This is the same as the Item Cost Maintenance option.



To validate the data, press **Enter**. To display Product Maintenance screen 3, press **Enter** twice.

Additional Parameters Window (F18)



To display this window, select **F18=Additional Parameters** on the Production Details screen.

Use this window to define a material's material type and to make a material ratio-based.

DB033		ZS - Style Demonstration Co.		USER GBJBAMS		29/02/96	
						14:54:59	
Item.....: ELF_BOOTS				Elfin Boots			
Item Type: <u>M</u> Manufactured				Specification Ref.... <u>SPEC:7979</u>			
Planner.....?..				Planning Route..... <u>2</u> Costing Route .. <u>2</u>			
Planning Type..... <u>1</u> (1=MPS)				Demand Policy.....?.. <u>2</u> Gtr of Sales or F/C, +			
Fabric Type.. <u>LEATHER</u>				Smoothing Policy..?.. <u>0</u> No Levelling			
Forecast Level..?.. <u>1</u>							
Minor Sequence..... <u>000200</u>							
Min Order Qty..... <u>150.000</u>							
Mult Order Qty.... <u>.000</u>							
Safety Stock..... <u>256.000</u>							
Production Lead Time.... <u>.09</u>							
Primary Stockroom.....?.. <u>FG</u>							
Finished Goods Stockroom							
Order Policy ..?.. <u>A</u> Discrete							
				Additional Parameters Major Sequence..... <u>BOOTS</u> Material Type.....?.. <u>-</u> Material Usage Policy?.. F4=Prompt F12=Previous			
F4=Prompt				F11=Delete F12=Cancel F18=Additional Parameters			
F19=Calc.Production Lead Time				F20=Calc.Cumulative Lead Time F21=Text F22=Costs			
16-62		SF		MW		KS IM II KENB20A PET166S2	

Fields:

Major Sequence

Styles/materials may be grouped under a common heading so that they might be planned and scheduled together, in the order set by the minor sequence defined on the Maintenance screen.



Note: This is the default setting for a material, the sequence can subsequently be re-set at style/colour/size level for individual process routes via the Full Product Details routine



Note: This flag may be re-set at individual route level via the Route/BOM Maintenance option.

Entries made will be validated against type PRSQ on the parameter file. This is a user-defined parameter.

Material Type

This parameter defines an style/material's material type, and determines which cost element it will be accumulated into. Enter one of the following:

0 or Blank - Fabric. The style/material is a single dimension material. Any costs associated with the style/material when used on a bill of material will be assigned to the Fabric cost element.

1 - Trim. The style/material is a single dimension trim or accessory style/material. Any costs associated with the style/material when used on a bill of material will be assigned to the Trim cost element.

2 - Packaging. The style/material is a single dimension packaging material. Any costs associated with the style/material when used on a bill of material will be assigned to the Packaging cost element.

3 - Fabric group. The style/material is a multi dimensional material. Any costs associated with the style/material when used on a bill of material will be assigned to the Fabric cost element.

4 - Trim group. The style/material is a multi dimensional trim or accessory style/material. Any costs associated with the style/material when used on a bill of material will be assigned to the Trim cost element.

5 - Packaging group. The style/material is a multi dimensional packaging material. Any costs associated with the style/material when used on a bill of material will be assigned to the Packaging cost element.

Codes are defined on the parameter file, against type MATP.

Material Usage Policy



Note: This field is only prompted for fabric, trim and packaging group styles/materials.

The setting of this parameter defines how the material quantity is determined when this style/material is specified on a bill of material.

Enter one of the following:

0 or Blank - Quantity Per based. Prompt for variant material quantity. During Route/BOM entry you will be prompted for the quantity per of this material that is required to make each variant of the parent style. Set up these quantities on the Material Quantity Requirements window in Style Route/Bill of Materials.

1 - Ratio-based. Auto-calculate variant material quantity. During route/BOM entry, the quantity per for each variant will be calculated automatically based upon user-defined (on relevant route/BOMs) material usage factors and the quantity per specified for the primary style/material. Set up these quantities on the Enter Material Usage Factors window in Style Route/Bill of Materials.

Codes are defined on the parameter file, against type IDXS.

Cost Set Selection Window (F22)



To display this screen, select **F22=Costs** from the Production Details screen.

Use this window to select a cost set for review. You can then review costs for the style or material.

```

DB033                H1 - RELAY CLOTHING                USER GBJBSPD    16/04/98
                                                           10:30:19

Item.....: 79002                Skirt
Item Type: M Manufactured        Specification Ref....
Planner.....?.. PD1                Planning Route..... 1 Costing Route .. 1
    Paul Duncan
Planning Type..... 1 (1=MPS)        Demand Policy.....?.. 6 Total Dmnd (F/C+Sales+
Fabric Type..                Smoothing Policy..?.. 0 No Levelling
Forecast
Minor Se
Min Orde
Mult Ord
Safety S
Producti
Primary
Fi
Order Po

Cost Set Selection
      02
S Rte C.Set Description                Recosted  Changed
- 1 Standard                        3/11/97  3/11/97
- 1 BUNDLE                        31/10/97 31/10/97
- 1 NEW Amended cost of 79002        13/02/98 26/03/98

1=Select
F12=Previous
F19=Calc.Production Lead Time F20=Calc.Cumulative Lead Time F21=Text F22=Costs

MA a                MW                15/013
  
```

Fields:

S

Select. To display the Item Cost Maintenance screen, enter 1 against a cost set.

Inventory Item Search Words Window (Option 8)

- To display this window, enter 8 in the Option field on Product Maintenance screen 3.
 - To display this window, press **Enter** from the **F8=Update** window.
- Use this window to enter search words for the style or material.

AP035

H1 - RELAY CLOTHING

User: GBJBARUC

9/03/98
16:25:19

Product Maintenance

Style Code..... SKIRT05

tweed skirt

Option... 8

1. Static Part

2. Static Warehouse

3. Warehouse Select

4. Colour Select

5. Size Mask Select

7. Production Details

8. Maintain Item Search

Inventory Item Search Words

Item Key Words:

Item Reference: SKIRT05

TWEED

SKIRT

F12=Previous

F13=Old Index

F3=Exit

F8=Update

F11=No Update

16-12

SA

MM

KS

CL

IM

DM

II

MARVIN

KB

PED201S1

- Press **Enter** to submit a batch job to update the variants for the style or material with the entered information. You then return to Product Maintenance screen 1.

Style Deletion Screen (Option 9)



To display this screen, enter 9 in the Option field on Product Maintenance screen 3.

Use this screen to delete the style or material. The screen shows the current stock and order position for this style/material and indicates whether it has ever been bought, sold or manufactured.

You can delete a colour or size associated with a style. You can also delete a style or material from a single stockroom only.

This screen is displayed when deletion of active styles (those that have been bought, sold or stocked) is allowed. This is controlled by the Delete Active Styles Flag on the Style Sales Order Processing company profile.



Note: You cannot delete a style/material if any one of the following circumstances is current:

- *If a style, there are still route/BOMs defined for the style.*
- *If a material, the material is still input to a route/BOM.*
- *There is a current production order for manufacture of the style or material.*
- *If a material, the material is a requirement on a production order.*

AP035D	H1 - RELAY CLOTHING	User GBJBARUC	9/03/98
Style deletion			16:28:17
Style.... SKIRT05		Where used:	
		Sales Orders.....	No
		Works orders.....	No
		Purchase Orders..	No
----- Quantity ----->			
Stkr	Physical	Sales order	Purchase order
			In transit
(There are no stockrooms for this style or colour)			
4=Remove from Stockroom 5=Physical 6=Sales Order 7=P/O 8=In-Transit			
F3=Exit F11=Delete F12=Previous			
1-1	SA	MM	KS CL IM DM II MARVIN KB PED201S1

Fields:

Untitled

Option. This field controls processing of a style within a particular stockroom. Enter one of the following:

4 - Remove From Stockroom. This is only available when all stock figures in the stockroom are zero.

5 - Physical. View physical stock in the stockroom.

6 - Sales Order. View sales order quantities against this stockroom.

7 - Purchase Order. View purchase order quantities against this stockroom.

8 - In Transit. View stock in transit to this stockroom.



*Note: To see the orders associated with any non-zero figures use **F13=Colour Select** for stock availability when the matrix is displayed. Position the cursor on the desired colour size then select **F13=Colour Select**.*

Functions:

F11

Delete. Press **F11=Delete** twice to delete the style or material.



*Note: Deletion of a style by pressing **F11=Delete** is only available when all stock figures are zero and no outstanding orders exist.*

F12

Return to Item/Warehouse Details screen.

F13

Colour select. Opens the Colour Code Selection window, displaying all colours for the current style and allows selection of a single colour.

F8=Update Window (F8)



To display the F8=Update window, select
F8=Update from Product Maintenance screen 3.

Use this window to generate article numbers.

```
AP035                ST - Style Test & QA Company      User QASTYLE      2/07/97
                                           9:48:00

Product Maintenance
Style Code..... H002                Sweatshirt

Option..  _

1. Static Part
2. Static Warehouse
3. Warehouse Select

6. Warehouse Details
7. Production Details
8. Maintain Item Search

Do you wish to generate article numbers for
style H002      ? 0 (0=No, 1=Yes)

Enter=Continue      F12=Previous

-----
F3=Exit  F8=Update  F11=No Update

16-47  SP  MW  KS  IM  II  KENB20A  PE9106S2
```

Fields:

Do You Wish To Generate Article Numbers For Style?

Enter one of the following:

0 - No. Do not generate article numbers.

1 - Yes. Generate article numbers.



Press **Enter** to display the Inventory Item Search
Words window.

Alternative Products

1... **2...** 6/STINM

This procedure enables alternatives to be identified for styles/products. This relationship may be reversed or it may not. It is possible to define the nature of the relationship on the single screen. This information can be used by operators of the Sales Order Processing application to offer alternatives to the customer if the original choice of product is not available, or if you wish to phase out an older product and introduce the new one in its place.

Alternative Product Code Maintenance Screen 1



This screen is displayed when the Alternative Product Code option is selected.

The purpose of this screen is to enable the selection of the product number for which alternatives are to be maintained.

IN006	ST - JBA System Test Company	USER GBJBARW2	8/11/95 13:49:23
Alternative Product Code Maintenance			
Product Code...?. _____			
F3=Exit F4=Prompt			
05-21	SA	MM	KS IM II KENB20A PET178S2

Fields:

Product Code

Either enter the style number for which you wish to maintain alternatives, or the full style/colour/size/fitting code, if known.



Press **Enter** to display the Alternative Product Code Maintenance screen 2.

Alternative Product Code Maintenance Screen 2



This screen is displayed when **Enter** is selected on the Alternative Product Code Maintenance screen.

The purpose of this screen is to create and maintain the Alternative relationships between a style once the style has been selected. A list of valid alternatives for the style is displayed. If the relationships are reversed then this is indicated. For each alternative, the following is displayed.

IN006 ST - JBA System Test Company USER GBJBARW2 8/11/95
13:54:44

Alternative Product Code Maintenance

Product Code..... LADYSH/2 Ladies Shoe 2

Alternative Product Code.?.	Description	Reverse? (0=No,1=Yes)
_____	_____	-
_____	_____	-
_____	_____	-
_____	_____	-
_____	_____	-
_____	_____	-
_____	_____	-
_____	_____	-
_____	_____	-
_____	_____	-
_____	_____	-
_____	_____	-
_____	_____	-
_____	_____	-
_____	_____	-

F3=Exit F4=Prompt F12=Previous
09-03 SF MK KS IM II KENB20A PET178S2

Fields:

Alternative Product Code

Enter up to 15 alphanumeric characters which specify the product number of the alternative product. The alternative product must be defined on the product file.

Reverse?

Enter one of the following:

- 0 - If the product substitution is not reversible. In this case a 38 inch leather belt might be an alternative item for a 34 inch leather belt - it could be cut - but if someone specifically wants a 38 inch leather belt, you could not supply a 34 inch leather belt.
- 1 To reverse the product substitution. In this case an associated record is set up for the alternative product. For example, one type of leather belt-item 0102 - is completely interchangeable with another item - 0101; that is, item number 0101 will be recorded as a functional alternative of 0102 as well as vice-versa.

Alternative product relationships may be deleted by removing the alternative from the list.



Press **Enter** to display the product descriptions of the product entered, and **Enter** again to update the file and return to the first screen.

VAT Codes At Full Product

1... 7/STINM **2...**

This procedure allows maintenance of the default VAT Code set against a style (in Style Maintenance) at the colour and size level.

This procedure involves the Select and Matrix screens.

VAT Code Maintenance Screen



This screen is displayed when the VAT Code option is selected.

It enables the selection of the style number to be maintained.

```
AP105          ST - JBA System Test Company    User GBJBARW2    8/11/95
                                           14:02:41

Vat Code Maintenance

Style.....?. _____

F3=Exit  F4=Prompt

06-22    SA    MK    KS    IM    II    KENB20A    PET178S2
```

The following data is entered.

Fields:

Style

Enter a valid style number or use the prompt facility.



Press **Enter** to display the VAT Code Maintenance Matrix screen.

VAT Code Maintenance Matrix Screen



This screen is displayed when Enter is selected from the VAT Code Maintenance screen.

The default VAT Code against each colour/size/fitting option of the selected style.

The following data may be entered.

Fields:

VAT Code

Override the displayed VAT Code with a valid VAT Code, that must exist on the Descriptions File (type VAT).



Press **Enter** to validate code.

Calendar



8/STINM

This procedure enables the maintenance of the current week, period and year number for the Inventory company. Calendars are used to run many background functions.

Once set up, these calendars are maintained by the week, period and year update routines within Style Inventory Management Utilities.

Maintain Calendar File Screen

 This is displayed when the Maintain Calendar File option is selected.

The calendar details must be created initially when the system is set up, but after this the current calendar position is maintained automatically by the week, period, and year batch update jobs. It should never be changed manually during the course of the year, except under exceptional circumstances where a re-run of the week, month, or year end update is necessary.

IN012 ST - JBA System Test Company USER GBJBARW2 8/11/95
14:03:26

Maintain Calendar File

Current year..... 87
Current week..... 18
Current period..... 6
No. of weeks this year..... 52
No. of weeks last year..... 52
No. of periods this year... 12

F3=Exit F11=Delete

06-30 SF MK KS IM II KENB20A PET178S2

Fields:

Current Year

Enter up to two numeric characters which specify the current year.

Current Week

Enter up to two numeric characters which specify the current week.

Current Period

Enter up to two numeric characters which specify the current period.

No Of Weeks This Year

Enter up to two numeric characters which specify the number of weeks this year.
The value entered must be less than or equal to 53.

No Of Weeks Last Year

Enter up to two numeric characters which specify the number of weeks last year.
The value entered must be less than or equal to 53.

No Of Periods This Year

Enter up to two numeric characters which specify the number of periods this year.
The value entered must be less than or equal to 13.



*Note: This information is linked to Sales Analysis
Company Profile and Forecasting Company
Profile Period/Backups Details.*



When you press **Enter**, the calendar is updated
with the changes are made automatically.

Period/Week End Control



9/STINM

This procedure enables the maintenance of the period and week end dates. These are used within the application to stamp movements and update history records with the correct year, period and week number. The procedure is normally used only when the system is initially set up, and to create dates for future years.



Tip: A period can be defined in a variety of different ways, but normally refers to a month.

Inventory Period End Control Maintenance Screen 1



This is displayed when the Inventory Period End Control option is selected.

The first screen enables the selection of the year number and period type for which end dates are to be maintained.

IN062	ST - JBA System Test Company	USER GBJBARW2	8/11/95
Inventory Period End Control Maintenance			14:04:12
Year	00	Type	_ (1=Weekly,2=Monthly)
F3=Exit			
05-13	SP	MM	KS IM II KENB20A PET178S2

Fields:

Year

Enter the year number of the year for which end dates are to be maintained.

Type

Enter one of the following to maintain end dates:

1 - Weeks.

2 - Periods.



When you press **Enter**, the maintenance screen is displayed for the selected year and period type.

Inventory Period End Control Maintenance Screen 2



This screen is displayed when you press **Enter** on the first maintenance screen after you have selected the year and period type.

It enables the maintenance of end dates for a selected year and period type (week or period).

The current period/week end values are displayed.

IN062		ST - JBA System Test Company		USER GBJBARW2		8/11/95 14:04:12	
Inventory Period End Control Maintenance							
Year 94		Type 1		(1=Weekly,2=Monthly)			
Week	End date	Week	End date	Week	End date	Week	End date
01	0/00/00	15	0/00/00	29	0/00/00	43	0/00/00
02	0/00/00	16	0/00/00	30	0/00/00	44	0/00/00
03	0/00/00	17	0/00/00	31	0/00/00	45	0/00/00
04	0/00/00	18	0/00/00	32	0/00/00	46	0/00/00
05	0/00/00	19	0/00/00	33	0/00/00	47	0/00/00
06	0/00/00	20	0/00/00	34	0/00/00	48	0/00/00
07	0/00/00	21	0/00/00	35	0/00/00	49	0/00/00
08	0/00/00	22	0/00/00	36	0/00/00	50	0/00/00
09	0/00/00	23	0/00/00	37	0/00/00	51	0/00/00
10	0/00/00	24	0/00/00	38	0/00/00	52	0/00/00
11	0/00/00	25	0/00/00	39	0/00/00		
12	0/00/00	26	0/00/00	40	0/00/00		
13	0/00/00	27	0/00/00	41	0/00/00		
14	0/00/00	28	0/00/00	42	0/00/00		
ENTER=Validate F3=Exit F8=Update F12=Previous							
08-10		SA	ML	KS	IM	II	KENB20A PET178S2

Fields:

End Date

Enter valid dates for the week or period end dates. Where this is the initial set up of end dates for a particular year, only the first date needs to be entered. When you press **Enter**, the application will automatically generate the rest of the dates for the year. You should take care when changing dates for a currently active year, as this may cause unpredictable results.



Tip: Where this is the initial set up of end dates for a particular year, only enter the first date. Press **Enter** and Style Inventory Management will automatically generate the rest. When entering periods, enter the first date as 28/01/XX as this allows the system to cater for 28 days in February.



Once all changes have been made, press **Enter** to validate the entries and then **F8=Update** to update the database.

Search Family Codes And Certificate of Conformance Codes



10/STINM

Up to 10 characteristics are defined for each code. These characteristics may be either descriptive or numeric.



Tip: Set these codes up before you start to create Product Styles.

Search Family Codes

A Search Family Code may be defined for each style in Style Maintenance.

Within Style Maintenance descriptions of characteristics are generated from colour descriptions and size/fitting descriptions. These descriptions/values then form the basis of Item Search type 5. Further details of this search method are given in the Style Search section.

Certificate Of Conformance Codes

A Certificate Of Conformance Code may be defined for each batch or lot controlled item within Item Maintenance.

Certificates Of Conformance can be set up with particular values defined for the Certificate Of Conformance Code characteristics.

When allocating against batches in order entry it is possible to make a certificate of conformance enquiry for each batch. The item characteristics, with the values for the selected batch, are shown. This enables you to select a batch which meets the customer requirements.

Certificate of Conformance Processing is not supported by Style.

Search Family/Certificate of Conformance Code Selection Screen

 This screen is displayed when you select the Search Family/Certificate of Conformance selection option.

It enables you to select the Search Family Code or Certificate of Conformance Code to be maintained.

IN200 ST - JBA System Test Company User GBJBARW2 8/11/95
14:06:15

Search Family / Certificate of Conformance Code Maintenance

Code.....?.. ____

F3=Exit F4=Prompt

05-26 SF MK KS IM II KENB20A PET178S2

Fields:

Code

Enter up to three characters to specify the code. This may be an existing code for amendment or a new code for addition.

 When you press **Enter**, the maintenance screen is displayed for the selected code.

Search Family Code/Certificate Of Conformance Code Maintenance Screen

 This screen is displayed when you select the Search Family code or Certificate of Conformance code and press **Enter** on the initial screen.

It enables the characteristics of the Search Family Code or Certificate of Conformance Code to be defined. It also enables the characteristics to be defined as descriptive or numeric. The Search Family Code or Certificate of Conformance Code is displayed at the top of the screen.

If the code has already been set up, then the code description is shown and the characteristics which have been defined for the code are listed. If the code has not been set up, these fields are blank awaiting the entry of data.

IN200 ST - JBA System Test Company User GBJBARW2 8/11/95
14:06:49
Search Family / Certificate of Conformance Code Maintenance
Code..... 001
Description..... Code 001

Sel	Seq	Characteristics Description	Number of decimals	Code (?)	No. of Values
-	01	Colour	-	_____	
-	02	Size	-	_____	
-	03	Fit	-	_____	
-		_____	-	_____	
-		_____	-	_____	
-		_____	-	_____	
-		_____	-	_____	
-		_____	-	_____	
-		_____	-	_____	
-		_____	-	_____	

1=Select
F3=Exit F4=Prompt F5=Refresh F8=Update F11=Delete F12=Previous
06-26 SF MW KS IM II KENB20A PET178S2

Fields:

Description

Enter up to 30 characters which describe the Search Family or Certificate of Conformance.

Characteristics Description

Enter up to 20 characters which describe the characteristic you wish to define. Up to 10 characteristics can be defined for each code.

No Of Decimals

Enter 0 to 5 for the number of decimal places associated with the characteristic if it is numeric.

Leave blank if the characteristic is descriptive. The number of decimals cannot be changed once the characteristic has been created.

Carton Maintenance




11/STINM

This process allows a carton to be set up by specifying the number of pieces it contains and the breakdown in terms of colour, size and fitting.



Tip: The Carton Profile maintenance option needs to be run before cartons can be maintained using this option.



```

AP0001          ST - JBA System Test Company      USER GBJBARW2      8/11/95
                                                    14:07:35

Maintain Cartons

Carton style.....?.. _____

F3=Exit  F4=Prompt

05-24  SF  MK  KS  IM  II  KENB20A  PET178S2

```

Carton Style

1-117

Maintain Cartons Screen 2



This screen is displayed when a valid style and colour/size/fitting option is entered on the initial screen to represent the carton.

Additional information must also be entered regarding the contents of the carton. This is done by using the Carton Maintenance Matrix screen.

AP001	ST - JBA System Test Company	USER GBJBARW2	8/11/95
			14:09:13
Maintain Cartons		* Create *	
Carton style.....	LADYSH/1		
	Ladies Shoe 1	ALPINE WHITE	36
Piece style.....?			
Set total.....			
Number of sets within a carton.....			
F3=Exit F4=Prompt F12=Previous F21=Text			
07-38	SA	MA	KS IM II KENB20A PET178S2

Fields:

Piece Style

Enter the code of the style that you will be holding within this carton.

Set Total

The total number of pieces within a set. A set could be a pre-pack within the carton or may simply be the total number of pieces within the carton.

Number Of Sets Within A Carton

The number of sets within the carton. This in conjunction with the set total gives the total number of pieces within the carton.

Example 1

A carton contains 12 pieces in the following split 3:6:3. In this example the set total is 12 and the number of sets 1.

Example 2

A carton contains 12 pieces in the split 1:2:1. In this example the set total is 4 and the number of sets is 3.



Note: The screen prompts for set total and the number of sets are tailorable within the carton company profile.

Functions:

F21

Carton text maintenance. Select to display the text window for additional information regarding this carton.



Press **Enter** to display the matrix screen.

Maintain Cartons Matrix Window



This screen is displayed when you press **Enter** on the second Carton Matrix screen.

The matrix for the piece is displayed and quantities may be entered totalling back to the set total entered on the Carton Maintenance Detail screen.

```

AP081                ST - JBA System Test Company        USER GJBARW2        8/11/95
                                                14:12:06

Maintain Cartons                * Create *

Carton style..... LADYSH/1
                        Ladies Shoe 1        ALPINE WHITE        36
Piece style.....?.. LADYSH/2

LADYSH/2
ALPINE WHITE
BLUE
BLACK
Brown      *
Red        *

Ladies Shoe 2
36      37      38      39      40      41      More:
36.5    37.5    38.5    39.5    40.5
[ ] [ ] [ ] [ ] [ ] [ ] [ ]
[ ] [ ] [ ] [ ] [ ] [ ] [ ]
[ ] [ ] [ ] [ ] [ ] [ ] [ ]
[ ] [ ] [ ] [ ] [ ] [ ] [ ]
[ ] [ ] [ ] [ ] [ ] [ ] [ ]
[ ] [ ] [ ] [ ] [ ] [ ] [ ]

F10=Change matrix F12=Previous

12-19  SA  MK  KS  IM  II  KENB20A  PET178S2

```

Fields:

Quantity

Enter a total quantity that is to be split between the applicable colour/size options.



Note: When a carton is defined for the first time, a function key is available that will duplicate this initial set up over all colours within the carton.

Functions:

F15

Duplicate Entries.



You are then prompted to confirm the quantities, by pressing **Enter**.

Default Size Distribution

1... 12/STINM **2...**

This procedure creates and maintains a default size distribution of a particular style, either for all customers or a selected customer. This default distribution is then applied at sales order entry time.

Default Size Distribution Screen

 This screen is the initial screen displayed when you select Default Size Distribution.

It enables the selection of the style and a specific customer, if applicable.

AP110 ST - JBA System Test Company USER GBJBARW2 8/11/95
13:56:21

Default Size Distribution

Customer number...?..

Style.....?..

F3=Exit F4=Prompt

06-26 ☐ SF ☐ MK KS IM II KENB20A PET178S2

The following data may be entered.

Fields:

Customer Number

Enter a valid customer number or leave blank for the style distribution to apply to all suppliers.

Style

Enter a valid style number. Mandatory entry.

Fields:

Quantity

Enter a total quantity that is to be split between the applicable colour/size options.

 **Warning: The quantity entered in the matrix must equal total quantity entered on Size Distribution Selection Screen.**

 Press **Enter** to validate the above entries and display the Size Distribution Matrix screen.

 Press **Enter** to display the style matrix.

Default Size Distribution Matrix Window

 The Matrix screen is displayed when you press **Enter** to validate the entries on the initial screen.

This matrix enables the quantity entered to be divided between the applicable colours/sizes/fittings.

AP110

ST - JBA System Test Company

USER GBJBARW2

8/11/95
13:59:44

Default Size Distribution

Customer number..... FC01

La Perfumerie Agnes
17A Rue de Rivoli

LADYSH/2

ALPINE WHITE

BLUE

BLACK

Brown *

Red *

Ladies Shoe 2

36 37 38 39 40 41

36.5 37.5 38.5 39.5 40.5

More:

F10=Change matrix F12=Previous

12-19

SA

ML

KS

IM

II

KENB20A

PET178S2

The style matrix is displayed. Then the following data is entered.

Fields:

Quantity

Enter a breakdown of the total quantity across the matrix. Not all colour/size /fitting options need to be input.

 Press **Enter** to validate quantity entries. Then, press **Enter** again to confirm acceptance.

Colour Type Master File Maintenance



13/STINM


Use this option to group colour codes together into colour types. These are used by Sales Analysis as one of the report and enquiries criteria.

Colour Type Master File Maintenance Screen

1

 This is the initial screen displayed when you select the Colour Type Master File option.

Use this screen to create or maintain a colour type.



```
AP012          ST - JBA System Test Company    User GBJBARW2  10/03/97
                                           11:49:24

Colour Type Master File Maintenance

Colour Type Code.....?: EWG

F3=Exit  F4=Prompt

05-31      MW      KS      IM      II  KENB20A  PE9106S2
```

Fields:

Colour Type Code

Enter up to 15 alphanumeric characters for the colour description. Data input in this field is mandatory. You can define a maximum of 300 colour codes for each style.

 Press **Enter** to display the second Colour Type Master File Maintenance screen.

Colour Type Master File Maintenance Screen



This screen is displayed by entering the Colour Type Code on the first Colour Type Master File Maintenance screen and pressing **Enter**.

It enables you to enter further colour codes for the colour type.

[illegible]

Fields:

Colour Code

You may enter up to 300 colour codes as defined in the Colour Code Selection screen in Colour Master File Maintenance.



Warning: You can only define a colour to one colour type.

FIFO Costs

1... 21/STINM **2...**

FIFO records are generated by the application when the costing method of a product is set to FIFO and goods are received into stock. If an error was made at the time of entry this facility can be used to amend the detail within a FIFO record. To audit any cost changes made, a movement is written to the transaction file. This has a zero quantity and a value equal to that of the adjustment, an audit report is then printed.

Maintain FIFO Costs Screen 1



This screen is the initial screen displayed when you select the option.

It enables the selection of the product/stockroom for FIFO cost amendment.

```
IN020          ST - JBA System Test Company    User GBJBARW2    8/11/95
                                           14:14:15

Maintain FIFO Costs

Product code .....? █
Stockroom .....?  _

F3=Exit  F4=Prompt

05-26  SA  MK  KS  IM  II  KENB20A  PET178S2
```

Fields:

Product Code

Enter the product codes of the stockholding for which FIFO costs are to be amended.

Stockroom

Enter the stockroom codes of the stockholding for which FIFO costs are to be amended.



When you press **Enter** the style matrix is displayed for selection of colour/size/fitting attributes. Multiple selections may be made.

Maintain FIFO Costs Style Matrix Window



To display this window select a product code and stockroom combination on the Maintain FIFO Costs screen 1 and press **Enter**.

Use this matrix window to select the style variants you want to amend FIFO costs for.



*Note: You can bypass this window by entering the full product reference number on the Maintain FIFO Costs screen 1 and pressing **Enter**.*

IN028 ST - JBA System Test Company User GBJBARW2 8/11/95
14:17:38

Maintain FIFO Costs

Product code?. ? _ _ _ _
Stockroom?. ? _ _ _ _

Item Master Scan

Select Item Reference Description More: +

Multiple Item Selection For Style Enquiries

PDTEST2	Test Style 2 Char	More:
	45" 60"	
Cherry/Thund	- -	
Turquoise	- -	
ForestGreen	- -	
Terracottadk	- -	
Terracottalt	- -	
TERRACOTTADK	- -	
TERRACOTTALT	- -	

F12=Previous

12-21 **SA** **ML** KS IM II KENB20A PET178S2

Fields:

Untitled

Select. Enter 1 against the style variants you want amend FIFO costs for.



Press **Enter** to display the second Maintain FIFO Costs screen.

Bar Code/Alternative Item Reference Maintenance



22/STINM

You can set up style and default details for bar coding or other item references at colour/size/fitting level with this option. These details are used to reference items when using Electronic Data Interchange (EDI).

Bar Code/Alternative Item Reference Maintenance Screen 1



This screen is displayed when you select the Bar Code/Alternative Item Reference option.

Use this screen to create or maintain bar codes or alternative item references, or both, for a selected style.

Fields:

Style

Enter a style code - a search is available.

Maintenance Type

Indicate whether the barcodes, alternative item references or both are to be maintained. Enter one of the following:

- 1 - Bar codes only.
- 2 - Alternative item references.
- 3 - Both bar codes and alternative references.

Default Bar Code

Enter a default for the barcodes to be maintained - this is an optional entry.

Alternative Reference Type

Enter the type of alternative reference to be maintained. Valid values are maintained on descriptions. A search is available.

External Agency

This can be used to hold a customer or supplier code when the alternative reference is associated with an external agency.

Default Alternative Reference

Enter a default for alternative references to be maintained. Optional entry.



Press **Enter** to display the Bar Code/Alternative Item Reference Maintenance screen 2.

Bar Code/Alternative Item Reference Maintenance Screen 2



This screen is displayed when 1 has been entered in the Maintenance Type field in the Bar Code/Alternative Item Reference Maintenance screen 1 and an article number rule has been entered.

It enables you to enter barcodes or alternative reference details for the colour/size/fitting definitions entered against each style.

AP106	ST - JBA System Test Company	User GBJBARW2	20/03/97 8:21:02
Bar Code/Alternative Item Reference Maintenance			
Style..... BERNIE bernie			
Rule..... BW1 Rule BW 1			
Article Numbering Type.. EAN EAN numbers			
Description	Company identifier	Article Subnumber	
BERNIE	0239750	<u>000001</u>	
BERNIE REDBIG	0239750	<u>000004</u>	
BERNIE RED10H	0239750	<u>000002</u>	
BERNIE RED11H	0239750	<u>014055</u>	
F3=Exit F5=Refresh F8=Update F12=Previous			
12-48 SF MW KS IM II EDN400A PE9106S2			

Fields:

Article Subnumber

Enter the article subnumbers for each style described as set up in Article Numbering Maintenance screen 2.

Maintain Stockroom Details At Full Product



23/STINM

Use this option to update stockroom details at full product level (style/colour/size/fitting) through the matrix. For stockroom details selected for maintenance a matrix is displayed to allow data to be entered.

Maintain Stockroom Details At Full Product Screen



This screen is displayed when you select the Stockroom Details at Full Product option.

Use this screen to select the details you wish to maintain for the item and stockroom combination you specify.

```

AP107              ST - JBA System Test Company      User GBJBARW2      8/11/95
                                                    14:31:52

Maintain Stockroom Details at Full Product

Item.....?.. █
Stockroom.....?.. _

Default
Reorder factor.....
Reorder point.....
Reorder quantity.....
Maximum stock.....
Economic order quantity.....
Standard cost.....
Latest cost.....
Average cost.....
Base list price.....
Bin 1.....
Bin 2.....

                        Maintain      Default rule
                        (1=Yes 0=No) (1=All 0=Zero/Blank only)
Reorder factor.....      0          0
Reorder point.....      0          0
Reorder quantity.....    0          0
Maximum stock.....      0          0
Economic order quantity.. 0          0
Standard cost.....      0          0
Latest cost.....        0          0
Average cost.....        0          0
Base list price.....     0          0
Bin 1.....               0          0
Bin 2.....               0          0

F3=Exit      F4=Prompt

05-27      SF      MW      KS      IM      II      KENB20A      PET178S2
  
```

Fields:

Item

Enter a style or combination of style and colour or size/fitting. A search facility is available.

Stockroom

Enter a stockroom for the style being maintained. This stockroom must be defined to the style entered. A search facility is available.

Enter 0 - To have only zero or blank colour/size/fitting combinations defaulted

Enter 1 against stockroom details that are to be maintained. Use the default rule to control defaulting of values into the matrix.

Enter 1 - To have all fields default.

Re-Order Factor

Enter up to three numeric characters to specify the re-order factor %. This may be used as a default when maintaining the re-order factor for the style. Valid values are in the range 0 to 999.

Re-Order Point

Enter up to 13 numeric characters, three decimals. This is only required if you do not want the system to calculate this value automatically. If you do enter this it will become the default.

Valid values are in the range 0 to 9,999,999,999.999.

Re-Order Quantity

Enter up to 13 numeric characters, three decimals to specify the re-order quantity. If this value is left at zero, the system will calculate a re-order quantity based on the Reorder Factor %. This only applies if re-order policy - ROQ is specified. If entered this will become the default.

Valid values are in the range 0 to 9,999,999,999.999.

Maximum Stock

Enter up to 13 numeric characters, three decimals. This is only required if you do not want the system to calculate this value automatically. If entered this will become the default.

Valid values are in the range 0 to 9,999,999,999.999.

Economic Order Quantity

Enter up to 11 numeric characters, three decimals, to specify the economic order quantity. If entered this will become the default.

Standard Cost

Enter up to 15 numeric characters, five decimals, to specify the standard cost of one issue unit of the item. If the item is specified as standard costed then this cost is used to value all stock movements. If entered this will become the default.

Valid values are in the range 0 to 9,999,999,999.99999.

Valid values are in the range 0 to 9,999,999,999.99999.

Latest Cost

Enter up to 15 numeric characters, five decimals, to specify the latest cost. The latest cost is maintained by the application as the unit cost associated with the last stock receipt recorded, but may be specified here when amendment is required. If entered this will become the default.

Valid values are in the range 0 to 9,999,999,999.99999.

Average Cost

Enter up to 15 numeric characters, five decimals, to specify the average cost of one issue unit of the item. If the item is specified as Average costed then this cost is used to value all stock movements. If entered this will become the default.

Base List Price

Enter up to 15 characters, five decimals. This data is for use in the valuation of forecasts in MPS, DRP and MRP, where these applications are installed. If entered this will become the default.

Valid values are in the range 0 to 9,999,999,999.99999.

Bin 1

Enter up to six alphanumeric characters to specify the first bin in which this item is stored within this stockroom. If entered this will become the default.

Valid values are any combination of characters not longer than six characters in length.

Bin 2

Enter up to six alphanumeric characters to specify the second bin in which the item is stored within this stockroom. If entered this will become the default.

Valid values are those which are any combination of characters not longer than six characters in length.

Maintain

Enter one of the following:

0 - (Or blank) For the system to recalculate the value according to the defaults already in the system.



Note: If this value is left at zero, the system will calculate a re-order quantity based on the Reorder Factor.

1 - For the details to be maintained.

Default Rule

Enter one of the following:

1 - The value that is shown on the screen will become the default value for the item.

0 - The value will not become the default

Enter 1 against stockroom details that are to be maintained. Use the default rule to control defaulting of values into the matrix. To have all fields default enter 1. To only have zero or blank colour/size/fitting combinations defaulted enter 0.

Divisional Information Maintenance



24/STINM

If your customers allow back orders (which is specified this on the Style Sales Order Processing Company Profile), then you can determine by division, the percentage of the order that must be picked and optionally packed, before it is deemed acceptable.

Use this option to maintain and pick percentage for divisional and back order lines for selected divisions.

Divisional Information Maintenance Selection Screen



This screen is displayed when you select the Divisional Information option.

Use this screen to specify the divisional choices for back orders.

AP882	ST - JBA System Test Company	USER GBJBARW2	14/03/97		
			9:10:54		
Divisional Information Maintenance					
Opt	Division	Description	Initial Line	Backorder Line	Record Exist
-	A	Clothing	100	100	1
-	A	Clothing	100	100	1
-	B	Equipment	0	0	0
-	C	Footwear	0	0	0
-	D	Apparel	0	0	0
-	E	Accessories	0	0	0
-	ED	Export/Domestic	0	0	0
-	F	Pirelli	0	0	0
-	G	Superga	0	0	0
-	H	Handbags	0	0	0
-	I	Nemrod	0	0	0
-	ID	Import/Domestic	0	0	0
					More...
2=Change 4=Delete					
F3=Exit					
09-03	SF	MW	KS	IM	II EDN400A PE9106S2

Fields:

Opt

Select. Enter one of the following:

2 - To amend the details, press **Enter** to display the update window.

4 - To delete the division line.

Division

This is the division that may be attached to the style.

Description

This is the division description.

Initial Line

This is the percentage of the Initial order line allocated before a picking note is produced.

Back Order Line

This is the percentage of the Back order line allocated before a picking note is produced.

Record Exist

Enter one of the following to indicate whether records exist or not:

0 - No records are kept.

1 - Records are kept by the system.



Note: These Divisional Information details are set at company level here, but can be changed for specific customers within Sales Order Processing Maintenance.



Note: More divisions are available when a + sign is displayed, by using the page up and down keys.



Enter an option against the division line and press **Enter**.



This window is displayed when option **2=Change** is entered against a division line. It enables you to update the division lines.

```

AP882                               STyle Distribution Demo Company   USER QASTYLE   19/09/96
                                         12:44:11

Division Percentage to Pick Maintenance

Opt Division      Description      Initial   Backorder   Record
Line             Line             Exist
A               Clothing             0           0           0
Division Pick Percentage Update
Division... ED             0           0           0
Initial           Backorders
Line              Line
  0               0
F8=Update  F12=Cancel             0           0           0
- ID            Import/Domestic             0           0           0
- J              Anita                      0           0           0
2=Change  4=Delete
F3=Exit

16-14  SF  MW  KS  IM  II  KENB20A  PET178S2

```

Fields:

Division

This is the division that may be attached to the style.

Initial Line

This is the percentage of the Initial order line allocated before a picking note is produced.

Back Orders Line

This is the percentage of the Back order line allocated before a picking note is produced.



Select **F8=Update** to update the details for the division line.

Maintain Item Detail At Full Product



25/STINM

This option enables you to update the Item level details at full product level (Style/ colour/ size/ fitting) through use of the Style matrix.

Item Detail At Full Product Maintenance Screen



This screen is displayed when you select the Item Detail At Full Product option.

It enables the selection of an item allowing you to maintain its details at full product level that is Style/Colour/Size (and Fit if the item is four dimensional).

AP108		ST - Style Test & QA Company		User GBJBARW2		8/12/97 10:11:31	
Maintain Item Details at Full Product							
Item.....?..		CHCART					
		Maintain		Default rule			
		(1=Yes 0=No)		(1=All 0=Zero/Blank only)			
Default			0		0		
Spec 1.....			0		0		
Spec 2.....			0		0		
Spec 3.....			0		0		
Effectivity Start Date..			0		0		
Effectivity End Date...			0		0		
Weight per selling unit.			0		0		
Superseded by.....			0		0		
Supersession date.....			0		0		
GL account.....			0		0		
Sales GL acct.....			0		0		
Cost of sales GL acct...			0		0		
Price variance acct....			0		0		
Sourcing warehouse...?..			0		0		
Size/fit description....			0		0		+
F3=Exit F4=Prompt							
5-27		SA		MW		KS CL IM DM II STUD140 KB PET179S1	

Fields:

Item

Select the item for which you want to maintain the full product details.

Maintain

Enter 1 against the following categories to maintain their details:

Effectivity Start Date.

Effectivity End Date.

Weight Per Selling Unit.

Superseded By.

Supersession Date.

GL Acct.

Cost of Sales GL Acct.

Sales GL Acct.

Price Variance Acct.

Sourcing Warehouse.

Size/Fit Description.

Default Rule

Enter one of the following:

0 - For the value to not become the default

1 - To make the value that is shown on the screen the default value for the item.

Enter 1 against the item details that are to be maintained. Use the default rule to control defaulting of values into the matrix. To have all fields default enter 1. To only have zero or blank colour/size/fitting combinations defaulted enter 0.



Press **Enter** to display the Style matrix to allow you to enter data for the selected item.

It allows you to set up a rule for article numbering. Articles refer to styles with specific colour/size/fit details, for example a style profile of long, black, halter neck may be designated cocktail dress at article level.

Fields:

Enter a rule to generate article numbers for a selected numbering convention. If a rule has been deactivated, numbers will not be generated for an item. If a number already exists for an item it will not be regenerated.



1-145

Article Numbering Maintenance Screen



This screen is displayed when you select a rule and press **Enter** on the Item Article Number Maintenance screen.

This option enables you to define article numbering rules for item maintenance and is deployed following entry of a valid rule code.

AP890	ST - JBA System Test Company	User GBJBARW2	14/03/97 9:50:55
Article Numbering Maintenance			*Active
Rule.....	SF5	SF Rule 5	
Article no. type...?..	UPC	Universal product codes	
Check digit.....	1	{0=No, 1=Yes}	
Check routine.....	M11	{M10=Modulus 10, M11=Modulus 11}	
Article no. length....	11		
Company length.....	6		
Article length.....	4		
Company Id.....			
Article subnumber.....			
F3=Exit F4=Prompt F8=Update F9=Activate/De-activate F11=Delete			
F12=Previous			
05-30 SF MW KS IM II EDN400A PE9106S2			

Fields:

Rule

Enter the appropriate rule to determine how an item is to be numbered. Rules are maintained using article numbering conventions held against the Inventory Descriptions type ANTP, for example, EAN, UPC, and so on.



*Note: A rule can only be deleted if no article numbers for a rule/type are attached to an item, that is , it has not been used. If you want to suspend a rule you can deactivate it by using **F9=Activate/Deactivate**, see Functions for more details.*

Article Numbering Type

Enter the article number type for the item.

Check Digit

A digit may be automatically calculated by the system and added to the article numbering length to validate manual data input using a check routine. If manual input does not conform to a preconfigured sequence the last digit will indicate an error. To activate a check routine you must set check digit to 1.

Enter one of the following:

0 - No. Select to suppress a check routine.

1 - Yes. Select to enter a check routine.

Check Routine

If check digit is set to 1 select one of the following standard check routines:

M10 - Modulus 10.

M11 - Modulus 11.

Article Numbering Length

Display only. The system automatically generates a value equal to the total number of digits defined in company length, article length and the check digit if set to 1. See the following three fields for further details.

Company Length

This is mandatory and numeric. You must enter a value equal to the total number of digits defined in the company Id. For example, a company Id of 1234567 gives a company length of 7.

Article Length

This is mandatory and numeric. You must enter the value equal to the total number of digits defined in the article subnumber field. For example, an article subnumber of 00343 gives an article length of 5.

Company ID

This is mandatory if you require automatic article numbers for manufactured and finished goods items. Enter your company Id as issued by the numbering body. Total the number of digits from this entry to determine your company length value, for example, a company ID of 12045 would give a company length of 5. This field can be left blank (providing that the Article Subnumber field is left blank also) in which case the Article Numbering Rule can be used for manually entering the company ID and article subnumber for bought in goods.

Article Subnumber

This is mandatory if you require automatic article numbers for manufactured and finished goods items. Enter your article subnumber. The total number of digits from this entry determines your article length value, for example, an article subnumber of 00343 would give an article length of 5. This field can be left blank (providing that the Company ID field is left blank also) in which case the Article Numbering Rule can be used for manually entering the company ID and article subnumber for bought in goods.

Functions:

F9

Activate/Deactivate. The rule to determine how each item is to be numbered may be active or inactive. If active, the article subnumber will be used and incremented by the system as numbers are assigned to items.

Item Article Number Maintenance




27/STINM

This option enables you to enter a rule against a style which has no article numbers generated for it, such as bought in items that would not have system generated numbers.

Item Article Number Maintenance Screen 1

 This screen is displayed when you select the Item Article Number maintenance option.

This option enables you to enter a rule against a style which has no article numbers generated for it, such as bought in items that would not have system generated numbers. Its use is dependent upon the Company ID and Article Subnumber fields being left blank in Article Numbering Maintenance screen.



```
AP109          ST - Style Test & QA Company    User QASTYLE    2/07/97
                                                    11:37:16
Article Number Maintenance
Style.....?..  _____
Rule.....?..   _____

F3=Exit  F4=Prompt
05-36    SF      MW      KS      IM      II  KENB20A  PE9106S2
```

Fields:

Style

Enter the style code for the item. A prompt is available.

Rule

Enter the rule that will be used for the style. A prompt is available.

 Press Enter to display the Article Number Maintenance screen.

Item/Article Rule Prompt Window



This screen displays when the **F4=Prompt** is used in the Rule field on Article Number Maintenance screen.

This option displays the rules defined for the entered style. Generally, only one rule will be available but there are some circumstances when more than one rule may be used to generate article numbers for a style. For example, when article numbers are generated for a style at division level, the division rule is amended and a new colour or size is added to the style. The new colour/size will then have article numbers generated using the new rule.

Opt	Type	Description
1	BW1	Bernie article rule

More

1=Select F12=Previous

F3=Exit F4=Prompt

00-17 SA MW KS IM II KENB20A PE9106S2

Item Article Number Maintenance Screen 2



This screen displays when Enter is pressed in Item Article Number Maintenance screen 1.

This screen enables you to enter and maintain the Company IDs and Article Subnumbers supplied with those style items that your company buys in.

It is possible for article numbers to be created for a new style and its SKUs, however, use of the Stop/Sell option can render the SKUs inactive, but the article numbers will not be deleted. Where multi-dimensional SKUs are entered, the style will not be displayed.

AP109	ST - Style Test & QA Company	User QASTYLE	2/07/97
			11:50:58
Article Number Maintenance			
Style..... ACHSCS3 ach st col siz 3			
Rule..... BW1 Bernie article rule			
Article Numbering Type.. EAN European Article Number			
Description	Company identifier	Article Subnumber	
	Enter 5 characters	Enter 7 characters	
ACHSCS3 00130	4006381	00949	
ACHSCS3 00132	4006381	00950	
ACHSCS3 00134	4006381	00951	
ACHSCS3 00136	4006381	00952	
ACHSCS3 00138	4006381	00953	
ACHSCS3 00140	4006381	00954	
ACHSCS3 00230	4006381	00955	
ACHSCS3 00232	4006381	00956	
ACHSCS3 00234	4006381	00957	
ACHSCS3 00236	4006381	00958	+
F3=Exit F5=Refresh F8=Update F12=Previous			
12-21 SA MW KS IM II KENB20A PE9106S2			

Fields:

Style

This is the style entered from Article Number Maintenance screen 1.

Rule

This is the rule entered from Article Number Maintenance screen 1.

Article Numbering Type

Enter the article numbering type for the item, for example, EAN, UPC, and so on.

Description

This is the description set up in Descriptions File Maintenance.

Company Identifier

This is a seven character field. Enter the company identifier of your supplier. This field can be left blank providing that the Article Subnumber field is left blank also.

Article Subnumber

This is a seven character field. Enter the suppliers own generated article subnumber. This field can be left blank providing that the Company Identifier field is left blank also.