

-
-
-
-
-

Chapter 3

Spooled File Distribution



Spooled File Distribution

If Network Manager has been used to configure your network, two output queues will have been created for each system. One queue is for users to send spooled files to each remote system from the local system. The default name for this queue is T_SYSNAME, where SYSNAME is the name of the remote system. The second queue is for users to send spooled files from a remote system to the local system. The default name for this queue is F_SYSNAME, where SYSNAME is the name of the remote system. These names may have been changed by your local administrator.

In order to send a spooled file from one IBM AS/400 to another IBM AS/400 in your network, the spooled file should be placed on the appropriate output queue (T_SYSNAME) and released. You may use the CHGSPLFA command to do this. For example, if the spooled file is to be sent to the system NEWSYS, from system OLDSYS, then place it on output queue T_NEWSYS. The system periodically checks prints on the output queues and sends them to the target system. When the print has been sent, it is deleted from the local system. The interval between each check is typically 5 minutes, but this is determined by the time set for the 'distribute wait time' when configuring the remote system (see the Remote Systems section). In our example the spooled file will arrive in the queue F_OLDSYS on the target IBM AS/400.

Manual Activation Of Distribution Queues

If the spooled file distributor is not automatically activated (see the Remote Systems section), or if you wish to send spooled files to a particular system before the normal time select option 1 using the Spooled File Distribution option to manually activate the spooled file distributor. The target system should be named (not prefixed by T_). Optionally, you may specify an output queue, and all ready-prints on that queue will be sent to the target system.

Monitoring Distribution

If the target is an adjacent IBM AS/400, the print should appear immediately on the queue F_SYSNAME. In an APPC environment, if the target is not an adjacent IBM AS/400 the print will appear on the queue T_SYSNAME on the adjacent system and will then be picked up by the IBM AS/400 and distributed by the IBM AS/400 routines as above. The adjacent system issues a command to activate the spooled file distributor and thus avoids the wait time on the intermediate system. In an APPN network, distribution from the source system to the target system is direct.

To check the progress of a spooled file select option 3 using the Spooled File Distribution option to view the subsystem which runs spooled file distribution.

To view spooled files on an output queue for a target system enter the command WRKOUTQ and press **F4**. Enter the name of the required output queue, that is T_SYSNAME, and the library which contains the queue and press **Enter**. A screen is displayed containing a list of all the spooled files for the specified target system, you are provided with options to change the status or priority of the spooled file, display the spooled file or change its attributes.

Starting The Subsystem

Spooled file distribution is initiated by starting the subsystem DSTSPLF.

STRSBSSBSD (IPGNWP4/DSTSPLF)

This will start distribution to all target systems designated as Auto-Start Senders (see the Remote Systems section). Those remote systems which are not designated as 'Auto-Start Senders' can be started via the STRDSTSPLF command (see the Activate section).



Note: If Machine Manager is in use it is recommended that a job is added to the Start-Day routine in order to automatically start the subsystem.

Start



Select option 2 from the Spooled File Distribution option and press **Enter**.

Distribution to remote systems, which are not automatically started by subsystem DSTSPLF being activated, can be activated via the command STRDSTSPLF.

```
NW121                      Network Manager                      System: STUDB30A
Start Spool File Distributor - STRDSTSPLF

To system . . . . . *ALLAUTO

Additional Parameters
From output queue . . . . . *DFT          (name,*DFT)
Stagger auto-start (secs) . . . *DFT      (0-999999,*IMMED,*DFT)

F3=Exit  F4=Browse  F12=Previous
```

Fields:

To System

Enter the name of the target system. *ALL automatically starts all target distribution queues. *ALLAUTO starts all target distribution queues for target systems flagged Y for 'Auto Start Sender' (see the section Remote Systems).



Tip: Select **F10** to display the remaining fields.

From Output Queue

Optionally specify an output queue. All ready prints on that queue are sent to the target system.


Stagger Auto-Start (Secs)

Use this option to specify a delay time between the start of the sender jobs. This prevents multiple requests being made at the same time.

Activate

-  Select option 2 from Spooled File Distribution and press **Enter**.

If the spooled file distributor is not automatically started (see the Remote Systems section), or if you want to send spooled files to a particular system before the normal time use this facility to manually activate the spooled file distributor.



Fields:

To System Name

Enter the name of the target system.

-  Tip: Select **F10** to display the remaining fields.

From Output Queue

Optionally specify an output queue. All ready prints on that queue are sent to the target system.

-  Press **Enter** to activate the spooled file distributor for the target system.

 *Note: The spooled file distributor for the target system remains active until the next IPL, or until spooled file distribution is terminated (see the End section).*

Work With



To check the progress of a spooled file select option 3 from Spooled File Distribution and press **Enter**.

```
NW151                      Network Manager                      System: STUDB30A
Work with Spool File Distributor - WRKDSTPLF

Output . . . . . *          (*,*PRINT)
Reset status statistics. . *NO  (*YES,*NO)

F3=Exit
```

Fields:

Output

Select the destination for the output. Enter * for display only or *PRINT for the system printer.

Reset Status Statistics

Enter *YES to reset the CPU usage and elapsed time to zero. You can then see the jobs which are currently active.



Press **Enter** to work with the spooled file distributor.

If there is no job for your target system, either start a job or activate the common sender using option 1 using the Spooled File Distribution option. If there is a job for your target system its function is probably DLY-300 stating that it is delayed for 300 seconds.

There should be a job called DSTSPLF which actually performs the send. Display this job and view its job log. There will be a message for each time it was activated and a message for each spooled file selected for send.

After a spooled file has been sent by DSTSPLF, it is processed by the IBM SNADS system. The SNADS system may only be viewed using the command WRKDSTQ. There should be a file being sent either to an adjacent node or from the distribution queue for your target system. You may also use the command WRKDSTQ as appropriate on intermediate systems.



Note: If problems occur, display message queue QSYSOPR on the source and target machines. Display messages on the queue NETWORK on both machines and a message queue on each machine whose name is that of the other machine.



Note: It may also be useful to display the job QNFTP in subsystem QSNADS, this produces the spooled files on the target machine.

To view spooled files on an output queue for a target system enter the command WRKOUTQ and press **F4**. Enter the name of the required output queue, that is T_SYSNAME, and the library which contains the queue and press **Enter**. A screen is displayed containing a list of all the spooled files for the specified target system, you are provided with options to change the status or priority of the spooled file, display the spooled file or change its attributes.

End



To terminate spooled file distribution select option 4 from Spooled File Distribution and press **Enter**.

```
NW161                      Network Manager                      System: STUDB30A
End Spool File Distributor - ENDSTSPLF

End distributor subsystem. . . . *YES      (*YES,*NO)

F3=Exit
```



Select *YES and press **Enter** to end spooled file distribution.