

-
-
-
-
-

Chapter 4

Object Distribution



Introduction To Object Distribution

Object distribution provides a mechanism for sending objects around a network defined to Network Manager.

Object Distribution consists of three functions, they are:

- Distribute
- Work with
- Print.

Not only are objects sent to remote system, but an audit of the progress of each object is also provided.

Distribute



To distribute objects, select option 1 from the Object Distribution menu.

Distribute Objects (DSTOBJ)

Type choices, press Enter.

Type of object to send	OBJTYPE	_____
Objects	OBJ	_____
	+ for more values	_____
Library names	LIB	_____
	+ for more values	_____
To system	TARGET	_____
	+ for more values	_____

Additional Parameters

Target release	TGTRLS	V2R2M0
Receiving library	RCVLIB	*SNDLIB
Object pre-check	PRECHK	*YES
Save access path	ACCPH	*NO
Data compression	DTACPR	*YES
Display distribution status . .	STSMG	*YES

More...

F3=Exit F4=Prompt F5=Refresh F12=Cancel F13=How to use this display
F24=More keys

Fields:

Type Of Object To Send

Enter the object type, such as *FILE, *PGM, or enter *ALL.

Objects

Enter a single object name, a list of object names, a generic object name or *ALL.

Library Names

Enter a single library name, a list of library names or a generic library name.

To System

Enter the names of the systems you want to distribute to.

Target Release

Enter the OS/400 release level of the system you are distributing to. Alternatively enter *PRV for the previous release of the host system or *CURRENT to for the same release level.

Receiving Library

Enter the name of the receiving library or use *SNDLIB to create a library on the target system with the same name as the transmitted library.



Note: Send Library does not overwrite an existing library. If the library exists on the target system use the Receiving Library parameter to send the library to a different name on the target

system.

Object Pre-Check

If you enter *YES in this field the send library operation ends if any of the following conditions is true:

1. Any of the objects do not exist.
2. Any of the objects are found to be damaged.
3. Any of the objects are locked by another job.
4. You do not have authority to the objects.

Enter *NO to continue the send library operation, sending only those objects which satisfy the above conditions.

Save Access Path

Enter *YES to transmit the logical file access paths associated with the physical files.

Enter *NO to prevent the logical file access paths from being transmitted with the library, for faster data transmission.



Note: The logical file access paths are re-built at the time specified for Access Path Recovery when the logical file was created, that is when the file is opened, after IPL, or during IPL.

Data Compression

You can use data compression to more efficiently transmit objects containing large numbers of embedded blanks. Data compression removes contiguous blank spaces contained in lines of code and replaces them with an edit code indicating the number of blank spaces removed. This process can typically reduce the size of a transmitted object by 30 to 40%. The compressed objects are automatically de-compressed during the restoration process at the target system.

Display Distribution Status

Enter *YES if you require an audit of the sending of the object from the host system and it's receipt on the target system.

Overwrite Existing Objects

Enter *YES if existing objects should be replaced.

Work With



To display a list of Object Distribution requests and their progress, select option 2 from the Object Distribution menu.

```
Work with the Object Distribution Log
```

	Request Op Number	FROM St System	TO System	User Profile	Object Name	Object Library	Submitted Date
-							
-							
-							
-							
-							
-							
-							
-							
-							
-							
-							
-							
-							
-							
-							
-							

F3=Exit F5=Refresh F13=Reverse Sequence

More...

The screen displays summary information from the Object Distribution Log. The status (St) of each job is indicated by a two character code for example:

SF - sender failed

SR - sender ran

SS - Send submitted

RC - receive completed

RF - receive failed

RR - receiver running



Enter 1 alongside a line to re-send the object. See the Distribute section for further details about distributing objects.

Display Object Distribution Detail Window



Enter 5 alongside a line to display more information.

The screenshot shows a terminal window titled "Work with the Object Distribution Log". It contains a table with the following columns: Request Number, FROM St System, TO System, User Profile, Object Name, Object Library, and Submitted Date. The first row of data shows "Op 5" in the Request Number column. Below the table, there is a section titled "Display Object Distribution Detail" which shows the object name "FC041CLP" and the object library "OSLFCX3". At the bottom of the window, there is a status bar with the text "F3=Ex F12=Previous" and a message: "Object OSLFCX3/FC041CLP type *PGM successfully restored into library FC03FIX."

Request Number	FROM St System	TO System	User Profile	Object Name	Object Library	Submitted Date
Op 5						

Display Object Distribution Detail

FC041CLP
*PGM

OSLFCX3

F3=Ex F12=Previous
Object OSLFCX3/FC041CLP type *PGM successfully restored into library FC03FIX.

This window displays more details for the selected object distribution.

Print



Select option 3 from the Object Distribution menu to print the Distribution Log.

NW330 System: STUDB30A

Print Object Distribution Log

From request number _____

To request number _____

Delete log items after printing . . . 0 (1=Yes, 0=No)

(Only allowed if from and to entered)

F3=Exit

Fields:

From Request Number

Use Work with to determine to which request numbers you want to print.

Delete Log Items

Enter 1 if you want to delete the log items once they have been printed.