

-
-
-
-
-

Chapter 2

The Workspace Designer Interface



Introduction To The Interface

This section tells you how to use Workspace Designer to tailor windows in Client Workspace at screen and field level.

You can customise the Client Workspace menus. For more information about this see the Soft Menu Maintenance section of the JBA Client Workspace product guide.

Windows Terms And Techniques

It is assumed that you are familiar with the standard elements of the Windows interface - controls for opening and closing windows, scroll bars, buttons and icons and so on.

Some elements of the Windows interface are less well known, and a brief listing of the elements used in Workspace Designer is given below.

For more information about Windows you should consult the Windows documentation.

Windows and Screens

In this product guide the difference between the terms window and screen is this:

A window contains different elements - fields, controls, buttons and screens.


A screen is contained by a System 21 Client Workspace window and is part of an application.

For example the Purchase Management company profile screens are contained by Client Workspace windows. The importance of this is that the Purchase Management company profile may be made up of many screens, but only one window, which will consistently display Purchase Management Company Profile in its title bar, whatever titles each screen may have.

Windows Controls

This section explains some of the controls used in Workspace Designer.


Spin Buttons



A Spin Button is a control consisting of two arrows, one pointing upward and one pointing down, usually associated with a field containing numeric characters.

When the upward pointing arrow is selected the associated numeric field is incremented; when the downward arrow is selected the associated numeric field is decremented.

Option Button Groups



☒ **None**
☐ **Description**
☐ **Variable Field**

An Option button group is a group of mutually exclusive options, each associated with an Option Button - a circle which when selected has a coloured dot in the centre of it. Option Buttons are sometimes called Radio Buttons.

Selecting one option in the group immediately deselects any other selected option.

Check Boxes



A check box is a control with two states, enabled and disabled. An unselected (disabled) check box is an empty box. When it is selected a cross appears in it and the function it is associated with is enabled.

Multiple check boxes are not mutually exclusive.

Selecting Items

Items that can be selected include Buttons, Check Boxes, Option Button Groups (sometimes known as Radio Buttons) icons, fields and field descriptions.

You select an item by clicking on it, usually with the left mouse button. If the item is a button or an icon its display characteristics may change on selection - it may take on a recessed or pressed look.

Displaying The Client Workspace

The following is a basic description and guide to the Client Workspace, from within which Workspace Designer is used. For a fuller description of Client Workspace you should consult the Client Workspace product guide.

Elements Of The Client Workspace

In order to reformat your screens using Workspace Designer you must first access the Client Workspace. The basic elements that make up the Client Workspace are covered below, but for fuller information you should see the Client Workspace product guide.

Drop-Down Menu

The Client Workspace uses a drop-down menu system, similar to other Windows applications. There are two systems of menus available for System 21:

- Classic Menus - Tasks are grouped by application and area. The hierarchy is as follows:
 - Application area
 - Application
 - Type of task within application (for example Processing or Enquiry etc)
 - Specific task.
- Class-based menus - Tasks are grouped by the type of information within an application you wish to work with, as follows:
 - Application area
 - Application
 - Information area (for example Customers or Inventory)
 - Type of task for this information area (Print, View, or Edit for example).

The menus can be customised using the Soft Menus Maintenance utility provided with Client Workspace.

Status Bar



Client Workspace Status Bar

The Status Bar is the area at the bottom of the main window, and is split into three sections.

The first section displays help for Icon properties.

The second section shows progress messages, alerting you to system activity.

The third section is reserved for the mailbox. If the letter symbol is displayed this means that there is a system message waiting for you. If there is no message waiting the section will be blank. Please note that this has nothing at all to do with your electronic mail messages.


Navigating In Client Workspace

Use the TAB key to move forward from field to field. Use Shift-TAB to move back to the previous field. If data already exists in a field, it is highlighted and may be amended by overtyping.

Click once in a field with the left mouse button to enter data in insert mode.

The arrow (   ) keys work like TAB keys.

To select an option from a window list click once in the selection field and double-click on the displayed Select option (usually Select=1). When you double-click on the Select option, the line is outlined briefly and the associated number is entered in the Selection field.



A/C Code	CC	Seq Name and Address
1 GS01	GBP 000	Premier Food and Drug Supplies Premier House Eastcote L
GS01	GBP 001	Premier Warehousing Co Ltd Winnersh Bulk Storage Units
GS02	GBP 000	Coles Commercial Chemicals Ltd Unit 10 Technology Busin
G200	ITL 000	Giovennzana Viale Forlanini 144 Garbagnate Milanese 204
P400	GBP 000	Premier Food and Drug Supplies Premier House Eastcote L

1=Select

Previous Expand

Selecting in a Window List

Details from the chosen option are entered directly into the appropriate field on the screen, confirming your choice:

Processing Order Entry

Order number.. Z000003
Supplier...?.. CS01
Address code.. 000
Premier Food and Drug Supplies
Premier House
Eastcote Lane
Wokingham
Order date..... 150796
Order class?...
P.Officer...?..
Schedule type...?..
Stockroom.....?..
Dly. ins. code..?..
Receiving address code?... 000
Central Purchasing Department
28 Marlborough Road
Havlin Industrial Estate
West Bromwich
Delivery date.
Department.....
Shipping code.....
Job number.....
Disc % 1.. Disc % 2..
Exit Prompt Receiving Address

The Client Workspace Toolbar



The Standard Client Workspace Toolbar

The JBA System 21 Workspace Toolbar is displayed above. If Workspace Designer has been enabled, when a window with a Screen Identifier is displayed, the Workspace Designer button is added to the standard Client Workspace toolbar:



This button switches the Workspace into Workspace Designer mode, displaying the toolbar and tools that allow you to reformat Workspace screens. When you are in Designer mode this button changes to the one shown below:



This is both an indication that you are in Designer mode and the button you select to return to Client Workspace mode.

The standard toolbar buttons used in Client Workspace are described in the JBA Client Workspace product guide.



Note: Client Workspace toolbar buttons are unavailable once you are reformatting a screen using Workspace Designer

The Workspace Designer

This section of the product guide is concerned with using the Workspace Designer to reformat screens. It is structured as follows:

- General elements of the Workspace Designer - moving objects, toolbars and so on.
- The Workspace Designer Field and Panel tools.
- Other tools and windows, grouped by whether they work at field or screen level.
- Linking Help files.
- System 21 files you should be aware of.

Operating Prerequisites

The Workspace Designer only operates when a window containing a Screen Identifier - a unique code for each screen stored at that server - is displayed in the Client Workspace.

Only the application that you are reformatting screens for can be active. No other application or host session can be active at the same time.



Note: It does not matter whether Reformatting is turned on or off in the System/Preferences window of Client Workspace

Moving Objects In Workspace Designer

The most basic reformatting that can be done in the Workspace Designer is moving fields, field descriptions and buttons around on the screen.

You do this by selecting the relevant object with the right mouse button and, keeping the mouse button depressed, dragging it to its new location.



Tip: It can be difficult to position objects exactly using drag and drop. An easy way to position items precisely is by using the Row and Column settings in the Field Details window.

The Workspace Designer Toolbar

When the Workspace Designer button is selected, the Workspace Designer toolbar is displayed:



The Workspace Designer Toolbar



Note: If an button has a dotted line around it, the function represented by it is unavailable

The Workspace Designer toolbar buttons have the following meaning:

Fields:

System Defaults



Selecting the System Defaults button displays the System Defaults window.

For more information see the System Defaults Window.

Insert Help



Selecting the Insert Help button displays System 21 Help Text window allowing you to attach help files to screens.

The help file details entered can be accessed from JBA System 21 Applications by use of the Help Menu options, and the F1 key.

For more information see the section of this guide regarding the System 21 Help text window.

Undo Help



Selecting the Undo Help button displays a message box prompting you to confirm deletion of all the help file links to the current screen. The following buttons are displayed:

OK - Delete all help text links for the current screen.

Cancel - Cancel this deletion.

Workspace Designer

Toggle this button to turn Designer on and off. The button changes from black to red.



Off - Click the button to use Designer.



On - Reformatting is in progress. Click the button to leave Designer. You will be prompted to save your changes.

Undo Button



This button is usually displayed in its disabled form (left). When you move an object (a field or field description), or change its properties using any of the field tools, the undo button is enabled; selecting it reverses the action you have taken.

Product Info



Selecting the Product Info button displays the System 21 Workspace Designer product information window.

Show/Hide The Designer Grid



Selecting the Show/Hide the designer grid button overlays the application screen with a grid to help you position fields and buttons more accurately. There are three types of grid mesh: narrow, medium and wide. You click on the button each time to move to a different type of mesh, finally returning to non-grid mode on the fourth click.

Custom Button



Selecting the Custom Button button displays the Button Details window.

Text Input/ Mask Drop-Down List



Warning: this is for System Administrators.
Please note that Workspace Designer does not support the *CHANGE* keyword with text that has been overwritten or masked at the Client.

In addition the toolbar displays a text input field/drop-down list.



This part of the toolbar has:

- A list area
- A tick button
- A cross button.

This is used to input text and edit text for items such as group boxes, field descriptions, and to select masks for screen data.

To edit text, select a field description with the left mouse button. The text appears in the text input field, and can be edited. Selecting the tick button accepts the change and selecting the cross button rejects it. You can also change the values of a field while in Workspace Designer, to, for example, evaluate the action of a mask on a field with no live data in it.

The masks available are:

MASK=REMOVE DECIMAL - Remove redundant zeros following the decimal point on a numeric field. For example:

`75.000` becomes `75`

but

`75.001` stays as `75.001`.

The following three masks offer various date conversion functions:

MASK=DDMMYY -> **MMDDYY**

MASK=MMDDYY -> **DDMMYY**

MASK=MM/DD/YY -> **DD/MM/YY**

The final mask is a dummy mask that you can use to create your own data masks. The mask is:

MASK=##,##0.00

This displays a numeric of (for example) 10000 as 10,000.00

The syntax for constructing your own mask is as follows:

Masks always begin with the keyword **MASK=**

Characters you can use in masks are specified in the Mask Formatting section of this product guide.

To select a mask for a field, first select the field you wish to apply the mask to. Select the mask from the drop-down list, and select the tick button to confirm. The mask is applied to the field's contents.

The Workspace Designer Tools

When the Workspace Designer button is selected, the Panel and Field Workspace Designer tools are displayed.

The Panel Tool



The Panel Tool

You use the Panel Tool to change the display characteristics of screens.

The Panel Tool displays the following fields and buttons:

Fields:

Sys Clipping

Clipping is the removal of lines of text and/or data from the top and bottom of the screen. The Sys Clipping field is a check box with the following options:

Checked - The values set up for clipping in the System Defaults window are used.

Unchecked - The System Default values are not used and values can be entered in the Clip Top and Clip Bottom fields (below).

Clip Top

This field contains a drop-down list containing the values 0-24 (the number of lines on a screen). Select the number of lines to remove from the top of the screen. This field is only available for entry if the Sys Clipping field is unchecked.

Clip Bottom

This field contains a drop down list containing the values 0-24 (the number of lines on a screen). Select the number of lines to remove from the bottom of the screen. This field is only available for entry if the Sys Clipping field is unchecked.

Remove Stops

Stops are the full stops that follow a field description on a System 21 screen that has not been reformatted, like this:

Order number.. Z000003

Removing the stops presents a clearer and less cluttered screen:

Order number Z000003

This field is a check box with the following options:

Checked - Stops are removed.

Unchecked - Stops are not removed.

Greyed Out - The values set up for Stops in the System Defaults window are used.

Remove Grp Box

This field contains a drop-down list of all the Group Boxes created using the Group Box button. Select the group box you wish to delete from the list.


Group Box



You can use this option to group common fields on a display. Select the Group Box button. Your cursor changes:



If you want your group box to have a title, enter it now in the text input box on the Workspace Designer toolbar. Hold down the right mouse button and draw a box around the fields you wish to group. Release the mouse button when you have finished. A group box surrounds the fields:



You can select the group box text, using the Left mouse button, in the Text Input box on the toolbar. You can select and drag the border to resize it while in group box mode (when the Group Box button is depressed).

Details

Selecting this button displays the Screen Definition window.

The Field Tool



The Field Tool

You use the Field Tool to change the display characteristic of fields or field descriptions, and to assign field values from and to variables.

The Field Tool displays the following fields and buttons:

Show

This field contains a drop-down list that displays any field or field description that has been hidden using the Hide button (see below).

Selecting a field from the drop-down list redisplayes it.

Fields are given as co-ordinates, for example Field (12,34) and descriptions as text, for example Customer Name.

Hide Button



You can use this button to remove a field or field description from the screen. Selecting the button puts the mouse pointer into hide mode, and changes the display characteristics of the button to red lettering on a white background.

While in hide mode, clicking on a field with the mouse pointer removes the field or field description from the display.

Highlight Button



You can use this button to highlight a field or field description's content, by inverting the field's display characteristics. Selecting the button puts the mouse pointer into highlight mode, and changes the display characteristics of the button to red and white.

While in highlight mode, clicking on a field with the mouse pointer inverts the display of the field or field description's contents. Another click on the same field returns it to normal display.

Bold Button

You can use this button to emphasise a field or field description by changing the font's colour to blue, and bolding the font. Selecting the button puts the mouse pointer into bold mode, and changes the display characteristics of the button to red and white.

While in bold mode clicking on a field with the mouse pointer bolds the display of the field or field description's contents. Another click on the same field returns it to normal display.

Border

The buttons within the Border group box change the border attributes of the field or field descriptions they are applied to.

The Border group box contains the following buttons:



- Prompt.

This button makes a prompt button available to the application user alongside the current field. To do this you click this Prompt button once and then select the field to which you want to apply the prompt. The Prompt Details window is displayed.



- Border recessed by 2 pixels.



- Border recessed by 3 pixels.



- Border bevelled (raised) by 2 pixels.



- 1 pixel single line border.



- No border.

Select the border style you want by selecting the relevant button - the display properties of the button changes to red on white, and the button appears pressed. Click with the left mouse button on the field or field description for which you want to change the border style. The border style changes.

The borders/objects rules are:

Fields can be recessed by 2 or 3 pixels or have a 1 pixel plain border.

Field descriptions can have no border or a bevelled border.

Variable To Field

Selecting this button and clicking on a field with the left mouse button displays the Field Variables Window.

Details

Selecting this button displays the Field Definitions window.

The System Defaults Window

The System Defaults window is displayed by selecting the System button on the Workspace Designer toolbar.



Note: This same window is available from the Preferences window when you are in Client Workspace.

From the System Defaults window you can set defaults for screen reformatting that is used throughout Workspace Designer wherever a defaults option is displayed.

System Defaults

Field Options

☒ Remove Stops

Title Style

☒ None
☐ Description
☐ Variable Field

Clipping

Top
2

Bottom
0

OK Cancel Help

The System window displays the following fields:

Fields:

Field Options

This group box contains the following option only:

Remove Stops

This Check box has the following options:

Checked (Default) - This takes out the row of dots that is included by default in field descriptions. This is what you get:

Customer? [] []

Unchecked - This leaves in the row of dots that is included by default in field descriptions. This is what you get:

Customer.....?.. [] []

Title Style Option Button Group

This option button group box determines what you see as the title of the task. These are your options:

None - You get the system default stored on the server.

Description - (Only available when reformatting screens within Workspace Designer.) You get whatever you enter in the Title field on the Screen Definitions window in Workspace Designer.

Variable Field - (Only available when reformatting screens within Workspace Designer.) You get the title of the first field to have the Title field checked on the Field Details window in Workspace Designer.

Clipping

This spin button group box is used to specify how many lines are to be removed from the top and/or bottom of the screen when it is displayed.

The top two lines of a System 21 default screen usually show the program name, company and user, date and time. The appearance can be improved by removing these lines and the freeing up of the pixels improves the resolution of the screen.

If the Company Name is clipped from the screen you can easily check on this in Task Manager on the System menu.

The default for the clipping at the top is two lines.

The default for the clipping at the bottom is zero lines.

Buttons:

Ok

Save any changes you have made and close the System Defaults window.


Cancel

Close the System Defaults window, without saving any changes.

Help

Selecting this Help button displays help text about Client Workspace Designer and how to use the Infobase. By further selecting the Infobase button you can view the help text for the entire range of System 21 applications.

The Button Details Window



The Button Details window is accessed from the Custom button on the Workspace Designer Toolbar.

The Button Details window displays the following fields:

Fields:

Options

This group box contains two option buttons:

Add Button - Choose to add a new button to your screen and go on to complete the Row, Column, Button Text and Action details for this button.

Remove Button - Choose to remove a button from your screen and select the name of the button in the Remove Button field.

Remove Button

This button displays a scroll down list of all the buttons on the screen. You can choose one of these to be removed, provided that the Remove Button option is selected on the left of the screen.

Add Button

This group box contains the following fields:

Row

Enter the number of rows from the top of the screen for the position of the new button.

Column

Enter the number of columns from the left of the screen for the position of the new button.

Button Text

Enter the text which you want to display alongside the new button.

Action

Use this group box to identify the function to be called when your new button is pressed.

This group box contains fields which allow the use of Classes and Methods contained in Dynamic Link Libraries (DLLs) to facilitate custom controls for displaying information under System 21.

These DLLs are written in Guidelines, JBA's multi-platform development environment. For more information about Messaging classes and DLLs you should refer to the JBA Guidelines product guides.



Warning: Only personnel trained in Guidelines, or acting under the supervision of JBA personnel should use the Messaging Class fields. You need to fully understand which parameters are being passed from and to the program code which executes this window.

Action Option buttons

Use these buttons to determine whether to enter Class and Method fields or DLL and Function fields. As you toggle between these two option buttons the names of the fields to the right of the buttons change from Class and Method to DLL and Function.

These are your options:

Class and Method - Select this to enter details in the Class and Method fields.

DLL and Function - Select this to enter details in the DLL and Function fields

Class

This field is only available if the Messaging Class check box is selected and the Class and Method option button is selected.

Enter the name of the Class containing the method, which you want to be executed by the pressing of the new button, as specified in the Method field.

Method

This field is only available if the Messaging Class check box is selected and the Class and Method option button is selected.

Enter the name of the method which you want to be executed by the pressing of the new button, and which is owned by the Class specified in the Class field.

DLL

This field is only available if the Messaging Class check box is selected and the DLL and Function option button is selected.

Enter the name of the DLL containing the function, specified in the Function field, which you want to be executed by the pressing of the new button.

Function

This field is only available if the Messaging Class check box is selected and the DLL and Function option button is selected.

Enter the name of the function to be executed by the pressing of the new button and which is owned by the DLL specified in the DLL field.

Buttons:

OK

Close the Screen Definition window, and save any changes.

Cancel

Close the Screen Definition window, without saving any changes.

The Screen Definition Window

The screenshot shows the 'Screen Definition' dialog box. It features a 'Screen Identifier' text box with the value '0E02X0E036'. Below it is an empty 'Title' text box. The 'Action' section contains two checkboxes: 'Messaging Class' (unchecked) and 'Reformat' (checked). Under 'Action', there are two groups: 'Before' and 'After'. Each group has two radio buttons: 'Class and Method' (selected) and 'Dll and Function' (unselected). To the right of each radio button group are two text boxes labeled 'Class:' and 'Method:'. On the right side of the dialog, there is an 'Options' section with two buttons: 'Clipping' and 'Panel'. At the bottom of the dialog are three buttons: 'Update', 'Cancel', and 'Help'.

The Screen Definition window is accessed from the Details button on the Panel Tool.

The Screen Definition window displays the following fields:

Fields:

Screen Identifier

This field is display only and shows the identification number for the selected screen.

Title

If you have selected the Description option in the Title Style option button group on the System Defaults window it should be entered here.

Action

Use this group box to add functions to your system either before or after the execution of this window.

This group box contains the following fields:

Messaging Class

Use this check box to make the Class and Method fields and the DLL and Function fields available for input. When the box is checked the fields become available.

These fields allow the use of Classes and Methods contained in Dynamic Link Libraries (DLLs) to facilitate custom controls for displaying information under System 21.

These DLLs are written in Guidelines, JBA's multi-platform development environment. For more information about Messaging classes and DLLs you should refer to the JBA Guidelines product guides.

Reformat

If unselected then no screen reformatting will be shown.



Warning: Only personnel trained in Guidelines, or acting under the supervision of JBA personnel should use the Messaging Class fields. You need to fully understand which parameters are being passed from and to the program code which executes this window.

Within Action group there are two sub-groups called Before and After. Use them to determine the Class and Methods or DLLs and Functions to be executed either immediately before or after this window is displayed. Both sub-groups contain the following option buttons and fields:

Option Buttons

Use these buttons to determine whether or not to enter Class and Method fields or DLL and Function fields. As you toggle between these two option buttons the names of the fields to the right of the buttons change from Class and Method to DLL and Function.

These are your options:

Class and Method - Select this to enter details in the Class and Method fields.

DLL and Function - Select this to enter details in the DLL and Function fields

Class

This field is only available if the Messaging Class check box is selected and the Class and Method option button is selected.

Enter the name of the Class containing the method which you want to be executed as specified in the Method field.

Method

This field is only available if the Messaging Class check box is selected and the Class and Method option button is selected.

Enter the name of the method which you want to be executed, contained by the Class specified in the Class field.

DLL

This field is only available if the Messaging Class check box is selected and the DLL and Function option button is selected.

Enter the name of the DLL containing the function, specified in the Function field, which you want to be executed.

Function

This field is only available if the Messaging Class check box is selected and the DLL and Function option button is selected.

Enter the name of the function to be executed which is owned by the DLL specified in the DLL field.

Buttons:

Options

The Options group box contains the following two buttons:

Clipping

This button displays the Window Clipping screen, allowing you to remove lines from the top and bottom of the display.

Panel

This button displays the Panel Options Screen.

Update

Save any changes you have made and close the Screen Definition window.

Cancel

Close the Screen Definition window, without saving any changes.


Help

Displays a help window for Designer.

The Window Clipping Window

System 21 has programs and data in common with systems that use a character-based display. Often information not necessary on System 21 (date and time or user, for example) is presented at the top and bottom of these screens. Window Clipping allows you to remove these extraneous lines.

The Window Clipping window is accessed from the Screen Definition window.



The Window Clipping window is organised into two groups of fields which are mutually exclusive and are displayed as follows:

Fields:

The Options group box contains the following field:

Use System Defaults

When this check box is selected the system defaults for clipping, as defined in the System Defaults window, are used.

The second, unnamed group box, contains the following fields, which are only available if the Use System Defaults check box is not selected:

None (1) And (2)

There are two check boxes, both titled None, positioned above and below a black oblong. Each has a spin button below it with an associated numeric field.

Initially the arrows on the spin buttons are greyed out and unavailable. Selecting the check box causes the field title None to change to Fixed and the arrows on

the spin buttons to become available. The numeric fields can then be incremented between the values 0 and 24 using the spin controls.

Both sets of controls have an identical purpose:

The top set is used to specify the number of lines at the top of the display to be removed.

The bottom set is used to specify the number of lines at the bottom of the display to be removed.

Buttons:

Ok

Save your changes and close the Window Clipping window.

Cancel

Close the Window Clipping window, without saving changes.

Defaults


Save your settings as new system defaults.

Help

Displays a help window for Designer.

The Panel Options Window

The Panel Options window is accessed from the Screen Definitions window and allows you to set default attributes for a reformatted screen.



The Panel Options window is organised into a number of groups of fields which are displayed as follows:

Fields:

The following fields are grouped by the Action group box:

Hide

This check box hides the entire screen.

This is useful for occasions when the Messaging Class options on the Screen Definition window have been used to display data using a custom control. If this is not used the standard screen is displayed following the display of the data using the custom control.

Function

This option is not currently implemented.

Field Behaviour Group Box

Use System Defaults

Select this check box to use the remove stops defaults set up in the System Defaults window for field behaviour.

Remove Stops

This check box is only available if the System Default check box is unselected. Selected stops are removed.

Title Style Group Box

Use System Defaults

When this check box is selected the default title style set up in System Defaults is used. Selecting this automatically sets the Title Style option button group to None.

Title Style Option Button Group

This option button groups has the following choices:

None. Leaves the screens title to default from the server.

Description. Uses the title entered in the Title field on the Screen Definitions window as the screen title.


Variable Field. Uses the first field set to Field Title in the Field Details window as the screen title.

The Prompt Details Window

The Prompt window is displayed by selecting the prompt button on the Field panel and then selecting a field on the current window.

Use the Prompt window to place a prompt alongside a field.

For example on this window you might enter a question mark as the text and select F4 for the function key. When the user selects the prompt (?) alongside the field it has the same effect as if the user had entered ? in the field and then pressed F4.



Fields:

Prompt on this field by:

This is a group field which contains two option buttons and an entry field.

The option buttons give you two choices:

Entering Text

Selecting this will enable you to specify the text to be put into the edit field before the user presses the specified key. It is most likely that this will be a question mark. This does not affect what appears on the button alongside the field as this will always be a question mark.

Setting Focus To This Field

Selecting this will enable you to set the focus to the selected field. This will have the same effect for the user as having pressed the tab keys until the field is selected by the cursor.

Pressing

This drop down list box displays a list of facilities for you to include in the prompt activity. For example F4.

Buttons

OK

Select this button to close the window and save the changes.

Cancel


Select this button to close the window without saving the changes.

The Field Variables Window

The Field Variables window is displayed selecting the Vars button on the Field Details window, or by selecting the Field/Variables button on the Field Tool and clicking on a field.

Values in fields can be assigned to variables, and values held in variables can be assigned to fields. This assignment can be done before or after the screen containing the fields is displayed.

The Field Variables window allows you to change the input/output variables associated with the selected field.



The Field Variables window is organised into two groups of fields which are displayed as follows:

Fields:

Before Display Group Box

Set To Variable

The Set To Variable field contains a drop down list of variables that have been defined on the system. Selecting a variable sets the field being amended to the value of the variable selected before the screen is displayed.

Store In Variable

The Store In Variable field contains a drop down list of variables that have been defined on the system. Selecting a variable of these assigns the value of the field being amended to the variable selected before the screen is displayed.

After Display Group Box

Set To Variable

The Set To Variable field contains a drop down list of variables that have been defined on the system. Selecting a variable sets the field being amended to the value of the variable selected after the screen is exited; that is, it is used to change data sent to the server.

Store In Variable

The Store In Variable field contains a drop down list of variables that have been defined on the system. Selecting one of these assigns the value of the field being amended to the variable selected after the screen is exited.

Buttons:

Ok

Save changes and close the Field Variables window.

Maint

Displays the Variable Definition window, allowing maintenance of variables.

Cancel

Close the Field Variables window, without saving changes.

Help

Displays a help window for Designer.

The Field Definition Window

The Field Definition window is displayed by selecting the Details button on the Field Tool:

The screenshot shows the 'FieldDefinition' window. It contains a table with columns: Index, Host Text, Override Text, Row, Column, and Length. The table lists various fields like PM080, Z1 - UK Demonstration Company, User, TOOLS, 8/10/96, Order Entry, *++PM022, 11:33:42, Order number, Supplier?, and Address code. To the right of the table is a 'Type' group box with two radio buttons: 'Input' and 'Output'. The 'Output' button is selected. At the bottom of the window are three buttons: 'OK', 'Cancel', and 'Help'.

Index	Host Text	Override Text	Row	Column	Length
0	PM080		00	01	1
1	Z1 - UK Demonstration Company		00	19	3
2	User		00	55	4
3	TOOLS		00	60	1
4	8/10/96		00	71	8
5	Order Entry		01	02	1
6	*++PM022		01	14	8
7	11:33:42		01	71	8
8	Order number		02	02	1
9	Supplier?		03	02	1
10	Address code		04	02	1

The Field Definition window is organised into a number of groups of fields or buttons which are displayed as follows:

Fields:

The following fields are grouped by the Output/Input Fields group box. This changes its name depending on whether the Input or Output button in Type group box is selected. Most of these fields are only useful to qualified JBA personnel. The following information is useful to the end user of Workspace Designer:

Host Text

The name of the field or field description at the Server.

Override Text

The text substituted at the Client.



Warning: This is for System Administrators.
Please note that Workspace Designer does not support the CHANGE keyword with text that has been overwritten or masked at the Client.

Row

The row on a character-based display connected to the server that the field is displayed at.

Column

The column on a character-based display connected to the server that the field is displayed at.

Length

The number of characters in the field.

The following two mutually exclusive buttons are grouped by the Type group box:

Input

Pressing this button redisplay the current screen with Input only fields shown, and sets the Output Fields group box title to Input Fields.

Output

Pressing this button redisplay the current screen with Output only fields shown, and sets the Input Fields group box title to Output Fields

Double-clicking on a field definition displays the Field Details window.

Buttons:

Ok

Save all changes and close the Field Definition window.

Cancel

Close the Field Definition window, without saving changes.

Help

Displays a help window for Designer.

The Field Details Window

The Field Details window is displayed by double-clicking on a line from the Field Definitions window.

It displays details of the Server and System 21 settings for the fields selected in the Field Definitions window.

Field Details

Host Definition

Row: 0 Type: Output

Column: 19 Text: Z1 - GB Demonstration Company

Length: 35

☐ Highlighted ☐ Reverse Image ☐ Hidden

☐ UnderScore ☐ Column Seperator ☐ Blink

Display Definition

Row: 0

Column: 19

Length: 35

☐ Override Text

☐ Highlighted ☐ Reverse Image ☐ Hidden

☐ UnderScore ☐ Column Seperator ☐ Blink

Border Effect: Default

☐ Title Field

Add Vars Cancel Help

The Field Details window is organised into two groups of fields:

- The Host Definition group of fields enables you to make changes to the way fields are displayed on the server.
- The Display Definition group of fields enables you to make changes to the way fields are displayed on the System 21 display.

Fields:

Host Definition

This group box contains the following fields:



Note: These fields are output only and cannot be overridden.

Row

The row position for the selected field on the server.

Column

The column position for the selected field on the server.

Length

The display length of the selected field on the server.

Type

Shows the Field Type - either Input or Output.

Text

The text for the entire field as it appears on the server. If this is an output field it contains the text of the output string. If an input field it contains the current contents of the field.

Highlighted

When selected this check box indicates that the field is highlighted when displayed on the server.

Reverse Image

When selected this check box indicates that the field is reversed out when displayed on the server.

Hidden

When selected this check box indicates that the field is hidden on the server.

UnderScore

When selected this check box indicates that the field is underlined when displayed on the server.

Column Separator

When selected this check box indicates that the field is marked as a column separator field when displayed on the server. The system can then use this as a way of identifying certain fields to be marked in a colour.

Blink

When selected this check box indicates that the field is marked as a blink field when displayed on the server. The system can then use this as a way of identifying certain fields to be marked in a colour.

Display Definition

This group box displays the following fields:

Row

This spin button allows you to change the display row position for the selected field.

Column

This spin button allows you to change the display column position for the selected field.

Length

This spin button allows you to change the display length of the selected field.

Override Text

This field allows you to change the display text of the selected field.



Warning: This is for System Administrators. Please note that Workspace Designer does not support the CHANGE keyword with text that has been overwritten or masked at the Client.

Highlighted

When selected this check box indicates that the field is highlighted when displayed on the System 21 display.

Reverse Image

When selected this check box indicates that the field is reversed out when displayed on the System 21 display.

Hidden

When selected this check box indicates that the field is hidden on the System 21 display.

The effect of this and the Highlighted and Hidden check boxes is duplicated on the Field Tool, so that these characteristics can be set interactively.

UnderScore

When selected this check box indicates that the field is underlined when displayed on the System 21 display.

Column Separator

When selected this check box indicates that the field is marked as a column separator field when displayed on the System 21 display. The system can then use this as a way of identifying certain fields to be marked in a colour.

Blink

When selected this check box indicates that the field is marked as a blink field when displayed on the System 21 display. The system can then use this as a way of identifying certain fields to be marked in a colour.

Title Field

When this checkbox is selected the field is defined as a Title Field and will be used as the screen title if the Title Style option button group on the System Defaults window is set to Variable.

Border Effect

This drop-down list allows you to select the display border style from. The following options are available:

- Default - The border style is set to the system's defaults, that is, a 2D Deep border for fields and no border for field descriptions.
- No Border.
- Line.
- Deep 2D.
- Deep 3D.

- Bevel.

These correspond to the options available in the Border group on the Field tool.

Buttons:

Add

Save all new entries and close the Field Details window.

Update

Save all changes and close the Field Details window.

Vars

Display the Field Variables window.

Cancel

Close the Field Details window, without saving changes.

Help

Displays a help window for Designer.

Delete Field Definition




This button is only displayed after reformatting has taken place. Select it to discard any changes not required.

The Variable Definition Window

A variable can be seen as a container for information, an object that you can store data in and read data from. You can use a variable to, for example, set a field to a pre-determined value.

The Variable Definitions window is displayed when the Maint button on the Field Variables window is selected. This window allows you to create, edit or delete variables.



The Variables Definition window shows all the current variables held (if any) in a table format, listing the following information:

Name

The name of the variable.

Description

A meaningful description of the variable.

Buttons:

Add

Display the Variable Details window, allowing you to add a new variable definition.

Edit

Display the Variable Details window, allowing you to edit a variable definition.

Delete

You can delete a selected variable definition by highlighting it in the Variable Definition window, and selecting Delete. A window is displayed prompting you for confirmation of your action.

Ok

Close the Variable Definition window and save all changes.

Cancel


Close the Variable Definition window without saving changes.

Help

Displays a help window for Designer.

The Variable Details Window

The Variable Details window is used to add and edit variables. It is displayed by selecting the Add or Edit buttons on the Variable Definitions window.



The Variable Details window displays the following fields and buttons:

Fields:

Name

If adding a variable enter its name here.

If editing an existing variable this field is display only - only the description can be amended.

Description

If adding a variable enter a meaningful description for it. If editing an existing variable, select the field make the required amendment.

Buttons:

Add

Save all changes and close the Variable Details Window.

Cancel

Close the Variable Details Window without saving changes.

Help

Displays a help window for Designer.

Delete Variable Definition

This button is only available when editing an existing variable, that is, when the Variable Details window has been displayed by selecting the Edit button of the Variable Definition window.

Selecting it deletes the currently selected Variable Definition.


Adding Help to System 21

You can add Context-Sensitive Help to the applications that run in JBA Client Workspace.

You define the links between the application and your help file using Workspace Designer.

The System 21 Help Text Window

The System 21 Help Text Window is displayed by selecting the help button on the Workspace Designer Toolbar:



System 21 Help Text Window



Note: All options in this window are mouse-driven only.

This window is used to define up to three areas of help for the current screen - Help, Getting Started and Hints and Tips. Each can have the same, or different, help text associated with the screen.

Each area of help - Help, Getting Started and Hints and Tips - is shown as a tab in a tabbed dialogue box. Each has the same fields on each tab, and the functionality of each tab is identical.

Fields:

Magic Number

This display only field holds the Screen Identifier (Magic Number) for the current screen. The number is determined automatically by the system and cannot be amended.



Note: The Screen Identifier (Magic Number) is only unique to a display file. Occasionally display files are used in two locations, and, as such, it is

possible that two different options may have the same number.

Help File

This drop-down list shows the prefixes of the Help and Help Project files (.HLP and .HPJ files) in the help files directory specified in the Help Files field in the File / Preferences / Paths window.

This path must be specified before you use Workspace Designer. The syntax is (for example): K:\HELPPFILES.

For more details of the Preferences window see the Client Workspace product guide.

Select the file you wish to link to from the drop-down list.

Help Panel Id.

This field holds the unique number (Tag Id.) associated with a topic in a Help file.

You can enter a number directly into the field (if known), or use the Browse button to select a number from the displayed table.

Description

This field shows the text of the associated Help Project file heading, as it appears in the help file. This field is entered automatically when you select a topic using the Browse button, or if you enter a number into the Help Panel Id. field.


Buttons:

View

Select this button to test the Help file link for the current screen.

The link is executed, and the selected Help topic is displayed exactly as it would be when the associated Help option is taken from JBA System 21 applications.

To close the test window and return to the Help File definition window, use File / Exit.



An Example Help File Window

Browse

Selecting the Browse button opens the Help File Browser window, which displays the three relevant areas of the selected Help Project File - Description, Panel Id., and Context String - in a table format. You can select the help topic to link to by double-clicking on a displayed topic.

Ok

Save the changes and close the System 21 Help Text window.

Cancel

Close the System 21 Help Text window without saving the changes.


Help

Displays a help window for Designer.

The Help File Browser Window

Selecting the Browse button opens the Help File Browser window, which displays the three relevant areas of the selected Help Project File - Description, Panel Id., and Context String - in a table format.

You can select the help topic to link to by double-clicking on a displayed topic.



The Help File Browser Window

You can use the scroll bars to move around the window, and select the required area of Help Text either by double-clicking on the required line, or by clicking once on the line and once on the OK button.

Alternatively, use the Cursor Keys to move around the window, and press **Enter** to select the highlighted Help Topic. TAB and Shift-TAB can be used to select the various buttons (for example, the View button to test the link).

Buttons

View

Select this button to test the Help file link for the current screen.

The link is executed, and the selected Help topic is displayed exactly as it would be when the associated Help option is taken from JBA System 21 applications.

To close the test window and return to the Help File definition window, use File / Exit.

Ok

Save the changes and close the Help File Browser Window.

Cancel

Close the Help File Browser Window without saving the changes.

Help

Displays a help window for Designer.

Type in the details, and click once on OK to accept the definitions, or Cancel to exit from the window without saving any changes.

Workspace Designer System Files

All the data concerning the reformatting is written to a set of files which reside in the directory defined for JBA System 21 on your PC.

See the JBA Client Workspace product guide for further details.



Warning: These files should be saved regularly!

They are as follows:-

SRUSER.IDX	SRUSER.DTA
SRCOMP.IDX	SRCOMP.DTA
S21HELP.IDX	S21HELP.DTA



Tip: These files can be copied to other machines, to enable common reformatting of screens - hence, one person could design a set of screens, then copy them to other machines.

Mask Formatting Method

The following table shows characters that can be used to design your own output masks for numeric data.

Characters	Meaning
0-9	Zero filled digit.
@	Space filled digit.
#	Unfilled digit.
+	All numbers preceded by a plus/minus sign.
-	Negative numbers preceded by a minus sign.
e	Scientific notation (lowercase).
E	Scientific notation (uppercase).
.	Decimal place.
,	Thousands indicator.
(	Open bracket displayed as a literal.
)	Close bracket displayed as a literal.
\$	Dollar sign displayed as a literal.
'literal'	Display the quoted literal.
"literal"	Display the quoted literal.