KryptoNetView

User Guide

Clearly display, document and securely manage your home network topology




Figure 1: *The main view of KryptoNetView (dark mode)*

Version 1.0 · As of: November 2026

All screenshots show the supplied sample configuration. Credentials are obscured.

Table of Contents

1 Introduction 4
1.1 What is KryptoNetView? 4
1.2 Key features at a glance 4
1.3 Who is this guide for? 4
1.4 Conventions used in this guide 5

2 Getting started 6
2.1 System requirements 6
2.2 Starting the program 6
2.3 First look 6
2.4 The sample data 7

3 The header and its buttons 8
3.1 After logging in 8
3.2 Canvas toolbar 8
3.3 Footer and legend 9

4 The five views 10
4.1 Net View 10
4.2 Circle view 10
4.3 Tree view 11
4.4 Rooms view 12
4.5 List view 12

5 Navigating the canvas 14
5.1 Zooming and panning 14
5.2 Hover information 14
5.3 Device node symbols 15

6 Device list, search and filters 16
6.1 The device list 16
6.2 Searching 16
6.3 Sorting 17
6.4 Filtering by category 18

7 Device details 19
7.1 Without login 19
7.2 With login 20
7.3 Closing the details 20

8 Logging in as administrator 21
8.1 Logging in 21
8.2 Wrong password 21
8.3 What changes after login 21
8.4 Logging out 22

9 Master password and security 23
9.1 How the encryption works 23
9.2 Changing the master password 23
9.3 Forgot the password? 24
9.4 Security recommendations 24

10 Edit mode 25
10.1 Turning on edit mode 25
10.2 What you can do in edit mode 25
10.3 Moving icons 25

11 Creating, editing and deleting devices 27
11.1 The edit form 27
11.2 Entering login data and WLAN 28
11.3 Parent node, connections and network colors 28
11.4 Choosing an icon and color 28
11.5 Creating a new device 29
11.6 Deleting a device 30

12 Settings: title, switch, categories 31
12.1 Title & Switch 31
12.2 Network colors 31
12.3 Managing categories 32
12.4 Creating a new category 33

13 Frames and groups 34
13.1 Drawing a frame 34
13.2 Managing frames 35

14 Saving and backing up 37
14.1 Browser storage (automatic) 37
14.2 Saving directly to the file 37
14.3 What is stored where in the file? 37
14.4 Backup strategy 37

15 CSV export and import 38
15.1 Export 38
15.2 Structure of the CSV file 38
15.3 Import 38

16 Printing 40
16.1 The print dialog 40
16.2 The print options 40
16.3 Page orientation 40
16.4 Examples 41
16.5 Printing credentials 42

17 Using it on a smartphone and tablet 43
17.1 Smartphone 43
17.2 Tablet 44
17.3 Touch gestures 45

18 Design and language 46
18.1 Light and dark mode 46
18.2 Language 46

19 Practical examples and tips 48
19.1 Documenting a new network device 48
19.2 Updating devices after a scan 48
19.3 Documenting the network for family or guests 48
19.4 Planning a move or rebuild 48
19.5 General tips 48

20 Troubleshooting (FAQ) 49

Appendix 50
A Button quick reference 50
B Device fields 50
C Default categories 51
D Technical data 51
E Glossary 51

1 Introduction

1.1 What is KryptoNetView?

KryptoNetView is a tool for displaying and documenting your home or small-office network as a graphical topology. Every device – router, switch, access point, phone, printer, smartphone or sensor – appears as an icon on a canvas and is connected by lines to the device it is attached to. For each device you store the IP address, hostname, MAC address, vendor, open ports, PoE status and a description.

Particularly sensitive information – login data and WLAN passwords – is stored **encrypted with AES-256** and only becomes visible after you log in with the master password.

The entire program consists of **a single HTML file**. No installation, no server and no internet connection to any service is required; your data stays with you.

1.2 Key features at a glance

- **Five views** of the same data: Net, Circle, Tree, Rooms and List.
- **Device list** with search, sorting and category filter next to the graph.
- **Detail view** per device with all master data and – after login – the credentials.
- **Edit mode** for moving icons and for creating, changing and deleting devices.
- **Frames/groups** for visually grouping devices (e.g. guest network, WLAN hub).
- **Categories, icons and colors** are freely configurable, as are the colors of the connection lines.
- **Encrypted credentials** (AES-256-GCM) with a changeable master password.
- **Print function** with six print options, always in a light, paper-friendly layout.
- **CSV export and import**, also for merging network scans.
- **Direct saving** into the HTML file (Chrome/Edge) or storage in the browser.
- **German and English**, **light and dark** view mode.
- **Mobile-friendly** on smartphone and tablet with touch operation.

1.3 Who is this guide for?

This guide is for everyone who wants to document their network – from beginners to experienced administrators. Chapters 2 to 7 are enough to understand and use the display (**viewer**). From Chapter 8 onward the topic is logging in and editing (**administrator**).

Chapter	Content	Audience
2–3	Getting started, interface, header	Everyone
4–7	Views, list, search, details	Everyone
8–9	Login, master password, security	Administrator
10–13	Editing, devices, categories, frames, settings	Administrator
14–16	Saving, CSV, printing	Everyone / Administrator
17–18	Mobile use, design and language	Everyone
19–20	Tips, troubleshooting, appendix	Everyone

1.4 Conventions used in this guide

- **Bold** type marks controls, e.g. the **Login** button.
- `Typewriter font` is used for inputs, file names and values.
- Colored boxes mark tips, notes, warnings and security notices.

> **Tip:** You may safely try out the accompanying sample data: as long as you do not save, the file remains unchanged.

2 Getting started

2.1 System requirements

Component	Recommendation	Note
Browser	Chrome or Edge (current)	Only these support **Save Directly** into the file
Alternative	Firefox, Safari	Works; back up changes in browser storage or via CSV
Internet	Optional	Fonts and icons are loaded online; without internet the appearance differs slightly
Screen	1280 × 720 or larger	Smartphones and tablets are supported
Installation	None	Simply open the HTML file

2.2 Starting the program

1. Save the file `Demo.html` (or your own file) in a place you will find again – e.g. in the **Documents** folder.
2. Open the file by **double-clicking** it. It starts in your default browser.
3. After a few seconds the topology appears. No login is needed to view the display.
4. To make changes, click **Login** and enter the master password (Chapter 8). The default password is `admin`.

> **Security:** Change the default password `admin` right after the first login (Chapter 9). Anyone who has the file and knows the default password can read all credentials.

2.3 First look

After starting you see four areas: the **header** with title and buttons, on the left the **sidebar** with search and device list, in the middle the **canvas** with the topology, and below it the **legend**.




Figure 2: *Main view with numbered areas (see the following table)*

No.	Area	Function
1	Header	Title, subnet, switch data and all buttons (Chapter 3)
2	Search and sorting	Find devices by name, IP or hostname (Chapter 6)
3	Category filter	Restrict list and graph to one device group
4	Device list	Cards of all devices; a click opens the details
5	View selection	Net, Circle, Tree, Rooms or List (Chapter 4)
6	Zoom and tools	Zoom in, zoom out, center, reset view, auto-arrange
7	Frames	Groups with colored outline, here e.g. guest network and WLAN hub
8	Logo and title	Name of your topology

2.4 The sample data

The supplied sample configuration describes a family home network with **41 devices**: a central switch (Cisco WS-C2960S-48LPS-L), routers and gateways, four WLAN access points, several VoIP phones, printers, servers, smart-home components, sensors, and smartphones and tablets. In addition there is a frame **AP-EG WLAN Hub** and a frame **Gastnetz (VPN / VLAN 192.168.179.x)**.

You can replace the sample data with your own devices at any time: delete or rename devices (Chapter 11) or import your own CSV file (Chapter 15).

> **Note:** The sample data is entirely fictitious; the passwords and SSIDs shown are placeholders.

3 The header and its buttons

The header at the top edge contains the logo, the title of your topology, the main network (subnet CIDR) and a line with the data of the **central switch** together with a note about the AES-256 vault. Below it are the buttons. Without login only some of them are active; the others are dimmed.




Figure 3: *Header in viewer mode (logged out) with numbered buttons*

No.	Button	Function	Login required?
1	DE / EN	Switch between German and English	No
2	Light / Dark	Switch between light and dark view mode	No
3	Print	Open the print dialog with six options	No*
4	Link to file	Save changes directly into the HTML file	No
5	Devices: 41	Number of all devices (display)	–
6	Login	Enter the master password	–
7	Title & Switch	Change title, subnet, switch and network colors	Yes
8	Categories	Manage device categories	Yes
9	+ Draw Frame	Drag out a new frame with the mouse	Yes
10	Groups/Frames	Manage, edit and delete frames	Yes
11	Edit Mode	Move icons and edit devices	Yes
12	Save Directly	Write the current state into the file	Yes
13	CSV	Export all data as a CSV file	Yes
14	Load	Import a CSV file	Yes

*Printing the credentials is only possible after login (Chapter 16).

3.1 After logging in

As soon as you are logged in, all buttons are highlighted in color. **Login** becomes **Logout (Admin Active)**, and **Change Password** and **New Device** appear in addition. The **Edit Mode** button changes to **Disable Mode** after it is switched on.




Figure 4: *Header when logged in with edit mode active*

3.2 Canvas toolbar

Directly above the graph is the toolbar of the canvas. On the left is the view selection, on the right the zoom and layout tools.



Figure 5: *Canvas toolbar*

Element	Function
View selection	Net View, Circle, Tree, Rooms or List
+ / –	Zoom the graph in or out (alternatively the mouse wheel)
Center	Fit the graph into the visible area
Reset view	Restore the saved arrangement of this view and fit it
Auto-arrange	Re-arrange the icons of this view automatically (replaces the saved arrangement)

> **Warning:** **Auto-arrange** overwrites your manually saved arrangement of the current view. If you have spent a long time moving icons, use **Reset view** instead.

3.3 Footer and legend

Below the graph, the **Connection Legend** shows the meaning of the line colors: Standard LAN, Gigabit Ethernet, AP-EG WLAN Radio and Guest Network VLAN. The legend adapts automatically when you change network colors (Chapter 12.2). Next to it is the hint “Click device for details”, in edit mode “Edit Mode Active: Drag & Drop & Click to Edit”.




Figure 6: *Connection legend and hint line*

4 The five views

All views show the same data, just arranged differently. You switch using the selection list on the left of the canvas toolbar. For each view KryptoNetView remembers zoom, pan and the position of the icons separately.

4.1 Net View

The default view. The central switch is in the middle and the connected devices group around it. Frames (e.g. WLAN hub, guest network) have a colored outline. Line colors show the connection type.




Figure 7: *Net View*

4.2 Circle view

All devices are placed on a circle around the central node. This view is suitable for showing many direct connections at a glance. There are no frames in the Circle view.




Figure 8: *Circle view*

4.3 Tree view

The devices are shown as a compact tree from top to bottom: devices without child nodes (leaves) are arranged as a grid below their parent node. This lets you see immediately what a device is attached to. Frames (e.g. WLAN hub, guest network) are retained as groups.



Figure 9: *Tree view*

4.4 Rooms view

The devices are grouped by category in blocks with a colored outline (e.g. Router, Printers, VoIP Phones, Sensors). Existing frames are retained as separate groups. Devices whose category no longer exists appear in the block **Other**.




Figure 10: *Rooms view*

4.5 List view

The devices are arranged in columns next to each other, sorted alphabetically or by IP address; frames are retained as separate groups. This view is particularly compact for very large networks.



Figure 11: *List view*

> **Tip:** Use the Tree view to trace cabling paths, the Rooms view to see devices grouped by category, and the Net View for the overall picture.

5 Navigating the canvas

5.1 Zooming and panning

- **Zoom:** turn the mouse wheel or use **+ / –** in the toolbar.
- **Pan:** click on empty space, hold the mouse button and drag.
- **Fit: Center** shows the entire topology.
- **Touch:** two fingers to zoom, one finger to pan (Chapter 17).




Figure 12: *Heavily zoomed-in section of the Net View*

5.2 Hover information

When you move the mouse over an icon, KryptoNetView highlights the device and its connections and fades in the most important data. A click opens the full detail view.




Figure 13: *Highlighted device while hovering with the mouse*

5.3 Device node symbols

Each node shows the device name, IP address and category. A small key symbol indicates that credentials are stored for the device. The color of the top edge corresponds to the category color.

Feature	Meaning
Colored top edge	Category of the device (router, switch, server, ...)
Key symbol	Credentials or WLAN data stored
Lighter outline	Central node (switch)
Line color	Connection type or network color
Dashed line	WLAN radio or guest network (depending on the network color)

6 Device list, search and filters

6.1 The device list

To the left of the graph is the device list. Each card shows the icon, name, category, IP address and – for devices powered over the network cable – the PoE badge. A key symbol marks devices with stored credentials. The note “via Cisco WS-C” names the device to which each device is connected.




Figure 14: *Device list in the sidebar*

6.2 Searching

The search field above the list filters in real time by device name, IP address or hostname. The graph is filtered as well: devices that do not match are hidden.

1. Click into the field **Search device, IP or hostname...**.
2. Type part of the name or the IP, e.g. `Cisco` or `178.9`.
3. The list and the graph now show only the matches. To reset, clear the search text.




Figure 15: *Search for “Cisco”: list and graph show only the matches*

6.3 Sorting

The selection to the right of the search field sets the order. The choices are **A–Z**, **Z–A**, **IP ↑**, **IP ↓** and **Category**.




Figure 16: *Sort selection*

6.4 Filtering by category

With the selection **All Categories (41)** you restrict list and graph to one category, e.g. only Printers or only WLAN Access Point. The value in brackets is the number of devices. The filter also affects the print option **Current screen section**.




Figure 17: *View filtered by category*

> **Note:** You can manage the categories themselves via **Manage** (next to the heading “Categories”) or via the **Categories** button after login (Chapter 12).

7 Device details

A click on a device – in the list or in the graph – opens the detail view on the right. It is divided into sections:

Section	Content
Head	Icon, name and category of the device; X to close
Network data	IP address, subnet/VLAN, connected to, Power over Ethernet
Scan data	Hostname, MAC address, vendor, device type (scan), open ports
Credentials / Login	Username and password – encrypted until login
WLAN Access (SSID)	SSID and WLAN password (for routers and access points)
Description & Function	Free text about the purpose of the device

7.1 Without login

As a viewer you see all master data. The sections **Credentials / Login** and **WLAN Access (SSID)** carry the badge **AES Encrypted** and only show the note “Credentials protected via AES-256” and the button **Login to Unlock**.




Figure 18: *Detail view without login: access point with WLAN section (left) and printer (right)*

7.2 With login

After login the badge shows **AES-256 Unlocked**. Username and password are displayed; the password is initially hidden as dots. The eye icon makes it visible, and the copy icon puts the username or password on the clipboard.




Figure 19: *Detail view after login with login and WLAN data*

> **Security:** Only reveal passwords when nobody can look over your shoulder. A screenshot of the open detail view will then also contain plain-text passwords.

7.3 Closing the details

You close the window with **X** at the top right, with **Close** in the edit form, or by clicking on the darkened background.

8 Logging in as administrator

To edit devices or view credentials, log in with the master password. In the delivered state it is `admin`.

8.1 Logging in

1. In the header click **Login** (or **Login to Unlock** in the detail view).
2. In the field **Master Password** enter the password. Use the eye icon to check your input.
3. Click **Login & Unlock Edit Mode** or press the Enter key.
4. A green message confirms: “Successfully logged in. Edit mode can now be enabled.”




Figure 20: *Login dialog (left) and error message for a wrong password (right)*

8.2 Wrong password

If you enter the wrong password, the message **Incorrect master password!** appears. Try again. There is no password recovery (see Chapter 9.3).

8.3 What changes after login

- Credentials and WLAN passwords are decrypted and can be displayed.
- The buttons **Title & Switch**, **Categories**, **+ Draw Frame**, **Groups/Frames**, **Edit Mode**, **Save Directly**, **CSV** and **Load** are enabled.
- The buttons **Change Password** and **New Device** appear.
- Printing the credentials list becomes possible (Chapter 16).




Figure 21: *Main view after successful login*

8.4 Logging out

Click **Logout (Admin Active)**. The session ends, credentials are hidden again and the editing functions are locked. A message “Successfully logged out.” confirms this.

> **Tip:** Always log out when you leave your seat – even for a short absence.

9 Master password and security

9.1 How the encryption works

All sensitive fields (login user, login password, WLAN SSID and WLAN password) are kept in a vault. From your master password a key is derived with PBKDF2 (100,000 iterations), and the data is encrypted and decrypted with it using AES-256-GCM. In the file the sensitive data is stored exclusively in encrypted form; the master password itself is not stored.

Data	Protection
Device name, IP, hostname, MAC, vendor, ports, description	Unencrypted (visible to anyone who opens the file)
Login username and password	AES-256-GCM
WLAN SSID and password	AES-256-GCM
Master password	Not stored; only the derived key verifies the input

> **Warning:** Only the credentials are encrypted. Do not enter any passwords in the **Description** field – the text there is stored in plain text.

9.2 Changing the master password

1. Log in (Chapter 8).
2. In the header click **Change Password** (alternatively **Change Master Password** in the login dialog).
3. Enter the **Current Password**.
4. Enter the **New Master Password** and repeat it under **Confirm New Password**.
5. Click **Save**. All vaults are re-encrypted with the new key. A message confirms the change.




Figure 22: *Dialog “Change Master Password”*

Choose a long, unique password, ideally a passphrase of several words. The longer the password, the harder it is to crack by trial and error.

9.3 Forgot the password?

> **Security:** There is no way to reset a forgotten master password. Without the password the encrypted credentials remain unreadable. Write the password down safely (e.g. in a password manager or a safe) and make regular backups (Chapter 14.4).

The unencrypted master data (devices, IPs, connections) remains usable even if the password is lost. Only logins and WLAN passwords are lost and have to be entered again.

9.4 Security recommendations

- Change the default password `admin` immediately.
- Keep the HTML file only in trustworthy places and protect backups.
- CSV exports contain passwords in plain text – delete them securely after use (Chapter 15).
- Keep printouts of credentials (Chapter 16) locked away or destroy them.
- Do not place the file in unencrypted cloud folders that others can access.
- When sharing the file, remove the credentials beforehand or create a copy without credentials.

10 Edit mode

10.1 Turning on edit mode

1. Log in.
2. Click **Edit Mode**. The button changes to **Disable Mode**.
3. A banner appears at the top: “EDIT MODE ACTIVE: Drag nodes/frames to move them.”
4. To finish, click **Disable Mode**.




Figure 23: *Active edit mode with hint banner*

10.2 What you can do in edit mode

Action	How
Move an icon	Drag the node with the mouse (drag & drop)
Move a frame	Drag the frame by its title bar
Edit a device	Click the icon or the card – the edit form opens
Create a device	New Device in the header
Draw a frame	+ Draw Frame, then drag with the mouse
Recalculate the arrangement	Auto-arrange

10.3 Moving icons

Drag an icon to the desired position; the connected lines follow automatically. The arrangement is saved per view, so you can, for example, lay out the Net View and the Rooms view differently.




Figure 24: *Moving icons in the Circle view (edit mode)*

> **Tip:** With **Reset view** you restore the last saved arrangement if you have moved things by accident.

> **Note:** Changes are initially only in the browser storage. To save them permanently, use **Save Directly** (Chapter 14).

11 Creating, editing and deleting devices

11.1 The edit form

In edit mode (or when logged in), a click on a device opens the edit form. It contains all fields of the device. The form is long and scrolls; the following figure shows it in two parts.




Figure 25: *Edit form: upper part (left) and lower part (right)*

Field	Description
Device Name / Hostname	Display name of the device in graph and list
IP Address	IPv4 address, e.g. 192.168.178.92
Category	Device type (router, switch, printer, ...); determines the default icon and color
Hostname, MAC address, Vendor, Device type (scan), Open ports	Technical details, usually from a scan
Edit Login Credentials	Username and password (stored encrypted)
SSID & WLAN Configuration	One or more SSIDs with password (for router/AP)
Connected to (Parent Node)	Device to which this one is connected – determines the line
Icon (FontAwesome)	Symbol of the device
Accent Color	Color of the symbol and the card borders

Field	Description
Network type (connection line)	Line style/color of the connection to the parent node
Link color (connection line)	Optional custom line color; Automatic resets it
Power over Ethernet (PoE)	Device is powered over the network cable
Description	Free text about the purpose and location of the device

11.2 Entering login data and WLAN

In the section **Edit Login Credentials** you enter username and password. The eye icon shows the password. For routers and access points there is additionally **SSID & WLAN Configuration**: enter SSID and password and add further radio networks via **Add Another SSID** (e.g. main network and guest network). The red trash can removes an SSID.

> **Security:** Only saving the form applies changes. When saving, login and WLAN data are immediately encrypted with AES-256.

11.3 Parent node, connections and network colors

The selection **Connected to (Parent Node)** determines which device the current one is connected to. This is how you reproduce the actual cabling or the WLAN association. The **Network type** sets color and line style (e.g. Gigabit Ethernet or WLAN radio). With **Link color** you override the color for a single device; **Automatic** restores the default color of the network type.

11.4 Choosing an icon and color

The icon selection opens a list with a search field; it contains the FontAwesome symbols. You choose the **Accent Color** from a palette or via a color picker with a color area, a hue bar and a hex input field.




Figure 26: *Icon selection (left) and color picker (right)*

11.5 Creating a new device

1. Log in and click **New Device**.
2. Enter at least the device name and IP address and choose the category.
3. Choose the parent node to which the device is connected.
4. Optionally add icon, color, PoE, description and credentials.
5. Click **Save Changes**. A message confirms: “New device created.”




Figure 27: *“New Device” form*

11.6 Deleting a device

Open the device in the edit form and click **Delete** at the bottom left. The device is removed together with its connections, and the message “Device deleted.” appears.

> **Warning:** Deleting cannot be undone. Back up the file beforehand or export a CSV file (Chapters 14 and 15). Assign devices that are attached to the device being deleted to another parent node first.

12 Settings: title, switch, categories

12.1 Title & Switch

Via **Title & Switch** you change the global parameters of the topology:

Field	Meaning
Topology Title	Name that is shown in the header and when printing
Main Subnet CIDR	Main network in CIDR notation, e.g. 192.168.178.0/24
Switch / Router Model	Designation of the central device
Switch IP Address	IP address of the central device




Figure 28: *Dialog “Configure Topology & Switch”*

12.2 Network colors

In the same dialog you set the line color and line style (solid, dotted, dashed) per connection type under **Network colors (connection lines)**. Standard types (Standard LAN, Gigabit Ethernet, AP-EG WLAN Radio, Guest Network VLAN) can only be renamed and recolored. With **Add new network color** you create your own types. The legend below the graph adapts automatically.




Figure 29: *Network colors (connection lines) in the settings dialog, with a new network color being added*

> **Warning:** If you delete a network type that is still used by devices, a warning appears with the number of affected devices. They then fall back to the automatic network color.

12.3 Managing categories

Categories (or **Manage** next to the heading Categories) opens the category management. There you create new device types and change names, icons and colors of existing categories.




Figure 30: *Dialog “Manage Categories”*

Field	Meaning
Category ID / Key	Internal identifier, e.g. router (lowercase letters and digits only)
Name / Label	Display name, e.g. Router
FontAwesome Icon	Default symbol of the category
Color / Accent	Color in graph, list and legend

12.4 Creating a new category

1. Open **Categories**.
2. Under **Add New Category** enter ID, name, icon and color.
3. Click **Save Category**.
4. Close the dialog with **Done / Apply**.




Figure 31: *Icon search in category management*

With **Delete** in the list of existing categories you remove a category that is no longer needed. The six basic categories (Router, Gateways, WLAN Access Point, Switch, Server, End Device) are marked with the note **Standard** and cannot be deleted.

13 Frames and groups

Frames visually group devices, e.g. all devices in the guest network or on a particular access point. They are available in the Net, Tree, Rooms and List views (not in the Circle view).

13.1 Drawing a frame

1. Log in and switch on edit mode.
2. Click **+ Draw Frame**. A banner points this out: “DRAW FRAME: Click and drag on the canvas to span a new visual frame.”
3. With the mouse button held down, drag out a rectangle on the canvas.
4. An input window asks for the name/title of the new frame (default “Neue Zone”). Confirm with **OK**.
5. To cancel, click **Cancel Drawing**.




Figure 32: *Frame drawing mode: banner and “Cancel Drawing” button*




Figure 33: *The newly drawn frame on the canvas*

13.2 Managing frames

With **Groups/Frames** you open the management of all existing zones. There you edit or delete frames and change titles and colors. **Add New Frame** creates a new frame (“Neue Zone”, 300 × 300) in the middle of the visible section, which you can then move and adjust.




Figure 34: *Dialog “Manage Groups & Frames”*




Figure 35: *Frames on the canvas*

> **Tip:** Devices inside a frame belong together visually. If you move the frame by its title bar, all devices it contains follow.

14 Saving and backing up

KryptoNetView offers three ways to keep changes. Which one is possible depends on the browser.

14.1 Browser storage (automatic)

Every change is additionally stored in the browser's local storage (localStorage). This protects against accidentally closing the window, but it is no substitute for a backup: if you delete the browser data or open the file in another browser, the changes are not there.

14.2 Saving directly to the file

In Chrome and Edge, KryptoNetView can write changes directly back into the HTML file. The file itself then becomes the data carrier – ideal when you pass it on or back it up.

1. In the header click **Link to file**.
2. In the file dialog select the same HTML file you have just opened and confirm the write access.
3. The button changes to **Saving to file: active**. From now on changes are written to the file automatically.
4. With **Save Directly** you can trigger writing manually at any time. A message confirms: "Changes saved directly into the local file!"

Button state	Meaning
Link to file	No file selected yet; a hint appears when you hover over it
Saving to file: active	Linked; all changes are saved automatically
Allow write access	The browser has reset the permission; confirm once
Browser storage only	The browser does not support the function (e.g. Firefox, Safari)

> **Note:** After restarting the browser, Chrome or Edge asks for write access again. Then click **Allow write access**.

14.3 What is stored where in the file?

The data is stored as a JSON block inside the HTML file. Sensitive fields are stored there exclusively in encrypted form. You can therefore copy the file like a document, send it by e-mail or archive it.

14.4 Backup strategy

- Before larger changes, make a copy of the HTML file (e.g. Network_2026-11-03.html).
- In addition, export a CSV file now and then and keep it safe.
- Store backups on a second storage medium or in encrypted cloud storage.
- Keep the master password separate from the file.

15 CSV export and import

15.1 Export

1. Log in.
2. Click **CSV**.
3. The security warning appears: **CSV Export**. The file contains all credentials in plain text.
4. Confirm with **Export Anyway** or cancel with **Cancel**.
5. The CSV file is downloaded: “Configuration exported as CSV.”




Figure 36: *Security warning before the CSV export*

> **Security:** The CSV file is not encrypted. Store it only in a safe place and delete it as soon as you no longer need it.

15.2 Structure of the CSV file

The full export contains all devices with their fields as well as categories and frames. A column **Record** identifies the record type (device, category, frame, setting). The column **IP Address** must be present for a file to be recognized as valid.

15.3 Import

1. Log in and click **Load**.
2. Select the CSV file.
3. KryptoNetView recognizes the format automatically and reports the result, e.g. “CSV loaded: 41 devices, 9 categories, 2 frames.”

CSV type	Detection	Effect
Full export	Column Record present	Replaces the topology: devices, categories, frames
Scan file	IP Address, Hostname, MAC ...	Updates existing devices (same IP) and adds new ones

For a scan import, KryptoNetView reports how many devices were updated and how many were newly added. This way you keep your topology up to date after a new network scan without re-entering everything.

> **Warning:** Importing a full export replaces the current data. Back up the file first.

Error messages: “Unknown CSV format: column “IP Address” is missing.” means that the column header is missing. “The CSV file contains no devices.” means that the file is empty.

16 Printing

KryptoNetView always prints in the light layout – even if you work in dark mode. This saves ink and keeps the printout readable.

16.1 The print dialog

1. In the header click **Print**.
2. Choose one of the print options.
3. Choose the page orientation.
4. Click **Print now**. The print window of your browser opens; there you choose a printer or “Save as PDF”.




Figure 37: *Print dialog*

16.2 The print options

Option	Content
Topology graph	Complete graph with all devices and legend, fitted to one page
Current screen section	Graph as currently displayed (zoom, pan, category filter, search)
Device list	All devices as a table, sorted by IP address
Devices by category	Devices grouped by category (router, switch, printers ...)
Graph + device list	Graph on page 1, followed by the device list
Devices with credentials	Only devices with login or WLAN data; credentials are printed too (logged in only)

16.3 Page orientation

Choose **Automatic (fits the graph)**, **Landscape** or **Portrait**. The automatic setting chooses the orientation based on the aspect ratio of the graph.

16.4 Examples





Figure 38: *Printout “Topology graph”*



Ulfenknulfen - GBit LAN

192.168.178.0/24 · Cisco WS-C2960S-48LPS-L (192.168.178.8)


Device list

11/4/2026, 7:11:01 AM

Total devices: 41

Name	IP address	Category	Hostname	MAC	Vendor	Connected to	PoE
Fritz!Box 7590	192.168.178.1	Router	fritz.box	E0:28:00:00:00:00	AVM Audiovisuelles Marketing und Computersysteme GmbH	Cisco WS-C2960S-48LPS-L	
Core Router	192.168.178.2	Router				Fritz!Box 7590	
Cisco WS-C2960S-48LPS-L	192.168.178.8	Switch		E8:ED:00:00:00:00	Cisco Systems, Inc	—	PoE
Hauptserver	192.168.178.10	Server				Cisco WS-C2960S-48LPS-L	
Power Schalter - Aussen	192.168.178.11	End Device		00:10:00:00:00:00	RITTAL-WERK RUDOLF LOH GmbH & Co.	Cisco WS-C2960S-48LPS-L	
Power Schalter - Innen	192.168.178.12	End Device		00:10:00:00:00:00	RITTAL-WERK RUDOLF LOH GmbH & Co.	Cisco WS-C2960S-48LPS-L	
IPMI Remote Mgmt	192.168.178.15	Server	IPMI-Server.fritz.box	00:30:00:00:00:00	Super Micro Computer, Inc.	Cisco WS-C2960S-48LPS-L	
Oneac Corporation .16	192.168.178.16	End Device		00:20:00:00:00:00	Oneac Corporation	Cisco WS-C2960S-48LPS-L	
Haustuer	192.168.178.20	Smart IoT & Cam	Cam-Haustuer.fritz.box	00:03:00:00:00:00	Mobotix AG	Cisco WS-C2960S-48LPS-L	PoE
Hof	192.168.178.21	Smart IoT & Cam	Cam-Hof.fritz.box	00:03:00:00:00:00	Mobotix AG	Cisco WS-C2960S-48LPS-L	PoE
Gartenhaus	192.168.178.22	Smart IoT & Cam	Cam-Gartenhaus.fritz.box	00:03:00:00:00:00	Mobotix AG	Cisco WS-C2960S-48LPS-L	PoE
Drucker hp p3015	192.168.178.30	Printers	hpp3015drucker.fritz.box	9C:B6:00:00:00:00	Hewlett Packard	Cisco WS-C2960S-48LPS-L	
Drucker-Ricoh	192.168.178.31	Printers				Cisco WS-C2960S-48LPS-L	
Drucker-BROTHER	192.168.178.32	Printers				Cisco WS-C2960S-48LPS-L	

Figure 39: *Printout “Device list” (page 1)*



Ulfenknulfen - GBit LAN

192.168.178.0/24 · Cisco WS-C2960S-48LPS-L (192.168.178.8)

Devices by category
11/4/2026, 7:11:02 AM

Router (2)

Name	IP address	Category	Hostname	MAC	Vendor	Connected to	PoE
Fritz!Box 7590	192.168.178.1	Router	fritz.box	E0:28:00:00:00:00	AVM Audiovisuelles Marketing und Computersysteme GmbH	Cisco WS-C2960S-48LPS-L	
Core Router	192.168.178.2	Router				Fritz!Box 7590	

Gateways (1)

Name	IP address	Category	Hostname	MAC	Vendor	Connected to	PoE
Fritz!Box Gast-Gateway	192.168.179.1	Gateways				Cisco WS-C2960S-48LPS-L	

WLAN Access Point (4)

Name	IP address	Category	Hostname	MAC	Vendor	Connected to	PoE
Cisco AP OG	192.168.178.90	WLAN Access Point	Cisco-AP-OG.fritz.box	84:B2:00:00:00:00	Cisco Systems, Inc	Cisco WS-C2960S-48LPS-L	PoE
Cisco AP EG	192.168.178.92	WLAN Access Point	Cisco-AP-EG.fritz.box	84:B2:00:00:00:00	Cisco Systems, Inc	Cisco WS-C2960S-48LPS-L	PoE
Cisco AP GH	192.168.178.94	WLAN Access Point	Cisco-AP-GH.fritz.box	84:B2:00:00:00:00	Cisco Systems, Inc	Cisco WS-C2960S-48LPS-L	PoE
Cisco AP EG (Gast-Trunk)	192.168.179.20	WLAN Access Point				Fritz!Box Gast-Gateway	PoE

Switch (1)

Name	IP address	Category	Hostname	MAC	Vendor	Connected to	PoE
Cisco WS-C2960S-48LPS-L	192.168.178.8	Switch		E8:ED:00:00:00:00	Cisco Systems, Inc	—	PoE

Figure 40: *Printout “Devices by category” (page 1)*

Every printout contains the title, subnet, switch model, print date and the number of devices. The device list shows the columns Name, IP address, Category, Hostname, MAC, Vendor, Connected to and PoE.

16.5 Printing credentials

The option **Devices with credentials** outputs login user, login password, WLAN SSID and WLAN password in plain text. It is only available after login. If there are no devices with credentials, a notice appears.

> **Security:** This printout contains all passwords in plain text. Keep it locked away (e.g. in a safe) and destroy it when it is no longer needed.

> **Tip:** In the print window of your browser you can choose “Save as PDF” to pass the topology on as a PDF. To do so, first choose Topology graph or Device list, not the credentials.

17 Using it on a smartphone and tablet

KryptoNetView adapts to the screen size. On small screens the header is shown as a grid, the device list can be collapsed and expanded, and the graph can be operated by touch.

17.1 Smartphone




Figure 41: *Smartphone: header (left), expanded device list (middle), device details (right)*

- The header shows the buttons as a two-column grid.
- The device list is collapsed by default: tap **Show devices** or **Devices & filters**.
- The device details appear as a window that slides up from the bottom edge; **X** closes it.

17.2 Tablet




Figure 42: *Tablet in portrait orientation*




Figure 43: *Tablet in landscape orientation*

17.3 Touch gestures

Gesture	Effect
Tap on an icon	Open the detail view
Drag with one finger	Pan the canvas
Spread/pinch two fingers	Zoom in/out
Tap Center	Fit the section

> **Note:** Editing is also possible on mobile. Moving individual icons is more precise on a computer with a mouse, however.

18 Design and language

18.1 Light and dark mode

With **Light** or **Dark** in the header you switch the view mode. Your choice is remembered. Light mode is suited to bright rooms and presentations; dark mode is easier on the eyes in low light.




Figure 44: *Main view in light mode*

18.2 Language

With **EN** or **DE** you switch the entire interface between German and English. Labels, messages, dialogs and printouts change with it. Your own entries (device names, descriptions) are not translated.




Figure 45: *Main view after switching the interface to English*

19 Practical examples and tips

19.1 Documenting a new network device

1. Log in, click **New Device**.
2. Enter name, IP address and category.
3. Choose the parent node (e.g. the switch or the access point).
4. Tick PoE if the device is powered over the network cable.
5. Add login data and description, and save.
6. **Save Directly** or CSV export as a backup.

19.2 Updating devices after a scan

1. Run a network scan with a suitable tool and save it as CSV with a column **IP Address**.
2. Log in to KryptoNetView and click **Load**.
3. Select the scan file. Existing devices (same IP) are updated, new ones are added.
4. Assign new devices: check category, parent node and name.

19.3 Documenting the network for family or guests

- Draw a frame for the guest network and color it orange.
- Create a separate network color for guest-network devices.
- Store the guest network SSID in the access point (**Add Another SSID**).
- Print the option **Devices with credentials** for the safe.

19.4 Planning a move or rebuild

- Switch to the Rooms view to see the devices grouped by category.
- In the Tree view, check which devices hang on a switch port.
- Print the option **Devices by category** in advance as a checklist.

19.5 General tips

- Use meaningful names (e.g. Printer-GF) so that the search quickly leads to the goal.
- Maintain the description (location, purpose) – it helps when someone else takes care of the network later.
- Combine category filter and search to get an overview of large networks.
- Make a backup after every larger change.
- Document passwords only in the encrypted fields intended for them.

20 Troubleshooting (FAQ)

Problem	Cause / solution
The page looks plain, icons are missing	Fonts and symbols are loaded online. Check your internet connection; the functionality is retained.
“Incorrect master password!”	Check the password (upper/lower case, keyboard layout). Default: admin. A forgotten password cannot be reset.
Credentials stay hidden	Log in. Without login KryptoNetView only shows “AES Encrypted”.
Buttons are dimmed	You are not logged in. Click Login.
Icons cannot be moved	Switch on edit mode (Edit Mode).
Changes are gone after a restart	Not saved. Use Link to file (Chrome/Edge) or export a CSV.
“Allow write access” appears	The browser has reset the permission. Click and confirm.
Button shows “Browser storage only”	The browser does not support direct saving. Use Chrome or Edge, or back up as CSV.
“Unknown CSV format”	The column IP Address is missing. Check the file or export from KryptoNetView first.
A device is not visible in the graph	Reset the search or category filter; click Center.
The graph looks messy	Click Reset view or Auto-arrange.
The printout is cut off	Choose the page orientation Automatic; in the browser print dialog enable “Fit to page” and set minimal margins.
The printout is dark	Printing is always light. In the print dialog enable background graphics.

Appendix

A Button quick reference

Button	Function	Chapter
DE / EN	Switch language	18
Light / Dark	Switch view mode	18
Print	Print dialog	16
Link to file	Save directly into the file	14
Login / Logout	Log in / log out	8
Change Password	Change the master password	9
Title & Switch	Global settings	12
Categories	Category management	12
+ Draw Frame	Drag out a frame	13
Groups/Frames	Frame management	13
Edit Mode	Editing on/off	10
New Device	Create a device	11
Save Directly	Save into the file now	14
CSV	Export	15
Load	Import	15

B Device fields

Field	Example	Sensitive?
Name	Cisco AP EG	No
IP address	192.168.178.92	No
Category	WLAN Access Point	No
Hostname	Cisco-AP-EG.fritz.box	No
MAC address	84:B2:00:00:00:00	No
Vendor	Cisco Systems, Inc	No
Open ports	80	No
Parent node	Cisco WS-C2960S-48LPS-L	No
PoE	Active (PoE 802.3at)	No
Login user / password	–	Yes (AES-256)
WLAN SSID / password	–	Yes (AES-256)
Description	Central WLAN hub	No (plain text!)

C Default categories

Category	Key	Deletable
Router	router	No (default)
Gateways	gateways	No (default)
WLAN Access Point	wlan_ap	No (default)
Switch	switch	No (default)
Server	server	No (default)
End Device	endgeraet	No (default)
Infrastructure	infrastructure	Yes
Sensors	sensors	Yes
VoIP Phones	voice	Yes

The sample data contains further categories, e.g. Printers, Smart Home Hubs and Smart TVs & Streaming.

D Technical data

Feature	Value
File format	One HTML file (HTML, CSS, JavaScript)
Encryption	AES-256-GCM
Key derivation	PBKDF2, 100,000 iterations
Storage locations	Browser storage (localStorage); optionally directly in the HTML file
Save directly	File System Access API (Chrome, Edge)
Export/import	CSV (full export and scan import)
Languages	German, English
View modes	Light, dark

E Glossary

Term	Explanation
AES-256-GCM	Strong encryption method; protects credentials
PBKDF2	Method that derives a key from a password
Vault	Encrypted area for credentials
CIDR	Notation for networks, e.g. 192.168.178.0/24
VLAN	Logically separated subnet, e.g. guest network
PoE	Power over Ethernet: power supply over the network cable
SSID	Name of a WLAN radio network
MAC address	Unique hardware address of a network card
Parent node	Device to which another device is connected
Frame	Group of devices with a colored outline in the graph
Topology	Arrangement and connection of the devices in the network