Embedding

CLASS torch.nn.Embedding(num_embeddings, embedding_dim, padding_idx=None, max_norm=None, norm_type=2.0, scale_grad_by_freq=False, sparse=False, _weight=None, _freeze=False, device=None, dtype=None) [SOURCE]

A simple lookup table that stores embeddings of a fixed dictionary and size.

This module is often used to store word embeddings and retrieve them using indices. The input to the module is a list of indices, and the output is the corresponding word embeddings.

Parameters

- num_embeddings (int) size of the dictionary of embeddings
- embedding_dim (int) the size of each embedding vector
- padding_idx (int, optional) If specified, the entries at padding_idx do not contribute to the gradient; therefore, the embedding vector at padding_idx is not updated during training, i.e. it remains as a fixed "pad". For a newly constructed Embedding, the embedding vector at padding_idx will default to all zeros, but can be updated to another value to be used as the padding vector.
- max_norm (float, optional) If given, each embedding vector with norm larger than max_norm is renormalized to have norm max_norm.
- norm_type (float, optional) The p of the p-norm to compute for the max_norm option. Default 2.
- scale_grad_by_freq (bool, optional) If given, this will scale gradients by the inverse of frequency of the words in the mini-batch. Default False .
- sparse (bool, optional) If True, gradient w.r.t. weight matrix will be a sparse tensor. See Notes for more details regarding sparse gradients.

Variables

weight (Tensor) – the learnable weights of the module of shape (num_embeddings, embedding_dim) initialized from $\mathcal{N}(0,1)$

Shape:

- Input: (*), IntTensor or LongTensor of arbitrary shape containing the indices to extract
- Output: (*,H), where * is the input shape and $H=\mathrm{embedding_dim}$

• NOTE

Keep in mind that only a limited number of optimizers support sparse gradients: currently it's optim. SGD (CUDA and CPU), optim. SparseAdam (CUDA and CPU) and optim. Adagrad (CPU)

• NOTE

When max_norm is not None | Embedding 's forward method will modify the weight tensor in-place. Since tensors needed for gradient computations cannot be modified in-place, performing a differentiable operation on Embedding.weight before calling Embedding 's forward method requires cloning Embedding.weight when max_norm is not None | For example:

```
n, d, m = 3, 5, 7
embedding = nn.Embedding(n, d, max_norm=1.0)
W = torch.randn((m, d), requires_grad=True)
idx = torch.tensor([1, 2])
a = embedding.weight.clone() @ W.t() # weight must be cloned for this to be differentiable
b = embedding(idx) @ W.t() # modifies weight in-place
out = (a.unsqueeze(0) + b.unsqueeze(1))
loss = out.sigmoid().prod()
loss.backward()
```

Examples:

CLASSMETHOD from_pretrained(embeddings, freeze=True, padding_idx=None, max_norm=None, norm_type=2.0, scale_grad_by_freq=False, sparse=False) [SOURCE]

Create Embedding instance from given 2-dimensional FloatTensor.

Parameters

- embeddings (Tensor) FloatTensor containing weights for the Embedding. First dimension is being passed to Embedding as num_embeddings, second as embedding dim.
- freeze (bool, optional) If True, the tensor does not get updated in the learning process. Equivalent to embedding.weight.requires_grad = False.

 Default: True
- padding_idx (int, optional) If specified, the entries at padding_idx do not contribute to the gradient; therefore, the embedding vector at padding_idx is not updated during training, i.e. it remains as a fixed "pad".
- max_norm (float, optional) See module initialization documentation.
- **norm_type** (*float*, *optional*) See module initialization documentation. Default 2.
- scale_grad_by_freq (bool, optional) See module initialization documentation. Default False .
- sparse (bool, optional) See module initialization documentation.

Examples:

```
>>> # FloatTensor containing pretrained weights
>>> weight = torch.FloatTensor([[1, 2.3, 3], [4, 5.1, 6.3]])
>>> embedding = nn.Embedding.from_pretrained(weight)
>>> # Get embeddings for index 1
>>> input = torch.LongTensor([1])
>>> embedding(input)
tensor([[ 4.0000, 5.1000, 6.3000]])
```

✓ Previous
Next >

© Copyright 2024, PyTorch Contributors.

Built with Sphinx using a theme provided by Read the Docs.

Docs

 $\label{lem:constraints} \mbox{Access comprehensive developer documentation for PyTorch}$

View Docs

Tutorials

Get in-depth tutorials for beginners and advanced developers

Resources

Find development resources and get your questions answered View Resources

PyTorch	Resources
Get Started	Tutorials
Features	Docs
Ecosystem	Discuss
Blog	Github Issues
Contributing	Brand Guidelines
Stay up to date	PyTorch Podcasts
Facebook	Spotify
Twitter	Apple
YouTube	Google
LinkedIn	Amazon
Terms Privacy	

© Copyright The Linux Foundation. The PyTorch Foundation is a project of The Linux Foundation. For web site terms of use, trademark policy and other policies applicable to The PyTorch Foundation please see www.linuxfoundation.org/policies/. The PyTorch Foundation supports the PyTorch open source project, which has been established as PyTorch Project a Series of LF Projects, LLC. For policies applicable to the PyTorch Project a Series of LF Projects, LLC, please see www.lfprojects.org/policies/.