Home Contact Us About Me Privacy Policy Sponsored Post Donate



Menu

# 31 Most Useful netsh command examples in Windows

August 3, 2021 by cyberithub

#### Table of Contents

:= ≑

Most Useful netsh command examples in Windows

Example 1: How to Check all Windows Firewall Rules

Example 2: How to Show all Firewall rules for Current Profile

Example 3: How to Check Network Interface Status

Example 4: How to Check Index Number of all the Network Interfaces

Example 5: How to Check all the Wireless Profiles

Example 6: How to Check all the Available Wireless Connections

Example 7: How to Check the Strength of all the Available Wireless Connections

Example 8: How to Disconnect from Currently Connected Wireless Device

Example 9: How to Connect to an Available Wireless Device

Example 10: How to Show all the Wireless Interfaces

Example 11: How to Show Drivers of Wireless Interfaces

Example 12: How to Check Current Proxy Setting in Windows

Example 13: How to Check TCP Global Parameters Status

Example 14: How to Check UDP Global Parameters Status

Example 15: How to Disable TCP RSS Global Parameter

Example 16: How to Enable TCP RSS Global Parameter

Example 17: How to List all the defined Aliases

Example 18: How to Reset Winsock entries to default

Example 19: How to Reset TCP/IP Stack to Installation Default

Example 20: How to Set Proxy in Windows using netsh command

Example 21: How to Change the IP Address of an Interface

Example 22: How to Show Multicast Joins for all Network Interfaces

Example 23: How to Allow a Port from Windows Firewall using netsh command

Example 24: How to Add a Primary DNS Server to an Interface

Example 25: How to Allow Ping requests through Windows Firewall

Example 26: How to Block Ping requests through Windows Firewall

Example 27: How to Disable Windows Firewall in all Profiles


Example 28: How to Reset Windows Firewall Settings to Default

Example 29: How to Capture Packets using netsh command

Example 30: How to Stop Trace using netsh command

Example 31: How to Check all the Options available with netsh command

In this article, I will take you through 31 Most Useful netsh command examples in Windows. netsh also known as Network Shell is a windows based command line utility to manage network interfaces and its configurations. netsh command can also be used for network troubleshooting purposes. You can capture network packets in a local file to help troubleshooting the networking issues. There are several other tasks that can be accomplished using netsh command which we will see in detail using some real world examples in below Section. More on Microsoft docs.



# **Most Useful netsh command examples in Windows**

Also Read: 27 Useful net command examples to Manage Windows Resources

#### **Example 1: How to Check all Windows Firewall Rules**

If you want to check all the current Windows Firewall Rules then you need to use netsh advfirewall firewall show rule name=all command as shown below.

#### C:\>netsh advfirewall firewall show rule name=all

Rule Name: Microsoft Edge (mDNS-In)

Enabled: Yes Direction: In

Profiles: Domain, Private, Public

Grouping: Microsoft Edge

LocalIP: Any RemoteIP: Any Protocol: UDP LocalPort: 5353 RemotePort: Any Edge traversal: No

Action: Allow

#### **Example 2: How to Show all Firewall rules for Current Profile**

If you are only interested in current profile firewall rules then you need to use netsh advfirewall show currentprofile command as shown below.

#### C:\>netsh advfirewall show currentprofile

#### Public Profile Settings:

-----

State ON

Firewall Policy BlockInbound, AllowOutbound LocalFirewallRules N/A (GPO-store only) LocalConSecRules N/A (GPO-store only) InboundUserNotification Enable

RemoteManagement Disable

UnicastResponseToMulticast Enable

Logging:

LogAllowedConnections Disable LogDroppedConnections Disable FileName %systemroot%\system32\LogFiles\Firewall\pfirewall.log MaxFileSize 4096

Ok.

#### **Example 3: How to Check Network Interface Status**

If you want to check all the network interface status then you need to use netsh interface show interface command as shown below.

#### C:\>netsh interface show interface

```
Admin State State Type Interface Name
------
Enabled Connected Dedicated Wi-Fi
Enabled Disconnected Dedicated Ethernet 2
Enabled Connected Dedicated VirtualBox Host-Only Network
Enabled Disconnected Dedicated Ethernet
```

#### **Example 4: How to Check Index Number of all the Network Interfaces**

If you want to check the Index number(Idx) of all the network interfaces then you can use netsh interface ip show interfaces command as shown below. This will show you all connected as well as disconnected interfaces Index number.

#### C:\>netsh interface ip show interfaces

```
Idx Met MTU State Name

1 75 4294967295 connected Loopback Pseudo-Interface 1
17 35 1500 connected Wi-Fi
18 65 1500 disconnected Bluetooth Network Connection
19 25 1500 disconnected Local Area Connection* 1
5 5 1500 disconnected Ethernet
7 25 1500 disconnected Local Area Connection* 10
6 35 1500 disconnected Ethernet 2
13 25 1500 connected VirtualBox Host-Only Network
```

## **Example 5: How to Check all the Wireless Profiles**

If you want to check all the wireless profiles then you need to use netsh wlan show prof command as shown below.

```
C:\>netsh wlan show profile

Profiles on interface Wi-Fi:

Group policy profiles (read only)
------
<None>

User profiles
------
All User Profile : Fibre You
All User Profile : AndyAP
All User Profile : Fibre You 1
All User Profile : vivo 1902
All User Profile : bright you
All User Profile : redmi
All User Profile : cherry
All User Profile : TP-LINK_8976A
All User Profile : John_5G
```

## **Example 6: How to Check all the Available Wireless Connections**

If you want to check all the available wireless connections then you need to use netsh wlan show networks command as shown below. As you can see we have 4 wireless network connections currently visible.

```
C:\>netsh wlan show networks
```

```
Interface name : Wi-Fi
There are 4 networks currently
```

There are 4 networks currently visible.

SSID 1 : Fibre You

Network type : Infrastructure Authentication : WPA2-Personal

Encryption : CCMP

SSID 2 : ServiceNet-2mbps Network type : Infrastructure Authentication : WPA2-Personal

Encryption : CCMP

SSID 3:

Network type : Infrastructure Authentication : WPA2-Personal

Encryption : CCMP

# **Example 7: How to Check the Strength of all the Available Wireless Connections**

If you are looking to check the strength of all the available wireless connections then you need to use netsh wlan networks mode=bssid command as shown below. This command will provide the Signal strength of the available wireless network connections along with other important informations like Radio type, Channel, Basic rates and other rates.

#### C:\>netsh wlan show networks mode=bssid

Interface name : Wi-Fi

There are 4 networks currently visible.

SSID 1 : Fibre You

Network type : Infrastructure Authentication : WPA2-Personal

Encryption : CCMP

BSSID 1 : a8:da:0a:6d:8c:67

Signal: 100%

Radio type : 802.11ac

Channel: 149

Basic rates (Mbps) : 6 12 24

Other rates (Mbps): 9 18 36 48 54

# **Example 8: How to Disconnect from Currently Connected Wireless Device**

If you want to disconnect from currently connected wireless device then all you need to do is to run netsh wlan disconnect command as shown below.

#### C:\>netsh wlan disconnect

Disconnection request was completed successfully for interface "Wi-Fi".

## **Example 9: How to Connect to an Available Wireless Device**

If you want to connect to an available wireless device by its name then you need to use netsh wlan connect name="<wireless\_device\_name>" syntax. In this example we are connecting to Fibre You wireless device by using netsh wlan connect name="Fibre You" command as shown below.

C:\>netsh wlan connect name="Fibre You"
Connection request was completed successfully.

## **Example 10: How to Show all the Wireless Interfaces**

If you want to check all the information about your Wireless Interface then you need to use netsh wlan show interfaces command as shown below. As you can see in my case, I have only one Qualcomm Wireless Adapter currently available in my System. Similarly, you can check in your System as well.

#### C:\>netsh wlan show interfaces

There is 1 interface on the system:

Name : Wi-Fi

Description: Qualcomm QCA9377 802.11ac Wireless Adapter

GUID: e90ba5b7-5926-4d9f-b09a-3ef5d7357b09

Physical address: 80:7c:a5:41:31:f9

State : connected
SSID : Fibre You

BSSID : a8:da:0a:6d:8c:67 Network type : Infrastructure

Radio type : 802.11ac

Authentication : WPA2-Personal

Cipher : CCMP

Connection mode : Profile

Channel: 149

Receive rate (Mbps): 433.3 Transmit rate (Mbps): 433.3

Signal : 100%

Profile : Fibre You

Hosted network status : Not available

## **Example 11: How to Show Drivers of Wireless Interfaces**

If you want to check the wireless interface driver information then you need to use netsh wlan show drivers command as shown below. This will give you complete information about the Wi-fi device driver like vendor details, provider information and driver version.

#### C:\>netsh wlan show drivers

Interface name: Wi-Fi

Driver : Qualcomm QCA9377 802.11ac Wireless Adapter

Vendor : Qualcomm Communications Inc. Provider : Qualcomm Communications Inc.

Date : 14-06-2020 Version : 12.0.0.953 INF file : oem41.inf

Type : Native Wi-Fi Driver

Radio types supported : 802.11b 802.11a 802.11g 802.11n 802.11ac

FIPS 140-2 mode supported : Yes

## **Example 12: How to Check Current Proxy Setting in Windows**

If you want to check your current proxy setting in Windows then you need to use netsh winhttp show proxy command as shown below.

```
C:\>netsh winhttp show proxy
```

Current WinHTTP proxy settings:

Direct access (no proxy server).

#### **Example 13: How to Check TCP Global Parameters Status**

If you want to check all the TCP Global parameters then you need to use netsh interface show global command as shown below.

C:\>netsh interface tcp show global
Querying active state...

TCP Global Parameters

-----

Receive-Side Scaling State : enabled Receive Window Auto-Tuning Level : normal Add-On Congestion Control Provider : default

ECN Capability : disabled

PEC 1323 Timestamps : disable

RFC 1323 Timestamps : disabled

Initial RTO: 1000

Receive Segment Coalescing State : enabled

Non Sack Rtt Resiliency : disabled

Max SYN Retransmissions : 4

Fast Open : enabled

Fast Open Fallback : enabled

HyStart : enabled

Proportional Rate Reduction : enabled

Pacing Profile : off

## **Example 14: How to Check UDP Global Parameters Status**

If you want to check UDP global parameters status then you need to use netsh interface udp show global command as shown below.

#### **Example 15: How to Disable TCP RSS Global Parameter**

If you are looking to disable any of the TCP Global parameter like RSS in this case then you need to use netsh interface tcp set global rss=disabled command as shown below.

C:\>netsh interface tcp set global rss=disabled
Ok.

#### **Example 16: How to Enable TCP RSS Global Parameter**

Similarly, if you want to enable any of the TCP Global Parameter like RSS in this case then you need to use netsh interface tcp set global rss=enabled command as shown below.

C:\>netsh interface tcp set global rss=enabled
Ok.

#### **Example 17: How to List all the defined Aliases**

If you want to list all the defined aliases then you need to use netsh show alias command as shown below.

C:\>netsh show alias

#### **Example 18: How to Reset Winsock entries to default**

If you are facing any issue and want to reset winsock catalog entries then you need to use netsh winsock reset catalog command as shown below.

C:\>netsh winsock reset catalog

Sucessfully reset the Winsock Catalog.
You must restart the computer in order to complete the reset.

#### **Example 19: How to Reset TCP/IP Stack to Installation Default**

If you are looking to reset TCP/IP stack then you can use netsh int ip reset reset.log command as shown below.

```
C:\>netsh int ip reset reset.log
Reseting Global, OK!
Reseting Interface, OK!
Restart the computer to complete this action.
```

## **Example 20: How to Set Proxy in Windows using netsh command**

If you want to set proxy in Windows then you can use below netsh command.

```
C:\>netsh winhttp set proxy "myproxy.proxyaddress.com:8484" "<local>;*.proxyaddr
Current WinHTTP proxy settings:
Proxy Server(s): myproxy.proxyaddress.com:8484
Bypass List: <local>;*.proxyaddress.com
```

#### **Example 21: How to Change the IP Address of an Interface**

You can change the IP address of a network interface using below netsh command.

```
C:\>netsh int ip set address "local area connection" static 192.168.29.101 255.2
```

Now if you check again using ipconfig command then you can see the new IP on below output.

```
C:\>ipconfig
Windows IP Configuration
Ethernet adapter Local Area Connection:
```

#### **Example 22: How to Show Multicast Joins for all Network Interfaces**

If you want to show multicast joins for all network interfaces then you need to use netsh interface ip show joins command as shown below.

#### Example 23: How to Allow a Port from Windows Firewall using netsh command

If you are looking to allow a port from windows firewall then you need to use below nets advfirewall command. In this example we are allowing Port 3389 from Windows firewall by

using netsh advfirewall firewall add rule name="Open Remote Desktop" protocol=TCP dir=in localport=3389 action=allow command as shown below.

C:\>netsh advfirewall firewall add rule name="Open Remote Desktop" protocol=TCP
Ok.

# **Example 24: How to Add a Primary DNS Server to an Interface**

If you want to add a Primary DNS Server then you need to use netsh interface ip add dns name="<Interface\_name>" addr=<IPv4 Address> syntax. In this example we are adding DNS Server 230.92.45.130 to Local Area Connection using netsh interface ip add dns name="Local Area Connection" addr=230.92.45.130 command as shown below.

C:/>netsh interface ip add dns name="Local Area Connection" addr=230.92.45.130

## **Example 25: How to Allow Ping requests through Windows Firewall**

If you want to allow ICMPv4 protocol through Windows Firewall then you need to use netsh advfirewall firewall add rule name="All ICMP V4" dir=in action=allow protocol=icmpv4 command as shown below.

C:\>netsh advfirewall firewall add rule name="All ICMP V4" dir=in action=allow properties.

#### **Example 26: How to Block Ping requests through Windows Firewall**

Similarly if you want to block ICMPv4 protocol through Windows Firewall then you need to use netsh advfirewall firewall add rule name="All ICMP V4" dir=in action=block protocol=icmpv4 command as shown below.

C:\>netsh advfirewall firewall add rule name="All ICMP V4" dir=in action=block r

Ok.

# **Example 27: How to Disable Windows Firewall in all Profiles**

If you are looking to disable Windows Firewall in all the profiles then you need to use netsh advfirewall set allprofiles state off command as shown below.

C:\>netsh advfirewall set allprofiles state off
Ok.

## **Example 28: How to Reset Windows Firewall Settings to Default**

If you are looking to reset windows firewall settings to default values then you need to use netsh advfirewall reset command as shown below.

C:\>netsh advfirewall reset
Ok.

## **Example 29: How to Capture Packets using netsh command**

If you are troubleshooting any network issues then you might want to capture the Network Packets to analyze the issue further. This can be easily done by using below netsh trace command. In this example we are starting network packets capture in trace.etl file under C drive using netsh trace start capture=yes tracefile=c:\trace.etl persistent=yes maxsize=4096 command as shown below.

C:\>netsh trace start capture=yes tracefile=c:\trace.etl persistent=yes maxsize=

Trace configuration:

Status: Running

Trace File: c:\trace.etl

Append: Off

Circular: On

Max Size: 4096 MB

Report: Off

#### **Example 30: How to Stop Trace using netsh command**

If you want to stop the Network trace then you need to use netsh trace stop command as shown below.

```
C:\>netsh trace stop
Merging traces ... done
Generating data collection ... done
The trace file and additional troubleshooting information have been compiled as
File location = c:\trace.etl
Tracing session was successfully stopped.
```

#### Example 31: How to Check all the Options available with netsh command

If you are looking to check all the options available with netsh command then you need to use netsh /? command as shown below.

```
C:\>netsh /?
Usage: netsh [-a AliasFile] [-c Context] [-r RemoteMachine] [-u [DomainName\]Use
[Command | -f ScriptFile]
The following commands are available:

Commands in this context:
? - Displays a list of commands.
add - Adds a configuration entry to a list of entries.
advfirewall - Changes to the `netsh advfirewall' context.
bridge - Changes to the `netsh bridge' context.
delete - Deletes a configuration entry from a list of entries.
dhcpclient - Changes to the `netsh dhcpclient' context.
dnsclient - Changes to the `netsh dnsclient' context.
dump - Displays a configuration script.
exec - Runs a script file.
firewall - Changes to the `netsh firewall' context.
```

help - Displays a list of commands.

MORE, Windows

How to Download and Install WinSCP on
Windows 10

A Complete Guide to Setup Kubernetes Cluster on EC2 Instance Using Kops

>

# 2 thoughts on "31 Most Useful netsh command examples in Windows"



#### n.m.

december 31, 2021 at 3:00 am

Hi,

Very nice and detailed work.

Something one would want from MS.

This far and you could at least post the best known settings for Interfaces to set and go, as "they" seem to secretly change some setting in every update ruining the day.

Regards

Reply



#### virel

october 5, 2023 at 11:20 pm

netsh int ip reset
netsh int ip set global icmpredirects=disabled
netsh int ip set global multicastforwarding=enabled
netsh int ip set global taskoffload=enabled
netsh int ipv6 set state disabled
netsh int isatap set state state=disabled
netsh int tcp reset
netsh int tcp set global autotuning=normal
netsh int tcp set global autotuninglevel=normal

netsh int tcp set global congestionprovider=ctcp netsh int tcp set global fastopen=enabled netsh int tcp set global fastopenfallback=enabled netsh int tcp set global initialRto=2000 netsh int tcp set global maxsynretransmissions=2 netsh int tcp set global netdma=enabled netsh int tcp set global dca=disabled netsh int tcp set global nonsackrttresiliency=disabled netsh int tcp set global pacingprofile=off netsh int tcp set global rsc=enabled netsh int tcp set global rss=enabled netsh int tcp set heuristics wsh=disabled forcews=disabled netsh int tcp set heuristics disabled netsh interface tcp set heuristics disabled netsh int tcp set security mpp=disabled netsh int tcp set security profiles=disabled netsh int tcp set supplemental Internet congestionprovider=dctcp netsh int tcp set supplemental InternetCustom congestionprovider=ctcp netsh interface teredo set state type=enterpriseclient netsh int udp set global uro=enabled netsh int ip delete arpcache netsh int ipv4 reset netsh int ipv6 reset netsh int ipv6 set prefix ::/96 60 3 netsh int ipv6 set prefix ::ffff:0:0/96 55 4 netsh int 6to4 set state state=disabled netsh interface ipv4 set subinterface "Bluetooth Network Connection" mtu=1500 store=persistent netsh interface ipv4 set subinterface "Ethernet" mtu=1500 store=persistent netsh interface ipv4 set subinterface "Wi-Fi" mtu=1500 store=persistent netsh int tcp set global timestamps=enabled netsh int tcp set global ecncapability=enabled netsh int tcp set global hystart=enabled netsh advfirewall set allprofiles state on netsh winsock reset netsh winsock reset catalog netsh winsock reset proxy netsh winsock set autotuning on netsh int 6to4 set state state=Disabled netsh int tcp set global prr=enabled

netsh int tcp set supp netsh int tcp set secu	enablecwndrestart=enabled	
Reply		
eave a Comment		
Nama *		
Name * Email *		
Website		

# Categories

Ansible

**AWS** 

Azure

Bash

C

C#

C++

Chef

Cloud

Database

DevOps

Docker

Docker

**ELK** 

Git

GO

Google

HTML

**Interview Questions** 

Java

JavaScript Kubernetes Linux macOS Monitoring **MORE MYSQL** Networking Node.js Openstack Oracle Perl PHP PostgreSQL Powershell **Programming Puppet** Python Redis Ruby Scripting Security Solaris **Terraform** 

Windows



# **Recent Posts**

[Solved]: "ERROR! Libpcap library/headers not found"

[Solved]: "autoreconf: not found" error

[Solved]: "CMake could not find OpenSSL" error

[Solved]: "Can't Find luajit" or No package 'luajit' found

How to Install and Use tfenv (Terraform version manager) on macOS

How to Install Snort on Ubuntu 22.04

How to Install jq(JSON processor) on Ubuntu 22.04

How to trigger a cronjob manually in Kubernetes Cluster

How to Install TFLint (Terraform Linter) on Linux

How to Install Snap on Ubuntu 22.04

## **Recent Comments**

IceMan on Solved "xcrun: error: invalid active developer path (/Library/Developer

## /CommandLineTools)"

VirEl on 31 Most Useful netsh command examples in Windows

Jason on How to Enable Nested VT-X/AMD-V in Virtualbox [Step by Step]

Brian on Solved "WslRegisterDistribution failed with error: 0x80370114"

Hieu on [Solved]: autoreconf: automake failed with exit status: 1

Stani82 on Solved "WslRegisterDistribution failed with error: 0x80370114"

Manoj on Error "activation of network connection failed" on Linux

Jim Desposito on How to Install Pi-Apps on Raspberry Pi OS in 10 Easy Steps naeem on Solved "WslRegisterDistribution failed with error: 0x80370114"

Lucas on 20 Useful wmic command examples in Windows | Cheat Sheet

# **LET'S KEEP IN TOUCH!**

We'd love to keep you updated with our latest articles

First Name *	
First Name *	
Last Name	
Last Name	
Email Address *	
Email Address *	

#### Keep me posted!

We don't spam! Read our <u>privacy policy</u> for more info.

Copyright © 2023 | Hosted By Rocket