

FleetLink

Transport and Warehouse Management System

User Manual — Release 4.2

Document reference	NBL/DOC/IT/FL-UM-42
Software release	4.2.7 (build 4207.118)
Release date	18 February 2025
Manual revision	3, dated 05 March 2025
Supersedes	FleetLink User Manual Release 3.8, revision 5
Applies to	Web client, driver mobile application 4.2.x, customer portal 2.6.x
Audience	Warehouse and transport operations users, supervisors, administrators and customer service staff
Prepared by	Application Support Group, Information Technology
Approved by	Head – Information Technology
Classification	Internal – Restricted

Screens reproduced in this manual are indicative. Field availability and default values vary by facility configuration and by the roles assigned to the signed-in user. Where this manual and the application disagree, raise a documentation defect with the Application Support Group rather than assuming either is correct.

Contents

1. About This Manual
2. System Overview
3. Getting Started
4. Navigating the Interface
5. User Roles and Permissions
6. Master Data
7. Creating a Consignment
8. Trip Planning and Vehicle Allocation
9. Freight Rating and Rate Cards
10. Track and Trace and Electronic Proof of Delivery
11. Inbound Receipt
12. Exception Management
13. Putaway and Bin Management
14. Reports
15. Driver Mobile Application
16. Integrations
17. Administration
18. Troubleshooting
19. Message and Error Codes
20. Support and Escalation
- A. Appendix A – Keyboard Shortcuts
- B. Appendix B – Inbound Receipt Field Reference
- C. Appendix C – Glossary

1. About This Manual

1.1 Purpose

This manual describes how to operate FleetLink release 4.2 for day-to-day transport and warehouse activity. It is a task manual: each chapter describes a job a user performs, the screen on which it is performed, the fields that must be completed, and the validations the system applies.

This manual does not describe why a business rule exists. Operational rules, approval limits and record-keeping obligations are set out in the relevant standard operating procedure. Where a chapter implements a rule defined elsewhere, the governing procedure is cited.

1.2 What is new in release 4.2

Area	Change	Chapter
Inbound receipt	Quality disposition is now a mandatory field. Receipts left blank default to quarantine rather than to unrestricted.	11
Inbound receipt	Residual shelf life is validated against the customer material master at the point of entry.	11
Exception management	Photographic evidence is enforced for five discrepancy codes; the record cannot be saved without an attachment.	12
Putaway	Blind bin confirmation has been withdrawn. Both the pallet label and the bin label must be scanned.	13
Putaway	Bin override now requires a reason selected from a fixed list and is written to the audit trail.	13
Rate cards	Fuel escalation may be configured as a formula linked to a published index rather than as a fixed percentage.	9
Mobile application	Electronic proof of delivery capture works offline and synchronises when connectivity is restored.	15
Security	Multi-factor authentication is mandatory for all administrative roles.	17
Competency	Transactions are refused where the signed-in user's training record for the relevant module has expired.	5
Reports	Nine new operational reports, including putaway ageing and dock-to-stock distribution.	14

1.3 Conventions used

Convention	Meaning
Bold	A button, menu item or field label exactly as it appears on screen.
Screen › Screen	A navigation path from the main menu.
Monospaced	A value to be typed exactly, or a code returned by the system.
Note	Information that helps but is not required to complete the task.
Caution	An action that cannot be reversed, or that creates a record visible to a customer.

2. System Overview

FleetLink is a single application covering transport execution and warehouse management across all Northbridge facilities. Before release 3.0 each facility operated its own system; consolidating onto one platform means that a consignment moving between two Northbridge facilities is a single record rather than a dispatch and an unrelated receipt.




Figure 2.1: FleetLink application architecture. All client traffic passes through the API gateway; no client connects directly to a service or to the database.

2.1 Functional modules

Module	Purpose	Primary users
Order management	Consignment creation, amendment and cancellation	Customer service, operations
Trip planning	Consolidation, route building, vehicle and driver allocation	Transport planners
Rating and billing	Freight computation, accessorial charges, invoice generation	Billing, commercial
Warehouse management	Inbound receipt, putaway, picking, stock adjustment	Warehouse operations
Track and trace	Milestone capture, exception visibility, customer enquiry	Customer service, customers
Document management	Electronic proof of delivery, invoices, certificates	All users
Exception management	Discrepancy recording, notification and closure	Warehouse and transport operations
Reporting	Operational and commercial reporting	Supervisors and above
Administration	Users, roles, facilities, master data, integrations	Application administrators

2.2 Supported clients

Client	Requirement	Notes
Web client	Chrome 118 or later, Edge 118 or later, Firefox 115 or later	Minimum screen width 1280 pixels. Internet Explorer is not supported.
Driver mobile application	Android 10 or later, iOS 15 or later	Camera and location permissions required for proof of delivery capture.
Customer portal	Any current browser	Read-only access scoped to the signed-in customer.
Handheld scanner	Android 10 or later, 2D imager	Used for warehouse receipt, putaway and picking.

3. Getting Started

3.1 Signing in

1. Open the application address supplied by the Application Support Group.
2. Enter your employee identifier as the user name. This is not your email address.
3. Enter your password and select **Sign in**.
4. Where your role requires multi-factor authentication, enter the six-digit code from your authenticator application.
5. Select the facility you are working at from the **Facility** list. Users assigned to one facility only skip this step.

The facility selected at sign-in determines which stock, docks and bins you can transact against. Selecting the wrong facility is the most common cause of a receipt appearing to be missing. The active facility is shown at all times in the top right of the header.

3.2 Password rules

Rule	Setting
Minimum length	12 characters
Composition	At least one upper case letter, one digit and one symbol
Reuse	The last 8 passwords cannot be reused
Maximum age	90 days for operational roles, 60 days for administrative roles
Failed attempts before lock	5
Lock duration	30 minutes, or until reset by an administrator
Session idle timeout	20 minutes
Concurrent sessions	1 per user; signing in elsewhere ends the earlier session

Passwords are never shared, including with a supervisor covering a shift. Where a user is absent, the supervisor performs the transaction under their own credentials. A transaction recorded under another person's identity destroys the audit trail that the record exists to provide.

3.3 If you cannot sign in

Symptom	Likely cause	Action
Message FL-1002 invalid credentials	Wrong user name or password	Retry once, then contact the service desk
Message FL-1007 account locked	Five failed attempts	Wait 30 minutes or request a reset
Message FL-1014 competency expired	Training record for your role has lapsed	Complete the module in the learning tab; access restores within 15 minutes
Message FL-1021 no facility assigned	Facility assignment missing	Contact your supervisor to request assignment
Sign-in page does not load	Network or gateway issue	Check connectivity, then contact the service desk

4. Navigating the Interface

4.1 Layout

The interface is divided into three regions. The header carries the active facility, the signed-in user and the notification bell. The left navigation lists the modules available to your roles. The work area occupies the remainder of the window.

FleetLink Orders > Create Consignment		r.deshmukh
Dashboard	Consignor Aurex Pharma Pvt Ltd	Consignee Medisale Distributors
Orders	Origin Chakan, Pune (MH)	Destination Hosur (TN)
Trips	Service type Contract - FTL	Cargo class Pharma, 2-8 °C
Vehicles	Line items 1 AUX-4410 Ambient 25 x 500 312 kg 2 AUX-4412 Cold 12 x 250 148 kg	
Rate cards		
ePOD	Save draft Validate Confirm order	
Invoices		
Reports		
Admin		

Figure 4.1: The Create Consignment screen, showing the header, left navigation and work area. Menu items not permitted by the signed-in user's roles are not displayed at all rather than being shown disabled.

4.2 Working with lists

- Select a column heading once to sort ascending and again to sort descending.
- Select **Filter** to add conditions. Filters combine with AND; there is no OR option in release 4.2.
- Saved filters are private to you unless you mark them as shared, in which case they are visible to all users at your facility.
- Select **Export** to download the current list as a spreadsheet. Export is limited to 50,000 rows and is written to the audit trail.
- Lists refresh automatically every 60 seconds. A row changed by another user while you are viewing it is highlighted until you acknowledge it.

4.3 Notifications

Notification	Raised when	Sent to
Receipt awaiting inspection	A gate entry has been open for more than 2 hours without a quality disposition	Quality Inspector
Putaway ageing	A pallet is unconfirmed more than 4 hours after receipt	Supervisor – Inbound
Temperature alert	A monitored zone reads outside its validated range	Quality Inspector, Warehouse Manager
Exception unclosed	A discrepancy has passed its target closure date	Resolution owner and their supervisor
Trip delayed	A trip milestone is overdue by more than 2 hours	Transport planner, customer service
Rate card expiring	A rate card expires within 14 days	Commercial team

5. User Roles and Permissions

Access is granted by role, never to an individual. A user may hold several roles, and the permissions granted are the union of those roles. Roles are assigned by an application administrator on the written request of the user's reporting manager.

Role	Can do	Cannot do
Order Entry	Create, amend and cancel consignments before dispatch	Change rate cards, post receipts, release quality holds
Transport Planner	Build trips, allocate vehicles and drivers, record milestones	Create consignments, amend rates
Warehouse Operator	Record unloading tally, scan putaway confirmations, execute picks	Post a goods receipt note, override a bin, close an exception
Inbound Executive	Post goods receipt notes, raise exceptions, enter batch and expiry data	Apply or release a quality disposition, override a bin
Quality Disposition	Record inspection results, apply and release quarantine	Post goods receipt notes, amend quantities
Bin Override	Confirm putaway to a bin other than the one assigned, with a reason	Create or retire bin addresses
Supervisor	All operational roles at the assigned facility, plus exception review and shift handover	Amend master data, assign roles, change rate cards
Billing	Generate invoices, apply accessorial charges, issue credit notes	Amend consignment quantities, post receipts
Commercial	Create and amend rate cards and customer masters	Post any operational transaction
Administrator	Manage users, roles, facilities, integrations and master data	Post operational transactions; approve their own role changes
Auditor	Read-only access to all records and the audit trail at all facilities	Create or amend any record

5.1 Segregation of duties

Four combinations are prohibited by the system and cannot be assigned to the same user, irrespective of authorisation. An attempt to assign a prohibited pair is rejected with message FL-3104.

Prohibited combination	Reason
Inbound Executive and Quality Disposition	The same person would both accept a quantity and clear it for release
Order Entry and Billing	The same person would both create a charge and invoice it
Commercial and Billing	The same person would set a rate and apply it
Administrator and any operational role	An administrator could grant themselves the means to transact and conceal it

5.2 Competency enforcement

From release 4.2, FleetLink checks the signed-in user's training record before permitting a transaction. Where the record for the relevant module has expired, the transaction is refused with message FL-1014 and the user is directed to the learning tab. This check cannot be bypassed by a supervisor.

6. Master Data

Master data drives validation throughout the application. An incorrect master record does not usually produce an error; it produces a transaction that is accepted and wrong. Master data is therefore maintained only by the Commercial and Administrator roles, and every change is written to the audit trail with the previous and new values.

Master	Key fields	Maintained by	Used by
Customer	Customer code, GSTIN, credit limit, payment terms, notification addresses	Commercial	Order entry, billing, exception notification
Customer material	SKU code, description, batch control flag, minimum residual shelf life, high-value flag, temperature class	Commercial	Inbound receipt, putaway, picking
Facility	Facility code, address, docks, temperature zones, licensed hazard classes	Administrator	Gate entry, dock allocation, receipt
Bin	Bin address, zone, capacity by weight and cube, velocity band	Administrator	Putaway, picking
Vehicle	Registration, type, capacity, ownership, fitness and permit validity	Administrator	Trip allocation, gate entry
Driver	Name, licence number and validity, competency record, contact	Administrator	Trip allocation, gate entry
Transporter	Code, GSTIN, rate card reference, detention terms	Commercial	Trip allocation, settlement
Rate card	Lane, service type, rate basis, validity, fuel escalation	Commercial	Rating, billing

Caution. Changing the minimum residual shelf life on a customer material record takes effect immediately and affects receipts in progress. Where a change is required while a vehicle is at the dock, make the change before the goods receipt note is posted, not after.

7. Creating a Consignment

7.1 Procedure

1. Navigate to **Orders > Create Consignment**.
2. Select the **Consignor**. The consignee list is filtered to addresses registered against that consignor.
3. Select the **Consignee**, or select **New address** to add one. A new address requires approval by the Commercial role before the consignment can be dispatched.
4. Confirm **Origin** and **Destination**. Both default from the selected parties and may be overridden.
5. Select the **Service type**. This determines which rate card applies and which milestones the trip will require.
6. Select the **Cargo class**. Selecting a temperature-controlled or hazardous class restricts the vehicles that can later be allocated.
7. Add line items. For each line enter the SKU, quantity, declared weight and, where the SKU is batch-controlled, the batch and expiry.
8. Select **Validate**. The system applies the checks in 7.2 and lists any failures without saving.
9. Correct any failures and select **Confirm order**. A consignment number is allotted in the format CN///.

7.2 Validations applied

Check	Failure message	Resolution
Consignor is active and within credit limit	FL-2101 credit limit exceeded	Refer to the Billing team for release
Consignee address is approved	FL-2104 address pending approval	Request approval from Commercial
Rate card exists for the lane and service type	FL-2108 no valid rate card	Refer to Commercial to create or extend the card
SKU exists in the customer material master	FL-2112 material not found	Request the SKU be added
Batch and expiry present where required	FL-2115 batch details mandatory	Obtain the batch and expiry from the consignor
Declared weight is within the service type limit	FL-2119 weight exceeds service limit	Split the consignment or change the service type
E-way bill required and value above threshold	FL-2124 e-way bill mandatory	Generate the e-way bill before dispatch
Hazard class licensed at both origin and destination	FL-2131 hazard class not licensed	Select an alternate facility or refer to Compliance

7.3 Amending and cancelling

A consignment may be amended freely while its status is Draft or Confirmed. Once a trip has been allocated, quantity and destination become read-only and an amendment requires the trip to be unallocated first. A consignment that has departed cannot be amended; a correction is recorded as a separate adjustment against the invoice.

Cancellation is permitted until departure. Cancelling a consignment allocated to a trip removes it from that trip and may leave the trip below its minimum utilisation, in which case the planner receives a notification.

8. Trip Planning and Vehicle Allocation

8.1 Trip lifecycle




Figure 8.1: Trip status lifecycle. A trip may be cancelled from any status up to In transit; after that a termination requires the Supervisor role and records a reason.

Status	Meaning	Permitted next status	Set by
Draft	Trip created, no consignments attached	Planned, Cancelled	Transport Planner
Planned	Consignments attached, no vehicle allocated	Allocated, Cancelled	Transport Planner
Allocated	Vehicle and driver allocated	In transit, Cancelled	Transport Planner
In transit	Vehicle has departed origin	Delivered, Cancelled	Gate or mobile application
Delivered	All consignments delivered	POD closed	Mobile application
POD closed	Proof of delivery captured and accepted for all consignments	Invoiced	Customer service
Invoiced	Invoice generated	None — terminal	Billing
Cancelled	Trip abandoned	None — terminal	Transport Planner or Supervisor

8.2 Allocating a vehicle

1. Navigate to **Trips > Planning board** and open the trip.
2. Select **Allocate vehicle**. The list shows only vehicles that satisfy the checks in 8.3.
3. Select the vehicle and then the driver. The driver list is filtered to drivers holding a valid licence for the vehicle class.
4. Enter the planned departure and arrival times.
5. Select **Confirm allocation**. The trip moves to Allocated and the driver receives the trip on the mobile application.

8.3 Vehicle eligibility checks

Check	Effect if failed
Fitness certificate valid on the planned departure date	Vehicle excluded from the list
Permit valid for every state on the route	Vehicle excluded from the list
Insurance valid	Vehicle excluded from the list
Pollution certificate valid	Vehicle excluded from the list
Capacity by weight and cube sufficient for the trip	Warning; may be overridden by a Supervisor
Temperature capability matches the cargo class	Vehicle excluded from the list
Hazard class compatibility	Vehicle excluded from the list
Vehicle not already allocated to an overlapping trip	Vehicle excluded from the list
Driver competency record current	Driver excluded from the list
Driver hours of service within limit	Warning; may be overridden by a Supervisor with a reason

9. Freight Rating and Rate Cards

9.1 Rate basis

Basis	Charge computed on	Typical use
Per trip	A flat amount for the lane	Full truck load contract lanes
Per tonne	Chargeable weight in tonnes	Bulk and part load
Per kilogram	Chargeable weight in kilograms	Express and air freight
Per cubic metre	Volume	Low-density cargo
Per pallet position	Pallet positions occupied	Palletised distribution
Per unit	Cases or units handled	Value-added services
Per square foot per month	Area occupied	Dedicated warehousing
Slab	The slab into which chargeable weight falls	Express parcel

Chargeable weight is the higher of actual weight and volumetric weight. The volumetric divisor is configured per service type; the default is 4,500 for surface and 5,000 for air.

9.2 Accessorial charges

Charge	Basis	Applied	Requires approval
Detention	Per hour beyond free time	Automatically from gate records	No
Loading and unloading	Per tonne or per trip	Where contracted	No
Multi-point pickup	Per additional point	Automatically from the trip	No
Multi-point delivery	Per additional point	Automatically from the trip	No
Waiting at delivery	Per hour beyond free time	From mobile application timestamps	No
Reattempt delivery	Per attempt	Manually by customer service	Supervisor
Special handling	Per consignment	Manually	Supervisor
Cold chain surcharge	Percentage of base freight	Automatically from cargo class	No
Hazardous surcharge	Percentage of base freight	Automatically from cargo class	No
Fuel escalation	Formula or percentage	Automatically at invoice	No

9.3 Fuel escalation

From release 4.2 fuel escalation may be configured as a formula referencing a published diesel price index rather than as a fixed percentage. The formula compares the index value at the invoice date with the base index recorded on the rate card, and applies the resulting movement to the escalable portion of the freight, subject to any cap or floor configured on the card.

Where an index value is unavailable for the invoice date, the last published value is used and the invoice is flagged for review. The system does not interpolate.

9.4 Rate card validity

- A rate card has a start date and an end date. Rating uses the card valid on the consignment booking date, not the invoice date.
- Overlapping cards for the same lane and service type are rejected on save with message FL-4118.
- A card within 14 days of expiry generates a notification to the Commercial team.
- A consignment booked on a lane with no valid card cannot be confirmed. It is not rated at zero.

10. Track and Trace and Electronic Proof of Delivery

10.1 Milestones

Milestone	Captured by	Mandatory	Visible to customer
Order confirmed	System	Yes	Yes
Vehicle allocated	System	Yes	No
Gate out at origin	Gate or mobile application	Yes	Yes
In transit checkpoint	Mobile application	No	Yes
Arrived at destination	Mobile application	Yes	Yes
Unloading started	Mobile application	No	No
Delivered	Mobile application	Yes	Yes
Proof of delivery captured	Mobile application	Yes	Yes
Proof of delivery accepted	Customer service	Yes	Yes
Exception raised	Any user	No	Yes

10.2 Capturing proof of delivery

Proof of delivery is captured on the driver mobile application at the point of delivery. The driver photographs the signed delivery challan, captures the receiver's name and designation, and records any shortage or damage observed by the receiver. Location and timestamp are recorded automatically and cannot be edited.

Where connectivity is unavailable, capture proceeds offline and the record synchronises when connectivity is restored. The timestamp recorded is the time of capture, not the time of synchronisation.

10.3 Accepting proof of delivery

Customer service reviews each proof of delivery before the trip can be invoiced. A document that is illegible, unsigned or inconsistent with the consignment is rejected and returned to the driver for recapture. A rejection reason is mandatory.

Rejection reason	Action required
Image illegible	Recapture the document
Signature missing	Obtain the receiver's signature
Receiver name not recorded	Record the name and designation
Quantity on document differs from consignment	Raise an exception under Chapter 12
Damage noted but not photographed	Photograph the damage and attach
Wrong consignment attached	Attach the correct document

11. Inbound Receipt

This chapter describes the screens used to record an inbound receipt. The operational sequence, verification standards and authority limits are defined in the inbound receiving standard operating procedure and are not repeated here. Where the two differ, the procedure governs and a documentation defect should be raised.

11.1 Expected receipts

Navigate to **Warehouse › Expected receipts** to view advance shipping notices for the active facility. The list shows the consignor, the expected arrival window, the number of lines and the declared quantity. An advance shipping notice may be accepted into the inbound plan, returned to the consignor, or entered manually where the consignor is not integrated.

11.2 Recording gate entry

1. Navigate to **Warehouse › Gate entry**.
2. Enter the vehicle registration number. Where an advance shipping notice exists for that vehicle it is offered for selection.
3. Enter the driver name, licence number and mobile number.
4. Enter the seal number as found on the vehicle. Where this differs from the seal number on the lorry receipt, the system requires an exception to be raised before the gate entry can be saved.
5. Enter the gross inward weight, or select **Fetch from weighbridge** where the weighbridge is integrated.
6. Select **Allot gate entry**. A gate entry number is generated and the vehicle may proceed to the allotted dock.

11.3 Posting a goods receipt note

1. Navigate to **Warehouse › Inbound receipt** and select the gate entry number.
2. Enter the invoice number and date from the tax invoice.
3. For each line, enter the **Received quantity** as verified on the tally sheet.
4. Enter the **Batch** and **Expiry** for every batch-controlled line.
5. Select the **Quality disposition** for each line. This field is mandatory from release 4.2; a line left blank is posted to quarantine.
6. Enter the tare weight, or fetch it from the weighbridge, so that net received weight is computed.
7. Select **Validate**. Any variance against the invoice quantity is listed.
8. Where a variance exists, select **Raise exception** and complete the record described in Chapter 12. The goods receipt note cannot be posted until the exception exists.
9. Select **Post GRN**. A goods receipt note number is generated and pallet labels are produced for printing.

Caution. Posting a goods receipt note is not reversible. A quantity posted in error is corrected by a stock adjustment, which requires the Supervisor role and is reported in the monthly adjustment summary. Verify the entered quantity against the tally sheet before posting.

11.4 Validations applied at receipt

Check	Message	Behaviour
Gate entry exists and is open	FL-5102 gate entry not found or closed	Blocks posting
Invoice number unique for the consignor	FL-5104 duplicate invoice	Blocks posting
SKU present in the customer material master	FL-5108 material not found	Blocks the line
Received quantity matches invoice or an exception exists	FL-5112 variance without exception	Blocks posting
Batch present where the SKU is batch-controlled	FL-5116 batch mandatory	Blocks the line
Residual shelf life meets the customer minimum	FL-5119 insufficient shelf life	Blocks the line unless overridden by Quality Disposition
Quality disposition selected	FL-5121 disposition mandatory	Defaults to quarantine if omitted
Net weight variance within tolerance	FL-5124 weight variance	Warns; requires an exception if beyond tolerance
Hazard class licensed at the facility	FL-5128 hazard class not licensed	Blocks posting
Temperature logger attached for cold chain	FL-5131 logger report required	Blocks posting

11.5 Printing pallet labels

Labels are produced automatically on posting and are queued to the printer configured for the dock. Select **Reprint labels** on the goods receipt note to produce a replacement for a damaged or illegible label. Every reprint is recorded in the audit trail with the user and reason, because an uncontrolled second label for the same pallet permits the same stock to be confirmed into two bins.

12. Exception Management

An exception records a departure from the expected condition of a consignment. Exceptions are visible to the customer through the portal from the moment they are saved, so accuracy at the point of entry matters more than speed.

12.1 Raising an exception

1. Navigate to **Exceptions › Raise exception**, or select **Raise exception** from within the inbound receipt or trip screen.
2. Select the **Exception code** from the list. Codes are defined in the governing standard operating procedure and are not user-definable.
3. Select the affected lines and enter the affected quantity for each.
4. Enter a description. A minimum of twenty characters is enforced; entries such as *short* or *damaged* are rejected.
5. Attach photographs. For codes marked mandatory in 12.2 the record cannot be saved without at least one attachment.
6. Select **Save and notify**. The consignor is notified at the addresses held on the customer master and the target closure date is computed.

12.2 Exception codes

Code	Exception	Photograph mandatory	Target closure
D-01	Shortage against invoice	No	2 working days
D-02	Overage against invoice	No	2 working days
D-03	Wrong material received	No	2 working days
D-04	Batch not listed on invoice	No	1 working day
D-05	Damaged packaging	Yes	3 working days
D-06	Insufficient residual shelf life	No	1 working day
D-07	Temperature excursion	Yes	Same day
D-08	Seal discrepancy	Yes	Same day
D-09	Weight variance beyond tolerance	No	2 working days
D-10	Document deficiency	No	1 working day
D-11	Pest or contamination evidence	Yes	Same day
D-12	Unmanifested cargo	Yes	Same day

12.3 Closing an exception

Only the resolution owner shown on the record may close it. Closure requires a resolution description and, where the resolution involves a stock movement, a reference to that movement. An exception cannot be closed while a linked stock quantity remains in quarantine status.

Closure type	Requires	Effect on stock
Accepted by consignor	Consignor confirmation attached	Quarantined quantity released to unrestricted
Credit note issued	Credit note number	No stock effect
Returned to consignor	Outbound consignment number	Quantity removed from stock

Closure type	Requires	Effect on stock
Destroyed	Destruction certificate attached	Quantity removed from stock
Written off	Supervisor approval and reason	Quantity removed from stock
Closed without adjustment	Explanation, minimum 40 characters	No stock effect

12.4 Ageing and escalation

An exception past its target closure date appears on the exception ageing report and generates a notification to the resolution owner and their supervisor. Exceptions unclosed beyond twice the target period are listed in the weekly operations review. The system does not close an exception automatically under any circumstance.

13. Putaway and Bin Management

13.1 Confirming putaway

1. On the handheld scanner, open **Putaway**.
2. Scan the pallet label. The screen shows the material, quantity and the assigned bin.
3. Move the pallet to the assigned bin.
4. Scan the bin label. Where the scanned bin matches the assigned bin, the confirmation is accepted immediately.
5. Where it does not match, and you hold the Bin Override role, select a reason from the list and select **Confirm override**. Where you do not hold that role, the confirmation is refused with message FL-6114.

Blind confirmation, in which the bin is keyed rather than scanned, was withdrawn in release 4.2. Both scans are required. This change was made because keyed confirmations accounted for the majority of stock located in a bin other than the one recorded.

13.2 Override reasons

Reason	Role required	Follow-up generated
Assigned bin physically blocked	Bin Override	Housekeeping task
Assigned bin damaged	Bin Override	Rack inspection request
Pallet dimension exceeds bin	Bin Override	Master data review task
Bin label unreadable	Warehouse Operator	Label reprint task
System allocation error	Supervisor	IT incident

13.3 Bin addressing

Bin addresses take the form Z-AA-LL-PP for zone, aisle, level and position. Addresses are created and retired by an administrator and are never reused for a different physical location, so that historical transactions continue to refer to the location they actually described.

13.4 Putaway ageing report

Bracket	Classification	Notification
Under 4 hours	Within target	None
4 to 8 hours	Alert	Supervisor – Inbound
8 to 24 hours	Breach	Supervisor and Warehouse Manager
Beyond 24 hours	Critical	Warehouse Manager and Head – Warehouse Operations

14. Reports

Report	Content	Available to	Refresh
Dock to stock	Distribution of elapsed time from gate entry to putaway confirmation	Supervisor and above	Hourly
Receipt accuracy	Goods receipt note lines subsequently adjusted, as a percentage	Supervisor and above	Daily
Putaway ageing	Pallets received but unconfirmed, by bracket	All warehouse roles	Every 15 minutes
Putaway accuracy	Audit findings of stock located other than as recorded	Supervisor and above	Daily
Exception ageing	Open exceptions by code, owner and days past target	Supervisor and above	Hourly
Stock ledger	All movements for a material and batch over a period	All warehouse roles	Real time
Stock ageing	Quantity on hand by receipt age bracket	All warehouse roles	Daily
Expiry watch	Stock within a configurable window of expiry	All warehouse roles	Daily
Temperature excursion	Monitored zone readings outside validated range	Quality roles	Every 5 minutes
Vehicle turnaround	Gate entry to gate exit, by vehicle and transporter	Supervisor and above	Hourly
Detention summary	Detention hours and value by transporter	Billing, Commercial	Daily
Trip profitability	Revenue less allocated cost, by trip and lane	Commercial	Daily
Rate card expiry	Cards expiring within a configurable window	Commercial	Daily
Audit trail extract	All changes to a record or by a user over a period	Auditor	Real time

Reports may be scheduled for delivery by email. Scheduling is configured under **Reports › Subscriptions**. A subscription that has failed to deliver on three consecutive occasions is suspended and the owner notified.

15. Driver Mobile Application

15.1 Capabilities

- Receive allocated trips and view consignment and route detail.
- Record departure, checkpoint, arrival and delivery milestones.
- Capture electronic proof of delivery including photograph, receiver name and designation, and observed shortage or damage.
- Raise an exception from the roadside.
- View and acknowledge trip amendments.
- Record fuel and toll expenses against the trip.

15.2 Offline behaviour

Activity	Available offline	Notes
View allocated trip	Yes	Cached at allocation
Record milestone	Yes	Queued; timestamp is time of capture
Capture proof of delivery	Yes	Photographs queued; may consume device storage
Raise exception	Yes	Queued and notified on synchronisation
View updated route	No	Requires connectivity
Acknowledge amendment	No	Requires connectivity

The application retains up to 200 queued records and 500 megabytes of queued photographs. Beyond that, capture is refused until synchronisation occurs. Drivers on long routes without connectivity should synchronise at every opportunity rather than at the end of the trip.

16. Integrations

Interface	Direction	Protocol	Frequency	Failure handling
Customer advance shipping notice	Inbound	REST, JSON	Event driven	Retry 3 times at 5-minute intervals, then alert
Customer order	Inbound	REST, JSON	Event driven	Retry 3 times, then alert
Customer milestone feed	Outbound	REST, JSON webhook	Event driven	Retry with exponential backoff for 24 hours
E-way bill portal	Bidirectional	Government API	Event driven	Queued; manual generation available as fallback
Weighbridge	Inbound	Serial or TCP	On demand	Manual entry permitted with supervisor authorisation
Temperature monitoring	Inbound	MQTT	Every 5 minutes	Alert after 2 missed intervals
Vehicle telematics	Inbound	REST, JSON	Every 2 minutes	Position marked stale after 15 minutes
Financial accounting	Outbound	Flat file	Nightly	File held and retransmitted; reconciliation report generated
Learning management	Inbound	REST, JSON	Nightly	Competency status retained until refreshed

Integration status is visible under **Administration › Integrations**. A failed interface shows the last successful transfer, the failure reason and the number of records held in the queue.

17. Administration

17.1 Creating a user

1. Navigate to **Administration › Users › New user**.
2. Enter the employee identifier, name, designation and reporting manager.
3. Assign one or more facilities. A user may transact only at an assigned facility.
4. Assign roles. Prohibited combinations are rejected with message FL-3104.
5. Select **Create**. The user receives a one-time activation link valid for 24 hours.

17.2 Audit trail

Every create, amend and delete action is recorded with the user identity, timestamp, the screen used, and the previous and new values of each changed field. The audit trail cannot be amended or deleted by any role, including Administrator. It is retained for eight years.

Recorded event	Retained
Record created, amended or deleted	8 years
Sign-in, sign-out and failed attempt	3 years
Role assigned or withdrawn	8 years
Quality disposition applied or released	8 years
Bin override with reason	3 years
Label reprint	3 years
Data export	3 years
Master data change with before and after values	8 years

17.3 Configuration parameters

Parameter	Scope	Default
Session idle timeout	Global	20 minutes
Putaway ageing alert threshold	Facility	4 hours
Weight variance tolerance	Facility	0.5 per cent or 25 kg, whichever is lower
Minimum residual shelf life	Customer material	75 per cent
Volumetric divisor	Service type	4,500 surface, 5,000 air
Detention free time	Transporter and vehicle type	Per contract
Export row limit	Global	50,000
Exception description minimum length	Global	20 characters

18. Troubleshooting

Symptom	Likely cause	What to do
A receipt I posted is not visible	Wrong facility selected at sign-in	Check the facility shown in the header and switch if required
Stock shows as unavailable for picking	Quality disposition is quarantine	Ask a Quality Disposition role holder to review and release
Cannot post a goods receipt note	Variance exists with no exception raised	Raise the exception first, then post
Bin scan is rejected	Scanned bin differs from the assigned bin	Move to the assigned bin, or request an override from a role holder
Pallet label will not print	Printer not mapped to the dock	Select Reprint and choose a printer, then raise an IT request
Rate shows as zero on a consignment	No valid rate card for the lane	Contact the Commercial team; do not confirm the consignment
Driver cannot see an allocated trip	Trip allocated after the driver last synchronised	Ask the driver to refresh; confirm the driver is assigned to the vehicle
Temperature readings have stopped	Sensor gateway offline	Check the gateway, then raise an IT incident; revert to manual logging meanwhile
Export produces an empty file	Filter excludes all rows, or row limit reached	Review the filter and narrow the date range
Competency error blocks a transaction	Training record expired	Complete the module; access restores within 15 minutes

19. Message and Error Codes

Code	Message	Category	User action
FL-1002	Invalid credentials	Authentication	Retry, then contact the service desk
FL-1007	Account locked	Authentication	Wait 30 minutes or request a reset
FL-1014	Competency record expired	Authorisation	Complete the training module
FL-1021	No facility assigned	Authorisation	Request facility assignment
FL-2101	Credit limit exceeded	Order	Refer to Billing for release
FL-2104	Consignee address pending approval	Order	Request Commercial approval
FL-2108	No valid rate card for lane and service	Order	Refer to Commercial
FL-2112	Material not found in customer master	Order	Request the SKU be added
FL-2115	Batch details mandatory	Order	Obtain batch and expiry
FL-2119	Weight exceeds service type limit	Order	Split or change service type
FL-2124	E-way bill mandatory	Order	Generate before dispatch
FL-2131	Hazard class not licensed at facility	Order	Select an alternate facility
FL-3104	Prohibited role combination	Administration	Revise the role request
FL-4118	Overlapping rate card exists	Rating	Amend validity dates
FL-5102	Gate entry not found or closed	Receipt	Verify the gate entry number
FL-5104	Duplicate invoice for consignor	Receipt	Verify the invoice number
FL-5108	Material not found	Receipt	Request the SKU be added
FL-5112	Quantity variance without exception	Receipt	Raise an exception
FL-5116	Batch mandatory for this material	Receipt	Enter batch and expiry
FL-5119	Insufficient residual shelf life	Receipt	Refer to Quality Disposition
FL-5121	Quality disposition mandatory	Receipt	Select a disposition
FL-5124	Net weight variance beyond tolerance	Receipt	Reweigh, then raise an exception if confirmed
FL-5128	Hazard class not licensed	Receipt	Do not unload; escalate
FL-5131	Temperature logger report required	Receipt	Attach the logger report
FL-6114	Bin override not permitted for your roles	Putaway	Request a role holder to confirm
FL-6118	Bin capacity exceeded	Putaway	Select an alternate bin
FL-6122	Bin holds a different material or batch	Putaway	Select an alternate bin
FL-7106	Exception description too short	Exception	Enter at least 20 characters
FL-7109	Photograph mandatory for this code	Exception	Attach a photograph
FL-7114	Quarantined quantity remains open	Exception	Resolve the stock position before closing
FL-8102	Integration queue full	Integration	Raise an IT incident
FL-9104	Export row limit exceeded	Reporting	Narrow the filter

20. Support and Escalation

Priority	Definition	Response	Resolution	Raise to
P1	Application unavailable at one or more facilities, or receipt and dispatch halted	15 minutes	4 hours	Service desk telephone, then IT duty manager
P2	A module unavailable, or a defect preventing a critical transaction	1 hour	1 working day	Service desk portal
P3	A defect with a workaround available	4 hours	5 working days	Service desk portal
P4	Cosmetic defect, documentation error or enhancement request	1 working day	Next release	Service desk portal

Where the application is unavailable, facilities revert to the manual fallback described in the inbound receiving standard operating procedure. Manual transactions are entered into FleetLink within four hours of service restoration and reconciled before the shift closes.

Appendix A — Keyboard Shortcuts

Shortcut	Action	Available on
Alt + N	New record	Any list screen
Alt + S	Save	Any entry screen
Alt + V	Validate	Order and receipt screens
Alt + F	Open filter	Any list screen
Alt + E	Export current list	Any list screen
Alt + R	Refresh	Any screen
Alt + Left	Back	Any screen
Ctrl + Enter	Add line item	Order and receipt screens
Ctrl + D	Duplicate the selected line	Order screens
Esc	Close dialogue without saving	Any dialogue
F1	Context help for the current screen	Any screen
F9	Switch facility	Any screen

Appendix B — Inbound Receipt Field Reference

Field	Type	Mandatory	Source	Validation
Gate entry number	Lookup	Yes	Gate entry screen	Must exist and be open
Invoice number	Text, 30	Yes	Tax invoice	Unique per consignor
Invoice date	Date	Yes	Tax invoice	Not later than today
SKU code	Lookup	Yes	Carton label	Must exist in customer material master
Invoice quantity	Decimal	Yes	Tax invoice	Greater than zero
Received quantity	Decimal	Yes	Tally sheet	Equal to invoice quantity or linked to an exception
Unit of measure	Lookup	Yes	Material master	Must match the material master
Batch	Text, 20	Conditional	Carton label	Mandatory if batch-controlled
Expiry date	Date	Conditional	Carton label	Must satisfy minimum residual shelf life
Manufacturing date	Date	Optional	Carton label	Not later than today
Quality disposition	List	Yes	Inspection report	Accept, Quarantine or Reject; defaults to Quarantine
Inspection reference	Text, 20	Conditional	Inspection report	Mandatory where disposition is Reject
Gross weight	Decimal	Yes	Weighbridge	Greater than tare weight
Tare weight	Decimal	Yes	Weighbridge	Greater than zero
Net weight	Decimal	Computed	System	Within tolerance of declared net weight
Storage bin	Lookup	Computed	Bin allocation logic	Empty or same material and batch
Temperature logger reference	Attachment	Conditional	Logger download	Mandatory for cold chain
Remarks	Text, 200	Optional	User	None

Appendix C — Glossary

Term	Meaning
Accessorial charge	A charge additional to base freight, such as detention or multi-point delivery.
Advance shipping notice	Electronic notification from a consignor of a consignment expected to arrive.
Chargeable weight	The higher of actual weight and volumetric weight.
Consignment	A quantity of goods moving under a single contract of carriage.
Disposition	The quality decision recorded against received stock: accept, quarantine or reject.
Electronic proof of delivery	Digital evidence of delivery comprising photograph, receiver detail, location and timestamp.
Exception	A recorded departure from the expected condition of a consignment.
Gate entry	The record created when a vehicle is admitted to a facility.
Goods receipt note	The system record of acceptance of an inbound consignment.
Lane	An origin and destination pair for which a rate is defined.
Milestone	A recorded event in the progress of a trip or consignment.
Putaway	Movement of received stock to a storage bin with system confirmation.
Quarantine	A system-blocked stock status preventing allocation pending quality decision.
Trip	One or more consignments moving together on one vehicle.
Velocity band	Classification of a material by pick frequency, determining where it is stored.
Volumetric weight	Volume divided by the configured divisor, used where cargo is low density.

End of FleetLink User Manual, Release 4.2, revision 3. Documentation defects and enhancement requests are raised through the service desk portal as priority P4.