Floorplan Dashboard – Figma Drawing Guideline

Export Floorplans from OfficeRnD **3**
Step 1 — Open the Location 3
Step 2 — Open the Outlet Floorplan 4
Download the Required Floorplan Copies 5
Importing the Floorplan into Figma **6**
Drawing Suite Areas in Figma **7**
Tools to use 7
Important notes 8
Final drawing example 9
Managing Layers in Figma **9**
Grouping into a Frame 10
Exporting the Final Drawing as SVG **11**
Editing the SVG Code to Add Suite IDs **11**
Step 1 — Open in VS Code 12
Step 2 — Preview the SVG 12
Step 3 — Identify each room 13
Step 4 — Insert Resource IDs 13
Step 5 — Save the SVG (Ctrl + S) 14
Uploading the SVG into the Floorplan Management System **16**
View the Updated Floorplan **17**

Overview

This document explains how to prepare, draw, label, and upload floorplans for the Floorplan Dashboard.
You will learn how to:


- Export floorplan images from OfficeRnD
- Prepare drawing references
- Draw suite boundaries in Figma
- Export the drawing as SVG
- Add resource IDs to the SVG code
  Upload the completed SVG into the Floorplan Management system


This guideline is written for internal users who prepare outlet floorplans.

Export Floorplans from OfficeRnD

Step 1 — Open the Location

Go to **OfficeRnD** → **Locations** and select the outlet you want to upload to the Floorplan Dashboard.






Step 2 — Open the Outlet Floorplan

Select New Outlet to upload on Floorplan Dashboard * select at what red arrow showing


Click the floorplan for the selected location




Then click **Export** at the top toolbar

Download the Required Floorplan Copies

You must download **two versions** of the same outlet floorplan:



Copy 1: Walls + Resources
Use this version for drawing in Figma.



Copy 2: Walls + Resources + Labels
Use this version as a reference to identify suite names.

Recommended file organization

Create a folder for each outlet, e.g.:


```
Floorplan/
    └── UBP/
        ├── UBP_floorplan_walls_resources.png
        ├── UBP_floorplan_reference_labels.png
```

This helps keep files organized for editing and uploading later.

Importing the Floorplan into Figma


Step 1

Open Figma in your browser.




Step 2

From the **Drafts** page, click **Import** → **Import from Computer**.
Select the **Copy 1** PNG file (Walls + Resources).



Step 3

Once the file appears in your Drafts, open it.




Figma layout:

- **Left panel**: Layer list
- **Right panel**: Properties (size, color, stroke, export section)
- **Bottom toolbar**: Drawing tools (pen, rectangle, etc.)

Drawing Suite Areas in Figma

Tools to use

- **Pen Tool (P)** — for irregular shapes
- **Rectangle Tool (R)** — for standard rectangular rooms






Important notes


When you draw using **Rectangle**, it will initially have a grey fill.
You must **remove the fill**:

1. Go to **Fill** in the right panel
2. Click the **(–)** button to remove the grey color
3. Ensure **Stroke = Black**, stroke width **2px**

This ensures all room boundaries are visible and consistent.



Pen: for irregular shapes.




Rectangle: for square/rectangular shapes.

Final drawing example



Managing Layers in Figma

- The PNG floorplan must remain **at the bottom layer**.
- Lock the PNG layer to avoid accidentally moving it.




Grouping into a Frame


To export properly, all shapes must be inside **one frame**.

You can:

- Select any shape → Right-click → **Frame Selection**
  OR

- Select everything (Shift + click drawing + PNG) → **Ctrl + Alt + G**







Exporting the Final Drawing as SVG

On the right panel, scroll to **Export**.
Select **SVG** and click **Export**.

(Page 14–15 show the Export SVG panel and resulting file.)

Save the SVG in the appropriate outlet folder.





Editing the SVG Code to Add Suite IDs


To make each room clickable inside the Floorplan Dashboard, each drawn shape must have an **ID**.


Step 1 — Open in VS Code

Click Open Folder → Find the folder where you saved all the outlet SVGs.

Step 2 — Preview the SVG

Right-click the file → **Preview SVG**.





Step 3 — Identify each room

When you click a suite in Preview mode:




- This panel appears at the top when you enter SVG preview mode. Click these two buttons  and  to enable clickable areas in the SVG.
- When you click any suite in the SVG, the corresponding XML code will be highlighted in the editor. You can then scroll to that section to edit it.

Step 4 — Insert Resource IDs

In the <rect> or <path> element, add:

id="resource_id_from_sheet"



Refer to the **Resources** sheet in Google Sheets (e.g., SG1_ORD → Resources tab).
Identify:


- Resource ID
- Resource Name
- Resource Type (team_room)

You may use **Copy 2 (Labels)** for room name reference


A	B	C	D	E	F	G	H	I	J	K	L
Extraction D	Resource ID	Resource Type	Resource Name	Prk	Dep	Res	Pax Size	Area in sq	Status	Office ID	Room ID
2025-12-08	5e32aad77801250b0e7511e2	team_room	Suite 01	3200	6400	1	4	9104497.337	occupied	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32ab1f7801250b0e7526ae	team_room	Suite 02	5220	10440	2	6	15329000.62	available_soon	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32ab407801250b0e753261	team_room	Suite 03	3200	6400	3	4		occupied	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32ab7567fd1a09c9ce6dc5	team_room	Suite 3A	5220	10440	4	6	14307067.24	available_soon	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32ab9367fd1a09c9ce7108	team_room	Suite 05	3200	6400	5	4	9104497.337	occupied	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32abbd67fd1a09c9ce7b7d	team_room	Suite 06	5220	10440	6	6	14307067.24	occupied	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32abfd67fd1a09c9ce906f	team_room	Suite 07	3200	6400	7	4	9290303.405	occupied	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32acee74f6270b06db8a0b	team_room	Suite 08	3200	6400	8	4	9290303.405	available_soon	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32ad0174f6270b06db9529	team_room	Suite 09 - WORQ	3200	6400	9	4	9290303.405	available_soon	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32ad737c07820b5d3f6e2d	team_room	Suite 10	4350	8700	10	5	11984491.39	occupied	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32ad9274f6270b06dbca5e	team_room	Suite 11	4350	8700	11	5	11798685.32	occupied	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32adad7c07820b5d3f7ae5	team_room	Suite 12	3200	6400	12	4	9847721.61	occupied	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32adcb7c07820b5d3f8009	team_room	Suite 13	4000	8000	13	5	11891588.36	occupied	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32aeb574f6270b06dc224c	team_room	Suite 13A	13600	27200	14	17	38647662.17	occupied	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32b42cbf261c0b2989cb5d	team_room	Suite 15	3480	6960	16	4	9754818.576	occupied	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32b452586ca50b79914e06	team_room	Suite 16	3480	6960	17	4	9754818.576	occupied	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32b467bf261c0b2989e4c4	team_room	Suite 17	3480	6960	18	4	10033527.68	available_soon	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32b4b8586ca50b799173a6	team_room	Suite 20	3200	6400	20	4	10219333.75	occupied	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32b4d7bf261c0b298a219a	team_room	Suite 21	3200	6400	21	4	10219333.75	occupied	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32b519586ca50b7991a8a2	team_room	Suite 22	4350	8700	22	5	12356103.53	occupied	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32b539bf261c0b298a3c62	team_room	Suite 23 - DD	3200	6400	23	4	10219333.75	unavailable	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32b558bf261c0b298a40b9	team_room	Suite 23A	4350	8700	24	5	12727715.67	occupied	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32b56dbf261c0b298a4878	team_room	Suite 25	3200	6400	25	4	10219333.75	occupied	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32b58ebf261c0b298a5f1e	team_room	Suite 26	2610	5220	26	3	9011594.303	occupied	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32b5b1bf261c0b298a78f2	team_room	Suite 27	4800	9600	27	6	13378036.9	occupied	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32b5cbbf261c0b298a8886	team_room	Suite 28	4800	9600	28	6	13378036.9	available	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32b5edbf261c0b298a90ad	team_room	Suite 29	3480	6960	29	4	10219333.75	occupied	565748274a955c790d808c77	5dd79e2104670400ba72
2025-12-08	5e32b62467fd1a09c9d5bfe8	team_room	Suite 30	4800	9600	30	6	13378036.9	available	565748274a955c790d808c77	5dd79e2104670400ba72

Companies | Locations | Resources | ResourceHelper | Accounts | Floors | Charges | Fees | Payments | Payments_Lines | Payments_Allocations | M

77 of 1,353 rows displayed




Step 5 — Save the SVG (Ctrl + S)




Uploading the SVG into the Floorplan Dashboard

After completing the drawing and adding all IDs:

1. Open the **Floorplan Management** page
2. Go to the **Upload** tab
3. Select the correct **Outlet**
    - This list comes from BigQuery (page 24 confirms this)
4. Choose the **Floor** (refer to OfficeRnD)
5. Select the **SVG file**
6. Click **Upload Floorplan**





View the Updated Floorplan

After uploading, go to the Floorplan Viewer:

- Select the same outlet

