司机端接口说明(iOS)

MADriverRouteManager

状态枚举

```
///行程状态
typedef NS_ENUM(NSInteger, MASCTXDRouteStatus)
{
    MASCTXDRouteStatusUnspecified = 0, ///<未指定状态
    MASCTXDRouteStatusPickupPassenger = 1, ///<去接乘客
    MASCTXDRouteStatusWaitPassenger = 2, ///〈等待乘客上车
    MASCTXDRouteStatusPassengerOnBoard = 3, ///〈乘客已上车
    MASCTXDRouteStatusOrderComplete = 4, ///〈订单已结束
};
```

司机端控制器

```
@interface MADriverRouteManager : NSObject
///司机信息自动上传时间间隔,单位秒,默认为10s。
@property (nonatomic, assign) NSInteger driverInfoUploadTimeInterval;
///地图对象
@property (nonatomic, weak) MAMapView *mapView;
@property (nonatomic, weak) id<MADriverRouteManagerDelegate> delegate;
///驾车导航manager, 司乘同显司机端生命周期期间需要导航的请使用此属性。
@property (nonatomic, weak, readonly) AMapNaviDriveManager *driveManager;
///导航策略, 默认AMapNaviDrivingStrategySingleDefault
@property (nonatomic, assign) AMapNaviDrivingStrategy;
///起点标注
@property (nonatomic, strong, readonly) MAPointAnnotation *beginAnnotation;
///终点标注
@property (nonatomic, strong, readonly) MAPointAnnotation *endAnnotation;
@property (nonatomic, strong, readonly) MAAnimatedAnnotation *carAnnotation;
///是否自动调整地图显示区域,默认为YES。默认行为:在司机位置回调后,调整地图可视范围以显示carAnnotation和终点annotation。注意,当
前版本内部自动调整不在选中annotation。如果要自定义此行为,请设置此属性为NO,且在routeStatusChangeForManager回调中对地图进行操作
,获取添加timer进行自定义操作。
@property (nonatomic, assign) BOOL automaticAdjustMapRegion;
///调整地图显示区域时间间隔, 默认10s
@property (nonatomic, assign) NSTimeInterval autoAdjustMapTimeInterval;
///地图显示区域改变后,自动调整地图时间间隔,默认10s
@property (nonatomic, assign) NSTimeInterval autoAdjustMapAfterRegionChangedTimeInterval;
///默认调整地图时需要设置的padding, 默认为(30, 30, 80, 30)
@property (nonatomic, assign) UIEdgeInsets automaticAdjustPadding;
```

```
///小车不进行动画的移动距离,单位米。默认为800。
@property (nonatomic, assign) double ignoreCarAnimationDistance;
///是否开启log输出,默认为NO。
@property (nonatomic, assign) BOOL enableDebugLog;
///是否开启模拟导航,默认为NO。
@property (nonatomic, assign) BOOL startWithEmulatorNavi;
///小车图片
@property (nonatomic, strong) UIImage *carImage;
///起点图片
@property (nonatomic, strong) UIImage *startImage;
///终点图片
@property (nonatomic, strong) UIImage *endImage;
///路况纹理 - 拥堵
@property (nonatomic, strong) UIImage *blockedImage;
///路况纹理 - 非常缓慢
@property (nonatomic, strong) UIImage *verySlowImage;
///路况纹理 - 缓慢
@property (nonatomic, strong) UIImage *slowImage;
///路况纹理 - 畅通
@property (nonatomic, strong) UIImage *goodImage;
///路况纹理 - 未知
@property (nonatomic, strong) UIImage *unknownImage;
///路线默认纹理
@property (nonatomic, strong) UIImage *defaultImage;
///步行路线纹理
@property (nonatomic, strong) UIImage *walkImage;
///线宽, 默认 18
@property (nonatomic, assign) CGFloat lineWidth;
///行程状态,设置行程状态会改变manager的行为
@property (nonatomic, assign) MASCTXDRouteStatus status;
@brief 设置订单信息,如果没有经纬度,请传 kCLLocationCoordinate2DInvalid.注意:如果endPosition传invalid,则送乘客阶段不显示
路线。
@param orderId 订单id
@param begin 起点坐标
@param end 终点坐标
*/
- (void)setOrderInfoWith:(NSString *)orderId
         beginPosition:(CLLocationCoordinate2D)begin
           endPosition:(CLLocationCoordinate2D)end;
@brief 设置小车弹出框,如果执行了此接口,则不显示默认callout。
@param calloutView 气泡显示内容
- (void)updateDriverInfoWith:(UIView *)calloutView;
/**
Mhriaf 设署起占annotation弹出标
```

```
@param calloutView 气泡显示内容
*/
- (void)updateStartAnnotationInfoWith:(UIView *)calloutView;
@brief 设置终点annotation弹出框
@param calloutView 气泡显示内容
- (void)updateEndAnnotationInfoWith:(UIView *)calloutView;
@brief 设置订单信息, 只在默认calloutView时有效果, 如果设置了自定义calloutView, 则无效。
@param distance 剩余距离,单位米
@param time 预估时间,单位秒
@param price 预估价格, 默认只在送驾时有效, 单位元
- (void)updateDriverInfoWithDistance:(double)distance time:(NSTimeInterval)time price:(double)price;
///判断是否是内部overlay
(BOOL)isInternalOverlay:(id<MAOverlay>)overlay;
///重新算路,只有在接乘客和送乘客阶段才会成功
(void)calculateNaviRoute;
#pragma mark - MapView代理相关方法
/**
* @brief 在mapView对应的delegate方法内调用此方法
* @param mapView 地图View
* @param animated 是否动画
- (void)mapView:(MAMapView *)mapView regionWillChangeAnimated:(BOOL)animated;
/**
* @brief 在mapView对应的delegate方法内调用此方法
* @param mapView 地图View
* @param animated 是否动画
- (void)mapView:(MAMapView *)mapView regionDidChangeAnimated:(BOOL)animated;
/**
* @brief 在mapView对应的delegate方法内调用此方法
                地图view
* @param mapView
* @param wasUserAction 标识是否是用户动作
*/
- (void)mapView:(MAMapView *)mapView mapWillMoveByUser:(BOOL)wasUserAction;
* @brief 在mapView对应的delegate方法内调用此方法
* @param mapView 地图view
* @param wasUserAction 标识是否是用户动作
- (void)mapView:(MAMapView *)mapView mapDidMoveByUser:(BOOL)wasUserAction;
* @brief 在mapView对应的delegate方法内调用此方法
* @param mapView
                地图view
* @param wasUserAction 标识是否是用户动作
- (void)mapView:(MAMapView *)mapView mapWillZoomByUser:(BOOL)wasUserAction;
* @brief 在mapView对应的delegate方法内调用此方法
* Ananam manView
                     州図いするい
```

MOLITOL MERCWAIIIOCCACIONTHIE

```
* @param wasUserAction 标识是否是用户动作
*/
- (void)mapView:(MAMapView *)mapView mapDidZoomByUser:(BOOL)wasUserAction;

/**
@brief 在mapView对应的delegate方法内调用此方法
@param mapView 地图对象
@param overlay overlay
@return 对于属于当前controller的overlay, 返回相应的MAOverlayRenderer对象, 否则返回nil
*/
- (MAOverlayRenderer *)mapView:(MAMapView *)mapView rendererForOverlay:(id <MAOverlay>)overlay;

/**

* @brief 在对应的地图delegate方法中调用此方法
* @param mapView 地图

* @param annotation 标注
* @return 对于属于当前controller的annotation, 返回相应的annotationview, 否则返回nil
*/
- (MAAnnotationView *)mapView:(MAMapView *)mapView viewForAnnotation:(id <MAAnnotation>)annotation;
@end
```

MADriverRouteManagerDelegate

司机端控制器代理