Pi File Server: Client Setup

Connect another Linux computer to the Pi's NFS share (192.168.1.50)

Run these on each **client computer**, not on the Pi. The share is `/srv/storage` on `192.168.1.50`, available to the `192.168.1.0/24` network.

Arch Linux

Install the NFS client software.

```
sudo pacman -S nfs-utils
```

Create the empty folder where the Pi's files will appear.

```
sudo mkdir -p /mnt/pi
```

Store the mount options in a variable (automount on first use, unmount after 60s idle, 10s timeout so it never hangs).

```
OPTS='noauto,x-systemd.automount,x-systemd.idle-timeout=60,x-systemd.mount-timeout=10,_netdev'
```

Add the Pi's share to /etc/fstab so it is set up automatically.

```
echo "192.168.1.50:/srv/storage  /mnt/pi  nfs4  $OPTS  0  0" | sudo tee -a /etc/fstab
```

Tell systemd to re-read fstab.

```
sudo systemctl daemon-reload
```

Activate the new network mount.

```
sudo systemctl restart remote-fs.target
```

Test: you should see the files from the Pi's drive.

```
ls /mnt/pi
```

Lubuntu / Ubuntu / Debian

Install the NFS client software.

```
sudo apt install nfs-common -y
```

Create the empty folder where the Pi's files will appear.

```
sudo mkdir -p /mnt/pi
```

Store the mount options in a variable (automount on first use, unmount after 60s idle, 10s timeout so it never hangs).

```
OPTS='noauto,x-systemd.automount,x-systemd.idle-timeout=60,x-systemd.mount-timeout=10,_netdev'
```

Add the Pi's share to /etc/fstab so it is set up automatically.

```
echo "192.168.1.50:/srv/storage  /mnt/pi  nfs4  $OPTS  0  0" | sudo tee -a /etc/fstab
```

Tell systemd to re-read fstab.

```
sudo systemctl daemon-reload
```

Activate the new network mount.

```
sudo systemctl restart remote-fs.target
```

Test: you should see the files from the Pi's drive.

```
ls /mnt/pi
```

If the test fails

Re-arm the automount, then try `ls /mnt/pi` again:

```
sudo systemctl restart mnt-pi.automount
```

Mount once by hand to see any error message:

```
sudo mount -t nfs4 192.168.1.50:/srv/storage /mnt/pi
```

If the Pi's IP ever changes

Edit the IP in `/etc/fstab` on each client, then reload:

```
sudo systemctl daemon-reload && sudo systemctl restart mnt-pi.automount
```