### RTMaps

RTMaps v3.4 (13/10/2010)

Generated by Doxygen 1.7.2

Wed Oct 13 2010 18:59:21

### **Contents**

1	Main 1.1		use this d	ocumentation	1
2	Depr	ecated L	ist		3
3	<b>Modu</b> 3.1	<b>ile Index</b> Module			5 5
4	<b>Name</b> 4.1	espace I Names			7 7
5	<b>Class</b> 5.1	s Index Class I	Hierarchy		9
6	<b>Class</b> 6.1	Index Class I	∟ist		3
7	<b>File I</b> 7.1	ndex File Lis	t		7 17
8	Modu	ıle Docu	mentation	1	9
	8.1	Basic o	data structi	ures	19
		8.1.1	Detailed I	Description	21
		8.1.2	Define Do	ocumentation	22
			8.1.2.1	MAPSForall	22
			8.1.2.2		22
			8.1.2.3		22
		8.1.3	21		23
		0.4.4	8.1.3.1		23
		8.1.4	8.1.4.1		23 23
	8.2	Input d	efinition m	-1	∠3 23
	0.2	8.2.1			23
		0.2.1	8.2.1.1		-0 23
			8.2.1.2		-0 24
	8.3	Output	•		 24
	0.0	8.3.1			- · 24
			8.3.1.1		 24
			8.3.1.2		24
			8.3.1.3		25

ii CONTENTS

			8.3.1.4	MAPS_OUTPUT_USER_STRUCTURE	25
	8.4	Proper	ty definition	n macros	26
		8.4.1	Define Do	ocumentation	26
			8.4.1.1	MAPS_BEGIN_PROPERTIES_DEFINITION	26
			8.4.1.2	MAPS_PROPERTY	27
			8.4.1.3	MAPS_PROPERTY_ENUM	27
			8.4.1.4	MAPS_PROPERTY_ENUM_UNIT	27
			8.4.1.5	MAPS_PROPERTY_READ_ONLY	28
			8.4.1.6	MAPS_PROPERTY_READ_ONLY_UNIT	28
			8.4.1.7	MAPS_PROPERTY_UNIT	28
	8.5	Action	definition m	nacros	29
		8.5.1	Define Do	ocumentation	29
			8.5.1.1	MAPS_ACTION	29
			8.5.1.2	MAPS_BEGIN_ACTIONS_DEFINITION	29
	8.6	Compo	nent desig	n	30
		8.6.1	Define Do	ocumentation	32
			8.6.1.1	MAPS_CHILD_COMPONENT_HEADER_CODE	32
			8.6.1.2	MAPS_CHILD_COMPONENT_HEADER_CODE_WITHOUT	
				CONSTRUCTOR	32
			8.6.1.3	MAPS_CLOCK_COMPONENT_HEADER_CODE	32
			8.6.1.4	MAPS_COMPONENT_DEFINITION	32
			8.6.1.5	MAPS_COMPONENT_DEFINITION_DOC	33
			8.6.1.6	MAPS_COMPONENT_DEFINITION_REGISTRATION	34
			8.6.1.7	MAPS_COMPONENT_DEFINITION_UNIQUE	34
			8.6.1.8	MAPS_COMPONENT_DYNAMIC_HEADER_CODE	35
			8.6.1.9	MAPS_COMPONENT_HEADER_CODE_WITHOUT_CONSTRU	JCTOR 35
			8.6.1.10	MAPS_COMPONENT_REGISTERING_HEADER_CODE	36
			8.6.1.11	MAPS_COMPONENT_STANDARD_HEADER_CODE	36
			8.6.1.12	MAPS_PARENT_COMPONENT_HEADER_CODE	
			8.6.1.13	MAPS_PARENT_COMPONENT_HEADER_CODE_WITHOUT_	
				CONSTRUCTOR	
	8.7			thod design	
		8.7.1		ocumentation	
			8.7.1.1	MAPS_RECORD_REPLAY_METHOD_BLACKBOX_HEADER	
				CODE	
			8.7.1.2	MAPS_RECORD_REPLAY_METHOD_COPY_HEADER_CODE	
			8.7.1.3	MAPS_RECORD_REPLAY_METHOD_DEFINITION	
			8.7.1.4	MAPS_RECORD_REPLAY_METHOD_HEADING_HINT_HEADI	
				CODE	39
			8.7.1.5	MAPS_RECORD_REPLAY_METHOD_PROCESS_HEADER	
				CODE	
			8.7.1.6	MAPS_RECORD_REPLAY_METHOD_STANDARD_HEADER	
				CODE	39
9	Name	espace [	Ocumentat	tion	41
•	9.1			e Reference	41
		9.1.1		Description	59
		9.1.2		Documentation	59
			9.1.2.1	About	59
			9.1.2.2	AbsoluteTime2Integer	59
				•	

CONTENTS iii

			9.1.2.3	AbsoluteTimeUTC2Timestamp	59
			9.1.2.4	Attach2	59
			9.1.2.5	GetInstallPath	60
			9.1.2.6	GetSynchronizer	60
			9.1.2.7	GetSystemAccurateTiming	60
			9.1.2.8	Integer2AbsoluteTime	60
			9.1.2.9	IplImageModel	61
			9.1.2.10	IplImageModel	61
			9.1.2.11	Memcpy	61
			9.1.2.12	MessageBox	61
			9.1.2.13	ReleaseCurrentThread	61
			9.1.2.14	Report	62
			9.1.2.15	ReportInfo	62
			9.1.2.16	SetSystemTime	62
			9.1.2.17	Sleep	62
			9.1.2.18	Timestamp2AbsoluteTimeUTC	63
			9.1.2.19	Timestamp2String	63
			9.1.2.20	TimestampFromString	63
			9.1.2.21	TimeString	63
			9.1.2.22	TypeFilter	63
		9.1.3	Variable [	Documentation	64
			9.1.3.1	EnumProperty	64
			9.1.3.2	TextAscii	64
10			entation		65
	10.1				65
				and the same of th	67
		10.1.2			67
			10.1.2.1	channelSeq	67
			10.1.2.2	colorModel	67
			10.1.2.3	depth	67
			10.1.2.4	imageld	67
			10.1.2.5	maskROI	68
			10.1.2.6	roi	68
	10.2	•			68
		10.2.1		•	68
		10.2.2			69
			10.2.2.1	coi	69
	10.3				69
					70
	10.4				70
				·	70
	10.5		-	•	70
					73
		10.5.2			73
			10.5.2.1	MAPSArray	73
			10.5.2.2	MAPSArray	73
		10.5.3	Member I	Function Documentation	73
			10.5.3.1	Alloc	73
			10.5.3.2	Append	74

iv CONTENTS

	10 5 0 0	analysis T
	10.5.3.3	operator T *
	10.5.3.4	operator[]
	10.5.3.5	Pop
	10.5.3.6	Realloc
	10.5.3.7	Set
	10.5.3.8	Shift
	10.5.3.9	Unshift
10.5.4		And Related Function Documentation
	10.5.4.1	operator<<
		Class Reference
		Description
10.6.2		tor & Destructor Documentation
	10.6.2.1	MAPSBaseClock
10.6.3	Member	Function Documentation
	10.6.3.1	CurrentTime
	10.6.3.2	GetAbsoluteTimeSpeed
	10.6.3.3	InitClock
	10.6.3.4	IsReplayable
	10.6.3.5	IsSynchronizable
	10.6.3.6	RunClock
	10.6.3.7	SetAbsoluteTimeSpeed
	10.6.3.8	ShutdownClock
10.7 MAPS	BasicList C	Class Reference
		Description
10.8 MAPS	BasicListIt	em Class Reference
		Description
		Struct Reference
		Description
		ct Reference
		Description
		Struct Reference
	•	Description
		at Class Reference
		Description
		Function Documentation
10.12.	10.12.2.1	
	10.12.2.2	
	10.12.2.2	
	10.12.2.4	Core
	10.12.2.4	
	10.12.2.6	
	10.12.2.7	
	10.12.2.7	
	10.12.2.9	
		NewAction
		1 NewAction
		2 NewInput
		3 NewInput
	10.12.2.14	4 NewOutput

CONTENTS

10.12.2.15 NewOutput	88
10.12.2.16 NewProperty	89
10.12.2.17 NewProperty	89
10.12.2.18 SetAutomaticStart	89
10.12.2.19 Start	89
	90
	90
10.13.2 Friends And Related Function Documentation	90
10.13.2.1 operator <<	90
<b>5</b> ,	91
· · · · · · · · · · · · · · · · · · ·	92
10.15MAPSDrawingObjectVariant Struct Reference	93
10.15.1 Detailed Description	93
10.16MAPSEllipse Struct Reference	93
10.16.1 Detailed Description	94
	94
	95
	95
	95
	95
	96
	97
	97
	97
	97
	97
	97
	97
	98
	98
55	98
	98
	99
10.19.1 Detailed Description	
10.19.2 Member Function Documentation	
10.19.2.1 FileClose	
10.19.2.2 FileClose	
10.19.2.3 FileNextLine	
10.19.2.4 FileOpen4Reading	
10.19.2.5 FileOpen4Writing	
10.19.2.6 FilePreviousLine	
10.19.2.7 FileRead	
10.19.2.8 FileWrite	
10.19.2.9 FileWriteText	
10.19.2.10 Unlock	
10.19.3 Member Data Documentation	
10.19.3.1 Endl	
10.20MAPSFileReadHandle Class Reference	
10.20.1 Detailed Description	
10.21 MAPSFileWriteHandle Class Reference	Ut

vi CONTENTS

10.01 1 Detailed Description	100
10.21.1 Detailed Description	
10.22MAPSHashTable $<$ TKey, TContent, H $>$ Class Template Reference	
10.22.1 Detailed Description	
10.22.2 Constructor & Destructor Documentation	
10.22.2.1 MAPSHashTable	
10.22.3 Member Function Documentation	
10.22.3.1 Clear	
10.22.3.2 Insert	
10.22.3.3 Insert	
10.22.3.4 Next	
10.23MAPSHashTableIterator Class Reference	
10.23.1 Detailed Description	
10.24MAPSImage Struct Reference	
10.24.1 Detailed Description	
10.25MAPSImageProcessing1Src1Dest Class Reference	
10.25.1 Detailed Description	
10.26MAPSImageProcessing1Src1DestDefinition Struct Reference	
10.26.1 Detailed Description	
10.27MAPSImageProcessing1Src1DestParams Struct Reference	
10.27.1 Detailed Description	. 114
10.28MAPSImageProcessing2Src1Dest Class Reference	. 114
10.28.1 Detailed Description	. 114
10.29MAPSImageProcessing2Src1DestDefinition Struct Reference	. 114
10.29.1 Detailed Description	. 115
10.30MAPSImageProcessing2Src1DestParams Struct Reference	. 115
10.30.1 Detailed Description	. 116
10.31MAPSInput Class Reference	. 116
10.31.1 Detailed Description	. 116
10.31.2 Member Function Documentation	
10.31.2.1 ConnectedOutput	117
10.31.2.2 IsConnected	
10.31.2.3 Name	
10.31.2.4 ShortName	
10.31.2.5 Type	
10.32MAPSIntegerHashTable< TContent > Class Template Reference	
10.32.1 Detailed Description	
10.33MAPSIOEIt Class Reference	
10.33.1 Detailed Description	
10.33.2 Member Function Documentation	
10.33.2.1 BufferSize	
10.33.2.2 Data	
10.33.2.3 Deserialize	_
10.33.2.4 Frequency	
10.33.2.5 IOEltBufferSizeInBytes	
10.33.2.6 IOEltUsedSizeInBytes	
10.33.2.7 IsDeserializable	
10.33.2.8 operator MAPSFloat &	
10.33.2.9 operator MAPSInt32 &	
10.33.2.10 operator MAPSInt64 &	
10.33.2.11 Quality	. 125

CONTENTS vii

10.33.2.12 Serialize	125
10.33.2.13 SerializedIOEltSizeInBytes	125
10.33.2.14 Size	
10.33.2.15 TimeOflssue	
10.33.2.16 Timestamp	
10.33.2.17 VectorSize	
10.34MAPSList< T >::MAPSIterator Class Reference	
10.34.1 Detailed Description	
10.35MAPSLine Struct Reference	_
10.35.1 Detailed Description	
10.36MAPSList < T > Class Template Reference	
10.36.1 Detailed Description	
10.36.2.1 Append	
10.36.2.2 Append	
10.36.2.3 Insert	
10.36.2.4 Insert	
10.36.2.5 InsertAfter	-
10.36.2.6 InsertAfter	-
10.36.2.7 InsertAfter	
10.36.2.8 InsertBefore	
10.36.2.9 InsertBefore	
10.36.2.10 InsertBefore	
10.36.3 Friends And Related Function Documentation	
10.36.3.1 operator <<	
10.37MAPSListItem< T > Class Template Reference	
10.37.1 Detailed Description	
10.38MAPSListIterator Class Reference	
10.38.1 Detailed Description	137
10.39MAPSMatrix Struct Reference	137
10.39.1 Detailed Description	138
10.39.2 Constructor & Destructor Documentation	138
10.39.2.1 MAPSMatrix	138
10.39.3 Member Function Documentation	139
10.39.3.1 lm	
10.39.3.2 operator MAPSMatrix2< double >	139
10.39.3.3 Real	139
10.40MAPSMatrix2< T > Class Template Reference	
10.40.1 Detailed Description	
10.40.2 Member Function Documentation	
10.40.2.1 Clone	
10.40.2.2 operator()	
10.40.2.3 operator=	
10.40.2.4 operator[]	
10.40.3 Friends And Related Function Documentation	
10.40.3.1 operator <<	
10.41 A Detailed Description	
10.41.1 Detailed Description	
10.41.2.1 AcknowledgePropertyChanged	100

viii CONTENTS

10.41.2.2	AcknowledgePropertyChange				
10.41.2.3	AcknowledgePropertyChange				
10.41.2.4	Die				
10.41.2.5	DirectSet		 	 	. 156
10.41.2.6	DirectSet		 	 	. 156
10.41.2.7	DirectSet		 	 	. 156
10.41.2.8	Error		 	 	. 156
10.41.2.9	Get		 	 	. 157
10.41.2.1	OlsDying		 	 	. 157
10.41.2.1	1 IsFIFOFull		 	 	. 157
10.41.2.1	2 LoseOneLife		 	 	. 157
10.41.2.1	3 MsgStartReading		 	 	. 157
10.41.2.1	4 MsgStartReading		 	 	. 158
10.41.2.1	5 MsgWait4Event		 	 	. 158
10.41.2.1	6 MsgWait4Events		 	 	. 159
10.41.2.1	7 NbProperties		 	 	. 159
10.41.2.1	8 NLastStartReading		 	 	. 159
10.41.2.1	OneMoreLife		 	 	. 160
10.41.2.2	PerformanceMonitoring		 	 	. 160
10.41.2.2	1 PropertyChanged		 	 	. 160
10.41.2.2	2 PropertyChanged		 	 	. 160
10.41.2.2	3 PropertyChanged		 	 	. 160
10.41.2.2	4 Report		 	 	. 160
10.41.2.2	5 ReportError		 	 	. 161
10.41.2.2	6 ReportInfo		 	 	. 161
10.41.2.2	7 ReportWarning		 	 	. 161
10.41.2.2	8 Rest		 	 	. 162
10.41.2.2	9 Set		 	 	. 162
10.41.2.3	O Set		 	 	. 162
10.41.2.3	1 Set		 	 	. 162
10.41.2.3	2 StartReading		 	 	. 163
10.41.2.3	3 StartReading		 	 	. 163
10.41.2.3	4 StopWriting		 	 	. 163
10.41.2.3	5 SynchroStartReading		 	 	. 164
10.41.2.3	6 <b>W</b> ait		 	 	. 164
10.41.2.3	7 Wait4Event		 	 	. 164
10.41.2.3	8 Wait4Event		 	 	. 165
10.41.2.3	9 Wait4Events		 	 	. 165
10.41.2.4	Wait4Handshake		 	 	. 165
10.42MAPSMutex Cla	ss Reference		 	 	. 166
10.42.1 Detailed	Description		 	 	. 166
	Function Documentation .				
10.42.2.1	Lock		 	 	. 167
10.42.2.2	Release		 	 	. 167
10.42.2.3	Reset		 	 	. 167
	ass Reference				
10.43.1 Detailed					
	Function Documentation .				
	ReleaseAll				
	ss Reference				
2.2.3.5.4.0.6		-			

CONTENTS ix

10.44.1 Detailed Description	70
10.44.2 Member Function Documentation	70
10.44.2.1 AllocOutputBuffer	70
10.44.2.2 AllocOutputBufferImage	71
10.44.2.3 AllocOutputBufferlpIImage	71
10.44.2.4 AllocOutputBufferMAPSImage	72
10.44.2.5 AllocOutputBufferMatrix	72
10.44.2.6 IOEltSizeBytes	72
10.44.2.7 Name	73
10.44.2.8 SetTypeName	73
10.44.2.9 SetTypeUnit	73
10.44.2.10 SetUnit	73
10.44.2.11 TypeName	73
10.45MAPSPair < TKey, TContent > Class Template Reference	74
10.45.1 Detailed Description	74
10.46MAPSProperty Class Reference	74
10.46.1 Detailed Description	77
10.46.2 Member Function Documentation	77
10.46.2.1 AcknowledgePropertyChanged	77
10.46.2.2 Get	77
10.46.2.3 Get	77
10.46.2.4 GetPropertyChangedEvent	78
10.46.2.5 Name	78
10.46.2.6 PropertyChanged	78
10.46.2.7 PropertyChangedEvent	78
10.46.2.8 Set	78
10.46.2.9 Set	78
10.46.2.10 ShortName	78
10.47MAPSPtrHashTable < TContent > Class Template Reference 1	79
10.47.1 Detailed Description	79
10.48MAPSRBRegion Class Reference	79
10.48.1 Detailed Description	83
10.48.2 Member Function Documentation	83
10.48.2.1 BesideRegion	83
10.48.2.2 Crop	84
10.48.2.3 Dilate	84
10.48.2.4 DuplicateToRB2	84
10.48.2.5 DuplicateToRB3	85
10.48.2.6 Erode	
10.48.2.7 Init	85
10.48.2.8 InverseRegion	85
10.48.2.9 operator[]	86
10.48.2.10 Pop	86
10.48.2.11 Popback	86
10.48.2.12 Push	87
10.48.2.13 SubRegion	87
10.49MAPSRealObject Struct Reference	87
10.49.1 Detailed Description	89
10.50MAPSRealObjectVariant Struct Reference	89
10.50.1 Detailed Description	89

x CONTENTS

10.51MAPSRecordingStateListener Class Reference	. 190
10.51.1 Detailed Description	
10.51.2 Member Function Documentation	. 190
10.51.2.1 CallbackRecordingStateChanged	. 190
10.52MAPSRecordReplayMethod Class Reference	. 19
10.52.1 Detailed Description	. 194
10.52.2 Member Function Documentation	. 194
10.52.2.1 Error	. 194
10.52.2.2 HeadingHint	. 195
10.53MAPSRectangle Struct Reference	. 195
10.53.1 Detailed Description	. 195
10.54MAPSRunnable < T > Class Template Reference	. 196
10.54.1 Detailed Description	
10.55MAPSRunShutdownListener Class Reference	
10.55.1 Detailed Description	
10.55.2 Member Function Documentation	
10.55.2.1 CallbackRun	
10.55.2.2 CallbackShutdown	
10.56MAPSSign Struct Reference	
10.56.1 Detailed Description	
10.57MAPSSpot Struct Reference	
10.57.1 Detailed Description	
10.58MAPSStackedString< BUFFER_SIZE > Class Template Reference	
10.58.1 Detailed Description	
10.58.2 Member Function Documentation	
10.58.2.1 Find	
10.58.2.2 Find	
10.58.2.3 Left	
10.58.2.4 Mid	
10.58.2.5 operator()	
10.58.2.6 Part	
10.58.2.7 Right	
10.58.2.8 Shorten	
10.58.2.9 Token	
10.58.2.10 Up2	
10.58.2.11 UpTo	
10.58.3 Friends And Related Function Documentation	
10.58.3.1 operator <<	
10.59MAPSStream8IOComponent Class Reference	
10.59.1 Detailed Description	
10.60MAPSStreamedString Class Reference	
10.60.1 Detailed Description	
10.61MAPSStringHashTable < TContent > Class Template Reference	
10.61.1 Detailed Description	
10.62MAPSSynchronizer Class Reference	
10.62.1 Detailed Description	
10.62.2 Member Function Documentation	
10.62.2.1 SignalSynchronizationCommand	
10.63MAPSText Struct Reference	
10.63.1 Detailed Description	. 212

CONTENTS xi

	10.64MAPSTimer Class Reference	
	10.64.1 Detailed Description	
	10.65MAPSTimeStateListener Class Reference	
	10.65.1 Detailed Description	
	10.65.2 Member Function Documentation	
	10.65.2.1 CallbackTimeJumped	
	10.65.2.2 CallbackTimePaused	
	10.65.2.3 CallbackTimeSpeedChanged	
	10.66MAPSTree Struct Reference	
	10.66.1 Detailed Description	
	10.67MAPSTriangles3D Struct Reference	
	10.67.1 Detailed Description	. 217
	10.68MAPSTypeFilter Class Reference	. 217
	10.68.1 Detailed Description	. 217
	10.69MAPSTypeFilterBase Struct Reference	. 217
	10.69.1 Detailed Description	
	10.69.2 Member Data Documentation	
	10.69.2.1 nameFilter	
	10.69.2.2 unitFilter	. 219
	10.70MAPSTypeInfo Struct Reference	
	10.70.1 Detailed Description	
	10.70.2 Member Function Documentation	
	10.70.2.1 SetName	
	10.70.2.2 SetUnit	
	10.70.3 Member Data Documentation	
	10.70.3.1 name	
	10.70.3.2 unit	
	10.71MAPSVehicle Struct Reference	
	10.71.1 Detailed Description	
	10.72MAPSWin32 Class Reference	
	10.72.1 Detailed Description	
	10.73MAPSTriangles3D::Object Struct Reference	
	10.73.1 Detailed Description	
	10.74MAPSTriangles3D::Point Struct Reference	
	10.74.1 Detailed Description	
	10.75MAPSTriangles3D::Triangle Struct Reference	
	10.75.1 Detailed Description	. 226
11	File Documentation	227
	11.1 maps.hpp File Reference	
	11.1.1 Detailed Description	
	11.1.2 Define Documentation	
	11.1.2.1 MAPS_PACKAGE_DEFINITION	
	11.1.2.2 MAPS_PI	
	11.1.3 Typedef Documentation	
	11.1.3.1 MAPS3States	_
	11.1.3.2 MAPSTimestaria	_
	11.1.3.3 MAPSTimestamp	
	11.2 MAPSImageProcessing1Src1Dest.h File Reference	. 254

xii CONTENTS

	11.2.1	Detailed I	Description				 			. 2	255
11.3	MAPSI	mageProc	essing2Src1	Dest.h File	Referen	nce	 			. 2	255
	11.3.1	Detailed I	Description				 			. 2	255
11.4	MAPSF	RBRegion.	h File Refere	ence			 			. 2	255
	11.4.1	Detailed I	Description				 			. 2	256
	11.4.2	Enumera	tion Type Do	cumentatio	on		 			. 2	256
		11.4.2.1	MAPSConst	RBRegionB	esideReg	jion	 			. 2	256
		11.4.2.2	MAPSConsti	RBRegionC	rop		 			. 2	256
		11.4.2.3	MAPSConsti	RBRegionD	ilation .		 			. 2	257
		11.4.2.4	MAPSConsti	RBRegionE	rosion .		 			. 2	257
		11.4.2.5	MAPSConsti	RBRegionSt	tate		 			. 2	257
		11.4.2.6	MAPSConsti	RBRegionS	ubRegion	١	 			. 2	257
11.5	MAPSS	SoundProc	essingComp	onent.h Fi	le Refere	ence				. 2	258
	11.5.1	Detailed I	Description				 			. 2	258
11.6	MAPSS	Stream8IO	Component.	h File Refe	rence.		 			. 2	258
	11.6.1	Detailed I	Description				 			. 2	258

### Main Page

#### 1.1 How to use this documentation

This documentation is the reference of the RTMaps SDK. Various entries are available, depending on what your are looking for, and what you know.

- You know the name of the class: the menus "Class Hierarchy", "Alphabetical List" and "Class List" give a direct access to the documentation of a class.
- You know the name of the function, define, typedef...: under "Class Members" you
  can find the documentation of a member of a class, while "File Members" offers
  a list of all the other documented items, for example C-style functions, defines or
  typedefs.
- Under "Related Pages" is the "Deprecated List". It lists all deprecated features that will be removed in the next version.
- An important section, especially for beginners, is called "Modules".

This is only a reference documentation. Don't forget to read the Developer's manual!

2 Main Page

# **Deprecated List**

**Member MAPS::AbsoluteTime2Integer(MAPSAbsoluteTime &time)** Transforms an absolute time to an integer, for absolute time comparison

Member MAPS::Integer2AbsoluteTime(MAPSInt64 integer, MAPSAbsoluteTime &time) Transforms an integer to an absolute time

4 Deprecated List

## **Module Index**

### 3.1 Modules

Horo	ic a	liet	of all	modules	
пеге	is a	IISL	ui aii	IIIOdules	٠.

Basic data structures	9
Component design	30
Input definition macros	23
Output definition macros	24
Property definition macros	26
Action definition macros	29
Record/replay method design	36
Property definition macros	26
Action definition macros	29

6 Module Index

# Namespace Index

4.1	Namespa	ice List
-----	---------	----------

lere is a list of all documented namespaces	s with brief descriptions:	
MAPS (The main RTMaps namespace )		4

8 Namespace Index

## **Class Index**

### 5.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

IpIImage
IpIROI
MAPSAbsoluteTime
MAPSAction
$MAPSArray < T > \dots                                $
$\label{eq:maps} \mbox{MAPSArray} < \mbox{MAPSList} < \mbox{MAPSPair} < \mbox{int, TContent} > > \ \ . \ \ . \ \ . \ \ . \ \ \ . \ \ \ \ \ \ \ \ \ \ \ . \ \ \ \ \ . \ \ . \ \ . \$
$\label{eq:maps} \mbox{MAPSArray} < \mbox{MAPSList} < \mbox{MAPSPair} < \mbox{MAPSString}, \mbox{TContent} >>> \ . \ . \ . \ . \ 70$
$\label{eq:maps} \mbox{MAPSArray} < \mbox{MAPSList} < \mbox{MAPSPair} < \mbox{void} \ *, \mbox{TContent} >>> . \ . \ . \ . \ . \ . \ . \ . \ . \$
MAPSBaseClock
MAPSBasicList
MAPSList < T >
MAPSList < MAPSPair < int, TContent >>
MAPSList < MAPSPair < MAPSString, TContent >>
MAPSList< MAPSPair< void *, TContent >>
MAPSBasicListItem
MAPSListItem < T >
MAPSCANFrame
MAPSComplex
$MAPSCouple < T > \dots $
MAPSDrawingObject
MAPSDrawingObjectVariant
MAPSCircle
MAPSEllipse
MAPSLine
MAPSRectangle
MAPSSpot
MAPSText
MAPSEnumStruct 94

10 Class Index

MAPSEvent		95
MAPSFileIO		99
MAPSRecordReplayMethod		191
MAPSFileReadHandle		105
MAPSFileWriteHandle		
MAPSHashTable < TKey, TContent, H >		
MAPSHashTable< int, TContent, MAPSIntegerHashFunction >		
MAPSIntegerHashTable < TContent >		
MAPSHashTable < MAPSString, TContent, MAPSStringHashFunction >		
MAPSStringHashTable < TContent >		
MAPSHashTable < void *, TContent, MAPSPtrHashFunction >		106
MAPSPtrHashTable < TContent >		179
MAPSHashTableIterator		110
MAPSImage		
MAPSImageProcessing1Src1DestDefinition		
MAPSImageProcessing1Src1DestParams		
MAPSImageProcessing2Src1DestDefinition		
MAPSImageProcessing2Src1DestParams		
MAPSInput		
MAPSIOEIt		
MAPSList< T >::MAPSIterator		
MAPSListIterator		
MAPSMatrix		
MAPSMatrix2< T >		
MAPSModule		
MAPSComponent		
MAPSImageProcessing1Src1Dest		
MAPSImageProcessing2Src1Dest		
MAPSStream8IOComponent		
MAPSRecordReplayMethod		
MAPSMutex		
MAPSMutex2		
MAPSOutput		168
MAPSPair < TKey, TContent >		174
MAPSProperty		174
MAPSRBRegion		179
MAPSRealObject		187
MAPSRealObjectVariant		189
MAPSSign		197
MAPSTree		
MAPSVehicle		221
MAPSRecordingStateListener		190
MAPSRunnable < T >		
MAPSRunShutdownListener		
MAPSStackedString< BUFFER_SIZE >		
MAPSStreamedString		
MAPSSynchronizer		

MAPSTimer
MAPSTimeStateListener
MAPSTriangles3D
MAPSTypeFilterBase
MAPSTypeFilter
MAPSTypeInfo
MAPSWin32
MAPSTriangles3D::Object
MAPSTriangles3D::Point
MAPSTriangles3D::Triangle

12 Class Index

## **Class Index**

### 6.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

IplImage (The famous IplImage structure, today's standard structure for image
processing )
IpIROI (The IPL Region Of Interest structure )
MAPSAbsoluteTime (Absolute time structure ) 69
MAPSAction (The RTMaps Module Action class )
$MAPSArray < T > (The RTMaps array class) \dots 70$
MAPSBaseClock (MAPSBaseClock class )
MAPSBasicList (The base class for the MAPSList template class ) 78
MAPSBasicListItem (The basic list item class )
MAPSCANFrame (CAN Frames structure )
MAPSCircle (The MAPSCircle structure )
MAPSComplex (Complex number structure )
MAPSComponent (The base class for all RTMaps components ) 83
$\label{eq:mapscouple} \mbox{MAPSCouple} < T > \mbox{(Template class for couple data )}  .  .  .  .  .  .  .  .  90$
MAPSDrawingObject (The MAPSDrawingObject : a standard for simple over-
lay shapes )
MAPSDrawingObjectVariant (All drawing objects in RTMaps (circles, etc.) in-
herit from MAPSDrawingObjectVariant )
MAPSEllipse (The MAPSEllipse structure )
MAPSEnumStruct (Enumeration structure )
MAPSEvent (The RTMaps event class )
MAPSFileIO (The RTMaps File I/O support class )
MAPSFileReadHandle (The class that is used to manage all RTMaps read file
operations )
MAPSFileWriteHandle (The class that is used to manage all RTMaps write file
operations )
$MAPSHashTable < TKey, TContent, H > \dots \dots$
MAPSHashTableIterator (The RTMaps hash table iterator )
MAPSImage (The RTMaps Image type)

14 Class Index

MAPSImageProcessing1Src1Dest (Image Processing component base class	
with 1 input and 1 output images )	112
MAPSImageProcessing1Src1DestDefinition (Definition structure for an image	
processing algorithm (1 Src 1 Dest operation) )	112
MAPSImageProcessing1Src1DestParams (Parameter structure for an image	
processing algorithm (1 Src 1 Dest operation))	113
MAPSImageProcessing2Src1Dest (Image Processing component base class	
with 2 input and 1 output images )	11/
MAPSImageProcessing2Src1DestDefinition (Definition structure for an image	114
- · · · · · · · · · · · · · · · · · · ·	444
processing algorithm (2 Src 1 Dest operation))	114
MAPSImageProcessing2Src1DestParams (Parameter structure for an image	
processing algorithm (2 Src 1 Dest operation) )	
MAPSInput (The RTMaps Module Input class)	116
MAPSIntegerHashTable < TContent > (The RTMaps integer hash table tem-	
plate class)	
MAPSIOEIt (The RTMaps I/O Buffer Element )	
$\label{eq:MAPSList} \begin{split} \text{MAPSList} < T > &:: \text{MAPSIterator (Iterator on MAPSList objects )}  \dots  .  .  . \end{split}$	
MAPSLine (The MAPSLine structure )	
	129
MAPSListItem < T > (The list item template class)	135
MAPSListIterator (The list iterator class )	136
MAPSMatrix (MATLAB-Like matrix (Complex and columnwise, like in fortran))	137
MAPSMatrix2 < T > (The RTMaps MAPSMatrix2 class, a powerful matrix	
management class )	139
MAPSModule (The base class for all RTMaps modules )	
MAPSMutex (The RTMaps mutex class )	
MAPSMutex2 (The RTMaps advanced mutex class )	
MAPSOutput (The RTMaps Module Output class)	
MAPSPair< TKey, TContent > (The RTMaps (key,content) pair template class)	
MAPSProperty (The RTMaps Module Property class)	
MAPSPtrHashTable < TContent > (The RTMaps pointer hash table template	.,
class)	170
MAPSRBRegion (MAPSRBRegion class: Ring-Buffer region manipulation	173
- · · · · · · · · · · · · · · · · · · ·	170
class)	
MAPSRealObject (The standard structure to transmit info about real objects).	10/
MAPSRealObjectVariant (All real objects in RTMaps (vehicles, etc.) inherit	400
from this structure )	
MAPSRecordingStateListener (The MAPSRecordingStateListener interface ) .	
MAPSRecordReplayMethod (The base class for all record/replay methods)	
MAPSRectangle (The MAPSRectangle structure )	
MAPSRunShutdownListener (The MAPSRunShutdownListener interface )	
MAPSSign (The MAPSSign structure: a kind of MAPSRealObject)	
MAPSSpot (The MAPSSpot structure)	199
MAPSStackedString< BUFFER_SIZE > (The RTMaps flexible and fast string	
template class)	200
MAPSStream8IOComponent (Processing component template with 1 Stream8	
input and 1 Stream8 output )	208
MAPSStreamedString (The RTMaps streamed string class)	
MAPSStringHashTable < TContent > (The RTMaps string hash table class)	
, , , , , , , , , , , , , , , , , , , ,	

6.1 Class List

MAPSSynchronizer (The RTMaps Synchroniser tool )
MAPSText (The MAPSText structure )
MAPSTimer (For managing timers )
MAPSTimeStateListener (The MAPSTimeStateListener interface) 213
MAPSTree (The MAPSTree structure: a kind of MAPSRealObject) 215
MAPSTriangles3D (The RTMaps structure for supporting 3D triangles output) 216
MAPSTypeFilter (The RTMaps type filter class)
MAPSTypeFilterBase (The RTMaps type filter structure)
MAPSTypeInfo (The RTMaps type information structure)
MAPSVehicle (The MAPSVehicle structure: a kind of MAPSRealObject) 221
MAPSWin32 (The RTMaps Win32 support class)
MAPSTriangles3D::Object (The object structure )
MAPSTriangles3D::Point (The 3D point structure )
MAPSTriangles3D::Triangle (The triangle structure itself)

16 Class Index

## File Index

### 7.1 File List

Here is a list of all documente	d files with l	orief descriptio	ns:		
maps.hpp (The RTMaps e MAPSImageProcessing1S	Src1Dest.h	The MAPSIma	ageProce	ssing1Sro	1Dest
component mode	-				
MAPSImageProcessing2S component mode		•	•	_	
MAPSRBRegion.h (The R		•			• •
)					
MAPSSoundProcessingCo	•	•		•	•
component	model	Format	of	Ю	element:
<ul> <li>Frequency() holds free</li> </ul>	equency info	o (!!! in mHz !!!	!)		
Misc1() holds the null	mber of cha	nnels			
<ul> <li>Misc2() holds the bits</li> </ul>	s info				
)					
model )	,				258

18 File Index

### **Module Documentation**

#### 8.1 Basic data structures

#### **Classes**

- class MAPSCouple < T >
   Template class for couple data.
- class MAPSBasicListItem

The basic list item class.

• class MAPSListIterator

The list iterator class.

• class MAPSListItem< T >

The list item template class.

class MAPSBasicList

The base class for the MAPSList template class.

• class MAPSList< T >

The RTMaps double linked list template class.

- class MAPSList < T >::MAPSIterator
   Iterator on MAPSList objects.
- class MAPSStackedString
   BUFFER\_SIZE >
   The RTMaps flexible and fast string template class.
- class MAPSStreamedString

The RTMaps streamed string class.

20 Module Documentation

class MAPSArray

The RTMaps array class.

class MAPSPair< TKey, TContent >

The RTMaps (key,content) pair template class.

· class MAPSHashTableIterator

The RTMaps hash table iterator.

- class MAPSHashTable < TKey, TContent, H >
- class MAPSStringHashTable < TContent >

The RTMaps string hash table class.

 $\bullet \ \, {\it class MAPSIntegerHashTable} {\it < TContent} >$ 

The RTMaps integer hash table template class.

class MAPSPtrHashTable < TContent >

The RTMaps pointer hash table template class.

#### **Defines**

- #define MAPSForallItems(it, L)
- #define MAPSForall(x, L)
- #define MAPSForallPtr(x, L)

#### **Typedefs**

• typedef MAPSStackedString< 40 > MAPSString

The RTMaps flexible and fast string class.

#### **Functions**

template<typename T >
 MAPSMatrix2< T > MAPSMatrix2::operator\* (const MAPSMatrix2< T > &A,
 const MAPSMatrix2< T > &B)

MAPSMatrix2 multiplication operator.

template<typename T >
 MAPSMatrix2< T > MAPSMatrix2::operator+ (const MAPSMatrix2< T > &A,
 const MAPSMatrix2< T > &B)

MAPSMatrix2 addition operator.

8.1 Basic data structures 21

template<typename T >
 MAPSMatrix2< T > MAPSMatrix2::operator- (const MAPSMatrix2< T > &A,
 const MAPSMatrix2< T > &B)

MAPSMatrix2 substraction operator.

template<typename T >
 MAPSArray< T > MAPSArray::operator\* (const MAPSMatrix2< T > &A, const
 MAPSArray< T > &b)

Multiplication of a MAPSMatrix2 with a MAPSArray.

template<typename T >
 MAPSMatrix2<</li>
 T > MAPSMatrix2::operator\* (const MAPSMatrix2<</li>
 T > &A, const T &b)

Multiplication of a MAPSMatrix2 with a scalar.

template<typename T >
 MAPSMatrix2< T > MAPSMatrix2::operator/ (const MAPSMatrix2< T > &A, const T &b)

Division of a MAPSMatrix2 by a scalar.

• template<typename T >  $\frac{\text{MAPSArray}}{\text{MAPSArray}} < \text{T} > \frac{\text{MAPSArray}}{\text{MAPSArray}} < \text{T} > \text{\&a, const}$   $\frac{\text{MAPSArray}}{\text{MAPSArray}} < \text{T} > \text{\&b})$ 

MAPSArrays addition.

template<typename T >
 MAPSArray< T > MAPSArray::operator- (const MAPSArray< T > &a, const MAPSArray< T > &b)

MAPSArrays substraction.

template<typename T >
 MAPSArray< T > MAPSArray::operator+ (const MAPSMatrix2< T > &a, const
 MAPSArray< T > &b)

Addition of a MAPSMatrix2 with a MAPSArray.

#### 8.1.1 Detailed Description

The following classes are the basis for all the data structures used by the RTMaps Engine. They are generally simpler but similar to their STL counterparts. These classes are available to developers using the RTMaps SDK to ensure portable code as they have been especially designed to be fully cross-platform.

22 Module Documentation

#### 8.1.2 Define Documentation

#### 8.1.2.1 #define MAPSForall( x, L)

Helper macro to walk through a MAPSList with an access to the list elements.

```
MAPSList<MAPSString> li;
// ... populate li ...
// Displays li elements:
MAPSString x;
MAPSForall(x,li) {
    std::cout << x << std::endl;
}</pre>
```

#### **Parameters**

X	a T object
L	a MAPSList <t></t>

#### 8.1.2.2 #define MAPSForallItems( it, L)

Helper macro to walk through a MAPSBasicList. Typical use is like:

```
MAPSList<MAPSString> li;
// ... populate the list ...
MAPSListIterator iter;
// Walk through the list:
MAPSForallItems(iter, li) {
    std::cout << li[iter] << std::endl;</pre>
```

#### **Parameters**

it	a MAPSListIterator
L	a MAPSBasicList

### 8.1.2.3 #define MAPSForallPtr( x, L)

Helper macro to walk through a MAPSList with an access to a pointer to the list elements.

```
MAPSList<MAPSString> li;
// ... populate li ...
// Displays li elements:
MAPSString* x;
MAPSForallPtr(x,li) {
    std::cout << (*x) << std::endl;
}</pre>
```

#### **Parameters**

X	a T* object
L	a MAPSList <t></t>

### 8.1.3 Typedef Documentation

### 8.1.3.1 MAPSStackedString < 40 > MAPSString

The RTMaps flexible and fast string class.

### See also

MAPSStreamedString

### 8.1.4 Function Documentation

8.1.4.1 template<typename T > MAPSArray< T > operator+ ( const MAPSMatrix2< T > & a, const MAPSArray< T > & b) [related, inherited]

Addition of a MAPSMatrix2 with a MAPSArray.

The result is a MAPSArray. Only the first column of the matrix a is added to the array b.

# 8.2 Input definition macros

### **Defines**

- #define MAPS\_BEGIN\_INPUTS\_DEFINITION(className)
   Starts the definition of the inputs of a module.
- #define MAPS\_INPUT(namex, filter, typex)
   Basic definition of an input.
- #define MAPS\_END\_INPUTS\_DEFINITION
   Ends the definition of the inputs of a module.

### 8.2.1 Define Documentation

### 8.2.1.1 #define MAPS\_BEGIN\_INPUTS\_DEFINITION( className )

Starts the definition of the inputs of a module.

### **Parameters**

className The module class name

### 8.2.1.2 #define MAPS\_INPUT( namex, filter, typex )

Basic definition of an input.

### **Parameters**

namex	a sin	ple string	used to	o furt	her ide	entify the	input (e	e.g. "input")
filter	the k	ind of exp	ected d	ata, a	MAP	STypeFil	terBase	(e.g. MAPS::FilterInteger)
typex	the	reader	type	of	the	input	(e.g.	MAPS::FifoReader,
	MAP	S::Sampli	ngRead	der)				

# 8.3 Output definition macros

### **Defines**

- #define MAPS\_BEGIN\_OUTPUTS\_DEFINITION(className)

  Starts the definition of the outputs of a module.
- #define MAPS\_OUTPUT(name, value, namex, unit, size)
   Basic definition of an output.
- #define MAPS\_OUTPUT\_FIFOSIZE(name, value, namex, unit, size, fifosize)
   Definition of an output with control of the FIFO size.
- #define MAPS\_OUTPUT\_USER\_STRUCTURE(name, structureName)

  Definition of an output using a user structure.
- #define MAPS\_END\_OUTPUTS\_DEFINITION
   Ends the definition of the outputs of a module.

### 8.3.1 Define Documentation

### 8.3.1.1 #define MAPS\_BEGIN\_OUTPUTS\_DEFINITION( className )

Starts the definition of the outputs of a module.

### **Parameters**

className T	The module class name
-------------	-----------------------

### 8.3.1.2 #define MAPS\_OUTPUT( name, value, namex, unit, size )

Basic definition of an output.

name	a simple string used to further identify the output (e.g. "output")
value	the type of the output data, a MAPSTypeInfoValue (e.g. MAPS::Integer)
namex	An optional name associated to the output data type. Can be ${\tt NULL}$ .
unit	A string describing the unit of the output data (e.g. "m/s"). Can be NULL.
size	The size of the output. Use 1 for a single piece of data, 0 if you do not know the data size yet, but do not forget to allocate the output later. MAPSOutput::AllocOutputBuffer documentation gives more details about output buffer allocation.

# 8.3.1.3 #define MAPS\_OUTPUT\_FIFOSIZE( name, value, namex, unit, size, fifosize )

Definition of an output with control of the FIFO size.

Basic definition of an output.

### **Parameters**

name	a simple string used to further identify the output (e.g. "output")
value	the type of the output data, a MAPSTypeInfoValue (e.g. MAPS::Integer)
namex	An optional name associated to the output data type. Can be $\mathtt{NULL}$ .
unit	A string describing the unit of the output data (e.g. "m/s"). Can be NULL.
size	The size of the output. Use 1 for a single piece of data, 0 if you do not know
	the data size yet, but do not forget to allocate the output later. MAPSOut-
	put::AllocOutputBuffer documentation gives more details about output buffer
	allocation.

### **Parameters**

fifosize	size of the FIFO (default size of the output FIFO is 16)

# 8.3.1.4 #define MAPS\_OUTPUT\_USER\_STRUCTURE( name, structureName )

Definition of an output using a user structure.

If you need to transmit your own data structure between RTMaps components, you can define your own structure. It is the goal of this macro.

I	name	a simple string used to further identify the output (e.g. "output")		
struc	cture-	the class name of your own structure		
^	Name			

# 8.4 Property definition macros

### **Defines**

• #define MAPS BEGIN PROPERTIES DEFINITION(className)

Starts the definition of the properties of a module.

#define MAPS\_PROPERTY(name, value, needs2BeInitialized, canBeChangedAfterInstantiation)

Basic definition of a property.

 #define MAPS\_PROPERTY\_UNIT(name, value, unit, needs2BeInitialized, can-BeChangedAfterInstantiation)

Basic definition of a property.

 #define MAPS\_PROPERTY\_ENUM(name, enumstr, selected, needs2BeInitialized, canBeChangedAfterInstantiation)

Basic definition of a property.

 #define MAPS\_PROPERTY\_ENUM\_UNIT(name, enumstr, selected, unit, needs2BeInitialized, canBeChangedAfterInstantiation)

Basic definition of a property.

• #define MAPS\_PROPERTY\_READ\_ONLY(name, value)

Definition of a read-only property.

• #define MAPS\_PROPERTY\_READ\_ONLY\_UNIT(name, value, unit)

Definition of a read-only property with a specified unit.

#define MAPS\_END\_PROPERTIES\_DEFINITION

Ends the definition of the properties of a module.

### 8.4.1 Define Documentation

### 8.4.1.1 #define MAPS\_BEGIN\_PROPERTIES\_DEFINITION( className )

Starts the definition of the properties of a module.

className	The module class name
-----------	-----------------------

# 8.4.1.2 #define MAPS\_PROPERTY( name, value, needs2BeInitialized, canBeChangedAfterInstantiation )

Basic definition of a property.

### **Parameters**

name	a simple string used to further identify the output (e.g. "property")
value	the initial value of the property. Its type is automatically deduced from this
	value. Use (char*) NULL to initialize an empty string.
	when set to true, the property must be initialized before run
needs2BeIniti	
can-	when set to false, the property cannot be changed while RTMaps is running
BeChangedA	
terInstantia-	
tion	

# 8.4.1.3 #define MAPS\_PROPERTY\_ENUM( name, enumstr, selected, needs2BeInitialized, canBeChangedAfterInstantiation )

Basic definition of a property.

### **Parameters**

name	a simple string used to further identify the output (e.g. "property")
enumstr	a string of enumeration values, e.g. "value0 value1 value2"
selected	the initial selected index (starting from 0)1 means not yet selected.
	when set to true, the property must be initialized before run
needs2BeIniti	
can-	when set to false, the property cannot be changed while RTMaps is running
BeChangedA	
terInstantia-	
tion	

# 8.4.1.4 #define MAPS\_PROPERTY\_ENUM\_UNIT( name, enumstr, selected, unit, needs2BeInitialized, canBeChangedAfterInstantiation )

Basic definition of a property.

Basic definition of a property.

name	a simple string used to further identify the output (e.g. "property")
enumstr	a string of enumeration values, e.g. "value0 value1 value2"
selected	the initial selected index (starting from 0)1 means not yet selected.
	when set to true, the property must be initialized before run
needs2BeIniti	

can-	when set to false, the property cannot be changed while RTMaps is running
BeChangedA	
terInstantia-	
tion	

unit	a simple string used for display only

### 8.4.1.5 #define MAPS\_PROPERTY\_READ\_ONLY( name, value )

Definition of a read-only property.

### **Parameters**

name	a simple string used to further identify the output (e.g. "property")
value	the initial value of the property. Its type is automatically deduced from this
	value. Use (char*) NULL to initialize an empty string.

# 8.4.1.6 #define MAPS\_PROPERTY\_READ\_ONLY\_UNIT( name, value, unit )

Definition of a read-only property with a specified unit.

Definition of a read-only property.

# **Parameters**

name	a simple string used to further identify the output (e.g. "property")
value	the initial value of the property. Its type is automatically deduced from this
	value. Use (char*) NULL to initialize an empty string.

### **Parameters**

unit	a simple string used for display only

# 8.4.1.7 #define MAPS\_PROPERTY\_UNIT( name, value, unit, needs2BeInitialized, canBeChangedAfterInstantiation )

Basic definition of a property.

Basic definition of a property.

name	a simple string used to further identify the output (e.g. "property")
value	the initial value of the property. Its type is automatically deduced from this
	value. Use (char*) NULL to initialize an empty string.

	when set to true, the property must be initialized before run			
needs2BeIniti				
can-	when set to false, the property cannot be changed while RTMaps is running			
BeChangedA				
terInstantia-				
tion				

unit	a simple string used for display only
urni	a simple string used for display only

# 8.5 Action definition macros

### **Defines**

• #define MAPS\_BEGIN\_ACTIONS\_DEFINITION(className)

Starts the definition of the actions of a module.

• #define MAPS\_ACTION(name, proc)

Basic definition of an action.

• #define MAPS\_ACTION2(name, proc, allowedWhenDead)

Second definition of an action.

• #define MAPS END ACTIONS DEFINITION

Ends the definition of the actions of a module.

### 8.5.1 Define Documentation

# 8.5.1.1 #define MAPS\_ACTION( name, proc )

Basic definition of an action.

This action definition is for use only while RTMaps is running.

### **Parameters**

name	a sir	nple string	used to fu	urthe	er identify	the ou	tput (	e.g. "act	ion"	)	
proc	the	callback	function	to	launch	when	the	action	is	called	(e.g.
	МуМ	<pre>fodule::</pre>	anActi	on)							

# 8.5.1.2 #define MAPS\_BEGIN\_ACTIONS\_DEFINITION( className )

Starts the definition of the actions of a module.

className The module class name

# 8.6 Component design

### Classes

• class MAPSOutput

The RTMaps Module Output class.

• class MAPSInput

The RTMaps Module Input class.

class MAPSProperty

The RTMaps Module Property class.

• class MAPSAction

The RTMaps Module Action class.

• class MAPSRunShutdownListener

The MAPSRunShutdownListener interface.

• class MAPSTimeStateListener

The MAPSTimeStateListener interface.

• class MAPSRecordingStateListener

The MAPSRecordingStateListener interface.

• class MAPSSynchronizer

The RTMaps Synchroniser tool.

class MAPSModule

The base class for all RTMaps modules.

• class MAPSComponent

The base class for all RTMaps components.

### **Modules**

- · Input definition macros
- · Output definition macros
- · Property definition macros
- · Action definition macros

### **Component definition macros**

#define MAPS\_COMPONENT\_DEFINITION(component, name, version, priority, kind, defaultBehaviour, nbOfInputs, nbOfOutputs, nbOfProperties, nbOfActions)

One of the standard macros required for the definition of an RTMaps component.

 #define MAPS\_COMPONENT\_DEFINITION\_DOC(component, name, version, priority, kind, defaultBehaviour, nbOfInputs, nbOfOutputs, nbOfProperties, nbOfActions, doc)

One of the standard macros required for the definition of an RTMaps component.

 #define MAPS\_COMPONENT\_DEFINITION\_UNIQUE(component, name, version, priority, kind, defaultBehaviour, nbOfInputs, nbOfOutputs, nbOfProperties, nbOfActions)

One of the standard macros required for the definition of an RTMaps component.

 #define MAPS\_COMPONENT\_DEFINITION\_REGISTRATION(component, name, version, priority, kind, defaultBehaviour, nbOfInputs, nbOfOutputs, nbOfProperties, nbOfActions)

One of the standard macros required for the definition of an RTMaps component.

### Component class declaration macros

- #define MAPS\_COMPONENT\_STANDARD\_HEADER\_CODE(component)
- #define MAPS CLOCK COMPONENT HEADER CODE(component)
- #define MAPS COMPONENT DYNAMIC HEADER CODE(component)
- #define MAPS\_COMPONENT\_HEADER\_CODE\_WITHOUT\_CONSTRUCTOR(component)
- #define MAPS COMPONENT REGISTERING HEADER CODE(component)
- #define MAPS\_CHILD\_COMPONENT\_HEADER\_CODE(component, parent)

Include this macro inside your component class definition if its parent is a descendant of MAPSComponent.

#define MAPS\_CHILD\_COMPONENT\_HEADER\_CODE\_WITHOUT\_CONSTRUCTOR(component, parent)

Include this macro inside your component class definition if its parent is a descendant of MAPSComponent and you need to implement your own constructor.

• #define MAPS PARENT COMPONENT HEADER CODE(component, parent)

Include this macro inside a parent component class definition.

#define MAPS\_PARENT\_COMPONENT\_HEADER\_CODE\_WITHOUT\_CONSTRUCTOR(component, parent)

Include this macro inside a parent component class definition when you need to implement your own constructor.

32 Module Documentation

### 8.6.1 Define Documentation

### 8.6.1.1 #define MAPS\_CHILD\_COMPONENT\_HEADER\_CODE( component, parent )

Include this macro inside your component class definition if its parent is a descendant of MAPSComponent.

This macro replaces MAPS\_COMPONENT\_STANDARD\_HEADER\_CODE.

#### **Parameters**

component	The class name of the component
parent	The class name of the parent (e.g. MAPSStream8IOComponent)

# 

Include this macro inside your component class definition if its parent is a descendant of MAPSComponent and you need to implement your own constructor.

This macro replaces MAPS COMPONENT STANDARD HEADER CODE.

#### **Parameters**

component	The class name of the component
parent	The class name of the parent (e.g. MAPSStream8IOComponent)

# 8.6.1.3 #define MAPS\_CLOCK\_COMPONENT\_HEADER\_CODE( component )

One of the standard macros required for the definition of an RTMaps component class. This macro has to be placed in the class definition (usually in the header file).

### **Parameters**

component	The class name of the component

Include this macro inside your component class definition if your component implements an RTMaps clock. Your component must derive from MAPSBaseClock in this case.

# 8.6.1.4 #define MAPS\_COMPONENT\_DEFINITION( component, name, version, priority, kind, defaultBehaviour, nbOflnputs, nbOfOutputs, nbOfProperties, nbOfActions )

One of the standard macros required for the definition of an RTMaps component.

When building an RTMaps component, one of these macros must be used in the implementation file.

component the class component name	(e.g. MAPSMyComponent)
------------------------------------	------------------------

name	a string used to identify the component (e.g. "myComponent")
version	the version of the component; can be any string, but we recommand the use of a float number when possible (e.g. "2.3")
priority	the default component priority; must be an integer between 0 (lowest) and 255
kind	MAPS::Sequential for a sequential only component, MAPS::Threaded for a threaded only component, or a combination with a ' ' if both behaviours are allowed
defaultBe-	MAPS::Sequential or MAPS::Threaded; must be coherent with the kind pa-
haviour	rameter
nbOfInputs	an integer indicating the (minimum) number of inputs
nbOfOutputs	an integer indicating the (minimum) number of outputs
nbOfProper-	an integer indicating the (minimum) number of properties
ties	
nbOfActions	an integer indicating the (minimum) number of actions

# 8.6.1.5 #define MAPS\_COMPONENT\_DEFINITION\_DOC( component, name, version, priority, kind, defaultBehaviour, nbOfInputs, nbOfOutputs, nbOfProperties, nbOfActions, doc )

One of the standard macros required for the definition of an RTMaps component.

Allows to add a short documentation to the component definition. One of the standard macros required for the definition of an RTMaps component.

When building an RTMaps component, one of these macros must be used in the implementation file.

component	the class component name (e.g. MAPSMyComponent)
name	a string used to identify the component (e.g. "myComponent")
version	the version of the component; can be any string, but we recommand the use
	of a float number when possible (e.g. "2.3")
priority	the default component priority; must be an integer between 0 (lowest) and
	255
kind	MAPS::Sequential for a sequential only component, MAPS::Threaded for a
	threaded only component, or a combination with a ' ' if both behaviours are
	allowed
defaultBe-	MAPS::Sequential or MAPS::Threaded; must be coherent with the kind pa-
haviour	rameter
nbOfInputs	an integer indicating the (minimum) number of inputs
nbOfOutputs	an integer indicating the (minimum) number of outputs
nbOfProper-	an integer indicating the (minimum) number of properties
ties	
nbOfActions	an integer indicating the (minimum) number of actions

doc	a string describing the component

# 8.6.1.6 #define MAPS\_COMPONENT\_DEFINITION\_REGISTRATION( component, name, version, priority, kind, defaultBehaviour, nbOfInputs, nbOfOutputs, nbOfProperties, nbOfActions )

One of the standard macros required for the definition of an RTMaps component.

Use this macro when you need to perform special operations on component (un)registration. One of the standard macros required for the definition of an RTMaps component.

When building an RTMaps component, one of these macros must be used in the implementation file.

### **Parameters**

component	the class component name (e.g. MAPSMyComponent)
name	a string used to identify the component (e.g. "myComponent")
version	, , ,
	of a float number when possible (e.g. "2.3")
priority	the default component priority; must be an integer between 0 (lowest) and 255
kind	MAPS::Sequential for a sequential only component, MAPS::Threaded for a
	threaded only component, or a combination with a ' ' if both behaviours are
	allowed
defaultBe-	MAPS::Sequential or MAPS::Threaded; must be coherent with the <i>kind</i> pa-
haviour	rameter
nbOfInputs	an integer indicating the (minimum) number of inputs
nbOfOutputs	an integer indicating the (minimum) number of outputs
nbOfProper-	an integer indicating the (minimum) number of properties
ties	
nbOfActions	an integer indicating the (minimum) number of actions

### Warning

When using this macro, you must use MAPS\_COMPONENT\_REGISTERING\_-HEADER\_CODE too.

# 8.6.1.7 #define MAPS\_COMPONENT\_DEFINITION\_UNIQUE( component, name, version, priority, kind, defaultBehaviour, nbOfInputs, nbOfOutputs, nbOfProperties, nbOfActions )

One of the standard macros required for the definition of an RTMaps component.

Use this macro when the component can be instantiated only once. One of the standard macros required for the definition of an RTMaps component.

When building an RTMaps component, one of these macros must be used in the implementation file.

component	the class component name (e.g. MAPSMyComponent)
name	a string used to identify the component (e.g. "myComponent")
version	the version of the component; can be any string, but we recommand the use
	of a float number when possible (e.g. "2.3")
priority	the default component priority; must be an integer between 0 (lowest) and
	255
kind	MAPS::Sequential for a sequential only component, MAPS::Threaded for a
	threaded only component, or a combination with a ' ' if both behaviours are
	allowed
defaultBe-	MAPS::Sequential or MAPS::Threaded; must be coherent with the kind pa-
haviour	rameter
nbOfInputs	an integer indicating the (minimum) number of inputs
nbOfOutputs	an integer indicating the (minimum) number of outputs
nbOfProper-	an integer indicating the (minimum) number of properties
ties	
nbOfActions	an integer indicating the (minimum) number of actions

### Warning

When using this macro, you must use  ${\tt MAPS\_COMPONENT\_REGISTERING\_-HEADER\_CODE}$  too.

### 8.6.1.8 #define MAPS\_COMPONENT\_DYNAMIC\_HEADER\_CODE( component )

Include this macro inside your component class definition if you need to create/suppress inputs, outputs, properties or actions dynamically. Then you need to implement MAPSComponent::Dynamic.

### **Parameters**

component	The class name of the component

# 8.6.1.9 #define MAPS\_COMPONENT\_HEADER\_CODE\_WITHOUT\_CONSTRUCTOR( component )

Include this macro inside your component class definition if you need to implement your own constructor. This macro replaces MAPS\_COMPONENT\_STANDARD\_HEADER\_CODE. You need then to implement MAPSMyComponent::MAPSMyComponent (const char\* componentName, MAPSComponentDefinition& md):MAPSComponent(componentName, md)

component	The class name of the component

### 8.6.1.10 #define MAPS\_COMPONENT\_REGISTERING\_HEADER\_CODE( component )

Include this macro inside your component class definition if you need to perform special operations whe the component is (un)registered. You need then to implement <code>void</code> MAPSMyComponent::Register(void) and void MAPSMyComponent::Unregister(void), which are static functions.

### **Parameters**

component	The class name of the component

### 8.6.1.11 #define MAPS\_COMPONENT\_STANDARD\_HEADER\_CODE( component )

One of the standard macros required for the definition of an RTMaps component class. This macro has to be placed in the class definition (usually in the header file).

#### **Parameters**

component	The class name of the component
-----------	---------------------------------

### 8.6.1.12 #define MAPS\_PARENT\_COMPONENT\_HEADER\_CODE( component, parent )

Include this macro inside a parent component class definition.

### **Parameters**

component	The class name of the component
parent	The class name of the parent (usually MAPSComponent).

# 

Include this macro inside a parent component class definition when you need to implement your own constructor.

### **Parameters**

component	The class name of the component
parent	The class name of the parent (usually MAPSComponent).

# 8.7 Record/replay method design

### Classes

class MAPSOutput

The RTMaps Module Output class.

class MAPSInput

The RTMaps Module Input class.

class MAPSProperty

The RTMaps Module Property class.

class MAPSModule

The base class for all RTMaps modules.

class MAPSRecordReplayMethod

The base class for all record/replay methods.

### **Modules**

- Property definition macros
- · Action definition macros

### **Defines**

 #define MAPS\_RECORD\_REPLAY\_METHOD\_DEFINITION(rrm, namex, version, filter, recordThreaded, replayThreaded, nbPropertiesRecord, nbPropertiesReplay)

Required for the implementation of an RTMaps record/replay method.

#define MAPS\_RECORD\_REPLAY\_METHOD\_STANDARD\_HEADER\_CODE(rrm)

Include this macro inside your RRM class definition.

• #define MAPS\_RECORD\_REPLAY\_METHOD\_BLACKBOX\_HEADER\_CODE(rrm)

Include this macro inside your RRM class definition if you intend to implement blackbox features.

• #define MAPS\_RECORD\_REPLAY\_METHOD\_PROCESS\_HEADER\_CODE(rrm)

Include this macro inside your RRM class definition if you need preprocessing before recording.

• #define MAPS\_RECORD\_REPLAY\_METHOD\_COPY\_HEADER\_CODE(rrm)

Include this macro inside your RRM class definition if you intend to implement special copy features.

38 Module Documentation

#define MAPS\_RECORD\_REPLAY\_METHOD\_HEADING\_HINT\_HEADER\_CODE(rrm)

Include this macro inside your RRM class definition if you intend to implement hint header.

### 8.7.1 Define Documentation

# 8.7.1.1 #define MAPS\_RECORD\_REPLAY\_METHOD\_BLACKBOX\_HEADER\_CODE( rrm )

Include this macro inside your RRM class definition if you intend to implement blackbox features.

You need then to implement MAPSRecordReplayMethod::BlackboxSwith and MAPSRecordReplayMethod::BlackboxDump.

### **Parameters**

rrm	The class name of the RRM
-----	---------------------------

# 8.7.1.2 #define MAPS\_RECORD\_REPLAY\_METHOD\_COPY\_HEADER\_CODE( rrm )

Include this macro inside your RRM class definition if you intend to implement special copy features.

You need then to implement MAPSRecordReplayMethod::Copy.

### **Parameters**

rrm	The class name of the RRM

# 8.7.1.3 #define MAPS\_RECORD\_REPLAY\_METHOD\_DEFINITION( rrm, namex, version, filter, recordThreaded, replayThreaded, nbPropertiesRecord, nbPropertiesReplay )

Required for the implementation of an RTMaps record/replay method.

When building a MAPSRecordReplayMethod, this macro must be used in the cpp file.

rrm	the class RRM name (e.g. MAPSMyRRM)
namex	a string used to identify the RRM (e.g. "myRRM")
version	the version of the RRM; use a float number if possible (e.g. "2.3")
filter	a MAPSTypeFilterBase value
	a boolean to indicate whether the record method is threaded
recordThread	
re-	a boolean to indicate whether the replay method is threaded
playThreaded	
nbProper-	the number of propreties for the record method
tiesRecord	

nbProper-	the number of propreties for the replay method
tiesReplay	

### 8.7.1.4 #define MAPS\_RECORD\_REPLAY\_METHOD\_HEADING\_HINT\_HEADER\_CODE( rrm )

Include this macro inside your RRM class definition if you intend to implement hint header.

You need then to implement MAPSRecordReplayMethod::HeadingHint(MAPSIOEIt&).

### **Parameters**

rrm	The class name of the RRM

# 8.7.1.5 #define MAPS\_RECORD\_REPLAY\_METHOD\_PROCESS\_HEADER\_CODE( rrm )

Include this macro inside your RRM class definition if you need preprocessing before recording.

You need then to implement MAPSRecordReplayMethod::DoProcessBufferItem and MAPSRecordReplayMethod::ProcessBufferItem.

### **Parameters**

rrm	The class name of the RRM

### 8.7.1.6 #define MAPS\_RECORD\_REPLAY\_METHOD\_STANDARD\_HEADER\_CODE( rrm )

Include this macro inside your RRM class definition.

You need then to implement MAPSRecordReplayMethod::Store, MAPSRecordReplayMethod::Hint, MAPSRecordReplayMethod::Replay, MAPSRecordReplayMethod::BirthRecord, MAPSRecordReplayMethod::DeathRecord, MAPSRecordReplayMethod::BirthReplay and MAPSRecordReplayMethod::DeathReplay.



# **Chapter 9**

# **Namespace Documentation**

# 9.1 MAPS Namespace Reference

The main RTMaps namespace.

# **RTMaps Typing related constants**

- const MAPSTypeInfoValue NoMask
   No mask.
- const MAPSTypeInfoValue NoType
   No type.
- const MAPSTypeInfoValue AnyType
   Any type.
- const MAPSTypeInfoValue TypeMask
   Type mask.
- const MAPSTypeInfoValue Structure

  User defined structure.
- const MAPSTypeInfoValue Integer Integer (32 bits, signed)
- const MAPSTypeInfoValue Float

  MAPSFloat (double : 64 bits, double precision)
- const MAPSTypeInfoValue TextAscii
   Ascii characters (1 character = 8 bits).

const MAPSTypeInfoValue TextUnicode

Unicode characters (1 character = 16 bits)

const MAPSTypeInfoValue IpIImage

IplImage (Image Processing Library image description structure)

const MAPSTypeInfoValue MAPSImage

MAPSImage (RTMaps specific image structure)

• const MAPSTypeInfoValue CANFrame

CAN frame.

• const MAPSTypeInfoValue Matrix

MATLAB-Like matrix.

• const MAPSTypeInfoValue RealObject

Real object (car, tree, etc.)

• const MAPSTypeInfoValue DrawingObject

Drawing object (line, circle, etc.)

• const MAPSTypeInfoValue Triangles3D

3D triangles for 3D scene rendering

const MAPSTypeInfoValue Stream8

8-bit stream (sound, numerized data)

• const MAPSTypeInfoValue Stream16

16-bit stream (sound, numerized data)

• const MAPSTypeInfoValue Stream32

32-bit stream (numerized data)

const MAPSTypeInfoValue Integer64

Integer (64 bits, signed)

const MAPSTypeInfoValue AnyText

Some textual information, ascii or unicode.

• const MAPSTypeInfoValue AnyInteger

32 or 64 bits integers.

• const MAPSTypeInfoValue VectorFlag

Indicates that the piece of data is a vector (an array) of a basic type.

const MAPSTypeInfoValue FrequencyFlag

Indicates that a frequency is provided with the data.

· const MAPSTypeInfoValue QualityFlag

Indicates that a quality is transmitted along with the data (for instance a compression or a noise ratio).

· const MAPSTypeInfoValue MiscFlag

Indicates that 3 miscellaneous integers are transmitted along with the data. See MAP-SIOElt::Misc1(), Misc2() and Misc3()

# **RTMaps Inputs behaviours**

· const int FifoReader

FIFO Reader behaviour.

· const int NeverSkippingReader

Never Skipping Reader behaviour.

· const int LastOrNextReader

Last or Next Reader behaviour.

• const int Wait4NextReader

Wait For Next Reader behaviour.

• const int SamplingReader

Sampling Reader behaviour.

# **RTMaps Properties types**

· const int BoolProperty

Boolean property (false or true)

• const int IntegerProperty

Integer property (64-bit signed integer)

· const int FloatProperty

Floating point property (double: 64-bit floating point number)

· const int StringProperty

String property (ASCII string) Enum property (ASCII string)

• const int EnumProperty

# **RTMaps Type Filters**

- const MAPSTypeFilterBase FilterStructure
   Filters any user-defined structure type.
- const MAPSTypeFilterBase FilterInteger Filters integer type (same as FilterIntegers)
- const MAPSTypeFilterBase FilterInteger64
   Filters 64 bits integer type (same as FilterIntegers64)
- const MAPSTypeFilterBase FilterFloat
   Filters MAPSFloat type (same as FilterFloats)
- const MAPSTypeFilterBase FilterNumber
   Filters integer or MAPSFloat type (same as FilterNumbers)
- const MAPSTypeFilterBase FilterIntegers
   Filters integer scalars or vectors.
- const MAPSTypeFilterBase FilterIntegers64
   Filters 64 bits integer scalars or vectors.
- const MAPSTypeFilterBase FilterFloats

  Filters MAPSFloat scalars or vectors.
- const MAPSTypeFilterBase FilterNumbers

  Filters integer or MAPSFloat scalars or vectors.
- const MAPSTypeFilterBase FilterOneInteger
   Filters integer type (excludes vectors of integers)
- const MAPSTypeFilterBase FilterOneInteger64
   Filters 64 bits integer type (excludes vectors of integers64)
- const MAPSTypeFilterBase FilterOneFloat
   Filters MAPSFloat type (excludes vectors of MAPSFloat)
- const MAPSTypeFilterBase FilterOneNumber Filters integer or MAPSFloat type (excludes vectors)
- const MAPSTypeFilterBase FilterTextAscii
   Filters ASCII text string.
- const MAPSTypeFilterBase FilterTextUnicode
   Filters Unicode (16 bits) text string.

- const MAPSTypeFilterBase FilterImage
   Filters IpIlmages or MAPSImages.
- const MAPSTypeFilterBase FilterlpIlmage Filters IpIlmages.
- const MAPSTypeFilterBase FilterMAPSImage
   Filters MAPSImages.
- const MAPSTypeFilterBase FilterCANFrame Filters CANFrames.
- const MAPSTypeFilterBase FilterMatrix Filters MATLAB-Like matrices.
- const MAPSTypeFilterBase FilterRealObjects
  Filters RTMaps Real Objects.
- const MAPSTypeFilterBase FilterDrawingObjects
  Filters RTMaps Drawing Objects.
- const MAPSTypeFilterBase FilterTriangles3D
   Filters 3D triangles.
- const MAPSTypeFilterBase FilterStream8
   Filters 8-bit data streams.
- const MAPSTypeFilterBase FilterStream16 Filters 16-bit data streams.
- const MAPSTypeFilterBase FilterStream32 Filters 32-bit data streams.
- const MAPSTypeFilterBase FilterAudioSignal
   Filters audio signals (either MAPSFloat or Stream8)
- const MAPSTypeFilterBase FilterAny
   Filters any kind of data.

# RTMaps kinds of information outputs

• const int Info
Simple information.

· const int Warning

Warning.

· const int Error

Error.

· const int ParserEcho

Echo from the parser.

# RTMaps replay modes

• const int ReplayModeNormal

Normal replay.

· const int ReplayModeImmediate

Immediate replay mode (replay ahead of real time)

const int ReplayModeTimestamp

Replay using timestamp instead of time of issue.

# RTMaps VCR Keys codes

- · const int VCRKeyStop
- · const int VCRKeyPlay
- · const int VCRKeyRecord
- · const int VCRKeyPause
- · const int VCRKeyRewind
- · const int VCRKeyForward
- const int VCRKeyNext
- const int VCRKeyOrganize
- · const int VCRSlider
- · const int VCRAIIKeys

# RTMaps Engine Keys codes

- · const int KernelKeyRun
- · const int KernelKeyShutdown
- · const int DefaultKeysState

### **Others RTMaps Constants**

• const MAPSString OperatingSystem

Contains the operating system string information ("Win32", "QNX" or "Linux" for instance)

· const int OSBuild

Contains the OS support build number information.

const MAPSString Distribution

Contains the distribution information string ("3.0" for instance)

· const MAPSString KernelVersion

Contains the engine version string information ("1.0" for instance)

const MAPSString RTMapsMinorVersion

Contains the RTMaps minor version (changes in the minor versions preserve backward compatibility with packages). "5" for example -> complete version string will look like "3.0.5".

· const int KernelBuild

Contains the engine build number information.

• const MAPSString Copyright

Contains the RTMaps copyright string information.

• const MAPSString License

Contains the RTMaps license grant string information (depends on the customer)

const MAPSString ProductName

Contains the operating system string information ("Win32", "QNX" or "Linux" for instance)

· const bool BigEndian

Tells if we are running on a big-endian platform (true) or a little-endian platform (false)

· const int DefaultTextSize

Default allocation size (in characters) for ascii text type outputs.

· const int Infinite

Infinite number.

· const int ModuleDied

State indicating a dead RTMaps module.

· const int GotAMessage

State indicating that RTMaps got a Windows message.

const int TimeOut

State indicating a time out in RTMaps.

• const int FatalKernelError

State indicating a fatal engine error.

• const int ErrorException

State indicating an error in an RTMaps module.

· const int Running

State telling that RTMaps is running (that time is flowing)

· const int Paused

State telling that RTMaps is in pause mode.

• const int ShuttingDown

RTMaps is currently shutting down.

· const int Resetting

RTMaps is currently resetting.

· const int WaitingForSynchBeforeRun

RTMaps is currently waiting to be synchronized before running.

• const int DeadState

State indicating a dead thread or module.

· const int DyingState

State indicating a dying thread or module.

· const int LivingState

State indicating a living thread or module.

· const int Threaded

The component is threaded.

· const int Sequential

The component is sequential.

### C standard library wrapper

These functions should be called instead of their C counterparts to ensures easier cross-platform design of components.

- int Atoi (const char \*a)
   Ascii to integer conversion.
- MAPSInt64 Atoi64 (const char \*a)

  Ascii to integer (64 bits) conversion.
- MAPSInt32 Strtol (const char \*s, char \*\*endptr, int base)
   Converts the initial part of the string in s to a MAPSInt32 according to the given base.
- MAPSUInt32 Strtoul (const char \*s, char \*\*endptr, int base)
   Converts the initial part of the string in s to a MAPSUInt32 according to the given base.
- MAPSInt64 Strtoi64 (const char \*s, char \*\*endptr, int base)
   Converts the initial part of the string in s to a MAPSInt64 according to the given base.
- MAPSUInt64 Strtoui64 (const char \*s, char \*\*endptr, int base)
   Converts the initial part of the string in s to a MAPSUInt64 according to the given base.
- int Strlen (const char \*s)
   Calculates the length of the string s.
- const char \* Strchr (const char \*s, char ch)
   Finds character ch in s.
- char \* Strchr (char \*s, char ch)
   Finds character ch in s.
- int Strcmp (const char \*s1, const char \*s2) String comparison.
- int Stricmp (const char \*s1, const char \*s2)
   Lowercase comparison of strings.
- int Strncmp (const char \*s1, const char \*s2, MAPSInt64 size)

  Compares the first size characters of two strings.
- char \* Strstr (const char \*s, const char \*strSearch)
   Returns a pointer to the first occurrence of a search string strSearch in the string s.
- char \* Strcpy (char \*strDest, const char \*strSrc)
   Copies strSrc into strDest.

```
    char * Strdup (const char *strSrc)
    Duplicate strings.
```

- char \* Itoa (int val, char \*buf, int radix=10)
   Integer to Ascii conversion.
- char \* Itoa (unsigned long val, char \*buf, int radix=10)
   Integer to Ascii conversion.
- char \* Itoa (MAPSInt64 val, char \*buf, int radix=10)
   Integer to Ascii conversion.
- bool IsSpace (char c)

  Is the character c a space, a tab or a carriage return?
- bool IsDigit (char c)
   Is the character c a digit?
- void \* Memcpy (void \*dest, const void \*source, MAPSInt64 size, MAPSEvent \*event=NULL)

Memory copy.

- void \* Memset (void \*dest, int c, MAPSInt64 size)
   Sets buffers to a specified character c, repeated size times.
- void \* Memmove (void \*dest, const void \*source, MAPSInt64 size)

  Moves one buffer to another.
- double Modf (double x, double \*intptr)
   Splits a floating-point value into fractional and integer parts.
- double Fabs (double x)
   Calculates the absolute value of the floating-point argument.

# **RTMaps Main functions**

- void Exit ()
   Required after any use of RTMaps...
- bool Run ()
   Starts the execution of the current session.
- bool Shutdown ()
   Shutdowns the RTMaps session currently running.

• bool Reset ()

Resets the RTMaps system.

• bool Parse (const char \*s)

Parses a string containing MAPSScript instructions.

bool ParseFile (const char \*s)

Parses a file containing MAPSScript instructions.

void LoadCoreFunction (const char \*cf)

Loads a core function and activates it.

• MAPSCoreFunctionInterface \* CoreFunction (const char \*cf)

Returns a pointer to the core function named cf if it was previously loaded (returns NULL otherwise)

void RegisterPackage (const char \*fileName)

Loads a package (set of components compiled as a shared object).

void UnregisterPackage (const char \*fileName)

Unloads a package (set of components compiled as a shared object).

• bool IsRunning ()

Is there a RTMaps system currently running?

• bool IsPaused ()

Is the RTMaps clock in paused state?

• bool IsReplaying ()

Returns true if a file is open for replay.

• int CheckLevel ()

Returns the level of structure control in the current system (0=no control, fastest, 2=max control, slowest)

# RTMaps functions for distribution and synchronization

• bool IsDistributedAsMaster ()

Is RTMaps acting as a Master on a network of distributed RTMaps.

• bool IsDistributedAsSlave ()

Is RTMaps acting as a Slave on a network of distributed RTMaps.

bool GetSynchronizer (void \*owner, MAPSSynchronizer \*\*ppSynchronizer)

Requests a pointer on the synchronizer object.

bool ReleaseSynchronizer (void \*module, MAPSSynchronizer \*\*ppSynchronizer)

Releases a pointer on the synchronizer object.

# **RTMaps Virtual Time management functions**

MAPSAbsoluteTime & TimeReference ()

Gets the time reference (the absolute time the timestamps always refer to)

• MAPSTimestamp CurrentTime (bool lock=true, bool release=true)

Gets the current time in the RTMaps system (virtual time)

void SetCurrentTime (MAPSTimestamp t)

Sets the current time (jumps in time!)

void SetTimeSpeed (int speed)

Sets the current time speed (1000 = real time)

• int TimeSpeed ()

Gets the current time speed (1000 = real time)

• int TimeState ()

Gets the current time state (MAPS::Running or MAPS::Paused)

# RTMaps Index management

• void SetIndex ()

Adds an index now (during recording)

void Go2Index (int num)

Goes to index num during replay.

void Go2PreviousIndex ()

Goes to previous index (during replay)

• void Go2NextIndex ()

Goes to next index (during replay)

### RTMaps Recording management

- void StartRecording (void)
   Starts recording information (starts all)
- void StopRecording (void)
   Stops recording information (stops all)

# RTMaps Type Filtering management

• bool TypeFilter (const MAPSTypeInfo &outputType, MAPSTypeFilterBase &filter)

### **RTMaps General purpose functions**

 ::IpIImage IpIImageModel (int width, int height, unsigned int channelSeq=MAPS\_-CHANNELSEQ\_BGR, unsigned int dataOrder=IPL\_DATA\_ORDER\_PIXEL, unsigned int depth=IPL\_DEPTH\_8U)

Creates a model of an operational *IplImage* structure with the provided parameters.

• ::IpIImage IpIImageModel (int width, int height, const char \*channelSeq, unsigned int dataOrder=IPL\_DATA\_ORDER\_PIXEL, unsigned int depth=IPL\_DEPTH\_8U)

Creates a model of an operational IplImage structure with the provided parameters.

bool lpllmageCheck (::lpllmage &image,::lpllmage &model)
 Checks that an image is the same type and size as the model given in second param-

# **RTMaps Maintenance functions**

eter.

· MAPSString About (void)

# **RTMaps Reporting functions**

For all these functions, the importance must be set between 0 (not important) to 2 (of the utmost importance)

- void ReportInfo (const char \*text, int importance=0)

  Reports a piece of information.
- void ReportWarning (const char \*text, int importance=0)
   Reports a warning.

- void ReportError (const char \*text, int importance=0)
   Reports an error.
- void Report (const char \*text, int type, int importance=0)
   Reports something (with user feedback + logging)
- void MessageBox (const char \*message, int type, int importance=0)
   Displays a modal MessageBox. To be used for debugging only since this function blocks until the user.

### Time conversion and handling functions

- MAPSTimestamp TimestampFromString (const char \*s, char \*\*endptr=NULL)
   Transforms a string of form hh:mm:ss.mmmuuu into a timestamp.
- MAPSString TimeString (MAPSTimestamp t)
- MAPSString Timestamp2String (MAPSTimestamp t)

Transforms a timestamp into a human readable string of form hh:mm:ss.mmmmmm.

• void Timestamp2AbsoluteTimeUTC (MAPSTimestamp t, MAPSAbsoluteTime \*utctime)

Transforms a timestamp in microseconds into an absolute time.

• MAPSTimestamp AbsoluteTimeUTC2Timestamp (const MAPSAbsoluteTime \*utctime)

Transforms an absolute time into a timestamp.

- MAPSInt64 AbsoluteTime2Integer (MAPSAbsoluteTime &time)
- void Integer2AbsoluteTime (MAPSInt64 integer, MAPSAbsoluteTime &time)
- MAPSString AbsoluteTime2String (MAPSAbsoluteTime absTime)

Transforms an absolute time into a string of form yyyy/mm/dd hh:mm:ss.mmmuuu.

- void GetAbsoluteTime (MAPSAbsoluteTime \*localtime)
   Gets the absolute current time (local time). Deprecated. Prefer using MAPS::GetAbsoluteTimeLocal.
- void GetAbsoluteTimeLocal (MAPSAbsoluteTime \*localtime)
   Gets the absolute current local time.

- void GetAbsoluteTimeUTC (MAPSAbsoluteTime \*utctime)
   Gets the absolute current time (UTC)
- bool AbsoluteTimeUTCToAbsoluteTimeLocal (const MAPSAbsoluteTime \*utctime, MAPSAbsoluteTime \*localtime)

Converts a UTC time to a local time. Returns true in case of success, false otherwise.

 bool AbsoluteTimeLocalToAbsoluteTimeUTC (const MAPSAbsoluteTime \*localtime, MAPSAbsoluteTime \*utctime)

Converts a local time to a UTC time. Returns true in case of success, false otherwise.

• bool SetSystemTime (const MAPSAbsoluteTime \*utctime)

Sets the computer system clock to the provided absolute time.

# RTMaps Flow monitoring functions

• MAPSString GetWriteStatistics ()

Gets the detailed statistics about the data flow to the hard disks (write file operations).

• MAPSString GetReadStatistics ()

Gets the detailed statistics about the read file operations.

• int GetRemainingTime ()

Gets the overall remaining recording time, if the flows stays constant.

• MAPSInt64 GetWriteFlow ()

Gets the total write flow (file write operations)

• MAPSInt64 GetReadFlow ()

Gets the total read flow (file read operations)

void RecordMemoryWriteFlow (MAPSInt64 size)

Notifies RTMaps that such a memory write flow has occured. Do not use in conjonction with MAPS::Memcpy(...)

void RecordMemoryReadFlow (MAPSInt64 size)

Notifies RTMaps that such a memory read flow has occured. Do not use in conjonction with MAPS::Memcpy(...)

• MAPSInt64 GetMemoryReadFlow ()

Gets the total memory read flow.

• MAPSInt64 GetMemoryWriteFlow ()

Gets the total memory write flow.

• MAPSInt64 GetMemoryFlow ()

Gets the total memory flow (read+write)

MAPSInt64 GetDiskFreeSpace (const char \*path)

Gets the free disk space on the disk containing path.

# RTMaps OS wrapping functions

These functions give access to all the needed features of an OS except file I/O. These functions should be called instead of their OS-specific counterparts to ensure a cross-platform programming.

MAPSTimestamp GetSystemAccurateTiming (void)

Gets an immediate timestamp (in microseconds).

bool CreateThread (void \*(\*startAdress)(void \*), void \*argList)
 Starts a thread.

void SetCurrentThreadPriority (int priority)
 Sets the priority of the current thread (between 0 and 255)

• MAPSThreadId GetCurrentThreadId ()

Gets an id for the current thread.

void ReleaseCurrentThread (void)

Releases the current thread.

• void Sleep (MAPSDelay delay)

Sleeps for a certain amount of time.

void Wait4AWhile (void)

Waits for a while. Useful little function.

• MAPSString GetCurrentDirectory ()

Gets the current directory path.

bool SetCurrentDirectory (const MAPSString path)

Sets the current directory path.

bool CreateDirectory (const char \*dirName)

Creates a directory.

• MAPSString GetTempDirectory ()

Gets a path to the temporary directory.

• MAPSString GetInstallPath (const char \*pathName)

Gets a path refering to RTMaps installation.

void \* AllocSharedMemory (int size)

Memory allocation. Assumes it is allocated in a way that it can be accessed by a RTMaps system running in another process.

void DeallocSharedMemory (void \*ptr)

Memory deallocation. Assumes it was allocated in a way that it can be accessed by a RTMaps system running in another process.

### RTMaps C++ interface functions

These functions are designed to control the RTMaps engine directly through C++ calls. These are rather low-level functions that are not of any interest for a component developer.

- bool GetBoolProperty (const char \*s, bool \*ok=NULL)
   Gets a boolean property.
- MAPSInt64 GetIntegerProperty (const char \*s, bool \*ok=NULL)
   Gets an integer property or enum property selected index.
- MAPSString GetStringProperty (const char \*s, bool \*ok=NULL)

  Gets a string property or enum property selected string.
- MAPSFloat GetFloatProperty (const char \*s, bool \*ok=NULL)
   Gets a float property.
- MAPSEnumStruct GetEnumsProperty (const char \*s, bool \*ok=NULL)
   Gets an enum property.
- MAPSComponent \* Component (const char \*s)
   Returns a pointer to component s (returns NULL if it does not exist)
- MAPSProperty \* Property (const char \*s)
   Returns a pointer to the property named s (returns NULL if it does not exist)
- MAPSComponent \* CreateComponent (const char \*modelName, const char \*componentName, bool start=true)

Component instantiation.

- void StartComponent (const char \*componentName)
   Starts the component if frozen.
- void KillComponent (const char \*componentName)
   Dynamically destroys a component.
- void KillComponent (MAPSComponent &component)
   Dynamically destroys a component.
- void RenameComponent (const char \*componentName, const char \*newName)

Renames a component.

void Attach (MAPSOutput &output, MAPSInput &input)

Dynamically attaches an input to an output.

void Attach (const char \*outputName, const char \*inputName)

Dynamically attaches an input to an output.

bool Attach2 (const char \*name, const char \*inputName)

Dynamically attaches an input to an output. Extended version.

• void Detach (MAPSOutput &output, MAPSInput &input)

Dynamically detaches an output from an input.

 void Record (const char \*outputName, const char \*recorder=NULL, const char \*method=NULL, bool neverskipping=false, bool useTimestamp=false)

Records an output.

 void Open (const char \*pattern, const char \*nspace=NULL, MAPSInt64 offset=0, MAPSTimestamp beginning=0, MAPSTimestamp end=0)

Opens a database to replay records from.

• void Replay (const char \*outputname)

Replays some data.

void Copy (const char \*outputname, const char \*recorderName)

Copies some data.

• void StopCopy (const char \*outputname)

Aborts the copy of an output.

void SetTimeAdapt (int ta)

Sets the time automatic adaptation algorithms.

MAPSTimestamp GetFirstTimestamp ()

Returns the first timestamp of all the currently open databases.

MAPSTimestamp GetLastTimestamp ()

Returns the last timestamp of all the currently open databases.

MAPSEvent \* GetShutdownEvent ()

Gets a pointer to the shutdown event.

### 9.1.1 Detailed Description

The main RTMaps namespace. The MAPS namespace contains a lot of useful functions to deal with the engine features. All its members are declared as static.

### 9.1.2 Function Documentation

### 9.1.2.1 MAPSString MAPS::About (void)

The returned string contains information on the RTMaps version and the list of all the registered modules with their respective versions.

### 9.1.2.2 MAPSInt64 MAPS::AbsoluteTime2Integer ( MAPSAbsoluteTime & time )

### **Deprecated**

Transforms an absolute time to an integer, for absolute time comparison

### Warning

Windows specific: The implementation of this function is not correct in RTMaps 3.x under Windows it will be corrected in RTMaps 4. In the meanwhile, prefer MAPS::AbsoluteTimeUTC2Timestamp.

Linux specific: The implementation of this function on Linux interprets the time as a local time and not UTC time. Prefer MAPS::AbsoluteTimeUTC2Timestamp.

# 9.1.2.3 MAPSTimestamp MAPS::AbsoluteTimeUTC2Timestamp ( const MAPSAbsoluteTime \* utctime )

Transforms an absolute time into a timestamp.

### **Parameters**

*utctime* Absolute time structure interpreted as UTC time to convert to a timestamp.

### Returns

Returns a timestamp in microseconds since the origin of UTC (1970, Jan 1rst, 0h)

# 9.1.2.4 bool MAPS::Attach2 ( const char \* name, const char \* inputName )

Dynamically attaches an input to an output. Extended version.

This new version of attach allows the name parameter to be the name of an output OR the name parameter of the type of an output. This allows dynamic connection using a plain name, not a technical output name.

This function is designed to be used in components that automatically attach to some outputs.

### 9.1.2.5 MAPSString MAPS::GetInstallPath ( const char \* pathName )

Gets a path refering to RTMaps installation.

### **Parameters**

pathName	Specifies the path to retrieve. Can be "mapspath", "jrepath", "classpath" for	1
	java classes, "docpath", "xmlpath".	

# 9.1.2.6 bool MAPS::GetSynchronizer ( void \* owner, MAPSSynchronizer \*\* ppSynchronizer )

Requests a pointer on the synchronizer object.

When the module no more needs the synchronizer ability, it has to call MAPS::ReleaseSynchronizer

### **Parameters**

owner	Pointer to the MAPSModule requesting the synchronizer ability
ppSynchro-	Pointer to the place where the synchronizer object pointer will be stored if
nizer	the function succeeds. If the function fails, it is set to ${ t NULL}$ .

### Returns

 ${\tt true}$  if the function succeeds,  ${\tt false}$  if the function fails (i.e. the synchronizer object is already held by someone else).

# 9.1.2.7 MAPSTimestamp MAPS::GetSystemAccurateTiming (void )

Gets an immediate timestamp (in microseconds).

Note that you must generally use MAPS::CurrentTime() in your own components, since the GetSystemAccurateTiming function returns a timestamp in real time, not in the RTMaps virtual time. Furthermore, the timestamp returned by this function has no reference. It is the RTMaps engine that uses this OS wrapping function to get some accurate timings and translates them to a referenced and scaled virtual time.

# 9.1.2.8 void MAPS::Integer2AbsoluteTime ( MAPSInt64 integer, MAPSAbsoluteTime & time )

# **Deprecated**

Transforms an integer to an absolute time

9.1.2.9 ::IplImage MAPS::IplImageModel ( int width, int height, unsigned int channelSeq = MAPS\_CHANNELSEQ\_BGR, unsigned int dataOrder = IPL\_DATA\_ORDER\_PIXEL, unsigned int depth = IPL\_DEPTH\_8U )

Creates a model of an operational IplImage structure with the provided parameters.

The generated model can be thus used with MAPSOutput::AllocOutputBufferIpIImage

#### See also

MAPSOutput::AllocOutputBufferIpIImage

9.1.2.10 ::IplImage MAPS::IplImageModel ( int width, int height, const char \* channelSeq, unsigned int dataOrder = IPL\_DATA\_ORDER\_PIXEL, unsigned int depth = IPL\_DEPTH\_8U )

Creates a model of an operational IpIImage structure with the provided parameters.

The generated model can be thus used with MAPSOutput::AllocOutputBufferlplImage

### See also

MAPSOutput::AllocOutputBufferIpIImage

9.1.2.11 void\* MAPS::Memcpy ( void \* dest, const void \* source, MAPSInt64 size, MAPSEvent \* event = NULL )

Memory copy.

Should be ALWAYS called instead of memcpy

9.1.2.12 void MAPS::MessageBox ( const char \* message, int type, int importance = 0 )

Displays a modal MessageBox. To be used for debugging only since this function blocks until the user.

# **Parameters**

message	The message to be displayed in the message box
type	The type can be MAPS::Info, MAPS::Warning, or MAPS::Error
importance	Unused

# 9.1.2.13 void MAPS::ReleaseCurrentThread (void)

Releases the current thread.

Gives up its remaining time slice. This may optimize the behaviour of a component and it is used in the RTMaps engine to optimize threads switching.

### 9.1.2.14 void MAPS::Report ( const char \* text, int type, int importance = 0 )

Reports something (with user feedback + logging)

### **Parameters**

type	The report type. Can be MAPS::Info, MAPS::Warning or MAPS::Error.
text	The message to report to the user
importance	Unused

### 9.1.2.15 void MAPS::ReportInfo ( const char \* text, int importance = 0 )

Reports a piece of information.

Only for use by programs out of the RTMaps system. For RTMaps components, please use the MAPSComponent::Report function.

#### See also

MAPSComponent::Report

### 9.1.2.16 bool MAPS::SetSystemTime ( const MAPSAbsoluteTime \* utctime )

Sets the computer system clock to the provided absolute time.

### **Parameters**

utctime   Absolute time in UTC to apply	to the current system clock.
---	------------------------------

### Returns

true in case of success, false otherwise.

### Remarks

The function may fail if the caller does not have administrator or super-user rights.

# 9.1.2.17 void MAPS::Sleep ( MAPSDelay delay )

Sleeps for a certain amount of time.

The current thread is released for a delay of delay microseconds. Note that it is not considered to be an accurate function. For instance, in the Windows implementation of RTMaps, the delay precision is about 40ms.

Note that you must generally use MAPSComponent::Rest() or MAPSComponent::Wait() in your own components, since the MAPS::Sleep function works in real time, not in the RTMaps virtual time. Furthermore, MAPSComponent::Rest() and MAPSComponent::Wait() are much more accurate.

# 9.1.2.18 void MAPS::Timestamp2AbsoluteTimeUTC ( MAPSTimestamp t, MAPSAbsoluteTime \* utctime )

Transforms a timestamp in microseconds into an absolute time.

### **Parameters**

t	Timestamp in microseconds, interpreted as the number of microseconds
	since the origin of UTC (1970, Jan 1rst, 0h).
utctime	Pointer to a structure of type MAPSAbsoluteTime to be filled in with UTC
	time (not local time).

# 9.1.2.19 MAPSString MAPS::Timestamp2String ( MAPSTimestamp t )

Transforms a timestamp into a human readable string of form hh:mm:ss.mmmmmm.

### **Parameters**

t A timestamp in microseconds.

### Warning

This method does not support absolute times so it will never generate strings of form yyyy/mm/dd hh:mm:ss.mmmuuu.

# 9.1.2.20 MAPSTimestamp MAPS::TimestampFromString ( const char \* s, char \*\* endptr = NULL )

Transforms a string of form hh:mm:ss.mmmuuu into a timestamp.

Warning: it does not support absolute time strings of form yyyy/mm/dd hh:mm:ss.mmmmmm. Only relative time strings.

# 9.1.2.21 MAPSString MAPS::TimeString ( MAPSTimestamp t )

### See also

Equivalent to MAPS::Timestamp2String.

# 9.1.2.22 bool MAPS::TypeFilter ( const MAPSTypeInfo & *outputType*, MAPSTypeFilterBase & *filter* )

Passes a type through a filter type

# **Parameters**

outputType	type to pass through the filter, generally the type of an output
filter	filter to use

### **Returns**

returns true when *filter* filters out *outputType* For RTMaps type filtering behaviour, see the documentation of MAPSTypeFilterBase.

### See also

MAPSTypeInfo MAPSTypeFilterBase

# 9.1.3 Variable Documentation

# 9.1.3.1 const int MAPS::EnumProperty

### See also

**MAPSEnumStruct** 

# 9.1.3.2 const MAPSTypeInfoValue MAPS::TextAscii

Ascii characters (1 character = 8 bits).

Remark: When dealing with an output with type TextAscii, the arbitrary convention is: the text bytes are ended with the '\0' character in the MAPSIOEIt buffer, but this '\0' character is not counted in the VectorSize() field of the MAPSIOEIt. So, ioElt->VectorSize() should return the same result than std::strlen(ioElt->TextAscii()).

# **Chapter 10**

# **Class Documentation**

# 10.1 Iplimage Struct Reference

The famous IpIImage structure, today's standard structure for image processing.

# **Public Attributes**

MAPSInt32 nSize

Size of iplImage struct.

• MAPSInt32 ID

Image header version.

• MAPSInt32 nChannels

Number of channels in the image (generally 1,3 or 4)

• MAPSInt32 alphaChannel

Alpha channel number (0 if there is no alpha channel in the image)

• MAPSInt32 depth

Bit depth of pixels.

• char colorModel [4]

A four-character string describing the color model.

• char channelSeq [4]

A four-character string describing the sequence of color channels.

• MAPSInt32 dataOrder

Can be IPL\_DATA\_ORDER\_PIXEL or IPL\_DATA\_ORDER\_PLANE.

### · MAPSInt32 origin

The origin of the image: can be <code>IPL\_ORIGIN\_TL</code> (top left corner) or <code>IPL\_ORIGIN\_-BL</code> (bottom left corner)

# • MAPSInt32 align

Alignment of image data: can be <code>IPL\_ALIGN\_DWORD</code> (4-byte align) or <code>IPL\_-ALIGN\_QWORD</code> (8-byte align)

### MAPSInt32 width

Width of the image in pixels.

# · MAPSInt32 height

Height of the image in pixels.

# • IpIROI \* roi

Pointer to a ROI (Region of interest) structure.

# • struct \_lplImage \* maskROI

Pointer to the header of another image that specifies the mask ROI.

### void \* imageId

The image ID.

# • struct \_lplTileInfo \* tileInfo

The pointer to the IplTileInfo structure containing information used for image tiling.

# • MAPSInt32 imageSize

Useful size in bytes.

# • char \* imageData

Pointer to aligned image.

### MAPSInt32 widthStep

The size of aligned line in bytes.

# • MAPSInt32 BorderMode [4]

The top, bottom, left and right border mode.

# • MAPSInt32 BorderConst [4]

Constants for the top, bottom, left and right border.

### • char \* imageDataOrigin

Pointer to full, nonaligned image.

# 10.1.1 Detailed Description

The famous lpllmage structure, today's standard structure for image processing. The lpllmage structure is the preferred structure for image processing with RTMaps.

The lpllmage structure is rather complex but very complete. Easy handling of this structure by RTMaps is provided by MAPS::lpllmageModel and MAPSOutput::AllocOutputBufferlpllmage.

### 10.1.2 Member Data Documentation

# 10.1.2.1 char lpllmage::channelSeq[4]

A four-character string describing the sequence of color channels.

Use MAPS\_CHANNELSEQ\_xxx to fill this field.

### 10.1.2.2 char lpllmage::colorModel[4]

A four-character string describing the color model.

Use MAPS\_COLORMODEL\_xxx to fill this field

# 10.1.2.3 MAPSInt32 IpIImage::depth

Bit depth of pixels.

Can be one of:

- IPL\_DEPTH\_1U
- IPL\_DEPTH\_8U
- IPL\_DEPTH\_8S
- IPL\_DEPTH\_16U
- IPL\_DEPTH\_16S
- IPL\_DEPTH\_32S
- IPL\_DEPTH\_32F.

# 10.1.2.4 void\* lpllmage::imageld

The image ID.

Field reserved for the use of the application to identify the image.

### 10.1.2.5 struct \_lpllmage\* lpllmage::maskROI

Pointer to the header of another image that specifies the mask ROI.

This argument can be  $\mathtt{NULL}$ , which indicates that no mask ROI is used. A pixel is processed if the corresponding mask pixel is 1, and is not processed if the mask pixel is 0. The *maskROI* field of the mask image's header is ignored.

### 10.1.2.6 IpIROI\* IpIImage::roi

Pointer to a ROI (Region of interest) structure.

This argument can be  $\mathtt{NULL}$ , which implies that a region of interest comprises all channels and the entire image area.

The documentation for this struct was generated from the following file:

maps.hpp

# 10.2 IpIROI Struct Reference

The IPL Region Of Interest structure.

# **Public Attributes**

• MAPSInt32 coi

The channel of interest number.

MAPSInt32 xOffset

The horizontal offset from the origin of the rectangular ROI.

MAPSInt32 yOffset

The vertical offset from the origin of the rectangular ROI.

MAPSInt32 width

The width of the rectangular ROI.

· MAPSInt32 height

The height of the rectangular ROI.

# 10.2.1 Detailed Description

The IPL Region Of Interest structure.

### 10.2.2 Member Data Documentation

### 10.2.2.1 MAPSInt32 lpIROI::coi

The channel of interest number.

This parameter indicates which channel in the original image will be affected by processing taking place in the region of interest; *coi* equal to 0 indicates that all channel will be affected

The documentation for this struct was generated from the following file:

• maps.hpp

# 10.3 MAPSAbsoluteTime Struct Reference

Absolute time structure.

# **Public Attributes**

- MAPSUInt32 year
   19XX or 20XX
- MAPSUInt32 month
   Ranging from 1 to 12.
- MAPSUInt32 day

  Ranging from 1 to 31.
- MAPSUInt32 hour

  Ranging from 0 to 23.
- MAPSUInt32 minutes

  Ranging from 0 to 59.
- MAPSUInt32 seconds

  Ranging from 0 to 59.
- MAPSUInt32 milliseconds
   Ranging from 0 to 999.
- MAPSUInt32 microseconds
   Ranging from 0 to 999.

# **Related Functions**

(Note that these are not member functions.)

• bool operator < (const MAPSAbsoluteTime &t0, const MAPSAbsoluteTime &t1) Standard comparison operator on absolute time.

- bool operator== (const MAPSAbsoluteTime &t0, const MAPSAbsoluteTime &t1)

  Standard comparison operator on absolute time.
- bool operator> (const MAPSAbsoluteTime &t0, const MAPSAbsoluteTime &t1)
   Standard comparison operator on absolute time.

# 10.3.1 Detailed Description

Absolute time structure. This is the RTMaps standard structure for absolute time handling

The documentation for this struct was generated from the following file:

• maps.hpp

# 10.4 MAPSAction Class Reference

The RTMaps Module Action class.

# **Public Member Functions**

virtual void Dolt ()=0
 Executes the action.

# 10.4.1 Detailed Description

The RTMaps Module Action class.

The documentation for this class was generated from the following file:

• maps.hpp

# 10.5 MAPSArray < T > Class Template Reference

The RTMaps array class.

# **Public Member Functions**

• T & operator[] (int i) const

Retrieves the element with index i in the array.

• T & operator() (int i)

Retrieves the element with index i in the array and resizes the array when necessary.

- MAPSArray < T > & operator= (const MAPSArray < T > &v)
   Copy operator.
- int Dim () const

Gets the current size of the array.

• int Size () const

Gets the current size of the array.

• T \* Vect () const

Returns a pointer to the data.

void Fill (const T &model)

Fills the array with model model.

• T & Append ()

Appends an element to the array.

void Set (T \*ptr, int d)

Sets the content of the array. The data is not copied.

• void Realloc (int d)

Reallocates the data.

• void Alloc (int d)

Allocates some data.

• void SetSize (int d)

Sets the size of the array. Moves the data (realloc) if needed.

• void Clear ()

Clears the array (i.e. Resets size to zero)

operator T \* ()

Cast operator. Returns a C-like array.

• T & Shift ()

Shifts an element from the array.

```
    void Unshift (const T &z)
```

Unshifts an element to the array.

• T & Pop ()

Pops an element from the end of the array.

void Push (const T &z)

Pushes an element to the end of the array.

• MAPSArray ()

Basic constructor.

• MAPSArray (int d)

Allocating constructor.

MAPSArray (const MAPSArray < T > &v)

Copy constructor.

• virtual  $\sim$ MAPSArray ()

Destructor.

# **Related Functions**

(Note that these are not member functions.)

```
    template < typename T >
        MAPSArray < T > operator* (const MAPSMatrix2 < T > &A, const MAPSArray <
        T > &b)
```

Multiplication of a MAPSMatrix2 with a MAPSArray.

MAPSArrays addition.

 • template<typename T > MAPSArray< T > operator- (const MAPSArray< T > &a, const MAPSArray< T > &b)

MAPSArrays substraction.

template<typename T >
 MAPSArray< T > operator+ (const MAPSMatrix2< T > &a, const MAPSArray<
 T > &b)

Addition of a MAPSMatrix2 with a MAPSArray.

 template<typename T >
 MAPSStreamedString & operator<< (MAPSStreamedString &out, const MAP-SArray< T > &v)

Standard operator.

# 10.5.1 Detailed Description

### template<typename T> class MAPSArray< T>

The RTMaps array class. This class implements a resizable one-dimensional array. It can also work as a very efficient ring buffer, a queue or even a stack. Indeed, it acts as a Perl-like array, that is with an offset management.

Using this class is generally faster than using MAPSList, since MAPSArray allocates objects by packets, and not one by one. MAPSArray is the preferable class to use when you need to use a queue or a stack.

### Note

The constructor and the destructor of class  $\mathbb T$  are never called. Use MAPSList if you need a systematic call to content constructors/destructors.

The size of the allocated array is always of power of 2, due to an optimization in the ring buffer behaviour management.

# 10.5.2 Constructor & Destructor Documentation

```
10.5.2.1 template<typename T> MAPSArray< T>::MAPSArray ( )
```

Basic constructor.

Allocates nothing. The size of the array is set to 0.

```
10.5.2.2 template<typename T> MAPSArray< T>::MAPSArray(int d) [explicit]
```

Allocating constructor.

Allocates an array of size d. Indeed, the true allocated size is a power of 2.

### 10.5.3 Member Function Documentation

# 10.5.3.1 template<typename T> void MAPSArray< T>::Alloc (int d)

Allocates some data.

Destroys previously allocated data.

### 10.5.3.2 template<typename T> T& MAPSArray< T>::Append ( )

Appends an element to the array.

Resizes the array and returns a reference to the new appended element.

### 10.5.3.3 template < typename T > MAPSArray < T >::operator T \* ( )

Cast operator. Returns a C-like array.

Returns a pointer to the data.

Should be used with care... Especially after the use of Shift() function, it will not give you what you expect, since the array will thus be used as a ring buffer. Furthermore, the pointer might not be valid for long due to possible reallocations.

### 10.5.3.4 template < typename T > T& MAPSArray < T >::operator[] ( int i ) const

Retrieves the element with index i in the array.

No memory allocation if *i* is superior to the actual size of the array.

# 10.5.3.5 template < typename T > T& MAPSArray < T >::Pop ( )

Pops an element from the end of the array.

This function returns a reference, but this reference is only valid up to the next call to another array related function, since the element can and will certainly be crushed by a further call to Push() of Unshift().

### 10.5.3.6 template < typename T > void MAPSArray < T >::Realloc ( int d )

Reallocates the data.

Moves previous data to a new location with room for *d* pieces of data.

### 10.5.3.7 template < typename T> void MAPSArray < T>::Set ( T \* ptr, int d )

Sets the content of the array. The data is not copied.

This is not a copy operator. The array will point to the T objects given in arguments. This data will not be destroyed when the object is destroyed (i.e. the array does not own the data).

# 10.5.3.8 template < typename T > T& MAPSArray < T >::Shift ( )

Shifts an element from the array.

Perl-like operator. Removes an element from the beginning of the array (efficiently, i.e. without moving all the elements to the left, but through the management of an "offset" variable) Note that further pointers returned by a Vect() function are not valid any more after a call to Shift().

This function returns a reference, but this reference is only valid up to the next call to another array related function, since the element can and will certainly be crushed by a further call to Push() of Unshift().

### 10.5.3.9 template<typename T> void MAPSArray< T>::Unshift ( const T & z )

Unshifts an element to the array.

Perl-like operator. It adds an element in front of the array. Inserts an element at the beginning of the array (efficiently, i.e. without moving all the elements to the right, but through the management of an "offset" variable) Note that further pointers returned by a Vect() function are not valid any more after a call to Shift().

```
10.5.3.10 template < typename T> T* MAPSArray < T>::Vect ( ) const
```

Returns a pointer to the data.

Should be used with care... Especially after the use of Shift() function, it will not give you what you expect, since the array will thus be used as a ring buffer. Furthermore, the pointer might not be valid for long due to possible reallocations.

# 10.5.4 Friends And Related Function Documentation

```
10.5.4.1 template < typename T > MAPSStreamedString & operator << ( MAPSStreamedString & out, const MAPSArray < T > & v ) [related]
```

Standard operator.

The documentation for this class was generated from the following file:

• maps.hpp

# 10.6 MAPSBaseClock Class Reference

MAPSBaseClock class.

### **Public Member Functions**

• unsigned char GetClockID ()

For internal use.

const char \* GetClockName ()

For internal use.

• virtual bool IsSynchronizable ()

For internal use. Do not overload.

• virtual bool IsReplayable ()

For internal use. Do not overload.

virtual void InitClock ()=0

Overloading this function is necessary.

• virtual void RunClock ()=0

Overloading this function is necessary.

virtual void ShutdownClock ()=0

Overloading this function is necessary.

- virtual MAPSTimestamp CurrentTime ()=0
- int GetAbsoluteTimeSpeed ()

This function returns the maximum "real" timespeed currently declared by this clock.

void SetAbsoluteTimeSpeed (int absoluteTimeSpeed)

Use this function to declare the maximum "real" timespeed your custom clock can reach.

• MAPSBaseClock (const char \*name)

Constructor.

# 10.6.1 Detailed Description

MAPSBaseClock class. Every object inheriting from this class has to implement a basic clock and this clock will be available for the RTMaps engine.

# 10.6.2 Constructor & Destructor Documentation

10.6.2.1 MAPSBaseClock::MAPSBaseClock ( const char \* name )

Constructor.

### **Parameters**

name	The name of your custom clock.	To be simple, just pass the name of your
	RTMaps component.	

### **10.6.3** Member Function Documentation

# 10.6.3.1 virtual MAPSTimestamp MAPSBaseClock::CurrentTime() [pure virtual]

This function is called each time someone in RTMaps (the VCR, the Player, or any other component) queries the current (through the MAPS::CurrentTime() method).

### Returns

The current time of your custom clock, expressed in microseconds.

### Warning

This function is called very often. It has to be the fastest possible.

This function can be called concurrently from several threads. Make sure it is thread safe.

# 10.6.3.2 int MAPSBaseClock::GetAbsoluteTimeSpeed ( )

This function returns the maximum "real" timespeed currently declared by this clock.

### **Returns**

The maximum timespeed your custom clock can reach on the absolute time base (i.e. your watch, not the RTMaps VCR).

### See also

SetAbsoluteTimeSpeed(int absoluteTimeSpeed);

# 10.6.3.3 virtual void MAPSBaseClock::InitClock( ) [pure virtual]

Overloading this function is necessary.

This function is called when the object is chosen as the current clock in the RTMaps diagram. You have to implement this function, but implemenation can often remain empty...

### 10.6.3.4 virtual bool MAPSBaseClock::IsReplayable() [virtual]

For internal use. Do not overload.

### Returns

Always return false.

### 10.6.3.5 virtual bool MAPSBaseClock::lsSynchronizable() [virtual]

For internal use. Do not overload.

### Returns

Always return false.

# 10.6.3.6 virtual void MAPSBaseClock::RunClock( ) [pure virtual]

Overloading this function is necessary.

This function is called when your custom clock has to start running.

# 10.6.3.7 void MAPSBaseClock::SetAbsoluteTimeSpeed ( int absoluteTimeSpeed )

Use this function to declare the maximum "real" timespeed your custom clock can reach.

### **Parameters**

absol	ute-
TimeSp	eed

The maximum "real" timespeed your custom clock can reach. "real" timespeed means "in comparison with real time", the time of your watch. Declaring a max. timespeed which is much higher than the effective timespeed of your clock will result in little more CPU consumption. On the other hand, declaring a max. timespeed which is lower thant the effective timespeed of your clock will result in timers inacurracy within RTMaps (the Wait and Rest functions will be affected). A value of 1000 means real-time, a value of 500 means half the real-time for example.

### 10.6.3.8 virtual void MAPSBaseClock::ShutdownClock( ) [pure virtual]

Overloading this function is necessary.

This function is called when your custom clock has to stop running.

The documentation for this class was generated from the following file:

· maps.hpp

### 10.7 MAPSBasicList Class Reference

The base class for the MAPSList template class.

Inheritance diagram for MAPSBasicList:



# **Public Member Functions**

• bool Empty () const

Returns true if the list is empty.

• int Length () const

Returns the length of the list (the number of elements in the list)

• int Size () const

Returns the number of elements in the list.

• int Dim () const

Returns the number of elements in the list.

MAPSBasicList ()

Default constructor.

# Iteration management

• MAPSListIterator First () const

Returns an iterator corresponding to the first element in the list (NULL if the list is empty)

· MAPSListIterator Iterator () const

• MAPSListIterator Begin () const

Returns an iterator corresponding to the first element in the list ( $\mathtt{NULL}$  if the list is empty)

• MAPSListIterator Last () const

• MAPSListIterator End () const

Returns a NULL iterator.

• MAPSListIterator & Next (MAPSListIterator &it) const

Increments iterator it. Returns the next item in the list.

MAPSListIterator & Previous (MAPSListIterator &it) const
 Decrements iterator it. Returns the previous item in the list.

- bool Finished (MAPSListIterator it) const

  Has the iterator it reached the end of the list?
- bool IsFirst (MAPSListIterator it) const
   Does the iterator it correspond to the first element in the list?
- bool IsLast (MAPSListIterator it) const
   Does the iterator it correspond to the last element in the list?

# 10.7.1 Detailed Description

The base class for the MAPSList template class. Should not be used directly.


The documentation for this class was generated from the following file:

· maps.hpp

# 10.8 MAPSBasicListItem Class Reference

The basic list item class.

Inheritance diagram for MAPSBasicListItem:



### **Friends**

class MAPSListIterator

# 10.8.1 Detailed Description

The basic list item class. This is the base element of a MAPSBasicList.

### Warning

Should not be used directly by the end user.

The documentation for this class was generated from the following file:

• maps.hpp

# 10.9 MAPSCANFrame Struct Reference

CAN Frames structure.

# **Public Attributes**

· MAPSUInt32 arbitrationId

The arbitration field for the frame (11 or 29 bits)

bool isRemote

Is this a remote frame ?

MAPSInt8 dataLength

The number of bytes in the frame, ranging from 1 to 8.

• MAPSUInt8 data [8]

The n bytes of data (1<n<8)

### **Static Public Attributes**

• static const MAPSUInt32 ExtendedId

The constant to "or" with arbitrationId if EXTENDED identifier is to be used.

• static const MAPSUInt32 StandardId

A 0 constant for STANDARD identifiers.

static const MAPSUInt32 AddressMask

The mask to use in order to get the id from arbitrationId member.

# 10.9.1 Detailed Description

CAN Frames structure. This is the RTMaps standard CAN frame type. It contains all the necessary members to describe completely a frame on a CAN bus


The documentation for this struct was generated from the following file:

• maps.hpp

# 10.10 MAPSCircle Struct Reference

The MAPSCircle structure.

Inheritance diagram for MAPSCircle:



# **Public Attributes**

• int x

The x-center of the circle.

• int y

The y-center of the circle.

· int radius

The radius of the circle.

# 10.10.1 Detailed Description

The MAPSCircle structure.

The documentation for this struct was generated from the following file:

• maps.hpp

# 10.11 MAPSComplex Struct Reference

Complex number structure.

# **Public Attributes**

· MAPSFloat r

Real part.

• MAPSFloat i

Imaginary part.

# 10.11.1 Detailed Description

Complex number structure. This is the RTMaps standard structure for complex numbers handling


The documentation for this struct was generated from the following file:

• maps.hpp

# 10.12 MAPSComponent Class Reference

The base class for all RTMaps components.

Inheritance diagram for MAPSComponent:



# **Public Member Functions**

- virtual void Set (MAPSProperty &p, bool value)
   Sets boolean value from boolean property p.
- virtual void Set (MAPSProperty &p, MAPSInt64 value)
   Sets integer value from integer property p.
- virtual void Set (MAPSProperty &p, MAPSFloat value)
   Sets float value from float property p.
- virtual void Set (MAPSProperty &p, const MAPSString &value)
   Sets string value from string property p.
- virtual void Set (MAPSProperty &p, const MAPSEnumStruct &enumStruct)

  Sets enum struct enumStruct from enum property p.
- void Start ()

Starts the component.

void SetAutomaticStart (bool s)

Sets automatic start mode.

# **Protected Member Functions**

MAPSInput & NewInput (int model, const char \*name=NULL)
 Dynamically creates an input.

MAPSInput & NewInput (const char \*model, const char \*name=NULL)
 Dynamically creates an input.

MAPSOutput & NewOutput (int model, const char \*name=NULL)
 Dynamically creates an output.

MAPSOutput & NewOutput (const char \*model, const char \*name=NULL)
 Dynamically creates an output.

MAPSProperty & NewProperty (int model, const char \*name=NULL)
 Dynamically creates a property.

- MAPSProperty & NewProperty (const char \*model, const char \*name=NULL)
   Dynamically creates a property.
- MAPSAction & NewAction (int model, const char \*name=NULL)

  Dynamically creates an action.
- MAPSAction & NewAction (const char \*model, const char \*name=NULL)
   Dynamically creates an action.
- void CreateThread (MAPSThreadFunction)
   Creates a new thread and associates it to the component.
- virtual void FreeBuffers ()
   Frees the output buffers.
- void CommitSuicide (void)

Must be called by the component itself.

- void CallDynamic ()
   Dynamic behaviour support.
- void DynamicConfirm ()
   Confirms all previously created inputs, outputs, actions and properties.

# **User provided functions**

- virtual void Dynamic (void)
   User provided function for dynamic input/output/property generation.
- virtual void Core (void)=0
   The component main function. Its brain.
- virtual void Birth (void)

The Birth function.

virtual void Banzai (void)

The Banzai function.

· virtual void Death (void)

The Death function.

# 10.12.1 Detailed Description

The base class for all RTMaps components. Some useful macros are available for easier development of components. They are detailed in Component design.

### 10.12.2 Member Function Documentation

```
10.12.2.1 virtual void MAPSComponent::Banzai (void ) [protected, virtual]
```

The Banzai function.

It is called as soon as someone asks the component to die. Must be defined only in very rare cases (generally when we need to kill a blocked on hardware related thread). For experts only.

```
10.12.2.2 virtual void MAPSComponent::Birth ( void ) [protected, virtual]
```

The Birth function.

Called only once, just before the first call to Core, when the component starts. Note that the birth function is executed in the very same thread as the Core function.

```
10.12.2.3 void MAPSComponent::CallDynamic() [protected]
```

Dynamic behaviour support.

Can be called so that inputs or outputs can be dynamically changed according to a user-supplied Dynamic() function

```
10.12.2.4 virtual void MAPSComponent::Core ( void ) [protected, pure
    virtual]
```

The component main function. Its brain.

Must be overloaded. Obviously.

In threaded mode, the code in Core() is executed in the main thread of the component, the one created automatically. In sequential mode, the code in Core() is executed each time data arrives on one of the component inputs.

```
10.12.2.5 void MAPSComponent::CreateThread ( MAPSThreadFunction ) [protected]
```

Creates a new thread and associates it to the component.

Takes the function to execute in parameter. This function takes itself no parameter, but is a function of an object, so the this pointer to this object is given as a hidden parameter.

MAPSThreadFunction is defined as:

```
typedef void (MAPSModule::*MAPSThreadFunction)(void);
```

To ensure portability, if the thread function is a member of MAPSMyComponentClass, it must be called like this:

```
CreateThread((MAPSThreadFunction)&MAPSMyComponentClass::memberFunction);
```

Reimplemented from MAPSModule.

```
10.12.2.6 virtual void MAPSComponent::Death ( void ) [protected, virtual]
```

The Death function.

Called when the component dies, after the call the Banzai() and the death of all threads. The Death function is executed in the very same thread as the Core function.

```
10.12.2.7 virtual void MAPSComponent::Dynamic (void ) [protected, virtual]
```

User provided function for dynamic input/output/property generation.

If your component dynamically creates inputs, outputs or properties through some calls to MAPSComponent::NewInput, ..., these calls must be made in a Dynamic() overloaded function, so that the RTMaps engine can update its view of the component. By default, confirm any previous inputs, outputs, properties and actions creation.

```
10.12.2.8 void MAPSComponent::DynamicConfirm ( ) [protected]
```

Confirms all previously created inputs, outputs, actions and properties.

Can be called in Dynamic(), if no change is detected.

```
10.12.2.9 virtual void MAPSComponent::FreeBuffers() [protected, virtual]
```

Frees the output buffers.

Note that this can be overloaded for very specific buffer allocations, like allocation of frames in DMA memory (by frame grabbers).

```
10.12.2.10 MAPSAction& MAPSComponent::NewAction ( int model, const char * name = NULL ) [protected]
```

Dynamically creates an action.

### **Parameters**

model	model number (its order in the MAPS_ACTIONS_DEFINITION description)
name	the name for the new action. If NULL, the model name is used.

# Returns

A reference to the newly created MAPSAction object.

Dynamically creates an action.

### **Parameters**

model	model name (its name in the MAPS_ACTIONS_DEFINITION description)
name	the name for the new action. If NULL, the model name is used.

# Returns

A reference to the newly created MAPSAction object.

# 10.12.2.12 MAPSInput& MAPSComponent::NewInput ( const char \* model, const char \* name = NULL ) [protected]

Dynamically creates an input.

# **Parameters**

model	model name (its name in the MAPS_INPUTS_DEFINITION description)
name	the name for the new input. If $\mathtt{NULL}$ , the model name is used.

### **Returns**

A reference to the newly created MAPSInput object.

Dynamically creates an input.

### **Parameters**

model	model number (its order in the MAPS_INPUTS_DEFINITION description)
name	the name for the new input. If NULL, the model name is used.

### Returns

A reference to the newly created MAPSInput object.

```
10.12.2.14 MAPSOutput& MAPSComponent::NewOutput ( int model, const char * name = NULL ) [protected]
```

Dynamically creates an output.

# **Parameters**

model	model number (its order in the MAPS_OUTPUTS_DEFINITION description)
name	the name for the new output. If $\mathtt{NULL}$ , the model name is used.

# Returns

A reference to the newly created MAPSOutput object.

```
10.12.2.15 MAPSOutput& MAPSComponent::NewOutput ( const char * model, const char * name = NULL ) [protected]
```

Dynamically creates an output.

# **Parameters**

model	model name (its name in the MAPS_OUTPUTS_DEFINITION description)
name	the name for the new output. If $\mathtt{NULL}$ , the model name is used.

### Returns

A reference to the newly created MAPSOutput object.

# 10.12.2.16 MAPSProperty& MAPSComponent::NewProperty ( const char \* model, const char \* name = NULL ) [protected]

Dynamically creates a property.

### **Parameters**

model	model name (its name in the MAPS_PROPERTIES_DEFINITION description)
name	the name for the new property. If $\mathtt{NULL}$ , the model name is used.

### **Returns**

A reference to the newly created MAPSProperty object.

# 10.12.2.17 MAPSProperty& MAPSComponent::NewProperty ( int *model*, const char \* *name* = NULL ) [protected]

Dynamically creates a property.

### **Parameters**

model	model number (its order in the MAPS_PROPERTIES_DEFINITION description)
name	the name for the new property. If $\mathtt{NULL}$ , the model name is used.

### **Returns**

A reference to the newly created MAPSProperty object.

### 10.12.2.18 void MAPSComponent::SetAutomaticStart (bool s)

Sets automatic start mode.

Usually, a component starts automatically on general run, or when the system is already running on creation. Sometimes, this is not the case, One wants to start the component later.

### See also

MAPS::CreateComponent

# 10.12.2.19 void MAPSComponent::Start ( )

Starts the component.

A component is started automatically if RTMaps is running, except when start is set to false in the call to MAPS::CreateComponent. If so, a call to Start is necessary to effectively start the component.

Reimplemented from MAPSModule.

The documentation for this class was generated from the following file:

• maps.hpp

# 10.13 MAPSCouple < T > Class Template Reference

Template class for couple data.

# **Public Member Functions**

```
• T & first ()
```

Returns a reference to the first element.

• T & second ()

Returns a reference to the second element.

• T & operator[] (int i)

Unsafe! Use it at your own risk.

# **Related Functions**

(Note that these are not member functions.)

```
    template < typename T >
        MAPSStreamedString & operator << (MAPSStreamedString &out, MAPSCouple < T > &c)
        Standard operator.
```

# 10.13.1 Detailed Description

```
template < typename T > class MAPSCouple < T >
```

Template class for couple data.

# 10.13.2 Friends And Related Function Documentation

```
10.13.2.1 template < typename T > MAPSStreamedString & operator << ( MAPSStreamedString & out, MAPSCouple < T > & c ) [related]
```

Standard operator.

The documentation for this class was generated from the following file:

· maps.hpp

# 10.14 MAPSDrawingObject Struct Reference

The MAPSDrawingObject : a standard for simple overlay shapes.

# **Public Attributes**

int kind

Specifies the kind of drawing object.

· int color

Use the MAPS\_RGB macro to set the color of this drawing object.

• int width

A width for the drawing.

• int id

An optional id for the element.

• MAPSLine line

The drawing object is a line.

• MAPSRectangle rectangle

The drawing object is a rectangle.

• MAPSCircle circle

The drawing object is a circle.

MAPSText text

The drawing object is some text.

MAPSSpot spot

The drawing object is a spot.

• MAPSEllipse ellipse

The drawing object is an ellipse.

# **Static Public Attributes**

· static const int Line

One kind of drawing object.

• static const int Rectangle

Another kind of drawing object.

· static const int Circle

Another kind of drawing object.

· static const int Text

Another kind of drawing object.

static const int Spot

Another kind of drawing object.

• static const int Ellipse

Another kind of drawing object.

# **User defined information**

• int misc1

Miscellaneous information 1.

• int misc2

Miscellaneous information 2.

• int misc3

Miscellaneous information 3.

void \* userdata

TO USE WITH CARE! C++ EXPERTS ONLY.

# 10.14.1 Detailed Description

The MAPSDrawingObject: a standard for simple overlay shapes. This structure can also be used as a standard to return sensor information.

The documentation for this struct was generated from the following file:

• maps.hpp

# 10.15 MAPSDrawingObjectVariant Struct Reference

All drawing objects in RTMaps (circles, etc.) inherit from MAPSDrawingObjectVariant. Inheritance diagram for MAPSDrawingObjectVariant:



# 10.15.1 Detailed Description

All drawing objects in RTMaps (circles, etc.) inherit from MAPSDrawingObjectVariant.


The documentation for this struct was generated from the following file:

• maps.hpp

# 10.16 MAPSEllipse Struct Reference

The MAPSEllipse structure.

Inheritance diagram for MAPSEllipse:



# **Public Attributes**

• int x

The x-center of the circle.

• int y

The y-center of the circle.

• int sx

The horizontal size of the ellipse.

• int sy

The vertical size of the ellipse.

# 10.16.1 Detailed Description

The MAPSEllipse structure.

The documentation for this struct was generated from the following file:

· maps.hpp

# 10.17 MAPSEnumStruct Struct Reference

Enumeration structure.

### **Public Member Functions**

MAPSEnumStruct ()

Default constructor: creates an empty enumeration.

• MAPSEnumStruct (const MAPSEnumStruct &enumStruct)

Copy constructor.

• void FromString (const MAPSString &str, const bool selectIndexOnly=false)

Counterparts of MAPSEnumStruct::ToString() unless selectIndexOnly is true; in this case, only the index is changed.

MAPSEnumStruct & operator= (const MAPSEnumStruct &enumStruct)

Assignement operator.

• MAPSInt32 GetSelected () const

Retrieves the index of the selected property.

• bool Select (const MAPSString &value)

Sets selectedEnum to the index of the string value in the collection.

• MAPSString ToString () const

Converts the enumeration and its associated index to a single string.

# **Static Public Member Functions**

static bool IsEnumString (const MAPSString &str)

Returns true if the string argument is a well-formatted enumeration string.

#### **Public Attributes**

• MAPSInt32 selectedEnum

The selection index. -1 means no item has been selected yet.

MAPSArray
 MAPSString > \* enumValues

A pointer to the collection of strings.

# 10.17.1 Detailed Description

Enumeration structure. This structure represents an array of strings with a selection index. The exchange string of a MAPSEnumStruct is like "numberOfItems|selectedItem|item0|item1|...|itemN'

#### 10.17.2 Member Function Documentation

#### 10.17.2.1 bool MAPSEnumStruct::Select ( const MAPSString & value )

Sets selectedEnum to the index of the string value in the collection.

Returns false if value is an invalid choice.

The documentation for this struct was generated from the following file:

• maps.hpp

# 10.18 MAPSEvent Class Reference

The RTMaps event class.

### **Public Member Functions**

• void Set ()

Sets the event.

• void Reset ()

Resets the event.

• int Wait (MAPSDelay timeout=-1)

Waits for the event to be set by another thread.

• bool State ()

Returns the current state of this event.

bool SetTrigger (MAPSDelay delay)

Sets a trigger on this event.

• void ResetTrigger ()

Resets a trigger;.

• HANDLE GetHandle ()

Returns the Windows event handle corresponding to this MAPSEvent (Windows only function)

• MAPSEvent (bool initialState=false, const char \*n=NULL)

The MAPSEvent constructor.

• MAPSEvent (HANDLE h)

Windows specific constructor.

virtual ∼MAPSEvent ()

The MAPSEvent destructor.

#### **Static Public Member Functions**

- static int Wait (int nCount, MAPSEvent \*events[], MAPSDelay timeout=-1)

  Waits for one of a set of events to be set by another thread.
- static int MsgWait (int nCount, MAPSEvent \*events[], MAPSDelay timeout=-1)

  Waits for one event to be set by another thread OR one message to arrive.
- static bool MsgInQueue ()

Tells if there is a message in the queue for this thread.

### **Friends**

• class MAPSWin32

# 10.18.1 Detailed Description

The RTMaps event class. An event is simply a 2-state variable, with wait and delayed set capabilities.

This is one of the most important classes in RTMaps. It is extensively used by the engine to rule all threads switching.

#### 10.18.2 Constructor & Destructor Documentation

#### 10.18.2.1 MAPSEvent::MAPSEvent (bool initialState = false, const char \* n = NULL )

The MAPSEvent constructor.

#### **Parameters**

initialState	Initial state for the event. Default is false.
n	Optionnal name to give to the event.

#### 10.18.2.2 MAPSEvent::MAPSEvent ( HANDLE h )

Windows specific constructor.

Embeds a Windows event in a MAPSEvent. Useful if you want to combine Windows provided event with RTMaps provided events and use the RTMaps MAPSEvent functions to control them.

This a very low-level function, OS-specific, that must be used with care.

#### 10.18.3 Member Function Documentation

#### 10.18.3.1 HANDLE MAPSEvent::GetHandle ( )

Returns the Windows event handle corresponding to this MAPSEvent (Windows only function)

This must be used only for low level RTMaps programming, since this function is OS-specific.

#### 10.18.3.2 static bool MAPSEvent::MsgInQueue( ) [static]

Tells if there is a message in the queue for this thread.

This function has a meaning only for message based operating systems, like Microsoft Windows.

# 10.18.3.3 static int MAPSEvent::MsgWait ( int *nCount*, MAPSEvent \* *events[]*, MAPSDelay *timeout =* -1 ) [static]

Waits for one event to be set by another thread OR one message to arrive.

This function exists only for message based operating systems, like Microsoft Windows. It allows to process some messages while processing some MAPSEvents. This is very useful to make some single-threaded Windows graphical components.

#### 10.18.3.4 void MAPSEvent::ResetTrigger ( )

Resets a trigger;.

This will cancel any previously set trigger.

#### 10.18.3.5 bool MAPSEvent::SetTrigger ( MAPSDelay delay )

Sets a trigger on this event.

This function is very important. It automatically sets the event after the expiry of a given delay. This means that is any thread is waiting on this event, the latter thread will be unblocked after a finite amount of time. This enables the scheduling of threads in RTMaps.

#### Warning

This functions uses multimedia timers. Under windows NT, 2000, XP, the number of multimedia timers is limited to 16. If the function fails, the function returns false.

#### 10.18.3.6 int MAPSEvent::Wait ( MAPSDelay timeout = -1 )

Waits for the event to be set by another thread.

The thread that called Wait will block until the event is set.

#### Warning

This is a very dangerous function since if it is badly used, it may block infinitely your RTMaps system. If you develop some components, please use MAPSComponent::Wait4Event. It is a safe function that will never dead lock your RTMaps system.

```
10.18.3.7 static int MAPSEvent::Wait ( int nCount, MAPSEvent * events[], MAPSDelay timeout = -1 ) [static]
```

Waits for one of a set of events to be set by another thread.

The thread that called Wait will block until one of the events are set.

#### Warning

This is a very dangerous function since if it is badly used, it may block infinitely your RTMaps system. If you develop some components, please use MAPSComponent::Wait4Events. It is a safe function that will never dead lock your RTMaps system.


The documentation for this class was generated from the following file:

• maps.hpp

# 10.19 MAPSFileIO Class Reference

The RTMaps File I/O support class.

Inheritance diagram for MAPSFileIO:



#### Static Public Attributes

• static const char \* Endl

End of line sequence for text files.

#### **Protected Member Functions**

virtual void Unlock (void \*)
 Unlocking function, for asynchronous I/O.

# File I/O flags

Constants to use in MAPSFileIO::OpenFile4Writing and MAPSFileIO::OpenFile4Reading

- static const int Asynchronous
   Sets an asynchronous mode of operation.
- static const int NoBuffering

Sets a no buffering mode of operation. The data are sent directly to disk. No caching.

• static const int Append

Opens the file in append mode. It means that it won't destroy the previous content if the fils existed.

• static const int RandomAccess

Specifies that the file will be accessed from any point. Optimizes the cache management for random access.

static const int SequentialAccess

Specifies that the file will always be accessed sequentially. Optimizes the cache management. (Random access is still possible but slower)

#### Fast file write functions

These functions take full advantage of the underlying OS and they collect automatically some performance data that are very important for the fine tuning of a RTMaps system. Please never use the functions provided by the OS for file I/O.

MAPSFileWriteHandle \* FileOpen4Writing (const char \*name, int options=0)
 Opens a file for writing.

• bool FileWrite (MAPSFileWriteHandle \*fileHandle, const void \*buffer, int size, void \*elt2Unlock=NULL)

Writes data to a file.

 bool FileWriteText (MAPSFileWriteHandle \*fileHandle, const MAPSString &text, bool mayContainCarriageReturns=true)

Writes text data to a file.

• void FileClose (MAPSFileWriteHandle \*fileHandle)

Closes the file.

#### File read functions

(That should have read-ahead capability)

All these functions work synchronously. No asynchronous mode is supported for reading operations.

- MAPSFileReadHandle \* FileOpen4Reading (const char \*name, int options=0)

  Opens a file for reading.
- bool FileRead (MAPSFileHandle \*fileHandle, void \*buffer, int size, int \*nbRead=NULL)

Reads some data from the file.

• void FileClose (MAPSFileReadHandle \*fileHandle)

Closes the file.

# **General purpose functions**

- bool FileSetPos (MAPSFileHandle \*fileHandle, MAPSInt64 pos)
   Sets the file pointer.
- bool FileMovePos (MAPSFileHandle \*fileHandle, int move)

Moves to another position in the file, relative to the current position.

• MAPSInt64 FileGetPos (MAPSFileHandle \*fileHandle)

Returns the current position of the file pointer in the file.

 bool FileNextLine (MAPSFileHandle \*fileHandle, MAPSString &record, MAPSInt64 \*oldPos=NULL)

Returns the next line in the text file.

 bool FilePreviousLine (MAPSFileHandle \*fileHandle, MAPSString &record, MAPSInt64 \*oldPos=NULL)

Returns the previous line in the text file.

 bool FileFind (MAPSFileHandle \*fileHandle, const MAPSString &lookFor, char delimiter=0, MAPSInt64 \*pos=NULL)

Finds a string in a file.

 bool FileFind (MAPSFileHandle \*fileHandle, const MAPSString &lookFor, MAPSString &result, char delimiter=0, MAPSInt64 \*pos=NULL)

Finds a string in a file.

• bool FileRewind (MAPSFileHandle \*fileHandle)

Rewinds the file.

• bool FileGo2End (MAPSFileHandle \*fileHandle)

Goes to the end of the file.

• MAPSInt64 FileSize (MAPSFileHandle \*fileHandle)

Returns the size of the file.

#### **Error management functions**

• void FileWriteError ()

Called when a write error occurs. Gets an explanation to the OS and reports it.

void FileReadError ()

Called when a read error occurs. Gets an explanation to the OS and reports it.

#### 10.19.1 Detailed Description

The RTMaps File I/O support class. Provides the functions that any RTMaps module MUST use so that it can properly run in the RTMaps environment. Please forget about fopen and fclose stuff.

#### 10.19.2 Member Function Documentation

# 10.19.2.1 void MAPSFilelO::FileClose ( MAPSFileWriteHandle \* fileHandle ) [protected]

Closes the file.

#### **Parameters**

fileHandle Specifies the file to close
--

# 10.19.2.2 void MAPSFilelO::FileClose ( MAPSFileReadHandle \* fileHandle ) [protected]

Closes the file.

#### **Parameters**

fileHandle	Specifies the file to close

# 10.19.2.3 bool MAPSFileIO::FileNextLine ( MAPSFileHandle \* fileHandle, MAPSString & record, MAPSInt64 \* oldPos = NULL ) [protected]

Returns the next line in the text file.

Removes the line feed/carriage return character from the read line of text.

# 10.19.2.4 MAPSFileReadHandle\* MAPSFilelO::FileOpen4Reading ( const char \* name, int options = 0 ) [protected]

Opens a file for reading.

#### **Parameters**

name	The name of the file to open
options	Can be a combination of the following flags:
	<ul> <li>RandomAccess: Optimization flag. Specifies that the file will be accessed from any point.</li> </ul>
	<ul> <li>SequentialAccess: Optimization flag. Specifies that the file will always be accessed sequentially.</li> </ul>

#### Returns

The file handle that can be used with fileReadXXX functions. Returns  ${\tt NULL}$  is the file does not exist.

# 10.19.2.5 MAPSFileWriteHandle\* MAPSFileIO::FileOpen4Writing ( const char \* name, int options = 0 ) [protected]

Opens a file for writing.

#### **Parameters**

name	The file name to create or open
options	Can be a combination of the following flags:
	<ul> <li>Asynchronous: Sets an asynchronous mode of operation. This means that all write operations will return immediately, before the write operation has really finished. With this mode of operation, you must specify an element to unlock (parameter elt2Unlock) to any write operation, so that RTMaps can know when the data can be disposed of.</li> <li>NoBuffering: Sets a no buffering mode of operation. This mode is very</li> </ul>
	fast on Windows NT/2000 for huge transfers to disk. It does not use any cache (so saves many memory transfers) but puts the data directly on the disk. Note that the size of the data must be proportional to the size of sector on the disk.
	<ul> <li>Append: Tells not to overwrite the file if it already exists, but to append any new data to the end of the file.</li> </ul>
	<ul> <li>RandomAccess: Optimization flag. Specifies that the file will be accessed from any point.</li> </ul>
	<ul> <li>SequentialAccess: Optimization flag. Specifies that the file will always be accessed sequentially.</li> </ul>

#### Returns

The file handle that can be used with fileWriteXXX functions. Returns  $\mathtt{NULL}$  is the file creation or opening failed.

Note that this function also opens the file for reading too.

10.19.2.6 bool MAPSFilelO::FilePreviousLine ( MAPSFileHandle \* fileHandle, MAPSString & record, MAPSInt64 \* oldPos = NULL ) [protected]

Returns the previous line in the text file.

Removes the line feed/carriage return character from the read line of text.

10.19.2.7 bool MAPSFilelO::FileRead ( MAPSFileHandle \* fileHandle, void \* buffer, int size, int \* nbRead = NULL ) [protected]

Reads some data from the file.

#### **Parameters**

fileHandle	Specifies the file to read from

buffer	Specifies the buffer to transfer the read bytes to
size	Max size of data to read
nbRead	Pointer to a variable that will get the resulting number of read bytes. If set to
	$\mathtt{NULL}$ , the function will not return this information. If $*nbRead$ is 0 and the
	function returns true, then the end of file was reached before the call to
	the function.

#### Returns

Returns false if an error was detected. Note that if the end of file is reached, this function returns true, but the nbRead result may be less than size.

10.19.2.8 bool MAPSFilelO::FileWrite ( MAPSFileWriteHandle \* fileHandle, const void \* buffer, int size, void \* elt2Unlock = NULL ) [protected]

Writes data to a file.

#### **Parameters**

fileHandle	Specifies the file to write to
buffer	Specifies where the data must be taken from
size	The size of data to write
elt2Unlock	The function automatically calls MAPSFileIO::Unlock with this parameter when the file write has finished. Should be NULL with synchronous write operations.

#### Returns

true if the operation has succeeded, false otherwise.

10.19.2.9 bool MAPSFilelO::FileWriteText ( MAPSFileWriteHandle \* fileHandle, const MAPSString & text, bool mayContainCarriageReturns = true ) [protected]

Writes text data to a file.

# Parameters

fileHandle	Specifies the file to write to
text	The string to write to the file
mayContain-	Indicates that the string may contains '\n' characters. If so, RTMaps will
CarriageRe-	convert all '\n' characters to the MAPSFileIO::Endl string which depends
turns	on the underlying operating system, so that the resulting text file can be
	read with a text editor. If you do know that your file does not contain '\n'
	characters, set this parameter to false and RTMaps will spare some time as
	it will not try to find out the '\n' in your string.

#### Returns

true if the operation has succeeded, false otherwise.

#### 10.19.2.10 virtual void MAPSFilelO::Unlock (void \* ) [protected, virtual]

Unlocking function, for asynchronous I/O.

Default implementation: do nothing

#### 10.19.3 Member Data Documentation

```
10.19.3.1 const char* MAPSFileIO::Endl [static]
```

End of line sequence for text files.

The presence of the carriage return ('\r') character depends on the OS. This sequence of characters defines the behaviour for text files in RTMaps.

For linux and QNX, this is set to '\n'.

For the Windows operating systems, this is set to '\r\n'

The documentation for this class was generated from the following file:

• maps.hpp

# 10.20 MAPSFileReadHandle Class Reference

The class that is used to manage all RTMaps read file operations.

Inherits MAPSFileHandle.

#### **Friends**

class MAPSFileIO

### 10.20.1 Detailed Description

The class that is used to manage all RTMaps read file operations.

The documentation for this class was generated from the following file:

• maps.hpp

# 10.21 MAPSFileWriteHandle Class Reference

The class that is used to manage all RTMaps write file operations. Inherits MAPSFileHandle.

#### **Friends**

class MAPSFileIO

# 10.21.1 Detailed Description

The class that is used to manage all RTMaps write file operations.

The documentation for this class was generated from the following file:

• maps.hpp

# 10.22 MAPSHashTable < TKey, TContent, H > Class Template Reference

Inherits MAPSBasicHashTable.

#### **Public Member Functions**

- void SetAutoAdjust (const bool x)
  - Sets the auto size adjustment behaviour of the hash table.
- int HashSize () const

Returns the size of the hash table.

• int Size () const

Returns the number of elements currently in the hash table.

• int NbElts () const

Returns the number of elements currently in the hash table.

• float Efficiency () const

Computes the number of buckets per stored element. When < 1, the hash table should be resized.

· void Insert (const TKey &key, const TContent &content)

Inserts element content with key key into the hash table.

TContent & Insert (const TKey &key)

Inserts a new element with key key into the hash table. Returns a reference to the content that you can further set up.

TContent \* Lookup (const TKey &key) const

Finds the element with key key. Returns NULL if that element cannot be found in the hash table.

• TContent Remove (const TKey &key)

Returns the element the key of which is key and removes it from the hash table.

MAPSHashTable & operator-= (const TKey &key)

Removes element the key of which is key and returns the hash table itself (faster than Remove())

TContent Remove (MAPSHashTableIterator &it)

Removes element corresponding to iterator it from the hash table, and returns its content.

MAPSHashTable & operator-= (MAPSHashTableIterator &it)

Removes element corresponding to iterator it from the hash table. Returns the hash table itself (faster than Remove())

MAPSHashTableIterator Iterator () const

Returns a new iterator.

void \* End () const

STL-like End()

• TKey & Key (const MAPSHashTableIterator &it) const

Returns the current key of an iterator.

• TContent & Content (const MAPSHashTableIterator &it) const

Returns the current content of an iterator.

TContent & operator[] (const MAPSHashTableIterator &it) const

Returns the current content of an iterator.

MAPSPair < TKey, TContent > & Pair (const MAPSHashTableIterator &it) const

Returns the current pair (key, content) of an iterator.

• MAPSHashTableIterator & Next (MAPSHashTableIterator &it) const

Iterates...

• void Resize (const int size)

Resizes the hash table to size (number of buckets)

• bool Adjust ()

Adjusts the size of the hash table if needed (smart function): double the current size of the hash while the efficiency is <1.

void Clear (const int n=16)

Clears the content of the hash table.

MAPSHashTable (const int n=16, const bool adjust=true)

Constructor.

#### 10.22.1 Detailed Description

template < typename TKey, typename TContent, typename H > class MAPSHashTable < TKey, TContent, H >

The RTMaps hash table class. You should not expect any order of the items. Hash table initialization example :

```
MAPSHashTable<MAPSString, int, MAPSStringHashFunction> hash_table(1000);
```

Here is an example of hash table use:

```
MAPSStringHashTable<int> HashTable(500);
HashTable.Insert("Hello",20);
HashTable.Insert("World",30);
HashTable.Insert("!",40);
int *res=HashTable.Lookup("Hello");
std::cout<<"res : "<<*res<<std::endl;
res=HashTable.Lookup("World");
std::cout<<"res : "<<*res<<std::endl;
HashTable.Remove("Hello");
res=HashTable.Lookup("Hello"); // Now res is NULL
MAPSHashTableIterator it(HashTable);
while (it) {
    std::cout<<HashTable.Key(it)<<" = "<<HashTable.Content(it)<<std::endl;
    it++;
}</pre>
```

#### 10.22.2 Constructor & Destructor Documentation

10.22.2.1 template < typename TKey , typename TContent , typename H > MAPSHashTable < TKey, TContent, H >::MAPSHashTable ( const int n = 16, const bool adjust = true ) [explicit]

Constructor.

#### **Parameters**

n must be set so that the number of elements that will be put in the hash table should be less than 3\*n, unless the hash table will work but will lose its efficiency. The default value for n is 16. We strongly recommend that you provide your own convenient value.

when set to true, the size of the hash table is automatically adjusted when needed with Adjust() function.

#### 10.22.3 Member Function Documentation

10.22.3.1 template < typename TKey , typename TContent , typename H > void MAPSHashTable < TKey, TContent, H >::Clear ( const int n = 16 )

Clears the content of the hash table.

#### **Parameters**

п	Same	as	n	parameter	in	the	constructor	MAP-
	SHashTa	ble::M/	APSH	ashTable(int,bo	ol)			

# 10.22.3.2 template<typename TKey, typename TContent, typename H> void MAPSHashTable< TKey, TContent, H>::Insert ( const TKey & key, const TContent & content )

Inserts element content with key key into the hash table.

#### Warning

This function does not check if an element with the same key exists. If it happens to be the case, the hash table content will be inconsistent.

# 10.22.3.3 template<typename TKey, typename TContent, typename H > TContent & MAPSHashTable < TKey, TContent, <math>H > ::Insert (const TKey & key)

Inserts a new element with key *key* into the hash table. Returns a reference to the content that you can further set up.

#### Warning

This function does not check if an element with the same key exists. If it happens to be the case, the hash table content will be inconsistent.

# 10.22.3.4 template<typename TKey, typename TContent, typename H> MAPSHashTableIterator& MAPSHashTable< TKey, TContent, H>::Next ( MAPSHashTableIterator & it) const

Iterates...

Note that the elements in the hash table are NOT sorted.

The documentation for this class was generated from the following file:

• maps.hpp

# 10.23 MAPSHashTableIterator Class Reference

The RTMaps hash table iterator.

#### **Public Member Functions**

• MAPSHashTableIterator & operator++ ()

The ++ operator: goes to the next element in the associated hash table.

• MAPSHashTableIterator operator++ (int)

The ++ operator: goes to the next element in the associated hash table.

• void Reset ()

Resets the iterator.

• MAPSHashTableIterator ()

Default constructor. Not that you cannot use the iterator directly. You must associate it to a hash table through a call to MAPSHashTable::Iterator or MAPSHashTable::Next.

• MAPSHashTableIterator (const MAPSBasicHashTable &hash\_table)

Another constructor that associates this iterator to a hash table.

# 10.23.1 Detailed Description

The RTMaps hash table iterator.

The documentation for this class was generated from the following file:

• maps.hpp

# 10.24 MAPSImage Struct Reference

The RTMaps Image type.

#### **Public Attributes**

• MAPSInt32 width

The width of the image in pixels.

MAPSInt32 height

The height of the image in pixels.

• MAPSInt32 imageSize

The number of bytes the stored image actually consumes.

• MAPSInt32 bufferSize

The number of bytes allocated in the buffer.

void \* imageId

Points to an identifier for the image.

void \* imageld2

Supplements imageld.

char \* imageData

Points to the actual bytes composing the image.

- char imageCoding [4]
  - 4 characters describing the coding used for the image
- char imageType [4]

4 characters that supplement imageCoding (generally "COLR" or "MONO")

#### 10.24.1 Detailed Description

The RTMaps Image type. The IpIImage structure must be preferably used when dealing with images, since these structures can be directly used with the IPL (Image Processing Library) or the CV lib (Open Source Computer Vision Library).

However, the IpIImage structure was not designed to contain some compressed images or some images coded neither pixel or planar oriented (for instance YUYV images). To deal with these kind of images, the MAPSImage structure should be used.

The MAPSImage structure is much simpler than the IpIImage structure: it retains only the main parameters, i.e. the width or the height of the image, and the imageSize parameters. Some new members appeared:

- · bufferSize, which contains the size in bytes of the buffer actually allocated
- · imageld, that can point to an identifier of the content, for instance a string.
- · imageld2, which can supplement imageld
- imageCoding, which can contain four characters specifying the coding used for the image, for instance "JPEG" or "YUYV"
- imageType, which can supplement imageCoding. Generally, it is "COLR" or "MONO"

#### See also


**IplImage** 

The documentation for this struct was generated from the following file:

· maps.hpp

# 10.25 MAPSImageProcessing1Src1Dest Class Reference

Image Processing component base class with 1 input and 1 output images. Inheritance diagram for MAPSImageProcessing1Src1Dest:



# 10.25.1 Detailed Description

Image Processing component base class with 1 input and 1 output images.

The documentation for this class was generated from the following file:

• MAPSImageProcessing1Src1Dest.h

# 10.26 MAPSImageProcessing1Src1DestDefinition Struct Reference

Definition structure for an image processing algorithm (1 Src 1 Dest operation).

#### **Public Attributes**

- · int transform
  - Algorithm identifier.
- const char \* str

  Algorithm name.
- int nbIntParams

Required number of integer parameters for this algorithm.

int nbDoubleParams

Required number of double parameters for this algorithm.

const char \* colorModel

Output color model for auto-allocation feature.

· int nbClicksUsed

Specify the number of 2D points the algorithm may expect.

# 10.26.1 Detailed Description

Definition structure for an image processing algorithm (1 Src 1 Dest operation).

The documentation for this struct was generated from the following file:

• MAPSImageProcessing1Src1Dest.h

# 10.27 MAPSImageProcessing1Src1DestParams Struct Reference

Parameter structure for an image processing algorithm (1 Src 1 Dest operation).

#### **Public Attributes**

int \* intParams

Integer parameters array.

• int nbIntParams

Number of integer parameters in the intParams array.

double \* dblParams

Double parameters array.

• int nbDblParams

Number of double parameters in the dblParams array.

• MAPSPoint2D \* clicks

2D points array.

• int nbClicks

Number of 2D points in the clicks array.

MAPSTimestamp ts

Timestamp of input image.

MAPSTimestamp toi

TimeOflssue of input image.

# 10.27.1 Detailed Description


Parameter structure for an image processing algorithm (1 Src 1 Dest operation).

The documentation for this struct was generated from the following file:

• MAPSImageProcessing1Src1Dest.h

# 10.28 MAPSImageProcessing2Src1Dest Class Reference

Image Processing component base class with 2 input and 1 output images. Inheritance diagram for MAPSImageProcessing2Src1Dest:



# 10.28.1 Detailed Description

Image Processing component base class with 2 input and 1 output images.

The documentation for this class was generated from the following file:

• MAPSImageProcessing2Src1Dest.h

# 10.29 MAPSImageProcessing2Src1DestDefinition Struct Reference

Definition structure for an image processing algorithm (2 Src 1 Dest operation).

### **Public Attributes**

int transform

Algorithm identifier.

• const char \* str

Algorithm name.

• int nbIntParams

Required number of integer parameters for this algorithm.

• int nbDoubleParams

Required number of double parameters for this algorithm.

• const char \* colorModel

Output color model for auto-allocation feature.

· int nbClicksUsed

Specify the number of 2D points the algorithm may expect.

# 10.29.1 Detailed Description

Definition structure for an image processing algorithm (2 Src 1 Dest operation).

The documentation for this struct was generated from the following file:

• MAPSImageProcessing2Src1Dest.h

# 10.30 MAPSImageProcessing2Src1DestParams Struct Reference

Parameter structure for an image processing algorithm (2 Src 1 Dest operation).

#### **Public Attributes**

int \* intParams

Integer parameters array.

· int nbIntParams

Number of integer parameters in the intParams array.

• double \* dblParams

Double parameters array.

· int nbDblParams

Number of double parameters in the dblParams array.

• MAPSPoint2D \* clicks

2D points array.

· int nbClicks

Number of 2D points in the clicks array.

· MAPSTimestamp ts [2]

Timestamps of input images (array of 2 timestamps)

• MAPSTimestamp toi [2]

TimeOflssues of input images (array of 2 timestamps)

# 10.30.1 Detailed Description

Parameter structure for an image processing algorithm (2 Src 1 Dest operation).

The documentation for this struct was generated from the following file:

• MAPSImageProcessing2Src1Dest.h

# 10.31 MAPSInput Class Reference

The RTMaps Module Input class.

#### **Public Member Functions**

- virtual bool IsConnected ()=0
   Returns true if the input is connected to another component output.
- virtual MAPSOutput \* ConnectedOutput ()=0
   Returns a pointer to the output (of type MAPSOutput) connected to this input.
- virtual MAPSTypeInfo & Type ()=0
   Gets the type of the output to which this input is connected.
- virtual MAPSString & Name ()=0

  Returns the name of the input.
- virtual const char \* ShortName ()=0
   Returns the short name of the input.
- virtual bool DataAvailableInFIFO ()=0
   Checks if any data is available in the FIFO connected to this input.

# 10.31.1 Detailed Description

The RTMaps Module Input class.

#### 10.31.2 Member Function Documentation

```
10.31.2.1 virtual MAPSOutput* MAPSInput::ConnectedOutput( ) [pure virtual]
```

Returns a pointer to the output (of type MAPSOutput) connected to this input.

Returns NULL if no output is connected

```
10.31.2.2 virtual bool MAPSInput::IsConnected() [pure virtual]
```

Returns true if the input is connected to another component output.

It is useless to try to get some data from an input that is not connected.

#### See also

MAPSComponent::StartReading

```
10.31.2.3 virtual MAPSString& MAPSInput::Name( ) [pure virtual]
```

Returns the name of the input.

In the form componentName.inputName

```
10.31.2.4 virtual const char* MAPSInput::ShortName( ) [pure virtual]
```

Returns the short name of the input.

This is the name after the dot

```
10.31.2.5 virtual MAPSTypeInfo& MAPSInput::Type( ) [pure virtual]
```

Gets the type of the output to which this input is connected.

Note that generally this function is used after a call to MAPSComponent::StartReading, that is after getting some data from the connected output, so that it is not generally necessary to check the connection.


The documentation for this class was generated from the following file:

• maps.hpp

# 10.32 MAPSIntegerHashTable < TContent > Class Template Reference

The RTMaps integer hash table template class.

Inheritance diagram for MAPSIntegerHashTable < TContent >:



#### **Public Member Functions**

MAPSIntegerHashTable (int n=16)
 Constructor.

#### 10.32.1 Detailed Description

 $template {<} typename \ TContent {>} \ class \ MAPSInteger Hash Table {<} \ TContent {>}$ 

The RTMaps integer hash table template class. As its name says, the key is an integer. The documentation for this class was generated from the following file:

· maps.hpp

# 10.33 MAPSIOEIt Class Reference

The RTMaps I/O Buffer Element.

#### **Public Member Functions**

- virtual void \*& Data ()=0
   Returns a pointer to the data contained in the buffer element.
- virtual MAPSTimestamp & TimeOflssue ()=0
   Returns the time of issue of the I/O element.
- virtual MAPSTimestamp & Timestamp ()=0
   Gets/Sets the Timestamp of the data contained in the buffer element.
- virtual MAPSInt32 & VectorSize ()=0
   Gets/Sets the variable size of a vector (must be less than the allocated size (the max size) returned by MAPSIOEIt::Size()
- virtual MAPSInt32 & Size ()=0
   Returns the allocated size for the buffer element.

virtual MAPSInt32 & BufferSize ()=0

Returns the allocated size for the buffer element.

virtual MAPSInt64 & Frequency ()=0

Gets/Sets the frequency of the data contained in the buffer element.

• virtual MAPSInt32 & Quality ()=0

Gets/Sets the quality of the data contained in the buffer element.

• virtual MAPSTypeInfo & Type ()=0

Returns the type of the data contained in the buffer element.

• virtual MAPSInt32 & Integer (int index=0)=0

Gets/Sets the value of the data contained in the buffer element (must be of integer type)

• virtual MAPSInt64 & Integer64 (int index=0)=0

Gets/Sets the value of the data contained in the buffer element (must be of MAPSInt64 type)

• virtual MAPSFloat & Float (int index=0)=0

Gets/Sets the value of the data contained in the buffer element (must be of MAPSFloat type)

virtual char \* Text ()=0

Gets/Sets the text content of the data contained in the buffer element (must be of TextAscii type)

• virtual char \* TextAscii ()=0

Gets/Sets the text content of the data contained in the buffer element (must be of TextAscii type)

• virtual wchar\_t \* TextUnicode ()=0

Gets/Sets the text content of the data contained in the buffer element (must be of TextUnicode type)

• virtual ::IpIImage & IpIImage ()=0

Gets a reference to the data contained in the buffer element (must be of IpIImage type)

• virtual ::MAPSImage & Image ()=0

Gets a reference to the data contained in the buffer element (must be of MAPSImage type)

virtual ::MAPSImage & MAPSImage ()=0

Gets a reference to the data contained in the buffer element (must be of MAPSImage type)

virtual MAPSCANFrame & CANFrame (int index=0)=0

Gets a reference to the data contained in the buffer element (must be of MAPSCAN-Frame type)

virtual MAPSMatrix & Matrix ()=0

Gets a reference to the data contained in the buffer element (must be of MAPSMatrix type)

virtual MAPSRealObject & RealObject (int index=0)=0

Gets a reference to the data contained in the buffer element (must be of MAPSRealObject type)

virtual MAPSDrawingObject & DrawingObject (int index=0)=0

Gets a reference to the data contained in the buffer element (must be of MAPS-DrawingObject type)

• virtual MAPSTriangles3D & Triangles3D ()=0

Gets a pointer to the stream packet contained in the buffer element (must be of MAP-STriangles3D type)

virtual MAPSUInt8 \* Stream8 ()=0

Gets a pointer to the stream packet contained in the buffer element (must be of MAPSStream8 type)

• virtual MAPSUInt16 \* Stream16 ()=0

Gets a pointer to the stream packet contained in the buffer element (must be of MAPSStream16 type)

virtual MAPSUInt32 \* Stream32 ()=0

Gets a pointer to the stream packet contained in the buffer element (must be of MAPSStream32 type)

• virtual MAPSInt32 & Misc ()=0

Gets/Sets additional information associated to the buffer element.

• virtual MAPSInt32 & Misc1 ()=0

Gets/Sets additional information associated to the buffer element.

• virtual MAPSInt32 & Misc2 ()=0

Gets/Sets additional information associated to the buffer element.

• virtual MAPSInt32 & Misc3 ()=0

Gets/Sets additional information associated to the buffer element.

• virtual operator char \* ()=0

Casts the data in the buffer element to char\* (only for TestAscii type data)

virtual operator wchar\_t \* ()=0
 Casts the data in the buffer element to wchar\_t\* (only for TestUnicode type data)

virtual operator MAPSInt32 & ()=0
 Casts the data in the buffer element to int& (only for integer type data)

• virtual operator MAPSInt64 & ()=0

Casts the data in the buffer element to MAPSInt 64& (only for MAPSInt64 type data)

virtual operator MAPSFloat & ()=0
 Casts the data in the buffer element to MAPSFloat & (only for MAPSFloat type data)

virtual operator::lpllmage \* ()=0
 Casts the data in the buffer element to lpllmage\* (only for lpllmage type data)

virtual operator::MAPSImage & ()=0
 Casts the data in the buffer element to MAPSImage (only for MAPSImage type data)

virtual operator MAPSCANFrame & ()=0
 Casts the data in the buffer element to MAPSCANFram& (only for MAPSCANFrame type data)

virtual operator MAPSMatrix & ()=0
 Casts the data in the buffer element to MAPSMatrix & (only for MAPSMatrix type data)

virtual operator MAPSRealObject & ()=0
 Casts the data in the buffer element to MAPSRealObject& (only for MAPSRealObject type data)

virtual operator MAPSDrawingObject & ()=0
 Casts the data in the buffer element to MAPSRealObject& (only for MAPSDrawingObject type data)

virtual operator MAPSTriangles3D & ()=0
 Casts the data in the buffer element to MAPSRealObject& (only for MAPSTriangles3D type data)

• virtual int IOEltBufferSizeInBytes (bool \*isMemContiguous)=0

Retrieves the size of the allocated buffer in bytes.

virtual int IOEltUsedSizeInBytes (bool \*isMemContiguous)=0
 Retrieves the size that is actually used in the allocated buffer in bytes.

virtual int Serialize (void \*dest, unsigned int maxSize)=0
 Copies the MAPSIOEIt object to a continuous zone in memory.

virtual int Deserialize (void \*serializedloElt, bool doAllocatelfNecessary=false)=0

Deserializes a memory zone from a serialized MAPSIOEIt to the current MAPSIOEIt.

#### **Static Public Member Functions**

- static int SerializedIOEltSizeInBytes (void \*serializedIoElt)
   Retrieves the memory size needed to deserialize a MAPSIOElt.
- static bool IsDeserializable (void \*serializedIoElt)
   Checks if serializedIoElt can be deserialized in the current MAPSIOEIt.

#### 10.33.1 Detailed Description

The RTMaps I/O Buffer Element. This class is of the highest interest for all RTMaps developers. It's the basic element of communication between RTMaps modules.

#### 10.33.2 Member Function Documentation

```
10.33.2.1 virtual MAPSInt32& MAPSIOEIt::BufferSize( ) [pure virtual]
```

Returns the allocated size for the buffer element.

Returns the allocated size for the buffer element.

The meaning of this info depends on the data type in the buffer :

- For vectors (of integers, MAPSFloat, MAPSCANFrame, MAPSRealObject), sets the max size of the vector
- · For text (TextAscii, TextUnicode), sets the max length of the string in the buffer
- For MAPSMatrix buffers, sets the max size of the matrix, i.e. the max m\*n elements in the matrix.
- For IpIImage buffers, retrieves the max size of the imageData zone of the IpIImage (call to MAPSOutput::AllocOutputBufferIpIImage).
- For MAPSImage buffers, retrieves the max size of the imageData zone of the MAPSImage (call to MAPSOutput::AllocOutputBufferMAPSImage).

#### See also

 $\label{locoutput} MAPSOutput::AllocOutputBufferIpIImage\ MAPSOutput::AllocOutputBufferIpIImage\ MAPSOutput::AllocOutputBufferMAPSImage\ MAPSOutputBufferIpIImage\ MAPSOutput$ 

```
10.33.2.2 virtual void * & MAPSIOEIt::Data ( ) [pure virtual]
```

Returns a pointer to the data contained in the buffer element.

Beware: Do not set this pointer yourself. Please let RTMaps set it itself during buffer allocation. The setting is allowed only for "expert" cases

```
10.33.2.3 virtual int MAPSIOEIt::Deserialize ( void * serializedloElt, bool doAllocatelfNecessary = false ) [pure virtual]
```

Deserializes a memory zone from a serialized MAPSIOEIt to the current MAPSIOEIt.

#### **Parameters**

serialize-	Pointer to the memory zone containing the serialized MAPSIOEIt.
dloElt	

#### Warning

The validity of this pointer cannot be checked entirely. Use it at your own risk.

#### **Parameters**

doAllo-	If true and if the current MAPSIOEIt (the destination one) is not allocated,
cateIfNeces-	the allocation is performed automatically. Deallocation then has to be done
sary	manually by the programmer. Usually let this parameter to false.

```
10.33.2.4 virtual MAPSInt64& MAPSIOEIt::Frequency() [pure virtual]
```

Gets/Sets the frequency of the data contained in the buffer element.

The frequency can be used by replay facilities to perfectly link data packets one to the others, when the time stamping are not accurate enough.

The value of frequency must be set such that 1000 means 1Hz. This implies that no signal slower than 0.001Hz can be considered, but signals with very high frequencies (GHz...) can.

Note that the frequency is considered as a valid value only when the flag MAPS::FrequencyFlag is set in the type specification.

### See also

MAPSIOEIt::Type

```
10.33.2.5 virtual int MAPSIOElt::IOEltBufferSizelnBytes ( bool * isMemContiguous ) [pure virtual]
```

Retrieves the size of the allocated buffer in bytes.

#### **Parameters**

isMemCon-	This boolean is set to true if the data contained in the MAPSIOEIt is kept
tiguous	in a contiguous memory zone. This is not the case for exemple for a MAP-
	SIOEIt containing an IpIImage: the imageData can be stored anywhere in
	memory.

#### Returns

the size of the allocated buffer in bytes, or -1 if the function fails.

# 10.33.2.6 virtual int MAPSIOEIt::IOEItUsedSizeInBytes ( bool \* isMemContiguous ) [pure virtual]

Retrieves the size that is actually used in the allocated buffer in bytes.

#### **Parameters**

isMemCon-	This boolean is set to true if the data contained in the MAPSIOEIt is kept
tiguous	in a contiguous memory zone. This is not the case for exemple for a MAP-
	SIOEIt containing an IpIImage: the imageData can be stored anywhere in
	memory.

#### **Returns**

the size used in the allocated buffer in bytes, or -1 if the function fails.

# 10.33.2.7 static bool MAPSIOElt::IsDeserializable ( void \* serializedloElt ) [static]

Checks if serializedIOEIt can be deserialized in the current MAPSIOEIt.

#### **Parameters**

serialize-	Pointer to the serialized MAPSIOEIt
dloElt	

# 10.33.2.8 virtual MAPSIOElt::operator MAPSFloat &( ) [pure virtual]

Casts the data in the buffer element to MAPSFloat & (only for MAPSFloat type data)

Use MAPSFloat & MAPSIOElt::Float(int index=0) for MAPSFloat vectors

```
10.33.2.9 virtual MAPSIOEIt::operator MAPSInt32 & ( ) [pure virtual]
```

Casts the data in the buffer element to int& (only for integer type data)

Use int& MAPSIOElt::Integer(int index=0) for integer vectors

#### 10.33.2.10 virtual MAPSIOElt::operator MAPSInt64 & ( ) [pure virtual]

Casts the data in the buffer element to MAPSInt 64& (only for MAPSInt64 type data)

Use MAPSInt64& MAPSIOElt::Integer64 (int index=0) for integer64 vectors

```
10.33.2.11 virtual MAPSInt32& MAPSIOEIt::Quality() [pure virtual]
```

Gets/Sets the quality of the data contained in the buffer element.

The quality contains an additional information about the data, for instance a signal/noise ratio or compression ratio.

Note that the quality is considered as a valid value only when the flag MAPS::QualityFlag is set in the type specification.

#### See also

MAPSIOEIt::Type

```
10.33.2.12 virtual int MAPSIOEIt::Serialize ( void * dest, unsigned int maxSize ) [pure virtual]
```

Copies the MAPSIOEIt object to a continuous zone in memory.

#### Warning

Since MAPSIOEIt structure can change with the version of RTMaps, do not use this function for recording purpose: your records may not be compatible with future versions.

#### **Parameters**

dest	Pointer to the destination memory zone. This zone has to be already allocated.
	Determines the size of the memory zone pointed by dest. The function fails
	if the zone is too small to contain the entire MAPSIOEIt.

# Returns

the size of the memory that has been used to serialize the MAPSIOEIt, or -1 if the function fails (*maxSize* is too small for example).

10.33.2.13 static int MAPSIOEIt::SerializedIOEItSizeInBytes ( void 
$$*$$
 serializedIoEIt ) [static]

Retrieves the memory size needed to deserialize a MAPSIOEIt.

sizeof(MAPSIOEIt) is not taken into account there. So add it if you need.

#### **Parameters**

serialize-	Pointer to the serialized MAPSIOEIt
dloElt	

#### Returns

Returns -1 if the function fails.

```
10.33.2.14 virtual MAPSInt32& MAPSIOEIt::Size() [pure virtual]
```

Returns the allocated size for the buffer element.

The meaning of this info depends on the data type in the buffer :

- For vectors (of integers, MAPSFloat, MAPSCANFrame, MAPSRealObject), sets the max size of the vector
- For text (TextAscii, TextUnicode), sets the max length of the string in the buffer
- For MAPSMatrix buffers, sets the max size of the matrix, i.e. the max m\*n elements in the matrix.
- For IpIImage buffers, retrieves the max size of the imageData zone of the IpIImage (call to MAPSOutput::AllocOutputBufferIpIImage).
- For MAPSImage buffers, retrieves the max size of the imageData zone of the MAPSImage (call to MAPSOutput::AllocOutputBufferMAPSImage).

#### See also

MAPSOutput::AllocOutputBuffer MAPSOutput::AllocOutputBufferlpIImage MAPSOutput::AllocOutputBufferMAPSImage

```
10.33.2.15 virtual MAPSTimestamp& MAPSIOEIt::TimeOflssue( ) [pure virtual]
```

Returns the time of issue of the I/O element.

The time of issue is the timestamp corresponding to the instant when the element was issued by the writing component. This might not be the same number as the timestamp of the data itself (which can be older and may have flowed through several components, or which may have been time stamped by a hardware device).

Not that you should not set this variable, since the time of issue time stamping is done automatically by the RTMaps system itself. In fact, setting this parameter can be useful in very "expert" cases.

#### 10.33.2.16 virtual MAPSTimestamp& MAPSIOElt::Timestamp() [pure virtual]

Gets/Sets the Timestamp of the data contained in the buffer element.

The timestamp is the real data time stamping. It is generally set by the acquisition component that grabbed the data.

If you do generate some data in your own components, you can time stamp them at your will, for instance by using "IOElt->Timestamp()=MAPS::CurrentTime()". If you do not timestamp yourself your data, RTMaps will do it for you and the timestamp will match the time of issue timestamp (i.e. the "IOElt->Timestamp()=MAPS::CurrentTime()" is executed within the call to StopWriting).

If you process some data in you own components, do not forget to propagate the timestamp of the incoming data, generally by writing "IOEltWriting->Timestamp()=IOEltReading->Timestamp()". This is very important, because if you never do that, you will not be able to trace back the origin of your data in the data flow.

#### 10.33.2.17 virtual MAPSInt32& MAPSIOEIt::VectorSize() [pure virtual]

Gets/Sets the variable size of a vector (must be less than the allocated size (the max size) returned by MAPSIOEIt::Size()

For variable length vectors, this function allows to set or retrieve the actual size of the vector, as opposed to the max size of the vector (the size allocated in memory for the buffer).

The vector size is automatically set to Size() by RTMaps if you do not set it. This means that the vector is considered by default to be full.

The documentation for this class was generated from the following file:

· maps.hpp

# 10.34 MAPSList < T >:: MAPSIterator Class Reference

Iterator on MAPSList objects.

#### **Public Member Functions**

MAPSIterator ()

Default constructor.

MAPSIterator (const MAPSIterator &iter)

Copy constructor.

• MAPSIterator (const MAPSList< T > &li)

Constructor associated to a MAPSList.

T & operator\* ()

Direct access to the data of the list item.

• bool HasNext ()

Returns true if the iterator has a successor.

• bool End ()

Returns true if the iterator corresponds to the end of the list.

• bool Initialized ()

Returns true if the iterator is associated to a real list item.

· void Reset ()

Puts the iterator in an uninitialized state.

# 10.34.1 Detailed Description

template<typename T> class MAPSList< T>::MAPSIterator

Iterator on MAPSList objects. This is a more efficient alternative to MAPSListIterator. Its usage is close to its STL counterpart. Following is an example that displays the content of a list of int:

```
MAPSList<int> li;
// ... populate li ...
// Get an iterator it on the list li
MAPSList<int>::MAPSIterator it(li);
// And walk through the list
for(;!it.End();++it) {
    std::cout << (*it) << std::endl;
}</pre>
```


The documentation for this class was generated from the following file:

· maps.hpp

# 10.35 MAPSLine Struct Reference

The MAPSLine structure.

Inheritance diagram for MAPSLine:



#### **Public Attributes**

- int x1
  - First point x.
- int y1

First point y.

• int x2

Second point x.

• int y2

Second point y.

# 10.35.1 Detailed Description

The MAPSLine structure.


The documentation for this struct was generated from the following file:

• maps.hpp

# 10.36 MAPSList < T > Class Template Reference

The RTMaps double linked list template class.

Inheritance diagram for MAPSList< T >:



# Classes

class MAPSIterator

Iterator on MAPSList objects.

### **Public Member Functions**

• T & operator[] (MAPSListIterator it) const

Returns the element corresponding to iterator it.

• T & operator[] (int n) const

Returns the nth element in the list (starting from 0)

• MAPSIterator Iter ()

Gets an iterator on the first element of the list.

• MAPSIterator IterFirst ()

Gets an iterator on the first element of the list.

• MAPSIterator IterLast ()

Gets an iterator on the last element of the list.

• void Clear ()

Destroys the content of the list.

MAPSListItem< T > & Item (MAPSListIterator it)

Access to the MAPSListItem from an iterator. Try to avoid this method.

- MAPSListItem< T > & Item (MAPSBasicListItem \*it)

Access to the MAPSListItem from a MAPSBasicListItem\*. Try to avoid this method.

- MAPSList< T > & operator= (const MAPSList< T > &L)
   List duplication.
- MAPSList< T > & operator+= (const MAPSList< T > &L)
   List concatenation.
- void Permutations (MAPSList< MAPSList< T > > &L)

Computes all the possible permutations in a list.

void Couples (MAPSList< MAPSCouple< T >> &L)

Computes all the couples of elements of the list.

void Bubblesort (int(\*compare\_function)(T \*t1, T \*t2))
 Bubblesorts the list.

• MAPSList ()

Default constructor.

virtual ∼MAPSList ()

Destructor.

• MAPSList (const MAPSList< T > &L)

Copy constructor.

# **Related Functions**

(Note that these are not member functions.)

template<typename T >
 MAPSStreamedString & operator<< (MAPSStreamedString &out, MAPSList</li>
 T > &L)
 Standard operator.

#### Adds an element to the list

- MAPSListItem< T > & Insert ()
   Inserts a new empty element in the front of the list (at position 0)
- void PushFront ()
   Inserts a new empty element in the front of the list (at position 0)
- MAPSListIterator Insert (const T &elt)
   Inserts element elt in the front of the list (at position 0)
- void PushFront (const T &elt)
   Inserts element elt in the front of the list (at position 0)
- MAPSListItem < T > & Append ()
   Appends a new empty element to the end of the list (the tail)
- void PushBack ()
   Appends a new empty element to the end of the list (the tail)
- MAPSListIterator Append (const T &elt)
   Appends element elt to the end of the list (the tail)
- void PushBack (const T &elt)
   Appends element elt to the end of the list (the tail)
- MAPSList< T > & operator<< (const T &elt)</li>
   Appends element elt to the end of the list (the tail)

# **Element insertion**

• MAPSListIterator InsertAfter (const MAPSListIterator itx, const T &elt)

Inserts element elt just after the element corresponding to the iterator itx.

MAPSListItem< T > \* InsertAfter (MAPSListItem< T > &it, const T &elt)
 Inserts element elt just after the element corresponding to the iterator itx.

- void InsertAfter (MAPSIterator &it, const T &elt)
   Inserts element elt just after the element corresponding to the iterator itx.
- MAPSListItem< T > & InsertAfter (const MAPSListIterator itx)
   Inserts a new empty element just after the element corresponding to the iterator itx.
- T & InsertAfter (MAPSIterator &it)
   Inserts a new empty element just after the element corresponding to the iterator itx.
- MAPSListIterator InsertBefore (const MAPSListIterator itx, const T &elt)

  Inserts element elt just before the element corresponding to the iterator itx.
- MAPSListItem< T > \* InsertBefore (MAPSListItem< T > &it, const T &elt)
   Inserts element elt just before the list item it.
- void InsertBefore (MAPSIterator &it, const T &elt)
   Inserts element elt just before the element corresponding to the iterator itx.
- MAPSListItem< T > & InsertBefore (MAPSListIterator itx)
   Inserts a new empty element just before the element corresponding to the iterator itx.
- T & InsertBefore (MAPSIterator &it)
   Inserts a new empty element just before the element corresponding to the iterator itx.

### Deletion

- MAPSList< T > & operator== (MAPSListIterator itx)
   Deletes the item corresponding to iterator itx.
- MAPSList< T > & operator = (MAPSList< MAPSListIterator > &L)
   Deletes all the items in list L.
- T Delete (MAPSListIterator itx)
   Deletes the item corresponding to iterator itx.
- void Delete (MAPSIterator &it)
   Deletes the item corresponding to iterator it.
- T Remove (MAPSListIterator it)

  Deletes the item corresponding to iterator it.
- MAPSList< T > & Remove (MAPSList< MAPSListIterator > &L)

Deletes all the items in list L.

• MAPSList< T > & Delete (MAPSList< MAPSListIterator > &L)

Deletes all the items in list L.

• T Pop ()

Removes and returns the last item in the list (Perl-like Pop)

• T Shift ()

Removes and returns the first element in the list (Perl-like Shift)

# **Order manipulation**

MAPSList< T > & Move2End (MAPSListIterator itx)

Moves an item to the end of the list.

• void Move2End (MAPSIterator &it)

Moves an item to the end of the list.

MAPSList< T > & Move2Front (MAPSListIterator itx)

Moves an item to the front of the list.

• void Move2Front (MAPSIterator &it)

Moves an item to the front of the list.

MAPSList
 T > & Swap (MAPSListIterator itx1, MAPSListIterator itx2)

Swaps two items.

• void Swap (MAPSIterator &it1, MAPSIterator &it2)

Swaps two items.

# 10.36.1 Detailed Description

 ${\it template}{<}{\it typename}~{\it T}{>}~{\it class}~{\it MAPSList}{<}~{\it T}{>}$ 

The RTMaps double linked list template class. MAPSLists have now a true iterator MAPSList::MAPSIterator. Future developments should always prefer this iterator to MAPSListIterator when possible. Methods that use MAPSListItem objects should be avoided as direct access to the list item might be removed in the next release.

#### 10.36.2 Member Function Documentation

10.36.2.1 template < typename T > MAPSListItem < T > & MAPSList < T >::Append ( )

Appends a new empty element to the end of the list (the tail)

Prefer MAPSList::PushBack() when possible

10.36.2.2 template < typename T > MAPSListIterator MAPSList< T >::Append (const T & elt)

Appends element elt to the end of the list (the tail)

Prefer MAPSList::PushBack(const T&) when possible

10.36.2.3 template<typename T> MAPSListItem<T>& MAPSList< T>::Insert ( )

Inserts a new empty element in the front of the list (at position 0)

Prefer MAPSList::PushFront() when possible

10.36.2.4 template<typename T> MAPSListIterator MAPSList< T>::Insert ( const T & elt )

Inserts element *elt* in the front of the list (at position 0)

Prefer MAPSList::PushFront(const T&) when possible

10.36.2.5 template<typename T> MAPSListIterator MAPSList< T>::InsertAfter ( const MAPSListIterator itx, const T & elt )

Inserts element elt just after the element corresponding to the iterator itx.

Prefer MAPSList::InsertAfter(MAPSIterator&, const T&) when possible

10.36.2.6 template < typename T > MAPSListItem < T > \* MAPSList < T >::InsertAfter ( MAPSListItem < T > & it, const T & elt )

Inserts element *elt* just after the element corresponding to the iterator *itx*.

Prefer MAPSList::InsertAfter(MAPSIterator&, const T&) when possible

10.36.2.7 template<typename T> MAPSListItem< T> & MAPSList< T>::InsertAfter ( const MAPSListIterator itx )

Inserts a new empty element just after the element corresponding to the iterator itx.

Prefer MAPSList::InsertAfter(MAPSIterator&) when possible

# 10.36.2.8 template<typename T> MAPSListIterator MAPSList< T>::InsertBefore ( const MAPSListIterator itx, const T & elt )

Inserts element elt just before the element corresponding to the iterator itx.

Prefer MAPSList::InsertBefore(MAPSIterator&, const T&) when possible

10.36.2.9 template MAPSListItem< T> 
$$*$$
 MAPSList< T>::InsertBefore ( MAPSListItem< T> &  $it$ , const T &  $elt$  )

Inserts element *elt* just before the list item *it*.

Prefer MAPSList::InsertBefore(MAPSIterator&, const T&) when possible

10.36.2.10 template < typename T > MAPSListItem < T > & MAPSList < T > ::InsertBefore ( MAPSListIterator 
$$itx$$
 )

Inserts a new empty element just before the element corresponding to the iterator itx.

Prefer MAPSList::InsertBefore(MAPSIterator&) when possible

# 10.36.3 Friends And Related Function Documentation

Standard operator.


The documentation for this class was generated from the following file:

maps.hpp

# 10.37 MAPSListItem < T > Class Template Reference

The list item template class.

Inheritance diagram for MAPSListItem< T >:



# 10.37.1 Detailed Description

```
template<typename T> class MAPSListItem< T>
```

The list item template class. Should be only for internal use.

The documentation for this class was generated from the following file:

· maps.hpp

# 10.38 MAPSListIterator Class Reference

The list iterator class.

# **Public Member Functions**

• MAPSListIterator & operator++ ()

Prefix increment operator. Increments iterator and returns the new iterator.

• MAPSListIterator operator++ (int)

Postfix increment operator. Increments iterator and returns the old iterator.

• MAPSListIterator & operator-- ()

Prefix decrement operator. Decrements iterator and returns the new iterator.

• MAPSListIterator operator-- (int)

Postfix decrement operator. Decrements iterator and returns the old iterator.

MAPSListIterator operator= (MAPSBasicListItem \*p)

Replaces the current list item by p.

bool operator== (MAPSBasicListItem \*p)

Ckecks if two list items are the same item (not only have the same content)

• MAPSListIterator ()

Default constructor.

MAPSListIterator (MAPSBasicListItem \*p)

Constructor from a basic list item p.

MAPSListIterator (MAPSBasicList &list)

Initializes the iterator to the first item of a MAPSBasicList or NULL if list is empty.

#### 10.38.1 Detailed Description

The list iterator class. Use this iterator in conjunction with MAPSBasicList or MAPSList.

The documentation for this class was generated from the following file:

• maps.hpp

# 10.39 MAPSMatrix Struct Reference

MATLAB-Like matrix (Complex and columnwise, like in fortran)

#### **Public Member Functions**

- MAPSFloat64 & Real (int row, int column)
   Gives access to the real part of one element of the matrix.
- MAPSFloat64 & Im (int row, int column)
   Gives access to the imaginary part of one element of the matrix.
- void Zero ()

Sets all the elements of a matrix to zero.

• void Free ()

Frees the real and imaginary part arrays. Called by the destructor.

- void Alloc (int mm, int nn)
   Allocates the real and imaginary part arrays.
- MAPSMatrix & operator= (MAPSMatrix2 < double > &mat)
   Copy operator, from a MAPSMatrix2 (easier to use)
- MAPSMatrix & operator= (MAPSMatrix &mat)
   Copy operator, from another MAPSMatrix.
- operator MAPSMatrix2< double > () const
   Cast to MAPSMatrix2. Very useful to process MAPSMatrix in input of components.
- MAPSMatrix ()

Creates a non allocated MAPSMatrix. Size is set by default to 0.

- MAPSMatrix (MAPSMatrix2 < double > &mat)
   Constructor that takes a MAPSMatrix2 in input.
- MAPSMatrix (MAPSMatrix &mat)

Copy constructor.

• MAPSMatrix (int mm, int nn)

Creates an allocated MAPSMatrix. Arrays are not initialized.

virtual ∼MAPSMatrix ()

Destructor.

#### **Public Attributes**

MAPSInt32 m

Number of rows in the matrix.

MAPSInt32 n

Number of columns in the matrix.

MAPSFloat64 \* pr

Real part. Array of double.

MAPSFloat64 \* pi

Imaginary part. Array of double.

bool owner

Determines if the memory was allocated by the component itself (owner=true), or by RTMaps (owner=false).

# 10.39.1 Detailed Description

MATLAB-Like matrix (Complex and columnwise, like in fortran) This is the RTMaps standard matrix type designed to be used as an output type. It is a very simple structure designed to contain an array of complex numbers.

Usually, this structure is used only for inter RTMaps components communication, and thus is usually allocated through a call to MAPSOutput::AllocOutputBuffer. As a matter of fact, this structure also has some constructors, so it can be used as a general purpose fortran-like matrix as well. Be aware that a much more powerful class exists for matrices computation in RTMaps: the MAPSMatrix2 class. We recommend that you use the latter for matrices computation and convert it to MAPSMatrix to output results from your components.

#### 10.39.2 Constructor & Destructor Documentation

10.39.2.1 MAPSMatrix::MAPSMatrix ( MAPSMatrix2< double > & mat )

Constructor that takes a MAPSMatrix2 in input.

#### See also

MAPSMatrix2

# 10.39.3 Member Function Documentation

# 10.39.3.1 MAPSFloat64& MAPSMatrix::Im ( int row, int column )

Gives access to the imaginary part of one element of the matrix.

This function allows to read or set the imaginary part of one element of the matrix

#### **Parameters**

row	the row of the element to get access to
column	the column of the element to get access to

#### Returns

a reference to the imaginary part of the (row, column) element of the matrix

# 10.39.3.2 MAPSMatrix::operator MAPSMatrix2< double > ( ) const

Cast to MAPSMatrix2. Very useful to process MAPSMatrix in input of components.

Note that this cast only converts the real part of the MAPSMatrix.

#### 10.39.3.3 MAPSFloat64& MAPSMatrix::Real ( int row, int column )

Gives access to the real part of one element of the matrix.

This function allows to read or set the real part of one element of the matrix

# **Parameters**

row	the row of the element to get access to
column	the column of the element to get access to

# Returns

a reference to the real part of the (row, column) element of the matrix

The documentation for this struct was generated from the following file:

• maps.hpp

# 10.40 MAPSMatrix2 T > Class Template Reference

The RTMaps MAPSMatrix2 class, a powerful matrix management class.

# **Public Member Functions**

• int M () const

Returns the number of rows.

• int N () const

Returns the number of columns.

• int NbRows () const

Returns the number of rows.

• int NbColumns () const

Returns the number of columns.

• int SizeX () const

Returns the number of columns.

• int SizeY () const

Returns the number of rows.

• int Dim1 () const

Returns the number of rows.

• int Dim2 () const

Returns the number of columns.

void To (T \*t[]) const

Maps to an array of pointers to each row, for handling by C functions.

# **Related Functions**

(Note that these are not member functions.)

```
    template<typename T >
        MAPSMatrix2< T > operator* (const MAPSMatrix2< T > &A, const MAPSMatrix2< T > &B)
```

MAPSMatrix2 multiplication operator.

```
• template<typename T >  \frac{\text{MAPSMatrix2}}{\text{MAPSMatrix2}} < \text{T} > \text{operator+ (const MAPSMatrix2} < \text{T} > \&\text{A, const MAPSMatrix2} < \text{T} > \&\text{B})
```

MAPSMatrix2 addition operator.

```
    template<typename T >
        MAPSMatrix2< T > operator- (const MAPSMatrix2< T > &A, const MAPSMatrix2< T > &B)
```

MAPSMatrix2 substraction operator.

```
    template<typename T >
        MAPSMatrix2< T > operator* (const MAPSMatrix2< T > &A, const T &b)
        Multiplication of a MAPSMatrix2 with a scalar.
```

- template<typename T >
   MAPSMatrix2< T > operator/ (const MAPSMatrix2< T > &A, const T &b)
   Division of a MAPSMatrix2 by a scalar.

Standard operator.

# **Operators**

- T & operator() (int i, int j) const
   Returns element (i,j) of the matrix.
- MAPSArray< T > & operator[] (int i) const
   Returns row i of the matrix. 0<= i < M().</li>
- MAPSMatrix2 & operator= (const MAPSMatrix2 &v)
   Warning! This operator does not make a copy (too slow).
- MAPSMatrix2 & operator= (T \*v)

Fills the matrix with data from C array v.

- MAPSMatrix2< T > operator $\sim$  () const
  - Transposition operator.
- MAPSMatrix2 < T > operator! () const
   Matrix inversion operator.
- MAPSMatrix2< T > operator\*= (const T &v)
   Matrix multiplication by a scalar.
- MAPSMatrix2< T > operator/= (const T &v)

Matrix division by a scalar.

# **Functions**

• void Clone ()

Makes a clone copy of the original matrix.

void Clear (void)

Sets all the elements of the matrix to 0.

void Id ()

Sets the current matrix to identity, i.e. all the elements of the matrix will be set to 0, except the diagonal elements that will be set to 1.

• MAPSMatrix2< T > Inverse () const

Computes the inverse of the matrix.

• T Det () const

Computes the determinant of the matrix.

• MAPSMatrix2< T > PseudoInverse () const

Computes the pseudo inverse of the matrix, i.e  $! (\sim A*A)*\sim A$ . This is the general formula. There are some optimizations if the matrix has special properties.

• MAPSArray< T > & Row (int i) const

Returns row i, where  $0 \le i \le M()$ 

• MAPSArray< T > Col (int i) const

Returns column i, where  $0 \le i \le N()$ 

# **Constructors and destructor**

• MAPSMatrix2 ()

Default constructor.

• MAPSMatrix2 (int m, int n)

Constructor with size of the matrix.

• MAPSMatrix2 (const MAPSMatrix2 &v)

Copy constructor.

virtual ∼MAPSMatrix2 ()

Destructor.

#### 10.40.1 Detailed Description

template<typename T> class MAPSMatrix2< T>

The RTMaps MAPSMatrix2 class, a powerful matrix management class.

#### 10.40.2 Member Function Documentation

```
10.40.2.1 template < typename T > void MAPSMatrix2 < T >::Clone ( )
```

Makes a clone copy of the original matrix.

When you use the operator = (such as in A=B), A is not really a copy of B. A and B share the same matrix in memory. If you do A.Clone(), the A will have its own image of the matrix in memory, i.e. any modification of A will not affect B any longer.

#### 10.40.2.2 template < typename T > T& MAPSMatrix2 < T >::operator() ( int i, int j ) const

Returns element (i,j) of the matrix.

Valid values are:  $0 \le i \le M()$ ,  $0 \le j \le N()$ 

# 10.40.2.3 template < typename T > MAPSMatrix2& MAPSMatrix2 < T > ::operator= ( const MAPSMatrix2 < T > & v )

Warning! This operator does not make a copy (too slow).

It is a real mathematical operator = (The MAPSMatrix2 class has a reference counter)

# 10.40.2.4 template < typename T > MAPSArray < T > & MAPSMatrix2 < T >::operator[] ( int i ) const

Returns row *i* of the matrix.  $0 \le i \le M()$ .

This allows the use of [i] [j] combination to retrieve an element of the matrix.

### 10.40.3 Friends And Related Function Documentation

# 10.40.3.1 template < typename T > MAPSStreamedString & operator << ( MAPSStreamedString & out, const MAPSMatrix2 < T > & $\nu$ ) [related]

Standard operator.


The documentation for this class was generated from the following file:

maps.hpp

# 10.41 MAPSModule Class Reference

The base class for all RTMaps modules.

Inheritance diagram for MAPSModule:



#### **Protected Member Functions**

- int NbInputs (void)
   Returns the number of inputs of the module.
- int NbOutputs (void)
   Returns the number of outputs of the module.
- int NbProperties (void)
   Returns the number of properties of the module.
- int NbActions (void)
   Returns the number of actions of the module.
- MAPSInput & Input (const int inputnb)
   Gets a reference to the input inputnb.
- MAPSInput & Input (const char \*name)
   Gets a reference to the input called name.
- MAPSOutput & Output (const int outputnb)
   Gets a reference to the output outputnb.
- MAPSOutput & Output (const char \*name)
   Gets a reference to the output called name.
- MAPSProperty & Property (const int propertynb)

  Gets a reference to the property propertynb.
- MAPSProperty & Property (const char \*name)

  Gets a reference to the property called name.

MAPSAction & Action (const int actionnb)

Gets a reference to the action actionnb.

MAPSAction & Action (const char \*name)

Gets a reference to the action called name.

bool PropertyChanged (MAPSProperty &p)

Tells if the property value has changed.

bool PropertyChanged (int propertynb)

Tells if the property value has changed.

• bool PropertyChanged (const char \*name)

Tells if the property value has changed.

void AcknowledgePropertyChanged (MAPSProperty &p)

Acknowledges the property value change.

void AcknowledgePropertyChanged (int propertynb)

Acknowledges the property value change.

void AcknowledgePropertyChanged (const char \*name)

Acknowledges the property value change.

• int RunningThreads ()

Returns the number of threads currently associated to the component.

• int & ReaderHandle (int inputnb)

Returns the FastI/O reader handle of input inputnb.

• bool IsConnected (MAPSInput &input)

Returns true if input input is connected to another component output. cf. MAPSInput::IsConnected.

• bool DataAvailableInFIFO (MAPSInput &input)

Returns true if some data are available in FIFO connected to this input.

• bool IsFIFOEmpty (MAPSOutput &output)

Returns true if the FIFO connected is empty.

• bool IsFIFOFull (MAPSOutput &output)

Returns true if the FIFO connected is full.

• void Wait4Handshake (MAPSOutput &output)

Waits for a handshake on output.

# **MAPSEvent management**

• bool Wait4Event (MAPSEvent \*event, MAPSDelay timeout=MAPS::Infinite)

Waits for an event to occur.

• bool Wait4Event (MAPSEvent & event, MAPSDelay timeout=MAPS::Infinite)

Waits for an event to occur.

 int Wait4Events (int nCount, MAPSEvent \*events[], MAPSDelay timeout=MAPS::Infinite, bool addIsDyingEvent=true)

Waits for some events to occur.

- int MsgWait4Event (MAPSEvent \*event, MAPSDelay timeout=MAPS::Infinite)
   Waits for an event to occur OR a message to come.
- int MsgWait4Events (int nCount, MAPSEvent \*events[], MAPSDelay timeout=MAPS::Infinite, bool addIsDyingEvent=true)

Waits for some events to occur OR a message to come.

# Virtual time management functions

- bool Rest (MAPSDelay delay, MAPSEvent \*cancel=NULL)
   Blocks the current thread for a delay of delay microseconds.
- bool Wait (MAPSTimestamp timestamp, MAPSEvent \*cancel=NULL)
   Blocks the current thread until the time reaches timestamp.

# **Death management functions**

• bool IsDying (void)

Returns true if the module is currently dying (but is not dead).

• bool IsDead (void)

Returns true if the module is dead.

# Threads management functions

void CreateThread (MAPSThreadFunction)
 Creates a thread associated to the module.

• void Die ()

Function to be called by the module itself during termination. Ask all the associated threads to die.

• void OneMoreLife (void)

Adds a "life" to the module. The "life" number is a counter for the threads associated to the module.

void LoseOneLife (void)

Removes a "life" from the module. The "life" number is a counter for the threads associated to the module.

• void Start ()

To be called when the module starts. It correctly resets the dying and death events and variables.

• bool Wait4Death ()

Waits for the death of all associated threads.

# **Error management functions**

virtual void Error (const char \*string, int importance=1)
 Emits an error.

# Reporting management functions

- virtual void ReportError (const char \*string, int importance=0)

  Reports an error.
- virtual void ReportWarning (const char \*string, int importance=0)

  Reports a warning.
- virtual void ReportInfo (const char \*string, int importance=0)

  Reports a piece of information.
- virtual void Report (const char \*string, int type=MAPS::Info, int importance=0)

  General report function.

# **DirectSet functions**

These functions do not check the <code>canBeModifierAfterStart</code> and <code>readOnly</code> parameters of properties, so the RTMaps modules can set their own properties with these functions in all situations. Usual MAPSModule::Set functions check the parameters of properties, and so cannot be used if for instance <code>readOnly</code> is set.

MAPSModule::DirectSet functions are protected, so they can only be used in RTMaps modules. On the contrary, MAPSModule::Set functions are public and thus can be called by anyone.

- void DirectSet (MAPSProperty &p, bool value)
   Sets boolean value for boolean property p.
- void DirectSet (MAPSProperty &p, MAPSInt64 value)
   Sets integer value for integer property p.
- void DirectSet (MAPSProperty &p, MAPSInt32 value)
- void DirectSet (MAPSProperty &p, double value)
   Sets float value for float property p.
- void DirectSet (MAPSProperty &p, const MAPSString &value)

  Sets string value for string property p.
- void DirectSet (MAPSProperty &p, const char \*value)
- void DirectSet (MAPSProperty &p, const char \*enumValues, MAPSInt32 selected)

Sets enum values to enum Values and the selected enum to selected for enum property p.

- void DirectSet (MAPSProperty &p, const MAPSString &enumValues, MAPSInt32 selected)
- void DirectSet (MAPSProperty &p, const MAPSEnumStruct &enumStruct)

  Sets enum value to enumStruct for enum property p.
- void DirectSetProperty (int propertynb, bool value)
   Sets boolean value for boolean property at index propertynb.
- void DirectSetProperty (int propertynb, MAPSInt64 value)
   Sets integer value for integer property at index propertynb.
- void DirectSetProperty (int propertynb, MAPSInt32 value)
   Sets integer value for integer property at index propertynb.
- void DirectSetProperty (int propertynb, double value)
   Sets float value for float property at index propertynb.
- void DirectSetProperty (int propertynb, const char \*value)

  Sets string value for string property at index propertynb.
- void DirectSetProperty (int propertynb, const MAPSString &value)

  Sets string value for string property at index propertynb.

void <u>DirectSetProperty</u> (int propertynb, const char \*enumValues, MAPSInt32 selected)

Sets enum values to enumValues and the selected enum to selected for enum property at index propertynb.

- void DirectSetProperty (int propertynb, const MAPSEnumStruct &enumStruct)

  Sets enum value to enumStruct for enum property at index propertynb.
- void DirectSetProperty (const char \*p, bool value)

  Sets boolean value for boolean property p.
- void DirectSetProperty (const char \*p, MAPSInt64 value)
   Sets integer value for integer property p.
- void DirectSetProperty (const char \*p, MAPSInt32 value)
   Sets integer value for integer property p.
- void DirectSetProperty (const char \*p, double value)
   Sets float value for float property p.
- void DirectSetProperty (const char \*p, const char \*value)
   Sets string value for string property p.
- void DirectSetProperty (const char \*p, const MAPSString &value)

  Sets string value for string property p.
- void DirectSetProperty (const char \*p, const char \*enumValues, MAPSInt32 selected)

Sets enum values to enumValues and the selected enum to selected for enum property p.

- void DirectSetProperty (const char \*p, const MAPSEnumStruct &enumStruct)

  Sets enum value to enumStruct for enum property p.
- virtual void PerformanceMonitoring ()
   Performance monitoring function.
- MAPSInput & SequentialInput ()

For a sequential module (or component), returns a reference to the input that is the source of the current execution.

- MAPSModule (const char \*n, bool perfMon=false, bool stdProperties=true)
   Constructor.
- virtual ∼MAPSModule ()

Virtual destructor. Overloaded.

#### **Get/Set property functions**

virtual void Get (MAPSProperty &p, bool &value)
 Gets boolean value from boolean property p.

- virtual void Get (MAPSProperty &p, MAPSInt64 &value)
   Gets integer value from integer property p.
- virtual void Get (MAPSProperty &p, MAPSFloat &value)
   Gets float value from float property p.
- virtual void Get (MAPSProperty &p, MAPSString &value)

  Gets string value from string property p.
- virtual void Get (MAPSProperty &p, MAPSEnumStruct &enumStruct)
   Gets enum struct enumStruct from enum property p.
- void Get (MAPSProperty &p, MAPSArray < MAPSString > &enumValues, MAPSInt32 &selectedValue)

Gets enum struct values into enumValues and selected item into selectedValue from enum property p.

- void Get (MAPSProperty &p, MAPSInt32 &value)

  Gets integer value from integer property p.
- void GetProperty (const int propertynb, bool &value)
   Gets boolean value from boolean property propertynb.
- void GetProperty (const int propertynb, MAPSInt32 &value)
   Get integer value from integer property propertynb.
- void GetProperty (const int propertynb, MAPSInt64 &value)

  Gets integer value from integer property propertynb.
- void GetProperty (const int propertynb, MAPSFloat &value)
   Gets float value from float property propertynb.
- void GetProperty (const int propertynb, MAPSString &value)
   Gets string value from string property propertynb.
- void GetProperty (const int propertynb, MAPSArray < MAPSString > &enumValues, MAPSInt32 &selectedValue)
  - Gets enum struct values into enumValues and selected item into selectedValue from enum property propertynb.
- void GetProperty (const int propertynb, MAPSEnumStruct &enumStruct)

  Gets enum struct value into enumStruct from enum property p.

- void GetProperty (const char \*p, bool &value)
   Gets boolean value from boolean property p.
- void GetProperty (const char \*p, MAPSInt32 &value)

  Gets integer value from integer property p.
- void GetProperty (const char \*p, MAPSInt64 &value)

  Gets integer value from integer property p.
- void GetProperty (const char \*p, MAPSFloat &value)
   Gets float value from float property p.
- void GetProperty (const char \*p, MAPSString &value)

  Gets string value from string property p.
- void GetProperty (const char \*p, MAPSArray< MAPSString > &enumValues, MAPSInt32 &selectedValue)

Gets enum struct values into enumValues and selected item into selectedValue from enum property p.

- void GetProperty (const char \*p, MAPSEnumStruct &enumStruct)

  Gets enum struct value into enumStruct from enum property p.
- bool GetBoolProperty (const int propertynb)
   Gets boolean value from boolean property propertynb.
- MAPSInt64 GetIntegerProperty (const int propertynb)
   Gets integer value from integer property propertynb.
- MAPSFloat GetFloatProperty (const int propertynb)
   Gets float value from float property propertynb.
- MAPSString GetStringProperty (const int propertynb)
   Gets string value from string property propertynb.
- MAPSEnumStruct GetEnumProperty (const int propertynb)
   Gets enum value from enum property propertynb.
- bool GetBoolProperty (const char \*p)
   Gets boolean value from boolean property p.
- MAPSInt64 GetIntegerProperty (const char \*p)

  Gets integer value from integer property p.
- MAPSFloat GetFloatProperty (const char \*p)

Gets float value from float property p.

MAPSString GetStringProperty (const char \*p)
 Gets string value from string property p.

MAPSEnumStruct GetEnumProperty (const char \*p)
 Gets enum value from enum property p.

bool GetBoolProperty (MAPSProperty &p)
 Gets boolean value from boolean property p.

MAPSInt64 GetIntegerProperty (MAPSProperty &p)
 Gets integer value from integer property p.

MAPSFloat GetFloatProperty (MAPSProperty &p)
 Gets float value from float property p.

MAPSString GetStringProperty (MAPSProperty &p)
 Gets string value from string property p.

MAPSEnumStruct GetEnumProperty (MAPSProperty &p)
 Gets enum value from enum property p.

virtual void Set (MAPSProperty &p, bool value)
 Sets boolean value from boolean property p.

virtual void Set (MAPSProperty &p, MAPSInt64 value)
 Sets integer value from integer property p.

virtual void Set (MAPSProperty &p, MAPSFloat value)
 Sets float value from float property p.

virtual void Set (MAPSProperty &p, const MAPSString &value)
 Sets string value from string property p.

• virtual void Set (MAPSProperty &p, const MAPSEnumStruct &enumStruct)

Sets enum struct enumStruct from enum property p.

- void Set (MAPSProperty &p, MAPSInt32 value)
- void Set (MAPSProperty &p, const char \*value)
- void Set (MAPSProperty &p, const char \*enumValues, MAPSInt32 selected)
- void Set (MAPSProperty &p, const MAPSString &enumValues, MAPSInt32 selected)

Sets enum values to enum Values and the selected enum to selected for enum property p.

void SetProperty (int propertynb, bool value)

Sets boolean value from boolean property propertynb.

- void SetProperty (int propertynb, MAPSInt32 value)

  Sets integer value from integer property propertynb.
- void SetProperty (int propertynb, MAPSInt64 value)
   Sets integer value from integer property propertynb.
- void SetProperty (int propertynb, MAPSFloat value)
   Sets float value from float property propertynb.
- void SetProperty (int propertynb, const MAPSString &value)
   Sets float value from float property propertynb.
- void SetProperty (int propertynb, const char \*value)

  Sets string value from string property propertynb.
- void SetProperty (int propertynb, const char \*enumValues, MAPSInt32 selected)

Sets enum values to enumValues and the selected enum to selected for enum property propertynb.

- void SetProperty (int propertynb, const MAPSEnumStruct &enumStruct)

  Sets enum value to enumStruct for enum property propertynb.
- void SetProperty (const char \*p, bool value)
   Sets boolean value from boolean property p.
- void SetProperty (const char \*p, MAPSInt32 value)

  Sets integer value from integer property p.
- void SetProperty (const char \*p, MAPSInt64 value)
   Sets integer value from integer property p.
- void SetProperty (const char \*p, MAPSFloat value)
   Sets float value from float property p.
- void SetProperty (const char \*p, const MAPSString &value)
   Sets string value from string property p.
- void SetProperty (const char \*p, const char \*value)
   Sets string value from string property p.
- void SetProperty (const char \*p, const char \*enumValues, MAPSInt32 selected)
   Sets enum values to enumValues and the selected enum to selected for enum property p.

void SetProperty (const char \*p, const MAPSEnumStruct &enumStruct)
 Sets enum value to enumStruct for enum property p.

# Start/Stop Reading/Writing functions

MAPSIOEIt \* StartWriting (MAPSOutput &output)

The StartWriting function, one of the most important functions in the RTMaps component architecture.

void StopWriting (MAPSIOEIt \*IOEIt, bool discard=false)

The StopWriting function, one of the most important functions in the RTMaps component architecture.

MAPSIOEIt \* StartReading (MAPSInput &input)

The StartReading function, one of the most important functions in the RTMaps component architecture.

MAPSIOEIt \* StartReading (int nCount, MAPSInput \*inputs[], int \*inputThatAnswered, int nCountEvents=0, MAPSEvent \*events[]=NULL)

The multiple StartReading function, one of the most important functions in the RTMaps component architecture.

MAPSIOEIt \* MsgStartReading (MAPSInput &input)

The MsgStartReading function.

MAPSIOEIt \* MsgStartReading (int nCount, MAPSInput \*inputs[], int \*inputThatAnswered, int nCountEvents=0, MAPSEvent \*events[]=NULL)

The multiple MsgStartReading function.

- MAPSTimestamp SynchroStartReading (int nb, MAPSInput \*\*inputs, MAPSIOElt \*\*IOElts, MAPSInt64 synchroTolerance=0, MAPSEvent \*abortEvent=NULL)
   The synchronized StartReading function.
- bool NLastStartReading (MAPSInput &input, int nb, MAPSIOEIt \*\*IOEIts)

  The N last MAPSIOEIts StartReading function.
- void StopReading (MAPSInput &input)

The StopReading function, one of the most important functions in the RTMaps component architecture.

#### **Action execution functions**

• void DoAction (MAPSAction &a)

Executes action a.

• void ExecuteAction (MAPSAction &a)

Executes action a.

• void DoAction (int nb)

Executes action number nb.

void DoAction (const char \*name)

Executes action called name.

void ExecuteAction (int nb)

Executes action a.

void ExecuteAction (const char \*name)

Executes action a.

# 10.41.1 Detailed Description

The base class for all RTMaps modules. Defines a scriptable module with inputs, outputs, properties and actions.

#### 10.41.2 Member Function Documentation

# 10.41.2.1 void MAPSModule::AcknowledgePropertyChanged ( MAPSProperty & p ) [protected]

Acknowledges the property value change.

Acknowledges the property value change.

Must be called regularly so that we can know the property has changed.

#### See also

MAPSProperty::PropertyChanged

# **10.41.2.2 void MAPSModule::AcknowledgePropertyChanged (int** *propertynb* ) [protected]

Acknowledges the property value change.

Acknowledges the property value change.

Must be called regularly so that we can know the property has changed.

#### See also

MAPSProperty::PropertyChanged

```
10.41.2.3 void MAPSModule::AcknowledgePropertyChanged ( const char * name ) [protected]
```

Acknowledges the property value change.

Acknowledges the property value change.

Must be called regularly so that we can know the property has changed.

#### See also

MAPSProperty::PropertyChanged

```
10.41.2.4 void MAPSModule::Die() [protected]
```

Function to be called by the module itself during termination. Ask all the associated threads to die.

The result is not immediate: some threads could refuse to die. Should be followed by a call to Wait4Death that waits for the death itself

```
10.41.2.5 void MAPSModule::DirectSet ( MAPSProperty & p, MAPSInt32 value )
[protected]
```

Sets integer value for integer property p.

```
10.41.2.6 void MAPSModule::DirectSet ( MAPSProperty & p, const char * value )

[protected]
```

Sets string *value* for string property *p*.

```
10.41.2.7 void MAPSModule::DirectSet ( MAPSProperty & p, const MAPSString & enumValues, MAPSInt32 selected ) [protected]
```

Sets enum values to *enumValues* and the selected enum to *selected* for enum property *p*.

Emits an error.

This will kill definitely the module. Use MAPSModule::ReportError if you want to go on executing some code.

#### **Parameters**

3 3 3 3 3 3 3 3 3 3 3 3 3 3 3 3 3 3 3 3	string Error string to log and display
---	--

importance | Importance of the error :

- 0 : The error is minor. It will not have any impact on the overall system behaviour. Some actions have been taken that will fix the problem.
- 1 : The error is important. Some actions have been taken that might fix the problem. The system can go on running, but it might not function properly.
- 2 : The error is critical. The system will not function properly thereafter.

Reimplemented in MAPSRecordReplayMethod.

# 10.41.2.9 virtual void MAPSModule::Get ( MAPSProperty & p, bool & value ) [virtual]

Gets boolean value from boolean property p.

The first 4 Get/Set functions can be overloaded. The other functions always call these 4 basic functions.

#### 10.41.2.10 bool MAPSModule::IsDying (void ) [protected]

Returns true if the module is currently dying (but is not dead).

Some other component or the RTMaps kernel asked for its death.

# 10.41.2.11 bool MAPSModule::IsFIFOFull ( MAPSOutput & output ) [protected]

Returns true if the FIFO connected is full.

This information can be very useful. When you know the FIFO is full, you know that you don't process the data fast enough. You can then act and process the data faster (or skip some data in a smart way)

#### 10.41.2.12 void MAPSModule::LoseOneLife(void) [protected]

Removes a "life" from the module. The "life" number is a counter for the threads associated to the module.

Do not use this function directly. Let the RTMaps kernel manage the life and death of module threads. Only for very experienced RTMaps developers.

# 10.41.2.13 MAPSIOEIt\* MAPSModule::MsgStartReading ( MAPSInput & input )

The MsgStartReading function.

Returns NULL when a detachment or a message occured.

#### Warning

Detachment is not completly transparent to this version of StartReading since when there is a detachment, nothing happens, but the next answer can be  $\mathtt{NULL}$  (that is, be a message) in that case, the last MAPSIOEIt is no longer valid (there was an implicit StopReading due to the detachment)

#### Note

This function has a meaning only with message based OSes like Windows.

```
10.41.2.14 MAPSIOEIt* MAPSModule::MsgStartReading ( int nCount, MAPSInput * inputs[], int * inputThatAnswered, int nCountEvents = 0, MAPSEvent * events[] = NULL )
```

The multiple MsgStartReading function.

The multiple StartReading returns  $\mathtt{NULL}$  when a detachment or a message occured. In that case, inputThatAnswered indicates which input was detached, except if inputThatAnswered is equal to  $\mathtt{MAPS}::GotAMessage$ , then the  $\mathtt{NULL}$  answer corresponds to a Windows Message. Sequential components: Always returns  $\mathtt{NULL}$  (should not be used)

#### Note

There is priority of inputs over events.

The order of priority among inputs is set by the inputs table inputs

This function has a meaning only with message based OSes like Windows.

# 10.41.2.15 int MAPSModule::MsgWait4Event ( MAPSEvent \* event, MAPSDelay timeout = MAPS::Infinite ) [protected]

Waits for an event to occur OR a message to come.

This function blocks until the event occurs OR a message comes to the thread. Note that this function has a meaning only for message based OS like Windows.

#### **Parameters**

event	Event to wait for
timeout	The wait aborts after <i>timeout</i> microseconds.

#### Returns

0 if the event occured (was set), MAPS::TimeOut if a timeout occured, MAPS::GotAMessage if a message arrived.

Note that using this function is safe. RTMaps knows how to unblock this function if the component dies, i.e. if the event never occurs, this function will not block your RTMaps system forever.

```
10.41.2.16 int MAPSModule::MsgWait4Events ( int nCount, MAPSEvent * events[],

MAPSDelay timeout = MAPS::Infinite, bool addIsDyingEvent = true )

[protected]
```

Waits for some events to occur OR a message to come.

This function blocks until one of the events occurs OR a message comes to the thread. Note that this function has a meaning only for a message based OS like Windows.

#### **Parameters**

nCount	Number of events to wait on. It's the size of the events parameter array.
events	Array of pointers to MAPSEvent classes.
timeout	The wait aborts after <i>timeout</i> microseconds.
addls-	
DyingEvent	

#### Returns

MAPS::TimeOut if a timeout occured, the index of the event that occured (was set) and led to the function return, MAPS::GotAMessage if a message arrived.

Note that using this function is safe. RTMaps knows how to unblock this function if the component dies, i.e. if no event ever occurs, this function will not block your RTMaps system forever.

### 10.41.2.17 int MAPSModule::NbProperties (void ) [protected]

Returns the number of properties of the module.

The number of properties may be higher that expected due to the fact that this function takes into account the module inputs and outputs properties (such as <code>subsampling</code>, <code>fifosize</code> etc. and also some fixed number of "hidden" properties that are reserved for internal use. In order to retrieve the number of "user" properties, you might use the <code>MAPSModule::firstUserPropertyIndex</code> member like: <code>NbProperties()</code> - <code>firstUserPropertyIndex</code>

# 10.41.2.18 bool MAPSModule::NLastStartReading ( MAPSInput & input, int nb, MAPSIOEIt \*\* IOEIts )

The N last MAPSIOEIts StartReading function.

Returns true when all the MAPSIOEIts are correctly fetched. In threaded mode, the function should always return true.

Returns false in sequential mode until the right number of elements are fetched, or when a dynamic detachment occurs.

#### 10.41.2.19 void MAPSModule::OneMoreLife (void ) [protected]

Adds a "life" to the module. The "life" number is a counter for the threads associated to the module.

Do not use this function directly. Let the RTMaps kernel manage the life and death of module threads. Only for very experienced RTMaps developers.

Performance monitoring function.

This function is called automatically by the RTMaps kernel along with the Core function of the component.

```
10.41.2.21 bool MAPSModule::PropertyChanged ( MAPSProperty & p ) [protected]
```

Tells if the property value has changed.

Tells if the property value has changed.

Returns true if the property value has changed since the last call to MAPSProperty::AcknowledgePropertyChanged

```
10.41.2.22 bool MAPSModule::PropertyChanged (int propertynb) [protected]
```

Tells if the property value has changed.

Tells if the property value has changed.

Returns true if the property value has changed since the last call to MAPSProperty::AcknowledgePropertyChanged

```
10.41.2.23 bool MAPSModule::PropertyChanged (const char * name) [protected]
```

Tells if the property value has changed.

Tells if the property value has changed.

Returns true if the property value has changed since the last call to MAPSProperty::AcknowledgePropertyChanged

```
10.41.2.24 virtual void MAPSModule::Report ( const char * string, int type = MAPS::Info, int
importance = 0 ) [protected, virtual]
```

General report function.

#### **Parameters**

Generated on Wed Oct 13 2010 18:59:21 for RTMaps by Doxygen

string	String to log and display
type	Type of report. Can be MAPS::Info, MAPS::Warning or MAPS::Error.
importance	Importance of the report (0: minor, 1: important, 2: critical)

# 10.41.2.25 virtual void MAPSModule::ReportError ( const char \* string, int importance = 0 ) [protected, virtual]

Reports an error.

#### **Parameters**

atrina	Error atring to log and display
string	Error string to log and display
importance	Importance of the error :
	• 0 : The error is minor. It will not have any impact on the overall system behaviour. Some actions have been taken that will fix the problem.
	<ul> <li>1: The error is important. Some actions have been taken that might fix the problem. The system can go on running, but it might not function properly.</li> </ul>
	• 2 : The error is critical. The system will not function properly thereafter.

# 10.41.2.26 virtual void MAPSModule::ReportInfo ( const char \* string, int importance = 0 ) [protected, virtual]

Reports a piece of information.

# **Parameters**

string	Info string to log and display
importance	Importance of the information :
	0 : The information is minor.
	• 1 : The information is important.
	• 2 : The information is critical.

# 

Reports a warning.

#### **Parameters**

string	Warning string to log and display	

#### importance

Importance of the warning:

- 0 : The warning is minor. It has no impact on the behaviour of the module.
- 1 : The warning is important. It signals a malfunction in the module that could result in an error.
- 2 : The warning is critical. It signals a major malfunction in the module. It will certainly result in an error.

# **10.41.2.28 bool MAPSModule::Rest ( MAPSDelay** *delay,* MAPSEvent \* *cancel* = NULL ) [protected]

Blocks the current thread for a delay of delay microseconds.

The parameters of these functions are expressed in virtual microseconds. This means that these functions make full usage of the RTMaps virtual time management feature. You MUST use these functions when you design some time-related components.

Any absolute reference is lost with this function. It works perfectly when the the virtual time speed is negative.

The optional parameter cancel allows to asynchronously stop the wait.

Returns true when the delay has elapsed. Returns false if the wait was canceled by setting the *cancel* event.

Note that using this function is safe. RTMaps knows how to unblock this function if the component dies, i.e. this function will not block your RTMaps system until the delay expires, which can take some hours...

### 10.41.2.29 void MAPSModule::Set ( MAPSProperty & p, MAPSInt32 value )

Sets integer value from integer property p.

# 10.41.2.30 void MAPSModule::Set ( MAPSProperty & p, const char \* enumValues, MAPSInt32 selected )

Sets enum values to *enumValues* and the selected enum to *selected* for enum property *p*.

#### 10.41.2.31 void MAPSModule::Set ( MAPSProperty & p, const char \* value )

Sets string value from string property p.

#### 10.41.2.32 MAPSIOEIt\* MAPSModule::StartReading ( MAPSInput & input )

The StartReading function, one of the most important functions in the RTMaps component architecture.

Sequential components: returns  $\mathtt{NULL}$  when no input is connected or when no data is directly available, or when a detachment was asked for.

#### Note

Dynamic detachment is transparent to this version of StartReading in threading mode, but not in sequential mode. Watch out for NULL return values when developping sequential mode compatible components.

# 10.41.2.33 MAPSIOEIt\* MAPSModule::StartReading ( int *nCount*, MAPSInput \* *inputS[]*, int \* *inputThatAnswered*, int *nCountEvents* = 0, MAPSEvent \* *events[]* = NULL )

The multiple StartReading function, one of the most important functions in the RTMaps component architecture.

The multiple StartReading returns  $\mathtt{NULL}$  when a detachment occured. In that case, inputThatAnswered indicates which input was detached.

This version of StartReading enables to simultaneously wait for data on inputs and wait for events, exactly like MAPSModule::Wait4Event does. If some events are specified, and one of these events is triggered, the function returns *NULL*. In order to discrimate between a detachment and an occured event, the user MUST test the *inputThatAnswered* variable. If *inputThatAnswered* is more than *nCount*, then obviously an event occured, and its number is given by inputThatAnswered-ncount, starting from 0.

#### Note

There is priority of inputs over events.

The order of priority among inputs is set by the inputs table inputs

# 10.41.2.34 void MAPSModule::StopWriting ( MAPSIOEIt \* IOEIt, bool discard = false )

The StopWriting function, one of the most important functions in the RTMaps component architecture.

# Parameters

IOEIt	A pointer to the MAPSIOEIt obtained by a previous call to StartWriting.
discard	If set to true, the write will not be done, that is the data will be lost.

```
10.41.2.35 MAPSTimestamp MAPSModule::SynchroStartReading ( int nb, MAPSInput ** inputs, MAPSIOEIt ** IOEIts, MAPSInt64 synchroTolerance = 0, MAPSEvent * abortEvent = NULL )
```

The synchronized StartReading function.

The SynchroStartReading function can retrieve synchronized data on several different inputs. The function returns when input data with the same timestamp are found on the inputs (or approximately the same in case the parameter *synchroTolerance* is specified and more than 0). The corresponding MAPSIOEIts are then returned via the provided *IOEIts* array.

An *abortEvent* can be provided in order to force the function to return when the event is set. In this case, the returned timestamp is -1 and the IOEIts in the array are set to <code>NULL</code>. This *abortEvent* can be used for example in order to update the *synchro-Tolerance* if the latest value has been too low and the function blocks since it cannot synchronize signals.

```
10.41.2.36 bool MAPSModule::Wait ( MAPSTimestamp timestamp, MAPSEvent * cancel = NULL ) [protected]
```

Blocks the current thread until the time reaches timestamp.

Beware : the time might never reach *timestamp*, especially if the virtual time speed is negative (the time goes backward).

The optional parameter cancel allows to asynchronously stop the wait.

Returns true when the timestamp *timestamp* is reached. Returns false is the wait was canceled by setting the *cancel* event.

Note that using this function is safe. RTMaps knows how to unblock this function if the component dies, i.e. this function will not block your RTMaps system until *timestamp* is reached, which might never happen.

```
10.41.2.37 bool MAPSModule::Wait4Event ( MAPSEvent * event, MAPSDelay timeout = MAPS::Infinite ) [protected]
```

Waits for an event to occur.

This function blocks until the event occurs.

#### **Parameters**

event	Event to wait for
timeout	The wait aborts after <i>timeout</i> microseconds.

#### Returns

 $\verb|true| if the event occurred (was set), \verb|false| if a timeout occured.$ 

Note that using this function is safe. RTMaps knows how to unblock this function if the component dies, i.e. if the event never occurs, this function will not block your RTMaps

system forever.

# 10.41.2.38 bool MAPSModule::Wait4Event ( MAPSEvent & event, MAPSDelay timeout = MAPS::Infinite ) [protected]

Waits for an event to occur.

This function blocks until the event occurs.

#### **Parameters**

event	Event to wait for
timeout	The wait aborts after <i>timeout</i> microseconds.

#### Returns

true if the event occurred (was set), false if a timeout occured.

Note that using this function is safe. RTMaps knows how to unblock this function if the component dies, i.e. if the event never occurs, this function will not block your RTMaps system forever.

Waits for some events to occur.

This function blocks until one of the events occurs.

#### **Parameters**

nCount	Number of events to wait on. It is the size of the event parameter array.
events	Array of pointers to MAPSEvent instances.
timeout	The wait aborts after <i>timeout</i> microseconds.
addls-	
DyingEvent	

#### **Returns**

MAPS::TimeOut if a timeout occured, the index of the event that occured (was set) and led to the function return.

Note that using this function is safe. RTMaps knows how to unblock this function if the component dies, i.e. if no event ever occurs, this function will not block your RTMaps system forever.

### 10.41.2.40 void MAPSModule::Wait4Handshake ( MAPSOutput & output ) [protected]

Waits for a handshake on output.

This function is useful for handshaking communication between components. It will

block until one of the components connected on *output* have read the data recently output by MAPSModule::StopWriting


The documentation for this class was generated from the following file:

• maps.hpp

# 10.42 MAPSMutex Class Reference

The RTMaps mutex class.

Inheritance diagram for MAPSMutex:



#### **Public Member Functions**

• MAPSMutex ()

Standard constructor.

- virtual  $\sim$ MAPSMutex ()
  - Standard destructor.
- void Lock ()

Locks the mutex.

• void Release ()

Releases the mutex.

• void Reset ()

Tries to lock the mutex.

# 10.42.1 Detailed Description

The RTMaps mutex class. A mutex blocks concurrent threads if they both want to access shared data at the same time.

#### 10.42.2 Member Function Documentation

### 10.42.2.1 void MAPSMutex::Lock ( )

Locks the mutex.

Any other thread will block until this thread calls MAPSMutex::Release

Reimplemented in MAPSMutex2.

#### 10.42.2.2 void MAPSMutex::Release ( )

Releases the mutex.

Any other thread blocked on this monitor will be able to lock it.

Reimplemented in MAPSMutex2.

#### 10.42.2.3 void MAPSMutex::Reset (void)

Tries to lock the mutex.

Resets the mutex

Reset is very important to avoid deadlocking: when a mutex is possibly still owned by a dead thread, then a call to reset in MAPSComponent::Death() will solve the problem. Not calling Reset() in that case will probably deadlock the component during its next start, on the first call to Lock().


The documentation for this class was generated from the following file:

• maps.hpp

## 10.43 MAPSMutex2 Class Reference

The RTMaps advanced mutex class.

Inheritance diagram for MAPSMutex2:



## **Public Member Functions**

• MAPSMutex2 ()

Standard constructor. No options.

• void Lock ()

Locks the mutex.

• bool TryLock ()

Tries to lock the mutex. If it is already locked by somebody else, returns false immediatly.

· void ReleaseAll ()

Releases all references on the mutex (if any)

• void Release ()

Releases the mutex.

## 10.43.1 Detailed Description

The RTMaps advanced mutex class. This mutex has a reference counter and knows which thread owns it. Therefore, a thread can lock it several times without deadlocking it!

#### 10.43.2 Member Function Documentation

#### 10.43.2.1 void MAPSMutex2::ReleaseAll ( )

Releases all references on the mutex (if any)

Very useful when an exception occured and we are not sure about the number of references really held by the thread.

The documentation for this class was generated from the following file:

· maps.hpp

## 10.44 MAPSOutput Class Reference

The RTMaps Module Output class.

## **Public Member Functions**

• virtual MAPSString & Name ()=0

Returns the name of the output.

• virtual int NbFIFOOverflows ()=0

Returns the number of FIFO overflows on this output (performance monitoring)

• virtual MAPSIOMonitor & Monitor ()=0

Returns a pointer to the MAPSIOMonitor object associated to this output (the buffer management system)

• virtual void MakeShareable ()=0

Makes this output buffer shareable among different RTMaps processes (expert only)

• virtual void MakeUnshareable ()=0

Makes this output buffer unshareable among different RTMaps processes (expert only)

• virtual int IOEltSizeBytes ()=0

Returns the size in bytes of one element of the buffer according to the allocation.

• virtual MAPSTypeInfo & Type ()=0

Returns the type of the output.

virtual void SetTypeUnit (const char \*unit)=0

Sets the unit of the output (dynamically modifies the type)

• virtual void SetUnit (const char \*unit)=0

Sets the unit of the output (dynamically modifies the type)

virtual const char \* TypeUnit ()=0

Gets the unit of the output ("m/s" for instance)

• virtual const char \* Unit ()=0

Gets the unit of the output ("m/s" for instance)

• virtual void SetTypeName (const char \*name)=0

Sets the name parameter of the type of the output (dynamically modifies the type)

• virtual const char \* TypeName ()=0

Gets the name parameter of the type of the output.

virtual ∼MAPSOutput ()

Destructor.

## **Buffer allocation functions**

These are very important functions.

#### Note

There is no deallocation functions, since RTMaps automatically deallocates the output buffer when the output dies.

virtual void AllocOutputBuffer (int size, bool doAllocate=true)=0
 Allocates an output buffer with an element size of size.

virtual void AllocOutputBufferIpIImage (IpIImage &model, bool headerOnly=false)=0

Allocates an IplImage output buffer.

virtual void AllocOutputBufferImage (int size, int w=0, int h=0, MAPSUInt32 coding=MAPS\_-IMAGECODING\_UNKNOWN, MAPSUInt32 imageType=MAPS\_IMAGETYPE\_COLOR, bool headerOnly=false)=0

Allocates a MAPSImage output buffer.

virtual void AllocOutputBufferMAPSImage (int size, int w=0, int h=0, MAPSUInt32 coding=MAPS\_IMAGECODING\_UNKNOWN, MAPSUInt32 imageType=MAPS\_IMAGETYPE\_COLOR, bool headerOnly=false)=0

Allocates a MAPSImage output buffer.

virtual void AllocOutputBufferMatrix (int m, int n)=0
 MAPSMatrix output buffer allocation.

## 10.44.1 Detailed Description

The RTMaps Module Output class. You must use this class in particular to allocate the data buffers in RTMaps. They are called "output buffers", because they are associated to the output. In the RTMaps component model, the outputs are responsible for the data buffering, and the components are responsible for their outputs.

## 10.44.2 Member Function Documentation

```
10.44.2.1 virtual void MAPSOutput::AllocOutputBuffer ( int size, bool doAllocate = true )

[pure virtual]
```

Allocates an output buffer with an element size of size.

This function is automatically called when an output is created, but it provides only basic output buffer capabilities, since it has only one parameter.

What this function really does depends on the type of the output:

- For "vectorizable" types, like integers, floats or CAN frames, this defines the size of the vector (*size* must be 1 for a scalar).
- For text types (MAPS::TextAscii or MAPS::TextUnicode), this function allocates some strings for the buffer of *size* characters. The default value MAPS::DefaultTextSize is generally used.

- For the MAPSMatrix type, an array of *size* elements is allocated for each buffer element, which means that the maximum m\*n size of the matrix must be less than *size*. m and n are set to 0 by default. A call to MAPSOutput::AllocOutputBufferMatrix can be more appropriate.
- For a MAPSImage type, an image buffer of size is allocated for each buffer element. All the parameters of the structure are set to 0 or unknown. A call to MAP-SOutput::AllocOutputBufferImage or MAPSOutput::AllocOutputBufferMAPSImage might be more appropriate.
- For an IpIImage type, no allocation is done whatever size is. You MUST call MAPSOutput::AllocOutputBufferIpIImage to allocate the buffer.

If *size* is 0, no output buffer allocation is done, and another call to an output buffer allocation function will have to be done before the buffer can be actually used.

Allocates a MAPSImage output buffer.

#### **Parameters**

size	The size in bytes to allocate for the image buffer. Note that it can be less
	than <i>w</i> * <i>h</i> since a MAPSImage can contain compressed images.
W	The width of the image
h	The height of the image
coding	Integer describing the code used by the image buffer. For instance ${\tt MAPS\}$
	IMAGECODING_JPEG or MAPS_IMAGECODING_YUYV.
imageType	Additional information describing the type of the image. Generally, it is set to MAPS IMAGETYPE COLOR or MAPS IMAGETYPE MONO.
	TO MAPS_IMAGETTEL_COLOR OF MAPS_IMAGETTEL_MONO.
headerOnly	If set to true, this function will only allocate the header, and no memory
	will be allocated for the content of the image. This is useful to directly con-
	nect the IplImage structure to a frame buffer allocated by a hardware frame
	grabber. For experts only. headerOnly should usually be set to false.

# 10.44.2.3 virtual void MAPSOutput::AllocOutputBufferlpllmage ( lpllmage & model, bool headerOnly = false ) [pure virtual]

Allocates an IplImage output buffer.

#### **Parameters**

model	A model to replicate for each buffer element. This model can be provided by
	a call to MAPS::IpIImageModel.

headerOnly	If set to true, this function will only allocate the header, and no memory
	will be allocated for the content of the image. This is useful to directly con-
	nect the IpIImage structure to a frame buffer allocated by a hardware frame
	grabber. For experts only. headerOnly should usually be set to false.

Allocates a MAPSImage output buffer.

Allocates a MAPSImage output buffer.

#### **Parameters**

size	The size in bytes to allocate for the image buffer. Note that it can be less
0,20	
	than $w*h$ since a MAPSImage can contain compressed images.
W	The width of the image
h	The height of the image
coding	Integer describing the code used by the image buffer. For instance MAPS
	IMAGECODING_JPEG or MAPS_IMAGECODING_YUYV.
imageType	Additional information describing the type of the image. Generally, it is set
	to MAPS_IMAGETYPE_COLOR or MAPS_IMAGETYPE_MONO.
headerOnly	If set to true, this function will only allocate the header, and no memory
	will be allocated for the content of the image. This is useful to directly con-
	nect the IplImage structure to a frame buffer allocated by a hardware frame
	grabber. For experts only. <i>headerOnly</i> should usually be set to false.

# 10.44.2.5 virtual void MAPSOutput::AllocOutputBufferMatrix ( int $\it m$ , int $\it n$ ) [pure virtual]

MAPSMatrix output buffer allocation.

## **Parameters**

т	The number of rows of the allocated matrix
n	The number of columns of the allocated matrix

## 10.44.2.6 virtual int MAPSOutput::IOEltSizeBytes ( ) [pure virtual]

Returns the size in bytes of one element of the buffer according to the allocation.

This is very useful to copy a buffer element. Beware that MAPS::Memcpy() cannot generally be used to copy buffers, in particular for lpllmage and MAPSImage

```
10.44.2.7 virtual MAPSString& MAPSOutput::Name() [pure virtual]
```

Returns the name of the output.

In the form componentName.outputName

```
10.44.2.8 virtual void MAPSOutput::SetTypeName ( const char * name ) [pure virtual]
```

Sets the name parameter of the type of the output (dynamically modifies the type)

#### See also

**MAPSTypeInfo** 

```
10.44.2.9 virtual void MAPSOutput::SetTypeUnit (const char * unit) [pure virtual]
```

Sets the unit of the output (dynamically modifies the type)

#### See also

**MAPSTypeInfo** 

```
10.44.2.10 virtual void MAPSOutput::SetUnit ( const char * unit ) [pure virtual]
```

Sets the unit of the output (dynamically modifies the type)

#### See also

MAPSTypeInfo

```
10.44.2.11 virtual const char* MAPSOutput::TypeName( ) [pure virtual]
```

Gets the name parameter of the type of the output.

This is completely different from the name of the output itself. Don't get confused.

## See also

**MAPSTypeInfo** 

The documentation for this class was generated from the following file:

• maps.hpp

# 10.45 MAPSPair < TKey, TContent > Class Template Reference

The RTMaps (key,content) pair template class.

## **Public Member Functions**

• TKey & Key ()

Returns the key stored in the pair.

• TContent & Content ()

Returns the content stored in the pair.

MAPSPair (TKey &kx, TContent &cx)
 Constructor.

• MAPSPair ()

Default constructor.

## 10.45.1 Detailed Description

template < typename TKey, typename TContent> class MAPSPair < TKey, TContent >

The RTMaps (key,content) pair template class.

#### See also

MAPSHashTable

The documentation for this class was generated from the following file:

• maps.hpp

## 10.46 MAPSProperty Class Reference

The RTMaps Module Property class.

## **Public Member Functions**

- virtual MAPSInt64 & IntegerValue ()=0
   Returns a reference to the integer content of the property.
- virtual MAPSString & StringValue ()=0

Returns a reference to the string content of the property.

- virtual bool & BoolValue ()=0
   Returns a reference to the boolean content of the property.
- virtual MAPSFloat & FloatValue ()=0
   Returns a reference to the float content of the property.
- virtual MAPSEnumStruct & EnumValues ()=0
   Returns a reference to the enum structure of the property.
- virtual MAPSString & Name ()=0
   Returns the name of the property.
- virtual MAPSString & ShortName ()=0
   Returns the short name of the property.
- virtual const char \* Unit ()=0
   Returns the unit of the property.
- virtual MAPSModule & Owner ()=0

  Returns the owner of this property.
- virtual int Type ()=0
   Returns the type of this property.
- virtual bool PropertyChanged ()=0
   Tells if the property value has changed.
- virtual void AcknowledgePropertyChanged ()=0
   Acknowledges the property value change.
- virtual MAPSEvent \* GetPropertyChangedEvent ()=0
   Gets the MAPSEvent related to the change of property value event.
- virtual MAPSEvent & PropertyChangedEvent ()=0
   Gets the MAPSEvent related to the change of property value event.

## The Set functions (to set the property value)

These functions call the MAPSModule::Set functions associated to the owner of the property. Behaviour might differ depending on the type of the property.

virtual void Set (bool value)=0
 Sets the boolean property value to value for boolean properties.

virtual void Set (MAPSInt64 value)=0

Sets the integer property value to value for integer properties, or the selected item for enum properties.

- virtual void Set (MAPSInt32 value)=0
- virtual void Set (MAPSFloat value)=0

Sets the float property value to value for floating point properties.

• virtual void Set (const char \*value)=0

Sets string property value to value for string properties, or fills the enum values for enum properties.

- virtual void Set (const MAPSString &value)=0
- virtual void Set (MAPSEnumStruct enumStruct)=0

Sets the enum property value to enumStruct (enum strings and the selected item) for enum properties.

virtual void Set (const MAPSString &enumValues, const int selected)=0

Sets enum values to enumValues and the selected enum value to selected for enum properties.

### The Get functions (to get the property value)

These functions call the MAPSModule::Get functions associated to the owner of the property. Behaviour might differ depending on the type of the property.

• virtual void Get (bool &value)=0

Gets the boolean property value into value for boolean properties.

virtual void Get (MAPSInt64 &value)=0

Gets the integer property value into value for integer properties, or the selected item for enum properties.

- virtual void Get (MAPSInt32 &value)=0
- virtual void Get (MAPSFloat &value)=0

Gets the float property value into value for float properties.

• virtual void Get (MAPSString &value)=0

Gets the string property value int value for string properties, or the selected item for enum properties.

virtual void Get (MAPSEnumStruct &enumStruct)=0

Gets the enum property value into enumStruct for enum properies.

virtual void Get (MAPSArray< MAPSString > &enumValues, MAPSInt32 &selectedValue)=0

Gets the enum property value for enum properties.

## Properties callback management functions

For RTMaps experts only!

- virtual void SetSetCallback (MAPSPropertySetCallback cb)=0
   Sets a callback which will be called on a call to Set.
- virtual void SetGetCallback (MAPSPropertyGetCallback cb)=0
   Sets a callback which will be called on a call to Get.

### 10.46.1 Detailed Description

The RTMaps Module Property class.

## 10.46.2 Member Function Documentation

```
10.46.2.1 virtual void MAPSProperty::AcknowledgePropertyChanged ( ) [pure
    virtual]
```

Acknowledges the property value change.

Must be called regularly so that we can know the property has changed.

#### See also

MAPSProperty::PropertyChanged

```
10.46.2.2 virtual void MAPSProperty::Get ( MAPSInt32 & value ) [pure virtual]
```

Gets the integer property value into *value* for integer properties, or the selected item for enum properties.

```
10.46.2.3 virtual void MAPSProperty::Get ( MAPSArray < MAPSString > & enumValues, MAPSInt32 & selectedValue ) [pure virtual]
```

Gets the enum property value for enum properties.

The enum value is split into the array of strings, put into *enumValues*, and the selected value, put into *selectedValue* 

```
10.46.2.4 virtual MAPSEvent* MAPSProperty::GetPropertyChangedEvent() [pure virtual]
```

Gets the MAPSEvent related to the change of property value event.

This can be very useful to make some wait on property value change. You can do that with the MAPSModule::Wait4Event or MAPSModule::Wait4Events function.

```
10.46.2.5 virtual MAPSString& MAPSProperty::Name( ) [pure virtual]
```

Returns the name of the property.

In the form componentName.propertyName

```
10.46.2.6 virtual bool MAPSProperty::PropertyChanged() [pure virtual]
```

Tells if the property value has changed.

Returns true if the property value has changed since the last call to MAPSProperty::AcknowledgePropertyChanged

Gets the MAPSEvent related to the change of property value event.

This can be very useful to make some wait on property value change. You can do that with the MAPSModule::Wait4Event or MAPSModule::Wait4Events function.

```
10.46.2.8 virtual void MAPSProperty::Set ( MAPSInt32 value ) [pure virtual]
```

Sets the integer property value to *value* for integer properties, or the selected item for enum properties.

```
10.46.2.9 virtual void MAPSProperty::Set ( const MAPSString & value ) [pure virtual]
```

Sets string property value to *value* for string properties, or fills the enum values for enum properties.

```
10.46.2.10 virtual MAPSString& MAPSProperty::ShortName() [pure virtual]
```

Returns the short name of the property.

Returns the part of the name after the first dot (module name)


The documentation for this class was generated from the following file:

· maps.hpp

## 10.47 MAPSPtrHashTable < TContent > Class Template Reference

The RTMaps pointer hash table template class.

Inheritance diagram for MAPSPtrHashTable < TContent >:



#### **Public Member Functions**

MAPSPtrHashTable (int n=16)
 Constructor.

## 10.47.1 Detailed Description

 $template < typename\ TContent > class\ MAPSPtrHashTable < TContent >$ 

The RTMaps pointer hash table template class. As its name says, the key is a pointer The documentation for this class was generated from the following file:

• maps.hpp

## 10.48 MAPSRBRegion Class Reference

MAPSRBRegion class: Ring-Buffer region manipulation class.

#### **Public Member Functions**

- MAPSConstRBRegionState Check () const Check that the region is consistent and returns its state.
- int operator[] (int i) const

A very important operator when manipulating regions.

## **Static Public Member Functions**

• static const MAPSString StateToString (const MAPSConstRBRegionState &st)

A very useful function to convert state into strings.

## **Public Attributes**

· int fifoSize

define the size of the ring-buffer.

· int offset

define the start of the region in the ring-buffer.

• int size

define the size of the region.

## **Constructors**

• MAPSRBRegion ()

Constructor of the class: just initialize all attributes to 0, and put the region to the MAPSConstRBRegionUninitialized state.

• MAPSRBRegion (const MAPSRBRegion &reg)

Copy constructor of the class.

## Initialization routines

- MAPSConstRBRegionState Init (int fifoSizex, int offsetx, int sizex)
   Initialize the region with default values.
- MAPSConstRBRegionState Reset ()

Reset the region : offset=0, size=0.

• MAPSConstRBRegionState Full ()

Fill entirely the region from current offset.

#### Attribute set methods.

• MAPSConstRBRegionState SetFifoSize (int value)

Set the ring-buffer size of the current region.

MAPSConstRBRegionState SetSize (int value)

Set the size attribute.

MAPSConstRBRegionState SetOffset (int value)

Set the offset attribute.

## Attributes or simple get methods

• int InverseSize () const

Returns the complementary size of the region (fifoSize-size)

• int FifoSize () const

Returns the size of the ring-buffer.

• int Size () const

Get size attribute.

• int Size0 () const

Get size attribute.

• int Size1 () const

Get size attribute.

• int Offset () const

Get offset attribute.

• int OffsetLastElement () const

Get the last offset of the region.

## Operation on the region itself

• MAPSConstRBRegionState Erode (MAPSConstRBRegionErosion type, int sizex)

Erosion of a region.

• MAPSConstRBRegionState Dilate (MAPSConstRBRegionDilation type, int sizex)

Dilation of a region.

MAPSConstRBRegionState Crop (MAPSConstRBRegionCrop type, int offsetX, int sizex)

Crop a region.

## Transformation of the region into a new one

MAPSConstRBRegionState SubRegion (MAPSRBRegion &dest, MAPSConstR-BRegionSubRegion type, int offsetX, int sizex) const

Extract a sub-region from current region.

 MAPSConstRBRegionState BesideRegion (MAPSRBRegion &dest, MAPSConstRBRegionBesideRegion type, int offsetX, int sizex) const

Define a new region next to current region.

MAPSConstRBRegionState InverseRegion (MAPSRBRegion &dest) const
 Define the complementary region of the current region (inversion).

## Direct-access operations: Push, Pop, etc...

 MAPSConstRBRegionState Push (int nbData, MAPSRBRegion &destSubregion, bool enableOverwrite=true)

Push some data in the ring-buffer (FIFO like operation)

• MAPSConstRBRegionState Pop (int nbData, MAPSRBRegion \*srcSubregion=NULL)

Pop some data from the ring-buffer (FIFO like operation)

MAPSConstRBRegionState Popback (int nbData, MAPSRBRegion \*srcSubregion=NULL)

Dequeues some data from the ring-buffer (STACK like operation). The data is removed from the last.

## **Templates**

template<class T >

int CopyFromRB (const T \*fifoData, T \*dest, int destMaxSize) const

A template function designed to copy the content of a circular buffer to a temporary linear buffer.

• template<class T >

int CopyToRB (T \*fifoData, const T \*src, int srcMaxSize)

A template function designed to copy the content of a temporary linear buffer to a circular buffer region.

• template<class T >

int DuplicateToRB (T \*fifoData, T data)

A template function designed to duplicate an element t of T into the whole region of dest.

template < class T >
 int DuplicateToRB2 (T \*fifoData, T data, T increment)

A template function designed to duplicate an element t of T into the whole region of dest with regular increments.

template<class T >
 int DuplicateToRB3 (T \*fifoData, T data, T increment, T min data value)

A template function designed to duplicate an element t of T into the whole region of dest with regular increments but with a minimum value.

## 10.48.1 Detailed Description

MAPSRBRegion class: Ring-Buffer region manipulation class. This class allows the user to manipulate regions of ring-buffers.

A region is built around the following variables:

- · offset : define the start of the region in the ring-buffer.
- size : define the size of the region. size=size0+size1
- size0 : define the size of the region up to the end of the ring-buffer.
- size1 : define the size of the region from the beginning of the ring-buffer.
- · fifoSize : define the size of the ring-buffer.

## 10.48.2 Member Function Documentation

10.48.2.1 MAPSConstRBRegionState MAPSRBRegion::BesideRegion ( MAPSRBRegion & dest, MAPSConstRBRegionBesideRegion type, int offsetX, int sizex ) const

Define a new region next to current region.

#### **Parameters**

dest	The destination region.
type	Define if the region must be taken from before or after the src region.
offsetX	Define an offset from the starting point (beginning or end).
sizex	Size of the new region.

Generated on Wed Oct 13 2010 18:59:21 for RTMaps by Doxygen

#### Returns

The return value is the state of the new region, if the operation succeeded. Else it returns  ${\tt MAPSConstRBRegionInvalidOp}$ 

# 10.48.2.2 MAPSConstRBRegionState MAPSRBRegion::Crop ( MAPSConstRBRegionCrop type, int offsetX, int sizex )

Crop a region.

#### **Parameters**

type	Define if the region must be croped from its beginning or its end
offsetX	Define an offset from the starting point (beginning or end).
sizex	Size of the new region (cropped).

#### Returns

The return value is the state of the new region, if the operation succeeded. Else it returns  ${\tt MAPSConstRBRegionInvalidOp}$ 

## 

Dilation of a region.

## **Parameters**

type	Define if the region must be dilated from its beginning and/or its end
sizex	Size of the dilation element.

## Returns

The return value is the state of the region, if the operation succeeded. Else it returns  ${\tt MAPSConstRBRegionInvalidOp}$ 

# 10.48.2.4 template < class T > int MAPSRBRegion::DuplicateToRB2 ( T \* fifoData, T data, T increment )

A template function designed to duplicate an element t of T into the whole region of dest with regular increments.

Usually used for timestamp data with frequency information (so we duplicate first the original timestamp, then increment it each step).

# 10.48.2.5 template < class T > int MAPSRBRegion::DuplicateToRB3 ( T \* fifoData, T data, T increment, T min\_data\_value )

A template function designed to duplicate an element t of T into the whole region of dest with regular increments but with a minimum value.

Usually used for timestamp data with frequency information and monotonous constraints The min\_data\_value parameter should then be the last timestamp duplicated to the RB at the previous call to DuplicateToRB3. So we duplicate first the original timestamp, then increment it each step, provided it is not lower that min\_data\_value. Otherwise, the current value is bounded to min\_data\_value. WARNING: when using with timestamp, this can be nice for real-time operation, but problematic in replay mode when jumping backwards in time.

## 

Erosion of a region.

#### **Parameters**

type	Define if the region must be eroded from its beginning and/or its end
sizex	Size of the erosion element.

#### Returns

The return value is the state of the region, if the operation succeeded. Else it returns MAPSConstRBRegionInvalidOp

# 10.48.2.7 MAPSConstRBRegionState MAPSRBRegion::Init ( int fifoSizex, int offsetx, int sizex )

Initialize the region with default values.

#### **Parameters**

fifoSizex	The size of the ring-buffer
offsetx	The start of the region in the ring-buffer.
sizex	The region size

### **Returns**

Returns the state of the defined region.

# 10.48.2.8 MAPSConstRBRegionState MAPSRBRegion::InverseRegion ( MAPSRBRegion & dest ) const

Define the complementary region of the current region (inversion).

#### **Parameters**

dest	The destination region.

#### Returns

The return value is the state of the new region, if the operation succeeded. Else it returns MAPSConstRBRegionInvalidOp

#### 10.48.2.9 int MAPSRBRegion::operator[] ( int i ) const

A very important operator when manipulating regions.

This operator returns the offset i of a given region. If i is an incorrect offset and in debug mode, this method generate an assert. Otherwise, it returns the direct offset in the ring-buffer of the i element of the current region.

# 10.48.2.10 MAPSConstRBRegionState MAPSRBRegion::Pop ( int nbData, MAPSRBRegion \* srcSubregion = NULL )

Pop some data from the ring-buffer (FIFO like operation)

#### **Parameters**

nbData	The number of element your want to pop from the FIFO
srcSubre-	Will contain the sub-region that contains data to pop.
gion	

#### **Returns**

The return value is the state of the new region, if the operation succeeded. Else it returns  ${\tt MAPSConstRBRegionInvalidOp}$ .

# 10.48.2.11 MAPSConstRBRegionState MAPSRBRegion::Popback (int nbData, MAPSRBRegion \* srcSubregion = NULL )

Dequeues some data from the ring-buffer (STACK like operation). The data is removed from the last.

#### **Parameters**

nbData	The number of element your want to popback from the stack
srcSubre-	Will contain the sub-region that contains data to popback.
gion	

## Returns

The return value is the state of the new region, if the operation succeeded. Else it returns MAPSConstRBRegionInvalidOp.

# 10.48.2.12 MAPSConstRBRegionState MAPSRBRegion::Push ( int *nbData*, MAPSRBRegion & *destSubregion*, bool *enableOverwrite* = true )

Push some data in the ring-buffer (FIFO like operation)

#### **Parameters**

nbData	The number of element your want to push in the FIFO. nbData will contain
	the real number of pushed data in the region.
destSubre-	Will contain the sub-region that must receive data to push.
gion	
	If set to true, a push with nbData too big will overwrite FIFO data. Else,

#### **Returns**

The return value is the state of the new region, if the operation succeeded. An over-flow will return MAPSConstRBRegionOverflowOp. Else it returns MAPSConstRBRegionInvalidOp.

# 10.48.2.13 MAPSConstRBRegionState MAPSRBRegion::SubRegion ( MAPSRBRegion & dest, MAPSConstRBRegionSubRegion type, int offsetX, int sizex ) const

Extract a sub-region from current region.

#### **Parameters**

dest	The destination region.
type	Define if the region must be extracted from the beginning or the end of src region.
offsetX	Define an offset from the starting point (beginning or end).
sizex	Size of the new region.

## Returns

The return value is the state of the new region, if the operation succeeded. Else it returns MAPSConstRBRegionInvalidOp

The documentation for this class was generated from the following file:

• MAPSRBRegion.h

## 10.49 MAPSRealObject Struct Reference

The standard structure to transmit info about real objects.

## **Public Attributes**

• int kind

Specifies the kind of real object for this object.

• int id

Identifier (for instance, obstacle number)

MAPSFloat x

The x coordinate of the object.

MAPSFloat y

The y coordinate of the object.

MAPSFloat z

The z coordinate of the object.

• int color

The main color of the real object (RGB 24bits, Intel oriented : use MAPS\_RGB macro)

• MAPSVehicle vehicle

The real object is a vehicle.

MAPSSign sign

The real object is traffic sign.

• MAPSTree tree

The real object is a tree.

## **Static Public Attributes**

• static const int Vehicle

One kind of real object.

• static const int Sign

Another kind of real object.

static const int Tree

Another kind of real object.

#### **User defined information**

int misc1

Miscellaneous 1.

• int misc2

Miscellaneous 2.

• int misc3

Miscellaneous 3.

void \* userdata

TO USE WITH CARE! C++ EXPERTS ONLY.

## 10.49.1 Detailed Description

The standard structure to transmit info about real objects. The real content of the MAP-SRealObject depends on the kind parameter.

By convention the coordinates of the object represent the position of the lower point in the middle of the object. The vehicle's coordinates represent the point on the floor at the middle of the back of the vehicle. A tree's coordinate is the coordinate of its trunk, at its base on the floor.

This structured type should evolve with the upcoming new RTMaps applications.


The documentation for this struct was generated from the following file:

• maps.hpp

## 10.50 MAPSRealObjectVariant Struct Reference

All real objects in RTMaps (vehicles, etc.) inherit from this structure.

Inheritance diagram for MAPSRealObjectVariant:



## 10.50.1 Detailed Description

All real objects in RTMaps (vehicles, etc.) inherit from this structure.

The documentation for this struct was generated from the following file:

· maps.hpp

## 10.51 MAPSRecordingStateListener Class Reference

The MAPSRecordingStateListener interface.

#### **Public Member Functions**

virtual void CallbackRecordingStateChanged (const bool recording)=0
 Implement this function if you want to execute some code when the recording mode is activated or deactivated.

## 10.51.1 Detailed Description

The MAPSRecordingStateListener interface. Your class should inherit from this interface if you want it to be notified when RTMaps starts and stops recording.

#### Warning

If a MAPSComponent inherits this class, the Callback function is called from a different thread than the main thread of the component. Pay attention to threads synchronization. The callback function can be called as soon as the child class is constructed (in case of a MAPSComponent, the callback can be called even when the component is not running).

#### 10.51.2 Member Function Documentation

10.51.2.1 virtual void MAPSRecordingStateListener::CallbackRecordingStateChanged ( const bool recording ) [pure virtual]

Implement this function if you want to execute some code when the recording mode is activated or deactivated.

#### **Parameters**

recording It is set to true when the recording is activated, and to false when recording is stopped.

The documentation for this class was generated from the following file:

• maps.hpp

## 10.52 MAPSRecordReplayMethod Class Reference

The base class for all record/replay methods.

Inheritance diagram for MAPSRecordReplayMethod:



## **Protected Member Functions**

• MAPSOutput & Output ()

Returns a reference the output recorded or replayed.

• MAPSString FileName ()

Returns the current file name.

MAPSString FastFileName ()

Returns the current fast file name.

MAPSString DumpFileName (int dumpNb)

Returns the dump file name (for the # dumpNb)

• MAPSString RecordPath ()

Returns the RRM recordPath if specified, the recorder recordPath otherwise.

MAPSString FastRecordPath ()

Returns the RRM fastRecordPath if specified, the recorder fastRecordPath otherwise.

• int NbRecords ()

Returns the current number of records.

• MAPSRecorder & Recorder ()

Returns the recorder associated to this record/replay method.

 MAPSRecordReplayMethod (MAPSRecordReplayMethodDefinition &rmd, MAP-SRecorder \*recorder, MAPSOutput &output, bool record, bool copy)

Constructor.

## Buffer and pre-processing management

• virtual bool DoProcessBufferItem (MAPSIOEIt &)

Returns whether some processing (compression for instance) is needed before the item is stored. Generally overloaded.

• virtual void ProcessBufferItem (MAPSIOEIt &source, MAPSIOEIt &dest)

The processing itself (for instance a compression algorithm). Generally overloaded.

## **Record management**

• void RecordTime (MAPSIOEIt &IOEIt)

Records the current record time in the .rec buffer.

void RecordHeading (MAPSIOEIt &IOEIt)

Records the heading in the .rec and .idy (the heading describes the output currently begin recorded)

• bool HeadingRecorded ()

Has the heading already been recorded?

• const char \* HeadingHint ()

Returns the heading hint (during replay)

• virtual void Store (MAPSIOEIt &IOEIt)=0

The store operation (write to disk). Must be overloaded.

virtual const char \* Hint (MAPSIOEIt &IOEIt)=0

The hint found in the .rec file. Must be overloaded.

• virtual MAPSString HeadingHint (MAPSIOEIt &)

The function that sets the heading hint during record. Generally overloaded.

 void FileWrite (MAPSFileWriteHandle \*fileHandle, const void \*buffer, int size, MAPSIOEIt \*IOEIt=NULL)

An overload of MAPSFileIO::FileWrite, to ease the design of asynchronous recording methods.

void Unlock (MAPSIOEIt &IOEIt)

The MAPSFileIO::Unlock overload.

## **Trigger management**

- void Set (MAPSProperty &p, bool value)
   Overload for set, taking into account the special "trigger" property.
- void Trigger (bool report=false)

  Sets the trigger.

## Replay management

virtual bool Replay (MAPSIOEIt &IOEIt, int rec, const char \*hint, MAPSTypeInfo &type)=0

The replay function. Must be overloaded.

## Birth and death management

- virtual void BirthRecord (void)=0
   Birth in record mode. Must be overloaded.
- virtual void BirthReplay (void)
   Birth in replay mode. Default does nothing.
- virtual void DeathRecord (void)=0
   Death in record mode. Must be overloaded.
- virtual void DeathReplay (void)
   Death in replay mode. Default does nothing.

## **Blackbox management**

• bool Blackboxed ()

Are we in blackbox recording mode?

- virtual bool BlackboxCompatible (void)
  - Is the component blackbox mode compatible? (default is no)
- virtual void BlackboxSwitch (MAPSString &)

The blackbox switch function. Must be overloaded for blackbox compatible record methods.

• virtual void BlackboxDump (MAPSString &)

The blackbox dump function.

## Copy management

The basic database editing feature

• MAPSRecordReplayMethod & CopyDestination ()

The record methods that is the destination of the current copy operation.

• bool Copying ()

Am I in copy mode?

virtual bool Copy (MAPSIOEIt &IOEIt, int rec, const char \*hint, MAPSTypeInfo &type)

The copy operation. Generally needs to be overloaded.

## **Error management**

void Error (const char \*string, int importance=1)
 Emits an error.

## 10.52.1 Detailed Description

The base class for all record/replay methods. Examples of record/replay methods (RRMs) are raw, jpeg, jseq, wave, txt, mfile, etc. Some useful macros are available for easier development of RRMs. They are detailed in Record/replay method design.

## 10.52.2 Member Function Documentation

Emits an error.

This will kill definitely the module. Use MAPSModule::ReportError if you want to go on executing some code.

#### **Parameters**

	string	Error string to log and display
	importance	Importance of the error :
		<ul> <li>0: The error is minor. It will not have any impact on the overall system behaviour. Some actions have been taken that will fix the problem.</li> <li>1: The error is important. Some actions have been taken that might fix the problem. The system can go on running, but it might not function properly.</li> <li>2: The error is critical. The system will not function properly thereafter.</li> </ul>
П		

Reimplemented from MAPSModule.

# 10.52.2.2 virtual MAPSString MAPSRecordReplayMethod::HeadingHint ( MAPSIOEIt & ) [protected, virtual]

The function that sets the heading hint during record. Generally overloaded.

By default, returns an empty string (no hint).


The documentation for this class was generated from the following file:

maps.hpp

# 10.53 MAPSRectangle Struct Reference

The MAPSRectangle structure.

Inheritance diagram for MAPSRectangle:



## **Public Attributes**

• int x1

First point x.

• int y1

First point y.

• int x2

Second point x.

int y2

Second point y.

## 10.53.1 Detailed Description

The MAPSRectangle structure.

The documentation for this struct was generated from the following file:

• maps.hpp

# 10.54 MAPSRunnable < T > Class Template Reference

Helper class to create worker threads.

#### 10.54.1 Detailed Description

template < typename T > class MAPSRunnable < T >

Helper class to create worker threads. A MAPSRunnableFunc function typically looks like: void\* myFunc(void\* dataPtr) { while(! myRunnable.IsStopRequested()) } { do some stuff } } where dataPtr is the user data pointer given to the ctor or the Init function.

The documentation for this class was generated from the following file:

• maps.hpp

## 10.55 MAPSRunShutdownListener Class Reference

The MAPSRunShutdownListener interface.

#### **Public Member Functions**

- virtual void CallbackRun ()=0
  - Implement this function to execute some code when diagram starts running.
- virtual void CallbackShutdown ()=0

Implement this function to execute some code when diagram stops running.

#### 10.55.1 Detailed Description

The MAPSRunShutdownListener interface. Your class should inherit from this interface if you want it to be notified of RTMaps Run/Shutdown events through functions CallbackRun() and CallbackShutdown();

#### Warning

If a MAPSComponent inherits this class, the Callback functions are called from a different thread than the main thread of the component. Pay attention to threads synchronization. The callback function can be called as soon as the child class is constructed (in case of a MAPSComponent, the callbacks can be called even when the component is not running).

#### 10.55.2 Member Function Documentation

## 10.55.2.1 virtual void MAPSRunShutdownListener::CallbackRun() [pure virtual]

Implement this function to execute some code when diagram starts running.

This function will be called by the RTMaps engine when the diagram starts to run, just before the diagram components start to run (i.e. just before their Birth() method are called).

Implement this function to execute some code when diagram stops running.

This function will be called by the RTMaps engine when the diagram stops running, after the diagram components stop running (i.e. after their Death() method are called).


The documentation for this class was generated from the following file:

· maps.hpp

## 10.56 MAPSSign Struct Reference

The MAPSSign structure: a kind of MAPSRealObject.

Inheritance diagram for MAPSSign:



### **Public Attributes**

int type

The type of the sign.

· int speedLimit

Speed limit information.

· int trafficLightState

State of a traffic light.

• char text [256]

Text information.

## **Static Public Attributes**

• static const int Stop

Stop sign.

static const int Yield
 Yield sign.

static const int OneWay
 One Way sign.

static const int TurnLeft
 Turn left sign.

• static const int TurnRight

Turn right sign.

static const int SpeedLimit
 Speed limit sign.

static const int EndOfSpeedLimit
 End of speed limit sign.

static const int TrafficLight
 A traffic light.

static const int TextOnly
 Text only sign.

static const int Red
 The traffic light is red.

static const int Orange
 The traffic light is orange.

• static const int Green

The traffic light is green.

static const int OrangeBlinking
 The orange is blinking.

## 10.56.1 Detailed Description

The MAPSSign structure: a kind of MAPSRealObject.

#### See also

MAPSRealObject


The documentation for this struct was generated from the following file:

· maps.hpp

## 10.57 MAPSSpot Struct Reference

The MAPSSpot structure.

Inheritance diagram for MAPSSpot:



## **Public Attributes**

• int x

The x coordinate of the spot.

• int y

The y coordinate of the spot.

• int kind

The kind of spot (MAPSSpot::Cross, etc.)

#### **Static Public Attributes**

• static const int Point

This spot is simply a point.

· static const int Cross

This spot is a cross.

· static const int Circle

This spot is a small circle.

· static const int CircledPoint

This spot is a point with a circle around.

• static const int CircledCross

This spot is a cross with a circle around.

## 10.57.1 Detailed Description

The MAPSSpot structure.

The documentation for this struct was generated from the following file:

· maps.hpp

# 10.58 MAPSStackedString < BUFFER\_SIZE > Class Template Reference

The RTMaps flexible and fast string template class.

## **Public Member Functions**

- int Length () const

  Returns the length of the string.
- int Len () const

  Returns the length of the string.
- char & operator[] (int pos) const
   Gets/Sets the character at position pos.
- operator const char \* () const
   Automatic cast to const char\*

String copy operator. Returns a reference to the current string (\*this).

MAPSStackedString & operator= (const char \*s)
 String copy operator. Returns a reference to the current string (\*this).

• MAPSStackedString & operator= (const MAPSStackedString &s)

MAPSRegExp & operator= (MAPSRegExp &regexp)
 Match against a regular expression.

• const char \* Beginning () const

Returns a pointer to the beginning of the string.

• int Pos (const char \*ptr) const

Returns the position corresponding to a pointer to a character of the string.

MAPSStackedString & Shorten (int pos)

Reduces the length of the string to pos.

• void Clear ()

Clears the content of the string.

• MAPSStackedString & UpdateLength ()

Updates the length of the string by finding the first 0 character in the string buffer.

MAPSStackedString & RemoveCRLF ()

Removes the trailing  $' \ n'$  or  $' \ r \ n'$  characters.

MAPSStackedString & RemoveSpaces ()

Removes spaces, tabs or carriage returns found at the beginning and at the end of the string.

• MAPSStackedString & Uppercase ()

Sets the string to uppercase ('abc'->'ABC'). Returns a reference to the current string (\*this).

• MAPSStackedString & FirstUppercase ()

Sets the first character of the string to uppercase.

• MAPSStackedString & Substitute (char s, char d)

Substitutes all s characters with d. Returns a reference to the current string (\*this).

• MAPSStackedString & Reverse (const MAPSStackedString &s)

Sets the current string to the reverse of string s. Returns a reference to the current string (\*this).

## **Related Functions**

(Note that these are not member functions.)

template<int BUFFER\_SIZE>

MAPSStreamedString & operator << (MAPSStreamedString & out, const MAPSStacked-String < BUFFER\_SIZE > &str)

Standard operator.

#### Strings comparison functions

- bool operator== (const MAPSStackedString &s) const
   String comparaison, equivalent to strcmp, i.e. case-sensitive.
- bool operator== (MAPSStackedString &s) const
   String comparaison, equivalent to strcmp, i.e. case-sensitive.
- bool operator!= (const MAPSStackedString &s) const
   String comparaison, equivalent to strcmp, i.e. case-sensitive.
- bool operator== (const char \*s) const

  String comparaison, equivalent to strcmp, i.e. case-sensitive.
- bool operator!= (const char \*s) const String comparaison, equivalent to strcmp, i.e. case-sensitive.
- bool operator< (const MAPSStackedString &s) const Simple string order, case sensitive.
- bool operator> (const MAPSStackedString &s) const Simple string order, case sensitive.
- bool Equals (const MAPSStackedString &s) const
   String comparison, equivalent to strcmp, i.e. case-sensitive.
- bool lequals (const MAPSStackedString &s) const
   String comparaison, equivalent to stricmp, i.e. lowercase comparison of strings.

## Strings concatenation functions

- MAPSStackedString & operator+= (const char \*s)
   String concatenation operator. Returns a reference to the current string (\*this).
- MAPSStackedString & operator+= (unsigned char \*s)
   String concatenation operator. Returns a reference to the current string (\*this).
- MAPSStackedString & operator+= (const MAPSStackedString &s)
   String concatenation operator. Returns a reference to the current string (\*this).
- MAPSStackedString & operator+= (const char c)
   Concatenates character c to the string. Returns a reference to the current string (\*this).

#### **Substring extraction functions**

All of these functions return a new string, or an array of strings.

- MAPSStackedString operator() (int start, int stop) const
   Extracts a part of the string.
- MAPSStackedString UpTo (char s, bool from\_beginning=true) const
   Returns the part of the string up to the first occurence of character s.
- MAPSStackedString Up2 (char s, bool from\_beginning=true) const
   Returns the part of the string up to the first occurence of character s.
- MAPSStackedString UpTo (int m, bool from\_beginning=true) const
   Returns the characters starting from the beginning of the string to mth character, counting from the beginning or the end of the string.
- MAPSStackedString Up2 (int m, bool from\_beginning=true) const
   Returns the characters starting from the beginning of the string to mth character,
   counting from the beginning or the end of the string.
- MAPSStackedString Tail (int m, bool from\_beginning=true) const
   Returns the characters starting from the mth character, counting from the beginning or
   the end of the string, to the last character.
- MAPSStackedString Tail (char s, bool from\_beginning=true) const
   Returns the characters found after the first occurence of character s, starting from the beginning or the end of the string.
- MAPSStackedString Part (int start, int stop) const
   Extracts a part of the string.
- MAPSStackedString Left (int length) const Extracts the left part of the string.
- MAPSStackedString Right (int length) const Extracts the right part of the string.
- MAPSStackedString Mid (int start, int length=-1) const Extracts a part of the string.
- MAPSArray < MAPSStackedString > Split (const char c) const
   Splits the string into several strings according to the specified separation character.

#### String tokenization functions

MAPSStackedString & TokenReset ()
 Resets the token search. Returns a reference to the current string (\*this).

- bool Token (const char \*delim, MAPSStackedString &s)
   Returns the next token.
- const char \* Strtok (const char \*delim)
   Equivalent to standard C library strtok.

#### **Find functions**

- bool Find (char c, int &pos, int start=0) const Finds character c in the string, starting at position start.
- bool Find (const char \*s, int &pos, int start=0) const
   Finds one of the characters in s in the string, starting at position start.
- int FindStr (const MAPSStackedString &s, int start=0) const Finds the substring s in the string, starting at position start.
- int FindStr (const char \*s, int start=0) const Finds the substring s in the string, starting at position start.

#### **Formatting**

- MAPSStackedString & Format (const char \*format\_string, const char \*s)
   Formats a string.
- MAPSStackedString & Format (const char \*format\_string, int m)
   Formats an integer.
- MAPSStackedString & Format (const char \*format\_string, double x)
   Formats a floating point number.

#### **Constructors**

- MAPSStackedString (const char \*string\_format, const char \*s)
   Formatting constructor.
- MAPSStackedString (const char \*string format, int n)

Formatting constructor.

MAPSStackedString (const char \*string\_format, double x)
 Formatting constructor.

MAPSStackedString (const char \*s)

Constructs a string from another string in C format.

MAPSStackedString (const char c)

Constructs a string containing a single character.

• MAPSStackedString (const MAPSStackedString &s)

Copy constructor.

• MAPSStackedString (int n, bool set\_length=false)

Preallocating constructor. By default, sets the length to 0. Optionally sets the length to n, setting the nth character to 0 (End of string)

• MAPSStackedString (int n, int nbdigits)

Simple integer formatting. Fills with 0 if the number n to format is too short.

MAPSStackedString ()

Simple constructor.

#### 10.58.1 Detailed Description

 $template < int BUFFER\_SIZE > class MAPSStackedString < BUFFER\_SIZE >$ 

The RTMaps flexible and fast string template class. This template class is a very efficient and exhaustive string template class. In this template class, the parameter <code>BUFFER\_-SIZE</code> gives the preallocated size in bytes for the string. The memory is preallocated in the stack, which avoids any slow call to malloc (and any memory fragmentation due to heap usage). Note that if the string actually contains more characters than the <code>BUFFER\_SIZE</code> template parameter, the buffer is automatically moved to the heap via malloc.

A common value for *BUFFER\_SIZE* is 40. The usual MAPSString class is defined as MAPSStackedString<40>.

Among other features, the MAPSStackedString class provides :

- string formatting features, based on the Microsoft familiar formatting features found in Visual Basic or Excel.
- operators and functions for basic string manipulation (concatenation, extraction, find, substitution)
- tokenization functions (strtok like)

#### See also

#### MAPSString MAPSStreamedString

#### 10.58.2 Member Function Documentation

## 10.58.2.1 template < int BUFFER\_SIZE > bool MAPSStackedString < BUFFER\_SIZE >::Find ( char c, int & pos, int start = 0 ) const

Finds character *c* in the string, starting at position *start*.

Returns true if found, and updates the pos variable.

### 

Finds one of the characters in *s* in the string, starting at position *start*.

Returns true if found, and updates the pos variable.

#### Warning

This function does not look for the whole string *s*. If this is what you want, have a look at FindStr functions.

## 10.58.2.3 template<int BUFFER\_SIZE> MAPSStackedString MAPSStackedString< BUFFER\_SIZE>::Left ( int length ) const

Extracts the left part of the string.

Similar to Visual Basic Left\$ function.

#### **Parameters**

length	Indicates how many characters to return. If 0, a zero-length string ("") is
	returned. If greater than or equal to the number of characters in the string,
	the entire string is returned.

## 10.58.2.4 template < int BUFFER\_SIZE > MAPSStackedString MAPSStackedString < BUFFER\_SIZE >::Mid ( int start, int length = -1 ) const

Extracts a part of the string.

Similar to Visual Basic Mid\$ function.

#### **Parameters**

start	Character position in the string at which the part to be taken begins. If start is
	greater than the number of characters in the string, Mid returns a zero-length
	string ("").

length (optional) Number of characters to return. If omitted or if there are fewer than length characters in the text (including the character at start), all characters from the start position to the end of the string are returned.

## 10.58.2.5 template<int BUFFER\_SIZE> MAPSStackedString MAPSStackedString< BUFFER\_SIZE>::operator() ( int *start*, int *stop* ) const

Extracts a part of the string.

Returns all the characters between positions start and stop (included).

#### 10.58.2.6 template<int BUFFER\_SIZE> MAPSStackedString MAPSStackedString< BUFFER\_SIZE>::Part (int *start*, int *stop* ) const

Extracts a part of the string.

Returns all the characters between positions start and stop (included).

## 10.58.2.7 template<int BUFFER\_SIZE> MAPSStackedString MAPSStackedString< BUFFER\_SIZE>::Right ( int *length* ) const

Extracts the right part of the string.

Similar to Visual Basic Right\$ function.

#### Parameters

length	Indicates how many characters to return. If 0, a zero-length string ("") is
	returned. If greater than or equal to the number of characters in the string,
	the entire string is returned.

## 10.58.2.8 template<int BUFFER\_SIZE> MAPSStackedString& MAPSStackedString< BUFFER\_SIZE>::Shorten ( int pos )

Reduces the length of the string to pos.

Puts a 0 (end of string) in position pos

## 10.58.2.9 template<int BUFFER\_SIZE> bool MAPSStackedString< BUFFER\_SIZE>::Token ( const char \* delim, MAPSStackedString< BUFFER\_SIZE > & s )

Returns the next token.

### **Parameters**

delim	The set of characters in <i>delim</i> specifies possible delimiters of the token to be found in the string on the current call
S	Holds the substring

Generated on Wed Oct 13 2010 18:59:21 for RTMaps by Doxygen

#### Returns

Returns false when no more tokens are found.

#### 10.58.2.10 template<int BUFFER\_SIZE> MAPSStackedString MAPSStackedString< BUFFER\_SIZE>::Up2 ( char s, bool from\_beginning = true ) const

Returns the part of the string up to the first occurence of character s.

Returns the part of the string up to the first occurence of character s.

Note: When *from\_beginning* is false, i.e. when we are seeking the first occurence of character s in the string beginning from the end of the string, if there is no such character, then the returned string is empty. On the other hand, when *from\_beginning* is true, i.e. when we are seeking the first occurence of character s in the string beginning from the first character of the string, if there is no such character, then the whole string is returned.

```
10.58.2.11 template<int BUFFER_SIZE> MAPSStackedString MAPSStackedString<
BUFFER_SIZE >::UpTo ( char s, bool from_beginning = true ) const
```

Returns the part of the string up to the first occurence of character s.

Note: When  $from\_beginning$  is false, i.e. when we are seeking the first occurence of character s in the string beginning from the end of the string, if there is no such character, then the returned string is empty. On the other hand, when  $from\_beginning$  is true, i.e. when we are seeking the first occurence of character s in the string beginning from the first character of the string, if there is no such character, then the whole string is returned.

#### 10.58.3 Friends And Related Function Documentation

```
10.58.3.1 template < int BUFFER_SIZE > MAPSStreamedString & operator << ( MAPSStreamedString & out, const MAPSStackedString < BUFFER_SIZE > & str) [related]
```

Standard operator.


The documentation for this class was generated from the following file:

· maps.hpp

## 10.59 MAPSStream8IOComponent Class Reference

Processing component template with 1 Stream8 input and 1 Stream8 output.

Inheritance diagram for MAPSStream8IOComponent:



#### **Protected Member Functions**

 virtual void NewDataCallback (MAPSRBRegion & region, const unsigned char \*data, const MAPSTimestamp \*timestamp, const MAPSTimestamp \*timeOflssue)=0

Processing function to implement in the child class.

### Output writing functions.

- virtual bool SendData (const unsigned char \*stream, int streamSize, MAPSTimestamp ts=0)
- virtual bool SendData (const char \*stream, int streamSize, MAPSTimestamp ts=0)

#### 10.59.1 Detailed Description

Processing component template with 1 Stream8 input and 1 Stream8 output.

The documentation for this class was generated from the following file:

• MAPSStream8IOComponent.h

### 10.60 MAPSStreamedString Class Reference

The RTMaps streamed string class.

Inherits MAPSStackedString< 40 >.

#### 10.60.1 Detailed Description

The RTMaps streamed string class. The MAPSStreamedString class extends the MAPSString features. The main extension is the operator << support. Special formatting options are also available, in the namespace MAPSSManip:

• dec, hex, oct for integers. For example:

```
MAPSStreamedString sx("Formatting test:");
unsigned int i = 15;
sx << "i=" << i << ", 0" << MAPSSManip::oct << i << ", 0x" << MAPSSManip::hex <<
    i;
Now sx contains: "Formatting test: i=15, 017, 0xF"</pre>
```

- endl: adds just a '\n' to the end of the string
- ends: adds just a '\0' to the end of the string

#### Note

```
If you use intensively formatting options, you can add using namespace MAPSSManip;
```

after the inclusion of maps.hpp, but you may have conflicts with STL names.

#### See also

MAPSString MAPSStackedString

The documentation for this class was generated from the following file:

· maps.hpp

# 10.61 MAPSStringHashTable < TContent > Class Template Reference

The RTMaps string hash table class.

 $Inheritance\ diagram\ for\ MAPSStringHashTable < TContent >:$ 

```
MAPSHashTable< MAPSString, TContent, MAPSStringHashFunction >

MAPSStringHashTable< TContent >
```

#### **Public Member Functions**

MAPSStringHashTable (int n=16)
 Constructor.

#### 10.61.1 Detailed Description

 $template < typename\ TContent > class\ MAPSStringHashTable < TContent >$ 

The RTMaps string hash table class. As its name says, the key is a string. Most of the code of hashing function for strings is inspired of Bob Jenkins' work (bob\_-jenkins@burtleburtle.net). See http://burtleburtle.net/bob/hash/evahash.html

The documentation for this class was generated from the following file:

· maps.hpp

## 10.62 MAPSSynchronizer Class Reference

The RTMaps Synchroniser tool.

#### **Public Member Functions**

void SignalSynchronizationCommand (MAPSTimestamp t)
 Sends a synchronization command to the synchronizable clock.

### 10.62.1 Detailed Description

The RTMaps Synchroniser tool. Provides the function that any RTMaps module can use to synchronize the RTMaps clock on an external signal/clock (GPS, another RTMaps...). Since there can be only one synchronizer at a time, the pointer to the synchronizer object can be requested through function MAPS::GetSynchronizer.

#### 10.62.2 Member Function Documentation

10.62.2.1 void MAPSSynchronizer::SignalSynchronizationCommand ( MAPSTimestamp t )

Sends a synchronization command to the synchronizable clock.

#### **Parameters**

 $t \mid$  Specifies the timestamp to synchronize the synchronizable clock on.


The documentation for this class was generated from the following file:

• maps.hpp

### 10.63 MAPSText Struct Reference

The MAPSText structure.

Inheritance diagram for MAPSText:



### **Public Attributes**

• int x

The leftmost coordinate.

• int y

The topmost coordinate.

· int cwidth

The width of one character (in pixels)

· int cheight

The height of one character (in pixels)

· int orientation

In degrees, around the upper left corner, counter clockwise.

• int bkcolor

Background color (Use the MAPS\_RGB macro to set the color).

• char text [32]

The text to write.

### 10.63.1 Detailed Description

The MAPSText structure.

The documentation for this struct was generated from the following file:

• maps.hpp

### 10.64 MAPSTimer Class Reference

The MAPSTimer class for managing timers.

#### **Public Member Functions**

• void Start ()

Starts the timer.

• void Stop ()

Stops the timer.

• void Reset ()

Resets the timer.

• MAPSTimestamp Time ()

Returns the current time measure in microseconds.

• MAPSTimer ()

Default constructor.

#### 10.64.1 Detailed Description

The MAPSTimer class for managing timers.

The documentation for this class was generated from the following file:

· maps.hpp

### 10.65 MAPSTimeStateListener Class Reference

The MAPSTimeStateListener interface.

#### **Public Member Functions**

- virtual void CallbackTimeJumped (const MAPSTimestamp destTimestamp)=0
   Implement this function to execute some code each time the RTMaps current time jumps. (due to an action of the user on the VCR slider for example)
- virtual void CallbackTimeSpeedChanged (const int newTimeSpeed)=0
   Implement this function to execute some code each time the RTMaps changes during execution of a diagram.
- virtual void CallbackTimePaused (const bool paused)=0
   Implement this function to execute some code each time the RTMaps execution is paused, or the pause is released.

#### 10.65.1 Detailed Description

The MAPSTimeStateListener interface. Your class should inherit from this interface if you want it to be notified of RTMaps clocks states changes such as changes of timespeed, jumps in time, or pausing events.

#### Warning

If a MAPSComponent inherits this class, the Callback functions are called from a different thread than the main thread of the component. Pay attention to threads synchronization. The callback function can be called as soon as the child class is constructed (in case of a MAPSComponent, the callbacks can be called even when the component is not running).

#### 10.65.2 Member Function Documentation

#### 

Implement this function to execute some code each time the RTMaps current time jumps. (due to an action of the user on the VCR slider for example)

#### **Parameters**

destTimes-	The timestamp that has been reached during the jump in time. This function
tamp	is called just after the destination timestamp has been taken into account by
	the RTMaps engine.

## 10.65.2.2 virtual void MAPSTimeStateListener::CallbackTimePaused ( const bool paused ) [pure virtual]

Implement this function to execute some code each time the RTMaps execution is paused, or the pause is released.

#### **Parameters**

paused	It is set to true if the execution is pause, and to false if the pause is
	released.

## 10.65.2.3 virtual void MAPSTimeStateListener::CallbackTimeSpeedChanged ( const int newTimeSpeed ) [pure virtual]

Implement this function to execute some code each time the RTMaps changes during execution of a diagram.

#### **Parameters**

newTime-	The new timespeed that has been reached. This function is called just after
Speed	the new timespeed has been taken into account by the RTMaps engine.


The documentation for this class was generated from the following file:

• maps.hpp

## 10.66 MAPSTree Struct Reference

The MAPSTree structure: a kind of MAPSRealObject.

Inheritance diagram for MAPSTree:



#### **Public Attributes**

- MAPSFloat height
  - The height of the tree.
- MAPSFloat radius

The radius of the tree.

• int shape

The shape of the tree.

### **Static Public Attributes**

- static const int Cone

  One possible shape.
- static const int Round
   Another possible shape.
- static const int Cylinder
   A third possible shape.

### 10.66.1 Detailed Description

The MAPSTree structure: a kind of MAPSRealObject.

#### See also

**MAPSRealObject** 

The documentation for this struct was generated from the following file:

· maps.hpp

## 10.67 MAPSTriangles3D Struct Reference

The RTMaps structure for supporting 3D triangles output.

#### **Classes**

struct Object

The object structure.

struct Point

The 3D point structure.

• struct Triangle

The triangle structure itself.

### **Public Attributes**

· int nbObjects

Number of objects in the scene.

• Object \* objects

All the objects in the scene.

• int nbPoints

Number of points in the scene.

• Point \* points

All the points in the scene.

· int nbTriangles

Number of triangles in the scene.

Triangle \* triangles

All the triangles in the scene.

#### 10.67.1 Detailed Description

The RTMaps structure for supporting 3D triangles output.

The documentation for this struct was generated from the following file:

· maps.hpp

## 10.68 MAPSTypeFilter Class Reference

The RTMaps type filter class.

Inheritance diagram for MAPSTypeFilter:



#### **Public Member Functions**

• MAPSTypeFilter (const MAPSTypeFilterBase &model, const char \*filterName=NULL, const char \*filterUnit=NULL)

Constructs a type filter based on a model. Assigns a new name or unit filter (regular expression) if needed.

### 10.68.1 Detailed Description

The RTMaps type filter class.


The documentation for this class was generated from the following file:

· maps.hpp

## 10.69 MAPSTypeFilterBase Struct Reference

The RTMaps type filter structure.

Inheritance diagram for MAPSTypeFilterBase:



#### **Public Attributes**

MAPSTypeInfoValue mask

First AND filter mask applied by MAPS::TypeFilter to the data type to pass through the filter

• MAPSTypeInfoValue x

The data type to pass through the filter is compared to x after applying the first AND mask.

MAPSTypeInfoValue maskX

The second AND filter mask.

· const char \* nameFilter

The optional name filter.

• const char \* unitFilter

The optional unit filter.

#### 10.69.1 Detailed Description

The RTMaps type filter structure. A type filter structure must be provided for each input, since all data flowing within a RTMaps system do have a type associated to it and are filtered before getting in an input.

The RTMaps type filtering behaviour is the following:

- First of all, if a name or a unit filter is set, only the data whose unit or name matches the filter unit or name parameter pass through the filter.
- In a second phase, a AND mask is applied to the type (parameter mask). The result of this AND operation must be equal to the x parameter. Otherwise, the type is rejected. This enables to test some bits. For instance, if we want to let only vectors pass through the filter, we set mask to MAPS::VectorFlag and set x to MAPS::VectorFlag. This will require the bit MAPS::VectorFlag to be set. On the contrary, if we don't want to let vectors pass through the filter, we set mask to MAPS::VectorFlag and set x to 0.

In a third and last phase, another AND mask is applied (parameter maskX). This
mask is less restrictive, since if the result is different from 0, i.e. if any of the bits
are set, the type will pass through the filter. For instance, if we want to let numbers
pass through the filter, we can set maskX to MAPS::Integer | MAPS::Float.

This is actually the code of the MAPS::TypeFilter function:

```
bool MAPS::TypeFilter(const MAPSTypeInfo& type, MAPSTypeFilterBase& filter)
{
    if (filter.nameFilter) {
        if (filter.nameRegexp==NULL) filter.nameRegexp=new MAPSRegExp(filter.
        nameFilter);
        if ((type.name==NULL)||(filter.nameRegexp->Match(*(type.name))==false)) {
            return false;
        }
    }
    if (filter.unitFilter) {
        if (filter.unitRegexp==NULL) filter.unitRegexp=new MAPSRegExp(filter.
        unitFilter);
        if ((type.unit==NULL)||(filter.unitRegexp->Match(*(type.unit))==false)) {
            return false;
        }
    }
    return (((type.value&filter.mask)==(filter.x&filter.mask))&&(type.value&filter.maskX));
}
```

#### See also

MAPS::TypeFilter

#### 10.69.2 Member Data Documentation

## 10.69.2.1 const char\* MAPSTypeFilterBase::nameFilter

The optional name filter.

Only the types matching this regular expression can pass through the filter. If set to  $\mathtt{NULL}$ , no optional name filtering is done (any named data can pass through the filter).

#### 10.69.2.2 const char\* MAPSTypeFilterBase::unitFilter

The optional unit filter.

Only the types matching this regular expression can pass through the filter. If set to  $\mathtt{NULL}$ , no unit filtering is done (any unit can pass through the filter).

The documentation for this struct was generated from the following file:

maps.hpp

## 10.70 MAPSTypeInfo Struct Reference

The RTMaps type information structure.

#### **Public Member Functions**

• void SetName (const char \*n)

Dynamically sets the optional name of the output data.

• void SetUnit (const char \*u)

Dynamically sets the unit of the output data.

MAPSTypeInfo & operator= (const MAPSTypeInfo &type)

Copy operator.

∼MAPSTypeInfo ()

Destructor.

#### **Public Attributes**

• MAPSTypeInfoValue value

This is the 64-bit value describing the type (integer, MAPSFloat...) of the output data.

• MAPSString \* name

An optional name associated to the output data type.

• MAPSString \* unit

A string describing the unit of the output data.

## 10.70.1 Detailed Description

The RTMaps type information structure. A MAPSTypeInfo structure must be provided for each output, since all data flowing within an RTMaps must have a type associated to it.

#### 10.70.2 Member Function Documentation

10.70.2.1 void MAPSTypeInfo::SetName ( const char \* n )

Dynamically sets the optional name of the output data.

Note that the optional name is usually set statically in the output definitions.

#### See also

MAPS\_OUTPUT

#### 10.70.2.2 void MAPSTypeInfo::SetUnit (const char \*u)

Dynamically sets the unit of the output data.

Note that the unit is usually set statically in the output definitions.

#### See also

MAPS\_OUTPUT

#### 10.70.3 Member Data Documentation

#### 10.70.3.1 MAPSString\* MAPSTypeInfo::name

An optional name associated to the output data type.

This is optional, except when value is set to MAPS::Structure, which means that the type of the output is a user-specific structure. In that case, a name must be associated to the structure in order to distinguish it among all the user-specific structures.

### 10.70.3.2 MAPSString\* MAPSTypeInfo::unit

A string describing the unit of the output data.

For instance, "km/h", or "m/s".


The documentation for this struct was generated from the following file:

• maps.hpp

### 10.71 MAPSVehicle Struct Reference

The MAPSVehicle structure: a kind of MAPSRealObject.

Inheritance diagram for MAPSVehicle:



### **Public Attributes**

· MAPSFloat theta

The vehicle's heading (in degrees)

· MAPSFloat speed

The vehicle's speed.

int kind

The kind of vehicle.

MAPSFloat width

The width of the vehicle (in meters)

· MAPSFloat height

The height of the vehicle (in meters)

MAPSFloat length

The length of the vehicle (in meters)

· int model

Type of car.

· bool braking

Is the vehicle currently breaking?

· MAPSFloat confidence

Confidence in the information about this vehicle.

#### **Static Public Attributes**

· static const int Car

The vehicle is a car (kind)

static const int Bus

The vehicle is a bus (kind)

static const int Truck

The vehicle is a truck (kind)

· static const int Bike

The vehicle is a bike (kind)

• static const int Motorcycle

The vehicle is a motorcycle (kind)

### The vehicle position accuracy

MAPSFloat dx

Accuracy of coordinate along x.

MAPSFloat dy

Accuracy of coordinate along y.

MAPSFloat dz

Accuracy of coordinate along z.

### 10.71.1 Detailed Description

The MAPSVehicle structure: a kind of MAPSRealObject.

#### See also

**MAPSRealObject** 

The documentation for this struct was generated from the following file:

• maps.hpp

### 10.72 MAPSWin32 Class Reference

The RTMaps Win32 support class.

#### **Friends**

class MAPSEvent

#### **Useful functions**

• static bool OSIsWindowsNT ()

 $\textit{Returns} \ \texttt{true} \ \textit{if the OS} \ \textit{is Windows 2000, XP or Server 2003}, \ \texttt{false otherwise}.$ 

• static int OSVersion ()

Returns 5 for Windows 2000, XP or Server 2003, 4 for Windows NT4.

static void AbsoluteTimeToSystemTime (MAPSAbsoluteTime &s, SYSTEMTIME &t)

Translate MAPSAbsoluteTime structure to Windows SYSTEMTIME structure.

static void SystemTimeToAbsoluteTime (SYSTEMTIME &t, MAPSAbsoluteTime &s)

Translate Windows SYSTEMTIME structure to MAPSAbsoluteTime structure.

• static DWORD MainThreadId ()

Returns the main thread Id (the one that processes WM\_QUIT messages generally)

### 10.72.1 Detailed Description

The RTMaps Win32 support class.

The documentation for this class was generated from the following file:

· maps.hpp

## 10.73 MAPSTriangles3D::Object Struct Reference

The object structure.

#### **Public Attributes**

int id

An ID for the object.

· int texture

Texture ID information.

· int firstTriangle

The index of the first triangle among all the triangles.

• int nbOfTriangles

The number of triangles for this object.

#### 10.73.1 Detailed Description

The object structure.

The documentation for this struct was generated from the following file:

• maps.hpp

## 10.74 MAPSTriangles3D::Point Struct Reference

The 3D point structure.

#### **Public Attributes**

float x

x coordinate

float y

y coordinate

float z

z coordinate

· int landmark

Optional. May be useful if you need to make space transformations. Just to keep an index to the reference location.

int xt

Texture x coordinate, for texture mapping.

• int yt

Texture y coordinate, for texture mapping.

### 10.74.1 Detailed Description

The 3D point structure.

The documentation for this struct was generated from the following file:

· maps.hpp

## 10.75 MAPSTriangles3D::Triangle Struct Reference

The triangle structure itself.

#### **Public Attributes**

• int p1

The 1st point constituting the triangle.

int p2

The 2nd point constituting the triangle.

• int p3

The 3rd point constituting the triangle.

• int color

The color of the triangle if no texture is provided (use MAPS\_RGB or MAPS\_RGBA to set the color)

## 10.75.1 Detailed Description

The triangle structure itself.

The documentation for this struct was generated from the following file:

• maps.hpp

## **Chapter 11**

## **File Documentation**

## 11.1 maps.hpp File Reference

The RTMaps engine header file - Version 3.4 build 99.

### **Classes**

- class MAPSCouple < T >
   Template class for couple data.
- class MAPSBasicListItem

The basic list item class.

• class MAPSListIterator

The list iterator class.

• class MAPSListItem< T >

The list item template class.

class MAPSBasicList

The base class for the MAPSList template class.

• class MAPSList< T >

The RTMaps double linked list template class.

- class MAPSList< T >::MAPSIterator
   Iterator on MAPSList objects.
- class MAPSStackedString
   BUFFER\_SIZE >

The RTMaps flexible and fast string template class.

228 File Documentation

· class MAPSStreamedString

The RTMaps streamed string class.

class MAPSArray

The RTMaps array class.

class MAPSMatrix2< T >

The RTMaps MAPSMatrix2 class, a powerful matrix management class.

class MAPSPair< TKey, TContent >

The RTMaps (key,content) pair template class.

• class MAPSHashTableIterator

The RTMaps hash table iterator.

- class MAPSHashTable < TKey, TContent, H >
- class MAPSStringHashTable < TContent >

The RTMaps string hash table class.

class MAPSIntegerHashTable < TContent >

The RTMaps integer hash table template class.

class MAPSPtrHashTable < TContent >

The RTMaps pointer hash table template class.

class MAPSMutex

The RTMaps mutex class.

class MAPSEvent

The RTMaps event class.

• class MAPSFileWriteHandle

The class that is used to manage all RTMaps write file operations.

• class MAPSFileReadHandle

The class that is used to manage all RTMaps read file operations.

• class MAPSWin32

The RTMaps Win32 support class.

struct IpIROI

The IPL Region Of Interest structure.

• struct IpIImage

The famous IpIImage structure, today's standard structure for image processing.

struct MAPSAbsoluteTime

Absolute time structure.

struct MAPSCANFrame

CAN Frames structure.

struct MAPSRealObjectVariant

All real objects in RTMaps (vehicles, etc.) inherit from this structure.

• struct MAPSVehicle

The MAPSVehicle structure: a kind of MAPSRealObject.

• struct MAPSTree

The MAPSTree structure: a kind of MAPSRealObject.

• struct MAPSSign

The MAPSSign structure: a kind of MAPSRealObject.

• struct MAPSRealObject

The standard structure to transmit info about real objects.

• struct MAPSDrawingObjectVariant

All drawing objects in RTMaps (circles, etc.) inherit from MAPSDrawingObjectVariant.

• struct MAPSLine

The MAPSLine structure.

• struct MAPSRectangle

The MAPSRectangle structure.

• struct MAPSCircle

The MAPSCircle structure.

struct MAPSEllipse

The MAPSEllipse structure.

struct MAPSText

The MAPSText structure.

struct MAPSSpot

The MAPSSpot structure.

• struct MAPSDrawingObject

The MAPSDrawingObject: a standard for simple overlay shapes.

struct MAPSTriangles3D

230 File Documentation

The RTMaps structure for supporting 3D triangles output.

• struct MAPSTriangles3D::Point

The 3D point structure.

• struct MAPSTriangles3D::Triangle

The triangle structure itself.

• struct MAPSTriangles3D::Object

The object structure.

struct MAPSComplex

Complex number structure.

struct MAPSMatrix

MATLAB-Like matrix (Complex and columnwise, like in fortran)

struct MAPSImage

The RTMaps Image type.

struct MAPSTypeInfo

The RTMaps type information structure.

struct MAPSTypeFilterBase

The RTMaps type filter structure.

class MAPSTypeFilter

The RTMaps type filter class.

• struct MAPSEnumStruct

Enumeration structure.

class MAPSOutput

The RTMaps Module Output class.

class MAPSInput

The RTMaps Module Input class.

class MAPSProperty

The RTMaps Module Property class.

• class MAPSAction

The RTMaps Module Action class.

class MAPSMutex2

The RTMaps advanced mutex class.

class MAPSFileIO

The RTMaps File I/O support class.

class MAPSIOEIt

The RTMaps I/O Buffer Element.

• class MAPSRunShutdownListener

The MAPSRunShutdownListener interface.

class MAPSTimeStateListener

The MAPSTimeStateListener interface.

• class MAPSRecordingStateListener

The MAPSRecordingStateListener interface.

• class MAPSBaseClock

MAPSBaseClock class.

• class MAPSSynchronizer

The RTMaps Synchroniser tool.

• class MAPSModule

The base class for all RTMaps modules.

• class MAPSComponent

The base class for all RTMaps components.

• class MAPSRecordReplayMethod

The base class for all record/replay methods.

class MAPSTimer

The MAPSTimer class for managing timers.

• class MAPSRunnable < T >

Helper class to create worker threads.

#### **Namespaces**

namespace MAPS

The main RTMaps namespace.

232 File Documentation

#### **Defines**

• #define MAPS\_RGB(r, g, b)

24-bit integer color representation

• #define MAPS\_RGBA(r, g, b, a)

24-bit integer color representation + 8-bit alpha value (transparency)

• #define MAPS PI

The Pi number.

• #define MAPS DEG2RAD(x)

Degrees to radians conversion macro.

• #define MAPS\_SAFE\_DELETE(p)

Standard macro for safely deleting a pointer to an array.

#define MAPS\_SAFE\_DELETE\_ARRAY(p)

Standard macro for safely deleting a single-element pointer.

- #define MAPSForallItems(it, L)
- #define MAPSForall(x, L)
- #define MAPSForallPtr(x, L)
- #define MAPS\_BEGIN\_INPUTS\_DEFINITION(className)

Starts the definition of the inputs of a module.

• #define MAPS INPUT(namex, filter, typex)

Basic definition of an input.

#define MAPS\_END\_INPUTS\_DEFINITION

Ends the definition of the inputs of a module.

• #define MAPS BEGIN OUTPUTS DEFINITION(className)

Starts the definition of the outputs of a module.

• #define MAPS\_OUTPUT(name, value, namex, unit, size)

Basic definition of an output.

• #define MAPS\_OUTPUT\_FIFOSIZE(name, value, namex, unit, size, fifosize)

Definition of an output with control of the FIFO size.

• #define MAPS\_OUTPUT\_USER\_STRUCTURE(name, structureName)

Definition of an output using a user structure.

• #define MAPS\_END\_OUTPUTS\_DEFINITION

Ends the definition of the outputs of a module.

#define MAPS\_BEGIN\_PROPERTIES\_DEFINITION(className)

Starts the definition of the properties of a module.

#define MAPS\_PROPERTY(name, value, needs2BeInitialized, canBeChangedAfterInstantiation)

Basic definition of a property.

• #define MAPS\_PROPERTY\_UNIT(name, value, unit, needs2BeInitialized, can-BeChangedAfterInstantiation)

Basic definition of a property.

 #define MAPS\_PROPERTY\_ENUM(name, enumstr, selected, needs2BeInitialized, canBeChangedAfterInstantiation)

Basic definition of a property.

 #define MAPS\_PROPERTY\_ENUM\_UNIT(name, enumstr, selected, unit, needs2BeInitialized, canBeChangedAfterInstantiation)

Basic definition of a property.

#define MAPS\_PROPERTY\_READ\_ONLY(name, value)

Definition of a read-only property.

• #define MAPS\_PROPERTY\_READ\_ONLY\_UNIT(name, value, unit)

Definition of a read-only property with a specified unit.

• #define MAPS\_END\_PROPERTIES\_DEFINITION

Ends the definition of the properties of a module.

• #define MAPS BEGIN ACTIONS DEFINITION(className)

Starts the definition of the actions of a module.

• #define MAPS\_ACTION(name, proc)

Basic definition of an action.

#define MAPS\_ACTION2(name, proc, allowedWhenDead)

Second definition of an action.

#define MAPS\_END\_ACTIONS\_DEFINITION

Ends the definition of the actions of a module.

• #define MAPS\_PACKAGE\_DEFINITION(name, version)

Use this macro to determine the version of your package file.

• #define MAPS\_RECORD\_REPLAY\_METHOD\_DEFINITION(rrm, namex, version, filter, recordThreaded, replayThreaded, nbPropertiesRecord, nbPropertiesReplay)

234 File Documentation

Required for the implementation of an RTMaps record/replay method.

#define MAPS\_RECORD\_REPLAY\_METHOD\_STANDARD\_HEADER\_CODE(rrm)

Include this macro inside your RRM class definition.

#define MAPS\_RECORD\_REPLAY\_METHOD\_BLACKBOX\_HEADER\_CODE(rrm)

Include this macro inside your RRM class definition if you intend to implement blackbox features.

• #define MAPS\_RECORD\_REPLAY\_METHOD\_PROCESS\_HEADER\_CODE(rrm)

Include this macro inside your RRM class definition if you need preprocessing before recording.

- #define MAPS\_RECORD\_REPLAY\_METHOD\_COPY\_HEADER\_CODE(rrm)
   Include this macro inside your RRM class definition if you intend to implement special copy features.
- #define MAPS\_RECORD\_REPLAY\_METHOD\_HEADING\_HINT\_HEADER\_CODE(rrm)

Include this macro inside your RRM class definition if you intend to implement hint header

#define MAPSFilterUserStructure(structureName)
 Defines for type filters.

### **Typedefs**

- typedef MAPSInt32 MAPSInteger
   The MAPSInteger should be a 32-bit integer, even on 64-bit architecture.
- typedef MAPSFloat64 MAPSFloat
   The MAPSFloat type is a double precision floating point number.
- typedef MAPSInt64 MAPSTimestamp
   The MAPSTimestamp type is a 64-bit integer.
- typedef MAPSInt64 MAPSDelay
   A 64-bit integer that specifies a delay in microseconds.
- typedef MAPSInt64 MAPSTypeInfoValue
   The MAPSTypeInfoValue type is a 64 bit-integer. All types in RTMaps are associated to a 64-bit value.

typedef MAPSInt32 MAPS3States

3-state value, generally used to tell the state of a thread.

typedef MAPSStackedString< 40 > MAPSString

The RTMaps flexible and fast string class.

### **Component definition macros**

#define MAPS\_COMPONENT\_DEFINITION(component, name, version, priority, kind, defaultBehaviour, nbOfInputs, nbOfOutputs, nbOfProperties, nbOfActions)

One of the standard macros required for the definition of an RTMaps component.

 #define MAPS\_COMPONENT\_DEFINITION\_DOC(component, name, version, priority, kind, defaultBehaviour, nbOfInputs, nbOfOutputs, nbOfProperties, nbOfActions, doc)

One of the standard macros required for the definition of an RTMaps component.

 #define MAPS\_COMPONENT\_DEFINITION\_UNIQUE(component, name, version, priority, kind, defaultBehaviour, nbOfInputs, nbOfOutputs, nbOfProperties, nbOfActions)

One of the standard macros required for the definition of an RTMaps component.

 #define MAPS\_COMPONENT\_DEFINITION\_REGISTRATION(component, name, version, priority, kind, defaultBehaviour, nbOfInputs, nbOfOutputs, nbOfProperties, nbOfActions)

One of the standard macros required for the definition of an RTMaps component.

#### Component class declaration macros

- #define MAPS COMPONENT STANDARD HEADER CODE(component)
- #define MAPS CLOCK COMPONENT HEADER CODE(component)
- #define MAPS COMPONENT DYNAMIC HEADER CODE(component)
- #define MAPS COMPONENT HEADER CODE WITHOUT CONSTRUCTOR(component)
- #define MAPS\_COMPONENT\_REGISTERING\_HEADER\_CODE(component)
- #define MAPS\_CHILD\_COMPONENT\_HEADER\_CODE(component, parent)

Include this macro inside your component class definition if its parent is a descendant of MAPSComponent.

#define MAPS\_CHILD\_COMPONENT\_HEADER\_CODE\_WITHOUT\_CONSTRUCTOR(component, parent)

Include this macro inside your component class definition if its parent is a descendant of MAPSComponent and you need to implement your own constructor.

236 File Documentation

#define MAPS\_PARENT\_COMPONENT\_HEADER\_CODE(component, parent)

Include this macro inside a parent component class definition.

#define MAPS\_PARENT\_COMPONENT\_HEADER\_CODE\_WITHOUT\_CONSTRUCTOR(component, parent)

Include this macro inside a parent component class definition when you need to implement your own constructor.

### RTMaps Typing related constants

- const MAPSTypeInfoValue MAPS::NoMask
   No mask.
- const MAPSTypeInfoValue MAPS::NoType
   No type.
- const MAPSTypeInfoValue MAPS::AnyType
   Any type.
- const MAPSTypeInfoValue MAPS::TypeMask
   Type mask.
- const MAPSTypeInfoValue MAPS::Structure
   User defined structure.
- const MAPSTypeInfoValue MAPS::Integer Integer (32 bits, signed)
- const MAPSTypeInfoValue MAPS::Float

  MAPSFloat (double : 64 bits, double precision)
- const MAPSTypeInfoValue MAPS::TextAscii

  Ascii characters (1 character = 8 bits).
- const MAPSTypeInfoValue MAPS::TextUnicode
   Unicode characters (1 character = 16 bits)
- const MAPSTypeInfoValue MAPS::IpIImage
   IpIImage (Image Processing Library image description structure)
- const MAPSTypeInfoValue MAPS::CANFrame

CAN frame.

• const MAPSTypeInfoValue MAPS::Matrix MATLAB-Like matrix.

const MAPSTypeInfoValue MAPS::RealObject
 Real object (car, tree, etc.)

const MAPSTypeInfoValue MAPS::DrawingObject
 Drawing object (line, circle, etc.)

const MAPSTypeInfoValue MAPS::Triangles3D
 3D triangles for 3D scene rendering

const MAPSTypeInfoValue MAPS::Stream8
 8-bit stream (sound, numerized data)

const MAPSTypeInfoValue MAPS::Stream16
 16-bit stream (sound, numerized data)

const MAPSTypeInfoValue MAPS::Stream32
 32-bit stream (numerized data)

const MAPSTypeInfoValue MAPS::Integer64
 Integer (64 bits, signed)

• const MAPSTypeInfoValue MAPS::AnyText Some textual information, ascii or unicode.

• const MAPSTypeInfoValue MAPS::AnyInteger 32 or 64 bits integers.

const MAPSTypeInfoValue MAPS::VectorFlag
 Indicates that the piece of data is a vector (an array) of a basic type.

• const MAPSTypeInfoValue MAPS::FrequencyFlag

Indicates that a frequency is provided with the data.

const MAPSTypeInfoValue MAPS::QualityFlag
 Indicates that a quality is transmitted along with the data (for instance a compression or a noise ratio).

const MAPSTypeInfoValue MAPS::MiscFlag
 Indicates that 3 miscellaneous integers are transmitted along with the data. See MAP-SIOEIt::Misc1(), Misc2() and Misc3()

238 File Documentation

#### **RTMaps Inputs behaviours**

const int MAPS::FifoReader
 FIFO Reader behaviour.

const int MAPS::NeverSkippingReader
 Never Skipping Reader behaviour.

const int MAPS::LastOrNextReader
 Last or Next Reader behaviour.

const int MAPS::Wait4NextReader
 Wait For Next Reader behaviour.

const int MAPS::SamplingReader
 Sampling Reader behaviour.

### **RTMaps Properties types**

- const int MAPS::BoolProperty

  Boolean property (false or true)
- const int MAPS::IntegerProperty
   Integer property (64-bit signed integer)
- const int MAPS::FloatProperty

  Floating point property (double: 64-bit floating point number)
- const int MAPS::StringProperty
   String property (ASCII string) Enum property (ASCII string)
- · const int MAPS::EnumProperty

### **RTMaps Type Filters**

- const MAPSTypeFilterBase MAPS::FilterStructure Filters any user-defined structure type.
- const MAPSTypeFilterBase MAPS::FilterInteger Filters integer type (same as FilterIntegers)
- const MAPSTypeFilterBase MAPS::FilterInteger64
   Filters 64 bits integer type (same as FilterIntegers64)

- const MAPSTypeFilterBase MAPS::FilterFloat Filters MAPSFloat type (same as FilterFloats)
- const MAPSTypeFilterBase MAPS::FilterNumber
   Filters integer or MAPSFloat type (same as FilterNumbers)
- const MAPSTypeFilterBase MAPS::FilterIntegers Filters integer scalars or vectors.
- const MAPSTypeFilterBase MAPS::FilterIntegers64 Filters 64 bits integer scalars or vectors.
- const MAPSTypeFilterBase MAPS::FilterFloats Filters MAPSFloat scalars or vectors.
- const MAPSTypeFilterBase MAPS::FilterNumbers Filters integer or MAPSFloat scalars or vectors.
- const MAPSTypeFilterBase MAPS::FilterOneInteger
   Filters integer type (excludes vectors of integers)
- const MAPSTypeFilterBase MAPS::FilterOneInteger64
   Filters 64 bits integer type (excludes vectors of integers64)
- const MAPSTypeFilterBase MAPS::FilterOneFloat
   Filters MAPSFloat type (excludes vectors of MAPSFloat)
- const MAPSTypeFilterBase MAPS::FilterOneNumber
   Filters integer or MAPSFloat type (excludes vectors)
- const MAPSTypeFilterBase MAPS::FilterTextAscii Filters ASCII text string.
- const MAPSTypeFilterBase MAPS::FilterTextUnicode
   Filters Unicode (16 bits) text string.
- const MAPSTypeFilterBase MAPS::FilterImage
   Filters IpIlmages or MAPSImages.
- const MAPSTypeFilterBase MAPS::FilterIpIImage Filters IpIImages.
- const MAPSTypeFilterBase MAPS::FilterMAPSImage Filters MAPSImages.
- const MAPSTypeFilterBase MAPS::FilterCANFrame

Filters CANFrames.

• const MAPSTypeFilterBase MAPS::FilterMatrix Filters MATLAB-Like matrices.

• const MAPSTypeFilterBase MAPS::FilterRealObjects Filters RTMaps Real Objects.

• const MAPSTypeFilterBase MAPS::FilterDrawingObjects Filters RTMaps Drawing Objects.

• const MAPSTypeFilterBase MAPS::FilterTriangles3D Filters 3D triangles.

const MAPSTypeFilterBase MAPS::FilterStream8
 Filters 8-bit data streams.

• const MAPSTypeFilterBase MAPS::FilterStream16 Filters 16-bit data streams.

• const MAPSTypeFilterBase MAPS::FilterStream32 Filters 32-bit data streams.

 const MAPSTypeFilterBase MAPS::FilterAudioSignal Filters audio signals (either MAPSFloat or Stream8)

const MAPSTypeFilterBase MAPS::FilterAny
 Filters any kind of data.

## RTMaps kinds of information outputs

• const int MAPS::Info

Simple information.

const int MAPS::Warning
 Warning.

• const int MAPS::Error *Error*.

const int MAPS::ParserEcho
 Echo from the parser.

#### RTMaps replay modes

- const int MAPS::ReplayModeNormal Normal replay.
- const int MAPS::ReplayModeImmediate
   Immediate replay mode (replay ahead of real time)
- const int MAPS::ReplayModeTimestamp
   Replay using timestamp instead of time of issue.

# RTMaps VCR Keys codes

- · const int MAPS::VCRKeyStop
- · const int MAPS::VCRKeyPlay
- · const int MAPS::VCRKeyRecord
- const int MAPS::VCRKeyPause
- · const int MAPS::VCRKeyRewind
- · const int MAPS::VCRKeyForward
- · const int MAPS::VCRKeyNext
- · const int MAPS::VCRKeyOrganize
- const int MAPS::VCRSlider
- const int MAPS::VCRAllKeys

#### **RTMaps Engine Keys codes**

- · const int MAPS::KernelKeyRun
- · const int MAPS::KernelKeyShutdown
- const int MAPS::DefaultKeysState

# **Others RTMaps Constants**

· const MAPSString MAPS::OperatingSystem

Contains the operating system string information ("Win32", "QNX" or "Linux" for instance)

• const int MAPS::OSBuild

Contains the OS support build number information.

• const MAPSString MAPS::Distribution

Contains the distribution information string ("3.0" for instance)

• const MAPSString MAPS::KernelVersion

Contains the engine version string information ("1.0" for instance)

#### · const MAPSString MAPS::RTMapsMinorVersion

Contains the RTMaps minor version (changes in the minor versions preserve backward compatibility with packages). "5" for example -> complete version string will look like "3.0.5".

· const int MAPS::KernelBuild

Contains the engine build number information.

const MAPSString MAPS::Copyright

Contains the RTMaps copyright string information.

const MAPSString MAPS::License

Contains the RTMaps license grant string information (depends on the customer)

const MAPSString MAPS::ProductName

Contains the operating system string information ("Win32","QNX" or "Linux" for instance)

• const bool MAPS::BigEndian

Tells if we are running on a big-endian platform (true) or a little-endian platform (false)

· const int MAPS::DefaultTextSize

Default allocation size (in characters) for ascii text type outputs.

• const int MAPS::Infinite

Infinite number.

· const int MAPS::ModuleDied

State indicating a dead RTMaps module.

const int MAPS::GotAMessage

State indicating that RTMaps got a Windows message.

• const int MAPS::TimeOut

State indicating a time out in RTMaps.

· const int MAPS::FatalKernelError

State indicating a fatal engine error.

· const int MAPS::ErrorException

State indicating an error in an RTMaps module.

• const int MAPS::Running

State telling that RTMaps is running (that time is flowing)

const int MAPS::Paused

State telling that RTMaps is in pause mode.

· const int MAPS::ShuttingDown

RTMaps is currently shutting down.

• const int MAPS::Resetting

RTMaps is currently resetting.

· const int MAPS::WaitingForSynchBeforeRun

RTMaps is currently waiting to be synchronized before running.

· const int MAPS::DeadState

State indicating a dead thread or module.

· const int MAPS::DyingState

State indicating a dying thread or module.

· const int MAPS::LivingState

State indicating a living thread or module.

· const int MAPS::Threaded

The component is threaded.

· const int MAPS::Sequential

The component is sequential.

# C standard library wrapper

These functions should be called instead of their C counterparts to ensures easier cross-platform design of components.

• int MAPS::Atoi (const char \*a)

Ascii to integer conversion.

• MAPSInt64 MAPS::Atoi64 (const char \*a)

Ascii to integer (64 bits) conversion.

• MAPSInt32 MAPS::Strtol (const char \*s, char \*\*endptr, int base)

Converts the initial part of the string in s to a MAPSInt32 according to the given base.

• MAPSUInt32 MAPS::Strtoul (const char \*s, char \*\*endptr, int base)

Converts the initial part of the string in s to a MAPSUInt32 according to the given base.

• MAPSInt64 MAPS::Strtoi64 (const char \*s, char \*\*endptr, int base)

Converts the initial part of the string in s to a MAPSInt64 according to the given base.

- MAPSUInt64 MAPS::Strtoui64 (const char \*s, char \*\*endptr, int base)
   Converts the initial part of the string in s to a MAPSUInt64 according to the given base.
- int MAPS::Strlen (const char \*s)

  Calculates the length of the string s.
- const char \* MAPS::Strchr (const char \*s, char ch)
   Finds character ch in s.
- char \* MAPS::Strchr (char \*s, char ch)
   Finds character ch in s.
- int MAPS::Strcmp (const char \*s1, const char \*s2) String comparison.
- int MAPS::Stricmp (const char \*s1, const char \*s2)

  Lowercase comparison of strings.
- int MAPS::Strncmp (const char \*s1, const char \*s2, MAPSInt64 size)

  Compares the first size characters of two strings.
- char \* MAPS::Strstr (const char \*s, const char \*strSearch)
   Returns a pointer to the first occurrence of a search string strSearch in the string s.
- char \* MAPS::Strcpy (char \*strDest, const char \*strSrc)
   Copies strSrc into strDest.
- char \* MAPS::Strdup (const char \*strSrc)
   Duplicate strings.
- char \* MAPS::Itoa (int val, char \*buf, int radix=10)
   Integer to Ascii conversion.
- char \* MAPS::Itoa (unsigned long val, char \*buf, int radix=10)
   Integer to Ascii conversion.
- char \* MAPS::Itoa (MAPSInt64 val, char \*buf, int radix=10)
   Integer to Ascii conversion.
- bool MAPS::IsSpace (char c)

  Is the character c a space, a tab or a carriage return?
- bool MAPS::IsDigit (char c)
   Is the character c a digit?

 void \* MAPS::Memcpy (void \*dest, const void \*source, MAPSInt64 size, MAP-SEvent \*event=NULL)

Memory copy.

void \* MAPS::Memset (void \*dest, int c, MAPSInt64 size)
 Sets buffers to a specified character c, repeated size times.

void \* MAPS::Memmove (void \*dest, const void \*source, MAPSInt64 size)
 Moves one buffer to another.

double MAPS::Modf (double x, double \*intptr)
 Splits a floating-point value into fractional and integer parts.

double MAPS::Fabs (double x)
 Calculates the absolute value of the floating-point argument.

#### **RTMaps Main functions**

• void MAPS::Exit ()

Required after any use of RTMaps...

• bool MAPS::Run ()

Starts the execution of the current session.

bool MAPS::Shutdown ()

Shutdowns the RTMaps session currently running.

• bool MAPS::Reset ()

Resets the RTMaps system.

• bool MAPS::Parse (const char \*s)

Parses a string containing MAPSScript instructions.

• bool MAPS::ParseFile (const char \*s)

Parses a file containing MAPSScript instructions.

• void MAPS::LoadCoreFunction (const char \*cf)

Loads a core function and activates it.

MAPSCoreFunctionInterface \* MAPS::CoreFunction (const char \*cf)
 Returns a pointer to the core function named cf if it was previously loaded (returns NULL otherwise)

void MAPS::RegisterPackage (const char \*fileName)

Loads a package (set of components compiled as a shared object).

void MAPS::UnregisterPackage (const char \*fileName)
 Unloads a package (set of components compiled as a shared object).

• bool MAPS::IsRunning ()

Is there a RTMaps system currently running?

bool MAPS::IsPaused ()

Is the RTMaps clock in paused state?

• bool MAPS::IsReplaying ()

Returns true if a file is open for replay.

int MAPS::CheckLevel ()

Returns the level of structure control in the current system (0=no control, fastest, 2=max control, slowest)

# RTMaps functions for distribution and synchronization

bool MAPS::IsDistributedAsMaster ()
 Is RTMaps acting as a Master on a network of distributed RTMaps.

• bool MAPS::IsDistributedAsSlave ()

Is RTMaps acting as a Slave on a network of distributed RTMaps.

• bool MAPS::GetSynchronizer (void \*owner, MAPSSynchronizer \*\*ppSynchronizer)

Requests a pointer on the synchronizer object.

• bool MAPS::ReleaseSynchronizer (void \*module, MAPSSynchronizer \*\*ppSynchronizer)

Releases a pointer on the synchronizer object.

#### RTMaps Virtual Time management functions

MAPSAbsoluteTime & MAPS::TimeReference ()
 Gets the time reference (the absolute time the timestamps always refer to)

MAPSTimestamp MAPS::CurrentTime (bool lock=true, bool release=true)
 Gets the current time in the RTMaps system (virtual time)

void MAPS::SetCurrentTime (MAPSTimestamp t)

Sets the current time (jumps in time!)

```
    void MAPS::SetTimeSpeed (int speed)
    Sets the current time speed (1000 = real time)
```

• int MAPS::TimeSpeed ()

Gets the current time speed (1000 = real time)

int MAPS::TimeState ()

Gets the current time state (MAPS::Running or MAPS::Paused)

# **RTMaps Index management**

• void MAPS::SetIndex ()

Adds an index now (during recording)

• void MAPS::Go2Index (int num)

Goes to index num during replay.

• void MAPS::Go2PreviousIndex ()

Goes to previous index (during replay)

void MAPS::Go2NextIndex ()

Goes to next index (during replay)

## RTMaps Recording management

void MAPS::StartRecording (void)
 Starts recording information (starts all)

void MAPS::StopRecording (void)

Stops recording information (stops all)

# RTMaps Type Filtering management

bool MAPS::TypeFilter (const MAPSTypeInfo &outputType, MAPSTypeFilterBase &filter)

#### **RTMaps General purpose functions**

 ::IpIImage MAPS::IpIImageModel (int width, int height, unsigned int channelSeq=MAPS\_-CHANNELSEQ\_BGR, unsigned int dataOrder=IPL\_DATA\_ORDER\_PIXEL, unsigned int depth=IPL\_DEPTH\_8U)

Creates a model of an operational IplImage structure with the provided parameters.

 ::IpIImage MAPS::IpIImageModel (int width, int height, const char \*channelSeq, unsigned int dataOrder=IPL\_DATA\_ORDER\_PIXEL, unsigned int depth=IPL\_DEPTH\_-8U)

Creates a model of an operational IplImage structure with the provided parameters.

bool MAPS::lpllmageCheck (::lpllmage &image,::lpllmage &model)

Checks that an image is the same type and size as the model given in second parameter.

#### **RTMaps Maintenance functions**

• MAPSString MAPS::About (void)

## **RTMaps Reporting functions**

For all these functions, the importance must be set between 0 (not important) to 2 (of the utmost importance)

- void MAPS::ReportInfo (const char \*text, int importance=0)

  Reports a piece of information.
- void MAPS::ReportWarning (const char \*text, int importance=0)
   Reports a warning.
- void MAPS::ReportError (const char \*text, int importance=0)

  Reports an error.
- void MAPS::Report (const char \*text, int type, int importance=0)
   Reports something (with user feedback + logging)
- void MAPS::MessageBox (const char \*message, int type, int importance=0)

  Displays a modal MessageBox. To be used for debugging only since this function blocks until the user.

#### Time conversion and handling functions

• MAPSTimestamp MAPS::TimestampFromString (const char \*s, char \*\*endptr=NULL)

Transforms a string of form hh:mm:ss.mmmuuu into a timestamp.

MAPSString MAPS::TimeString (MAPSTimestamp t)

MAPSString MAPS::Timestamp2String (MAPSTimestamp t)

Transforms a timestamp into a human readable string of form hh:mm:ss.mmmmmm.

 void MAPS::Timestamp2AbsoluteTimeUTC (MAPSTimestamp t, MAPSAbsolute-Time \*utctime)

Transforms a timestamp in microseconds into an absolute time.

 MAPSTimestamp MAPS::AbsoluteTimeUTC2Timestamp (const MAPSAbsolute-Time \*utctime)

Transforms an absolute time into a timestamp.

- MAPSInt64 MAPS::AbsoluteTime2Integer (MAPSAbsoluteTime &time)
- void MAPS::Integer2AbsoluteTime (MAPSInt64 integer, MAPSAbsoluteTime &time)
- MAPSString MAPS::AbsoluteTime2String (MAPSAbsoluteTime absTime)

Transforms an absolute time into a string of form yyyy/mm/dd hh:mm:ss.mmmuuu.

void MAPS::GetAbsoluteTime (MAPSAbsoluteTime \*localtime)
 Gets the absolute current time (local time). Deprecated. Prefer using MAPS::GetAbsoluteTimeLocal.

void MAPS::GetAbsoluteTimeLocal (MAPSAbsoluteTime \*localtime)

Gets the absolute current local time.

void MAPS::GetAbsoluteTimeUTC (MAPSAbsoluteTime \*utctime)

Gets the absolute current time (UTC)

 bool MAPS::AbsoluteTimeUTCToAbsoluteTimeLocal (const MAPSAbsoluteTime \*utctime, MAPSAbsoluteTime \*localtime)

Converts a UTC time to a local time. Returns true in case of success, false otherwise.

 bool MAPS::AbsoluteTimeLocalToAbsoluteTimeUTC (const MAPSAbsoluteTime \*localtime, MAPSAbsoluteTime \*utctime)

Converts a local time to a UTC time. Returns true in case of success, false otherwise.

bool MAPS::SetSystemTime (const MAPSAbsoluteTime \*utctime)

Sets the computer system clock to the provided absolute time.

# RTMaps Flow monitoring functions

MAPSString MAPS::GetWriteStatistics ()

Gets the detailed statistics about the data flow to the hard disks (write file operations).

MAPSString MAPS::GetReadStatistics ()

Gets the detailed statistics about the read file operations.

• int MAPS::GetRemainingTime ()

Gets the overall remaining recording time, if the flows stays constant.

• MAPSInt64 MAPS::GetWriteFlow ()

Gets the total write flow (file write operations)

• MAPSInt64 MAPS::GetReadFlow ()

Gets the total read flow (file read operations)

void MAPS::RecordMemoryWriteFlow (MAPSInt64 size)

Notifies RTMaps that such a memory write flow has occured. Do not use in conjonction with MAPS::Memcpy(...)

void MAPS::RecordMemoryReadFlow (MAPSInt64 size)

Notifies RTMaps that such a memory read flow has occured. Do not use in conjonction with MAPS::Memcpy(...)

• MAPSInt64 MAPS::GetMemoryReadFlow ()

Gets the total memory read flow.

MAPSInt64 MAPS::GetMemoryWriteFlow ()

Gets the total memory write flow.

MAPSInt64 MAPS::GetMemoryFlow ()

Gets the total memory flow (read+write)

MAPSInt64 MAPS::GetDiskFreeSpace (const char \*path)

Gets the free disk space on the disk containing path.

# RTMaps OS wrapping functions

These functions give access to all the needed features of an OS except file I/O. These functions should be called instead of their OS-specific counterparts to ensure a cross-platform programming.

MAPSTimestamp MAPS::GetSystemAccurateTiming (void)

Gets an immediate timestamp (in microseconds).

bool MAPS::CreateThread (void \*(\*startAdress)(void \*), void \*argList)

Starts a thread.

void MAPS::SetCurrentThreadPriority (int priority)

Sets the priority of the current thread (between 0 and 255)

• MAPSThreadId MAPS::GetCurrentThreadId ()

Gets an id for the current thread.

void MAPS::ReleaseCurrentThread (void)

Releases the current thread.

• void MAPS::Sleep (MAPSDelay delay)

Sleeps for a certain amount of time.

void MAPS::Wait4AWhile (void)

Waits for a while. Useful little function.

MAPSString MAPS::GetCurrentDirectory ()

Gets the current directory path.

bool MAPS::SetCurrentDirectory (const MAPSString path)

Sets the current directory path.

bool MAPS::CreateDirectory (const char \*dirName)

Creates a directory.

MAPSString MAPS::GetTempDirectory ()

Gets a path to the temporary directory.

• MAPSString MAPS::GetInstallPath (const char \*pathName)

Gets a path refering to RTMaps installation.

void \* MAPS::AllocSharedMemory (int size)

Memory allocation. Assumes it is allocated in a way that it can be accessed by a RTMaps system running in another process.

void MAPS::DeallocSharedMemory (void \*ptr)

Memory deallocation. Assumes it was allocated in a way that it can be accessed by a RTMaps system running in another process.

# RTMaps C++ interface functions

These functions are designed to control the RTMaps engine directly through C++ calls. These are rather low-level functions that are not of any interest for a component developer.

bool MAPS::GetBoolProperty (const char \*s, bool \*ok=NULL)
 Gets a boolean property.

• MAPSInt64 MAPS::GetIntegerProperty (const char \*s, bool \*ok=NULL)

Gets an integer property or enum property selected index.

MAPSString MAPS::GetStringProperty (const char \*s, bool \*ok=NULL)
 Gets a string property or enum property selected string.

- MAPSFloat MAPS::GetFloatProperty (const char \*s, bool \*ok=NULL)
   Gets a float property.
- MAPSEnumStruct MAPS::GetEnumsProperty (const char \*s, bool \*ok=NULL)
   Gets an enum property.
- MAPSComponent \* MAPS::Component (const char \*s)
   Returns a pointer to component s (returns NULL if it does not exist)
- MAPSProperty \* MAPS::Property (const char \*s)

  Returns a pointer to the property named s (returns NULL if it does not exist)
- MAPSComponent \* MAPS::CreateComponent (const char \*modelName, const char \*componentName, bool start=true)
   Component instantiation.
- void MAPS::StartComponent (const char \*componentName)

  Starts the component if frozen.
- void MAPS::KillComponent (const char \*componentName)
   Dynamically destroys a component.
- void MAPS::KillComponent (MAPSComponent &component)
   Dynamically destroys a component.
- void MAPS::RenameComponent (const char \*componentName, const char \*newName)

Renames a component.

- void MAPS::Attach (MAPSOutput &output, MAPSInput &input)
   Dynamically attaches an input to an output.
- void MAPS::Attach (const char \*outputName, const char \*inputName)

  Dynamically attaches an input to an output.
- bool MAPS::Attach2 (const char \*name, const char \*inputName)
   Dynamically attaches an input to an output. Extended version.
- void MAPS::Detach (MAPSOutput & output, MAPSInput & input)
   Dynamically detaches an output from an input.
- void MAPS::Record (const char \*outputName, const char \*recorder=NULL, const char \*method=NULL, bool neverskipping=false, bool useTimestamp=false)

Records an output.

void MAPS::Open (const char \*pattern, const char \*nspace=NULL, MAPSInt64 offset=0, MAPSTimestamp beginning=0, MAPSTimestamp end=0)

Opens a database to replay records from.

• void MAPS::Replay (const char \*outputname)

Replays some data.

- void MAPS::Copy (const char \*outputname, const char \*recorderName)
   Copies some data.
- void MAPS::StopCopy (const char \*outputname)
   Aborts the copy of an output.
- void MAPS::SetTimeAdapt (int ta)
   Sets the time automatic adaptation algorithms.
- MAPSTimestamp MAPS::GetFirstTimestamp ()
   Returns the first timestamp of all the currently open databases.
- MAPSTimestamp MAPS::GetLastTimestamp ()

Returns the last timestamp of all the currently open databases.

MAPSEvent \* MAPS::GetShutdownEvent ()

Gets a pointer to the shutdown event.

# 11.1.1 Detailed Description

The RTMaps engine header file - Version 3.4 build 99.

# 11.1.2 Define Documentation

#### 11.1.2.1 #define MAPS\_PACKAGE\_DEFINITION( name, version )

Use this macro to determine the version of your package file.

Use this macro in one (and only one) of your package .cpp files in order to set a version for your RTMaps .pck file. If this macro is not present, the version of the package is 1.0.

#### 11.1.2.2 #define MAPS\_PI

The Pi number.

You should use this instead of M PI, which is not defined on some plateforms.

#### 11.1.2.3 #define MAPS\_RGB( r, g, b )

24-bit integer color representation

Stricly equivalent to the Windows RGB macro. Please use this one in place of RGB for better portability of the code.

# 11.1.3 Typedef Documentation

#### 11.1.3.1 typedef MAPSInt32 MAPS3States

3-state value, generally used to tell the state of a thread.

It can take the MAPS::DeadState, MAPS::DyingState and MAPS::LivingState values.

#### 11.1.3.2 typedef double MAPSFloat

The MAPSFloat type is a double precision floating point number.

RTMaps always uses MAPSFloat (double = 64-bit floating point numbers). Please never use float (float = 32 bits floating point numbers)

#### 11.1.3.3 typedef MAPSInt64 MAPSTimestamp

The MAPSTimestamp type is a 64-bit integer.

RTMaps always timestamps data with a 64-bit integer representing the amount of time in microseconds since the last Run command execution (the reference time)

# 11.2 MAPSImageProcessing1Src1Dest.h File Reference

The MAPSImageProcessing1Src1Dest component model.

#### **Classes**

- struct MAPSImageProcessing1Src1DestDefinition
   Definition structure for an image processing algorithm (1 Src 1 Dest operation).
- struct MAPSImageProcessing1Src1DestParams
   Parameter structure for an image processing algorithm (1 Src 1 Dest operation).
- class MAPSImageProcessing1Src1Dest

Image Processing component base class with 1 input and 1 output images.

#### 11.2.1 Detailed Description

The MAPSImageProcessing1Src1Dest component model.

# 11.3 MAPSImageProcessing2Src1Dest.h File Reference

The MAPSImageProcessing2Src1Dest component model.

#### Classes

- struct MAPSImageProcessing2Src1DestDefinition
   Definition structure for an image processing algorithm (2 Src 1 Dest operation).
- struct MAPSImageProcessing2Src1DestParams

  Parameter structure for an image processing algorithm (2 Src 1 Dest operation).
- class MAPSImageProcessing2Src1Dest
   Image Processing component base class with 2 input and 1 output images.

#### 11.3.1 Detailed Description

The MAPSImageProcessing2Src1Dest component model.

# 11.4 MAPSRBRegion.h File Reference

The RTMaps Ring-buffer region class and associated types.

# Classes

• class MAPSRBRegion

MAPSRBRegion class: Ring-Buffer region manipulation class.

#### **Enumerations**

• enum MAPSConstRBRegionState {

MAPSConstRBRegionEmpty, MAPSConstRBRegionReady, MAPSConstRBRegionWarnings, MAPSConstRBRegionUninitialized,

 $\label{lem:maps} MAPS ConstRBRegionOverflowOp, MAPS ConstRBRegionErrors, MAPS ConstRBRegionInvalid, MAPS ConstRBRegionInvalidOp \}$ 

Flags for ring-buffer region state.

 enum MAPSConstRBRegionErosion { MAPSConstRBRegionErosionBeginning, MAPSConstRBRegionErosionEnd }

Flags for the MAPSRBRegion::Erode method.

 enum MAPSConstRBRegionDilation { MAPSConstRBRegionDilationBeginning, MAPSConstRBRegionDilationEnd }

Flags for the MAPSRBRegion::Dilate method.

enum MAPSConstRBRegionCrop { MAPSConstRBRegionCropBeginning, MAPSConstRBRegionCropEnd }

Flags for the MAPSRBRegion::Crop method.

enum MAPSConstRBRegionSubRegion { MAPSConstRBRegionSubRegionFromBeginning, MAPSConstRBRegionSubRegionFromEnd }

Flags for the MAPSRBRegion::SubRegion method.

 enum MAPSConstRBRegionBesideRegion { MAPSConstRBRegionBesideRegion-Previous, MAPSConstRBRegionBesideRegionNext }

Flags for the MAPSRBRegion::BesideRegion method.

#### 11.4.1 Detailed Description

The RTMaps Ring-buffer region class and associated types.

#### 11.4.2 Enumeration Type Documentation

## 11.4.2.1 enum MAPSConstRBRegionBesideRegion

Flags for the MAPSRBRegion::BesideRegion method.

#### **Enumerator:**

*MAPSConstRBRegionBesideRegionPrevious* Take the region before the source region.

MAPSConstRBRegionBesideRegionNext Take the region after the source region.

## 11.4.2.2 enum MAPSConstRBRegionCrop

Flags for the MAPSRBRegion::Crop method.

#### **Enumerator:**

**MAPSConstRBRegionCropBeginning** Crop from the beginning of the region. **MAPSConstRBRegionCropEnd** Crop from the end of the region.

#### 11.4.2.3 enum MAPSConstRBRegionDilation

Flags for the MAPSRBRegion::Dilate method.

#### **Enumerator:**

MAPSConstRBRegionDilationBeginning Dilate from the beginning of the region.MAPSConstRBRegionDilationEnd Dilate from the end of the region.

#### 11.4.2.4 enum MAPSConstRBRegionErosion

Flags for the MAPSRBRegion::Erode method.

#### **Enumerator:**

MAPSConstRBRegionErosionBeginning Erode from the beginning of the region.MAPSConstRBRegionErosionEnd Erode from the end of the region.

#### 11.4.2.5 enum MAPSConstRBRegionState

Flags for ring-buffer region state.

## Enumerator:

MAPSConstRBRegionEmpty When the region has been initialized, but is empty.

**MAPSConstRBRegionReady** When the region has been initialized and contains some data.

MAPSConstRBRegionWarnings Warnings common flag.

MAPSConstRBRegionUninitialized When the region has not been initialized.

**MAPSConstRBRegionOverflowOp** When the region has been initialized, is full, and the last operation returned an overflow. This could never be the state of a region, but the state of an operation on a region.

MAPSConstRBRegionErrors Errors common flag.

**MAPSConstRBRegionInvalid** When the region is invalid (offset, size, fifoSize are inconsistent)

**MAPSConstRBRegionInvalidOp** Only returned by an operation when the operation is invalid on the current region. This could never be the state of a region, but the state of an operation on a region.

## 11.4.2.6 enum MAPSConstRBRegionSubRegion

Flags for the MAPSRBRegion::SubRegion method.

#### **Enumerator:**

**MAPSConstRBRegionSubRegionFromBeginning** Extract the sub-region from the beginning of the source region.

**MAPSConstRBRegionSubRegionFromEnd** Extract the sub-region from the end of the source region.

# 11.5 MAPSSoundProcessingComponent.h File Reference

The MAPSSoundProcessingComponent component model Format of IO element:

- Frequency() holds frequency info (!!! in mHz !!!!)
- Misc1() holds the number of channels
- · Misc2() holds the bits info.

# 11.5.1 Detailed Description

The MAPSSoundProcessingComponent component model Format of IO element:

- Frequency() holds frequency info (!!! in mHz !!!!)
- · Misc1() holds the number of channels
- · Misc2() holds the bits info.

# 11.6 MAPSStream8IOComponent.h File Reference

The MAPSStream8IOComponent component model.

#### Classes

class MAPSStream8IOComponent

Processing component template with 1 Stream8 input and 1 Stream8 output.

#### 11.6.1 Detailed Description

The MAPSStream8IOComponent component model.

# Index

About	BesideRegion
MAPS, 59	MAPSRBRegion, 183
AbsoluteTime2Integer	Birth
MAPS, 59	MAPSComponent, 85
AbsoluteTimeUTC2Timestamp	BufferSize
MAPS, 59	MAPSIOEIt, 122
AcknowledgePropertyChanged	,
MAPSModule, 155	CallbackRecordingStateChanged
MAPSProperty, 177	MAPSRecordingStateListener, 190
Action definition macros, 29	CallbackRun
actiondef	MAPSRunShutdownListener, 197
MAPS ACTION, 29	CallbackShutdown
MAPS BEGIN ACTIONS DEFINITION	ON, MAPSRunShutdownListener, 197
 29	CallbackTimeJumped
Alloc	MAPSTimeStateListener, 214
MAPSArray, 73	CallbackTimePaused
AllocOutputBuffer	MAPSTimeStateListener, 214
MAPSOutput, 170	CallbackTimeSpeedChanged
AllocOutputBufferImage	MAPSTimeStateListener, 214
MAPSOutput, 171	CallDynamic
AllocOutputBufferIpIImage	MAPSComponent, 85
MAPSOutput, 171	channelSeq
AllocOutputBufferMAPSImage	IplImage, 67
MAPSOutput, 172	Clear
AllocOutputBufferMatrix	MAPSHashTable, 109
MAPSOutput, 172	Clone
Append	MAPSMatrix2, 143
MAPSArray, 73	coi
MAPSList, 134	IpIROI, 69
Attach2	colorModel
MAPS, 59	IplImage, 67
	component
Banzai	MAPS_CHILD_COMPONENT_HEADER
MAPSComponent, 85	CODE, 32
Basic data structures, 19	MAPS_CHILD_COMPONENT_HEADER
bds	CODE_WITHOUT_CONSTRUCTOR,
MAPSForall, 22	32
MAPSForallItems, 22	MAPS_CLOCK_COMPONENT_HEADER_
MAPSForallPtr, 22	CODE, 32
MAPSString, 23	MAPS_COMPONENT_DEFINITION,
operator+, 23	32

MAPS_COMPONENT_DEFINITION DOC, 33	MAPSComponent, 86 DynamicConfirm
MAPS_COMPONENT_DEFINITION REGISTRATION, 34	
MAPS_COMPONENT_DEFINITION	Endl
UNIQUE, 34	MAPSFileIO, 105
MAPS_COMPONENT_DYNAMIC_HEA	
CODE, 35	MAPS, 64
MAPS COMPONENT HEADER COD	
WITHOUT_CONSTRUCTOR, 35	MAPSRBRegion, 185
MAPS_COMPONENT_REGISTERING	<del>-</del>
HEADER_CODE, 35	MAPSModule, 156
MAPS_COMPONENT_STANDARD	MAFShecoruneplayMethod, 194
HEADER_CODE, 36	- Fila Close
MAPS_PARENT_COMPONENT_HEAD	MAPSFileIO, 102
CODE, 36	
MAPS_PARENT_COMPONENT_HEAD	THEINEXITIE
CODE_WITHOUT_CONSTRUCT	OR, MAPSFILLIO, 102
36	FileOpen4Reading
Component design, 30	MAPSFileIO, 102
ConnectedOutput	FileOpen4Writing
MAPSInput, 117	MAPSFileIO, 102
Core	FilePreviousLine
MAPSComponent, 85	MAPSFileIO, 103
CreateThread	FileRead
MAPSComponent, 86	MAPSFileIO, 103
Crop	FileWrite
MAPSRBRegion, 184	MAPSFileIO, 104
CurrentTime	FileWriteText
MAPSBaseClock, 77	MAPSFileIO, 104
	Find
Data	MAPSStackedString, 206
MAPSIOEIt, 122	FreeBuffers
Death	MAPSComponent, 87
MAPSComponent, 86	Frequency
depth	MAPSIOEIt, 123
IplImage, 67	
Deserialize	Get
MAPSIOEIt, 123	MAPSModule, 157
Die	MAPSProperty, 177
MAPSModule, 156	GetAbsoluteTimeSpeed
Dilate	MAPSBaseClock, 77
MAPSRBRegion, 184	GetHandle
DirectSet	MAPSEvent, 97
MAPSModule, 156	GetInstallPath
DuplicateToRB2	MAPS, 60
MAPSRBRegion, 184	GetPropertyChangedEvent
_	MAPSProperty, 177
DuplicateToRB3	• •
MAPSRBRegion, 184	GetSynchronizer
Dynamic	MAPS, 60

GetSystemAccurateTiming MAPS, 60	MAPSIOEIt, 124 IsDying MAPSModule, 157
HeadingHint	IsFIFOFull
MAPSRecordReplayMethod, 195	MAPSModule, 157
c. toocia. topia,	IsReplayable
Im	MAPSBaseClock, 77
MAPSMatrix, 139	IsSynchronizable
imageld	MAPSBaseClock, 77
IplImage, 67	With a Bassalosk, 77
Init	Left
MAPSRBRegion, 185	MAPSStackedString, 206
InitClock	Lock
MAPSBaseClock, 77	MAPSMutex, 167
Input definition macros, 23	LoseOneLife
inputdef	MAPSModule, 157
MAPS_BEGIN_INPUTS_DEFINITION	
23	MAPS, 41
MAPS_INPUT, 23	About, 59
Insert	AbsoluteTime2Integer, 59
MAPSHashTable, 109	AbsoluteTimeUTC2Timestamp, 59
MAPSList, 134	Attach2, 59
InsertAfter	EnumProperty, 64
MAPSList, 134	GetInstallPath, 60
InsertBefore	GetSynchronizer, 60
MAPSList, 134, 135	GetSystemAccurateTiming, 60
Integer2AbsoluteTime	Integer2AbsoluteTime, 60
MAPS, 60	IplImageModel, 60, 61
InverseRegion	Memcpy, 61
MAPSRBRegion, 185	MessageBox, 61
IOEltBufferSizeInBytes	ReleaseCurrentThread, 61
MAPSIOEIt, 123	Report, 61
IOEltSizeBytes	ReportInfo, 62
MAPSOutput, 172	SetSystemTime, 62
IOEltUsedSizeInBytes	Sleep, 62
MAPSIOEIt, 124	TextAscii, 64
lpllmage, 65	Timestamp2AbsoluteTimeUTC, 62
channelSeq, 67	Timestamp2String, 63
colorModel, 67	TimestampFromString, 63
depth, 67	TimeString, 63
imageld, 67	TypeFilter, 63
maskROI, 67	maps.hpp, 227
roi, 68	MAPS3States, 254
IpIImageModel	MAPS_PACKAGE_DEFINITION, 253
MAPS, 60, 61	MAPS_PI, 253
IpIROI, 68	MAPS_RGB, 253
coi, 69	MAPSFloat, 254
IsConnected	MAPSTimestamp, 254
MAPSInput, 117	MAPS3States
IsDeserializable	maps.hpp, 254

```
MAPS ACTION
                                 MAPS PARENT COMPONENT HEADER -
   actiondef, 29
                                         CODE
                                     component, 36
MAPS BEGIN ACTIONS DEFINITION
   actiondef, 29
                                 MAPS_PARENT_COMPONENT_HEADER_-
MAPS_BEGIN_INPUTS_DEFINITION
                                         CODE WITHOUT CONSTRUCTOR
                                     component, 36
   inputdef, 23
                                 MAPS PI
MAPS BEGIN OUTPUTS DEFINITION
                                     maps.hpp, 253
   outputdef, 24
MAPS_BEGIN_PROPERTIES_DEFINITIONMAPS_PROPERTY
                                     propdef, 26
   propdef, 26
MAPS_CHILD_COMPONENT_HEADER_- MAPS_PROPERTY_ENUM
                                     propdef, 27
       CODE
                                 MAPS_PROPERTY_ENUM_UNIT
   component, 32
                                     propdef, 27
MAPS_CHILD_COMPONENT_HEADER -
       CODE_WITHOUT_CONSTRUCTOMAPS_PROPERTY_READ_ONLY
                                     propdef, 28
   component, 32
MAPS_CLOCK_COMPONENT_HEADER_- MAPS_PROPERTY_READ_ONLY_UNIT
                                     propdef, 28
       CODE
                                 MAPS PROPERTY UNIT
   component, 32
                                     propdef, 28
MAPS_COMPONENT_DEFINITION
                                 MAPS_RECORD_REPLAY_METHOD_BLACKBOX_-
   component, 32
                                         HEADER CODE
MAPS_COMPONENT_DEFINITION_DOC
                                     rrm, 38
MAPS_COMPONENT_DEFINITION_REGISTRATION.....
   component, 33
   component, 34
MAPS_COMPONENT_DEFINITION_UNIQUE MAPS_RECORD_REPLAY_METHOD_DEFINITION
   component, 34
MAPS_COMPONENT_DYNAMIC_HEADER_MAPS_RECORD_REPLAY_METHOD_HEADING_-
       CODE
                                         HINT HEADER CODE
   component, 35
                                     rrm, 39
MAPS COMPONENT HEADER CODE -
                                 MAPS RECORD REPLAY METHOD PROCESS -
       WITHOUT_CONSTRUCTOR
                                         HEADER CODE
   component, 35
                                     rrm, 39
MAPS_COMPONENT_REGISTERING_HEADERS_RECORD_REPLAY_METHOD_STANDARD_-
       CODE
                                         HEADER CODE
   component, 35
                                     rrm, 39
MAPS_COMPONENT_STANDARD_HEADEMAPS_RGB
       CODE
                                     maps.hpp, 253
   component, 36
                                 MAPSAbsoluteTime, 69
MAPS_INPUT
                                 MAPSAction, 70
   inputdef, 23
                                 MAPSArray, 70
MAPS OUTPUT
                                     Alloc, 73
   outputdef, 24
                                     Append, 73
MAPS OUTPUT FIFOSIZE
                                     MAPSArray, 73
   outputdef, 25
                                     operator T *, 74
MAPS_OUTPUT_USER_STRUCTURE
                                     operator <<, 75
   outputdef, 25
                                     Pop, 74
MAPS_PACKAGE_DEFINITION
                                     Realloc, 74
   maps.hpp, 253
                                     Set, 74
```

Shift, 74	MAPSConstRBRegionDilationEnd
Unshift, 75	MAPSRBRegion.h, 257
Vect, 75	MAPSConstRBRegionEmpty
MAPSBaseClock, 75	MAPSRBRegion.h, 257
CurrentTime, 77	MAPSConstRBRegionErosion
GetAbsoluteTimeSpeed, 77	MAPSRBRegion.h, 257
InitClock, 77	MAPSConstRBRegionErosionBeginning
IsReplayable, 77	MAPSRBRegion.h, 257
IsSynchronizable, 77	MAPSConstRBRegionErosionEnd
MAPSBaseClock, 76	MAPSRBRegion.h, 257
RunClock, 78	MAPSConstRBRegionErrors
SetAbsoluteTimeSpeed, 78	MAPSRBRegion.h, 257
ShutdownClock, 78	MAPSConstRBRegionInvalid
MAPSBasicList, 78	MAPSRBRegion.h, 257
MAPSBasicListItem, 80	MAPSConstRBRegionInvalidOp
MAPSCANFrame, 81	MAPSRBRegion.h, 257
MAPSCircle, 82	MAPSConstRBRegionOverflowOp
MAPSComplex, 82	MAPSRBRegion.h, 257
MAPSComponent, 83	MAPSConstRBRegionReady
Banzai, 85	MAPSRBRegion.h, 257
Birth, 85	MAPSConstRBRegionState
CallDynamic, 85	MAPSRBRegion.h, 257
Core, 85	MAPSConstRBRegionSubRegion
CreateThread, 86	MAPSRBRegion.h, 257
Death, 86	MAPSConstRBRegionSubRegionFromBeginning
Dynamic, 86	MAPSRBRegion.h, 258
DynamicConfirm, 86	MAPSConstRBRegionSubRegionFromEnd
FreeBuffers, 87	MAPSRBRegion.h, 258
NewAction, 87	MAPSConstRBRegionUninitialized
NewInput, 87, 88	MAPSRBRegion.h, 257
NewOutput, 88	MAPSConstRBRegionWarnings
NewProperty, 88, 89	MAPSRBRegion.h, 257
SetAutomaticStart, 89	MAPSCouple, 90
Start, 89	operator<<, 90
MAPSConstRBRegionBesideRegion	MAPSDrawingObject, 91
MAPSRBRegion.h, 256	MAPSDrawingObjectVariant, 93
MAPSConstRBRegionBesideRegionNext	MAPSEllipse, 93
MAPSRBRegion.h, 256	MAPSEnumStruct, 94
MAPSConstRBRegionBesideRegionPreviou	us Select, 95
MAPSRBRegion.h, 256	MAPSEvent, 95
MAPSConstRBRegionCrop	GetHandle, 97
MAPSRBRegion.h, 256	MAPSEvent, 97
MAPSConstRBRegionCropBeginning	MsgInQueue, 97
MAPSRBRegion.h, 256	MsgWait, 97
MAPSConstRBRegionCropEnd	ResetTrigger, 97
MAPSRBRegion.h, 256	SetTrigger, 98
MAPSConstRBRegionDilation	Wait, 98
MAPSRBRegion.h, 256	MAPSFileIO, 99
MAPSConstRBRegionDilationBeginning	Endl, 105
MAPSRBRegion.h, 257	FileClose, 102

FileNextLine, 102	IOEltUsedSizeInBytes, 124
FileOpen4Reading, 102	IsDeserializable, 124
FileOpen4Writing, 102	operator MAPSFloat &, 124
FilePreviousLine, 103	operator MAPSInt32 &, 124
FileRead, 103	operator MAPSInt64 &, 124
FileWrite, 104	Quality, 125
FileWriteText, 104	Serialize, 125
Unlock, 105	SerializedIOEltSizeInBytes, 125
MAPSFileReadHandle, 105	Size, 126
MAPSFileWriteHandle, 106	TimeOflssue, 126
MAPSFloat	Timestamp, 126
maps.hpp, 254	VectorSize, 127
MAPSForall	MAPSLine, 128
bds, 22	MAPSList, 129
MAPSForallItems	Append, 134
bds, 22	Insert, 134
MAPSForallPtr	InsertAfter, 134
bds, 22	InsertBefore, 134, 135
MAPSHashTable, 106	operator<<, 135
Clear, 109	MAPSList::MAPSIterator, 127
Insert, 109	MAPSListItem, 135
MAPSHashTable, 108	MAPSListIterator, 136
Next, 109	MAPSMatrix, 137
MAPSHashTableIterator, 110	lm, 139
MAPSImage, 110	MAPSMatrix, 138
MAPSImageProcessing1Src1Dest, 112	operator MAPSMatrix2< double >, 139
MAPSImageProcessing1Src1Dest.h, 254	Real, 139
MAPSImageProcessing1Src1DestDefinition	
112	Clone, 143
MAPSImageProcessing1Src1DestParams,	operator<<, 143
113	operator(), 143
MAPSImageProcessing2Src1Dest, 114	operator=, 143
MAPSImageProcessing2Src1Dest.h, 255	MAPSModule, 144
MAPSImageProcessing2Src1DestDefinition	
114	Die, 156
MAPSImageProcessing2Src1DestParams,	DirectSet, 156
115	Error, 156
MAPSInput, 116	Get, 157
ConnectedOutput, 117	IsDying, 157
IsConnected, 117	IsFIFOFull, 157
Name, 117	LoseOneLife, 157
ShortName, 117	MsgStartReading, 157, 158
Type, 117	MsgWait4Event, 158
MAPSIntegerHashTable, 117	MsgWait4Events, 158
MAPSIOEIt, 118	NbProperties, 159
BufferSize, 122	NLastStartReading, 159
Data, 122	OneMoreLife, 159
Deserialize, 123	PerformanceMonitoring, 160
Frequency, 123	PropertyChanged, 160
IOEltBufferSizeInBytes, 123	Report, 160

ReportError, 161	Pop, 186
ReportInfo, 161	Popback, 186
ReportWarning, 161	Push, 186
Rest, 162	SubRegion, 187
Set, 162	MAPSRBRegion.h, 255
StartReading, 162, 163	MAPSConstRBRegionBesideRegion,
StopWriting, 163	256
SynchroStartReading, 163	MAPSConstRBRegionBesideRegion-
Wait, 164	Next, 256
Wait4Event, 164, 165	MAPSConstRBRegionBesideRegion-
Wait4Events, 165	Previous, 256
Wait4Handshake, 165	MAPSConstRBRegionCrop, 256
MAPSMutex, 166	MAPSConstRBRegionCropBeginning,
Lock, 167	256
Release, 167	MAPSConstRBRegionCropEnd, 256
Reset, 167	MAPSConstRBRegionDilation, 256
MAPSMutex2, 167	MAPSConstRBRegionDilation, 230 MAPSConstRBRegionDilationBeginning,
ReleaseAll, 168	
	257
MAPSOutput, 168	MAPSConstRBRegionDilationEnd, 257
AllocOutputBuffer, 170	MAPSConstRBRegionEmpty, 257
AllocOutputBufferImage, 171	MAPSConstRBRegionErosion, 257
AllocOutputBufferIpIImage, 171	MAPSConstRBRegionErosionBeginning,
AllocOutputBufferMAPSImage, 172	257
AllocOutputBufferMatrix, 172	MAPSConstRBRegionErosionEnd, 257
IOEltSizeBytes, 172	MAPSConstRBRegionErrors, 257
Name, 172	MAPSConstRBRegionInvalid, 257
SetTypeName, 173	MAPSConstRBRegionInvalidOp, 257
SetTypeUnit, 173	MAPSConstRBRegionOverflowOp, 257
SetUnit, 173	MAPSConstRBRegionReady, 257
TypeName, 173	MAPSConstRBRegionState, 257
MAPSPair, 174	MAPSConstRBRegionSubRegion, 257
MAPSProperty, 174	MAPS ConstRBRegion SubRegion From Be-
AcknowledgePropertyChanged, 177	ginning, 258
Get, 177	MAPSConstRBRegionSubRegionFromEnd
GetPropertyChangedEvent, 177	258
Name, 178	MAPSConstRBRegionUninitialized, 257
PropertyChanged, 178	MAPSConstRBRegionWarnings, 257
PropertyChangedEvent, 178	MAPSRealObject, 187
Set, 178	MAPSRealObjectVariant, 189
ShortName, 178	MAPSRecordingStateListener, 190
MAPSPtrHashTable, 179	CallbackRecordingStateChanged, 190
MAPSRBRegion, 179	MAPSRecordReplayMethod, 191
BesideRegion, 183	Error, 194
Crop, 184	HeadingHint, 195
Dilate, 184	MAPSRectangle, 195
DuplicateToRB2, 184	MAPSRunnable, 196
DuplicateToRB3, 184	MAPSRunShutdownListener, 196
Erode, 185	CallbackRun, 197
Init, 185	CallbackShutdown, 197
InverseRegion, 185	MAPSSign, 197
miroroon togion, 100	Colgii, loi

MAPSSoundProcessingComponent.h, 258	MessageBox
MAPSSpot, 199	MAPS, 61
MAPSStackedString, 200	Mid
Find, 206	MAPSStackedString, 206
Left, 206	MsgInQueue
Mid, 206	MAPSEvent, 97
operator<<, 208	MsgStartReading
operator(), 207	MAPSModule, 157, 158
Part, 207	MsgWait
Right, 207	MAPSEvent, 97
Shorten, 207	MsgWait4Event
Token, 207	MAPSModule, 158
Up2, 208	MsgWait4Events
UpTo, 208	MAPSModule, 158
MAPSStream8IOComponent, 208	
MAPSStream8IOComponent.h, 258	Name
MAPSStreamedString, 209	MAPSInput, 117
MAPSString	MAPSOutput, 172
bds, 23	MAPSProperty, 178
MAPSStringHashTable, 210	name
MAPSSynchronizer, 211	MAPSTypeInfo, 221
SignalSynchronizationCommand, 211	nameFilter
MAPSText, 211	MAPSTypeFilterBase, 219
MAPSTimer, 212	NbProperties
MAPSTimestamp	MAPSModule, 159
maps.hpp, 254	NewAction
MAPSTimeStateListener, 213	MAPSComponent, 87
CallbackTimeJumped, 214	NewInput
CallbackTimePaused, 214	MAPSComponent, 87, 88
CallbackTimeSpeedChanged, 214	NewOutput
MAPSTree, 215	MAPSComponent, 88
MAPSTriangles3D, 216	NewProperty
MAPSTriangles3D::Object, 224	MAPSComponent, 88, 89
MAPSTriangles3D::Point, 225	Next
MAPSTriangles3D::Triangle, 225	MAPSHashTable, 109
MAPSTypeFilter, 217	NLastStartReading
MAPSTypeFilterBase, 217	MAPSModule, 159
nameFilter, 219	,
unitFilter, 219	OneMoreLife
MAPSTypeInfo, 220	MAPSModule, 159
name, 221	operator MAPSFloat &
SetName, 220	MAPSIOEIt, 124
SetUnit, 221	operator MAPSInt32 &
unit, 221	MAPSIOEIt, 124
MAPSVehicle, 221	operator MAPSInt64 &
MAPSWin32, 223	MAPSIOEIt, 124
maskROI	operator MAPSMatrix2< double >
IplImage, 67	MAPSMatrix, 139
Memcpy	operator T *
MAPS, 61	MAPSArray, 74
0, 01	1111 11 01 11 ay, 1 1

operator<<	Quality
MAPSArray, 75	MAPSIOEIt, 125
MAPSCouple, 90	
MAPSList, 135	Real
MAPSMatrix2, 143	MAPSMatrix, 139
MAPSStackedString, 208	Realloc
operator()	MAPSArray, 74
MAPSMatrix2, 143	Record/replay method design, 36
MAPSStackedString, 207	Release
operator+	MAPSMutex, 167
•	ReleaseAll
bds, 23	MAPSMutex2, 168
operator=	ReleaseCurrentThread
MAPSMatrix2, 143	MAPS, 61
Output definition macros, 24	Report
outputdef	MADO 61
MAPS_BEGIN_OUTPUTS_DEFINITION	ON, MAPSMadula 100
24	MAPSModule, 160
MAPS_OUTPUT, 24	ReportError
MAPS_OUTPUT_FIFOSIZE, 25	MAPSModule, 161
MAPS_OUTPUT_USER_STRUCTUR	EReportInfo
25	1VII 11 0, 02
	MAPSModule, 161
Part	ReportWarning
MAPSStackedString, 207	MAPSModule, 161
PerformanceMonitoring	Reset
_	MAPSMutex, 167
MAPSModule, 160	ResetTrigger
Pop NAA DOA waxay 74	MAPSEvent, 97
MAPSArray, 74	Rest
MAPSRBRegion, 186	MAPSModule, 162
Popback	Right
MAPSRBRegion, 186	MAPSStackedString, 207
propdef	roi
MAPS_BEGIN_PROPERTIES_DEFIN	ITION <sub>IplImage, 68</sub>
26	rrm
MAPS_PROPERTY, 26	MAPS_RECORD_REPLAY_METHOD
MAPS_PROPERTY_ENUM, 27	BLACKBOX_HEADER_CODE, 38
MAPS_PROPERTY_ENUM_UNIT, 27	MAPS_RECORD_REPLAY_METHOD
MAPS_PROPERTY_READ_ONLY, 28	COPY HEADER CODE, 38
MAPS_PROPERTY_READ_ONLY_UN	NIT, MAPS_RECORD_REPLAY_METHOD
28	DEFINITION, 38
MAPS_PROPERTY_UNIT, 28	MAPS RECORD REPLAY METHOD -
Property definition macros, 26	HEADING HINT HEADER CODE,
PropertyChanged	39
MAPSModule, 160	MAPS RECORD REPLAY METHOD -
MAPSProperty, 178	PROCESS_HEADER_CODE, 39
PropertyChangedEvent	MAPS_RECORD_REPLAY_METHOD
MAPSProperty, 178	STANDARD HEADER CODE, 39
Push	RunClock
MAPSRBRegion, 186	MAPSBaseClock, 78
W. C. C. Logion, 100	THE COURT OF THE C

Coloot	Cynabra CtartDaadina
Select OF	SynchroStartReading  MARSModule 160
MAPSEnumStruct, 95 Serialize	MAPSModule, 163
MAPSIOEIt, 125	TextAscii
SerializedIOEItSizeInBytes	MAPS, 64
MAPSIOEIt, 125	TimeOflssue
Set	MAPSIOEIt, 126
MAPSArray, 74	Timestamp
MAPSModule, 162	MAPSIOEIt, 126
MAPSProperty, 178	Timestamp2AbsoluteTimeUTC
SetAbsoluteTimeSpeed	MAPS, 62
MAPSBaseClock, 78	Timestamp2String
SetAutomaticStart	MAPS, 63
MAPSComponent, 89	TimestampFromString
SetName	MAPS, 63
MAPSTypeInfo, 220	TimeString
SetSystemTime	MAPS, 63
MAPS, 62	Token
SetTrigger	MAPSStackedString, 207
MAPSEvent, 98	Type
SetTypeName	MAPSInput, 117
MAPSOutput, 173	TypeFilter
SetTypeUnit	MAPS, 63
MAPSOutput, 173	TypeName
SetUnit	MAPSOutput, 173
MAPSOutput, 173	
MAPSTypeInfo, 221	unit
Shift	MAPSTypeInfo, 221
MAPSArray, 74	unitFilter
Shorten	MAPSTypeFilterBase, 219
MAPSStackedString, 207	Unlock
ShortName	MAPSFileIO, 105
MAPSInput, 117	Unshift
MAPSProperty, 178	MAPSArray, 75
ShutdownClock	Up2
MAPSBaseClock, 78	MAPSStackedString, 208
SignalSynchronizationCommand	UpTo
MAPSSynchronizer, 211	MAPSStackedString, 208
Size	
MAPSIOEIt, 126	Vect
Sleep	MAPSArray, 75
MAPS, 62	VectorSize
Start MARCCompany and 80	MAPSIOEIt, 127
MAPSComponent, 89	Wait
StartReading	
MAPSModule, 162, 163	MAPSEvent, 98
StopWriting MARSModule 163	MAPSModule, 164 Wait4Event
MAPSModule, 163	
SubRegion MAPSRBRegion, 187	MAPSModule, 164, 165 Wait4Events
WAL STEET LEGION, 107	v vait+L vaiit9

MAPSModule, 165 Wait4Handshake MAPSModule, 165