FlyWithLua Dear ImGui Font Guide

FlyWithLua 2.8.20+ -- ImgWindow v2.3.0+ -- Dear ImGui 1.92.8

A Developer & User Guide to Scalable Fonts, Custom Typefaces, and the Named Font Registry

October 25, 2026
Authors: William Good & Steven L. Goldberg (`@slgoldberg`), with help from Google Gemini
Target Release: FlyWithLua 2.8.20+ (Built against Dear ImGui 1.92.8 & ImgWindow v2.3.0)

FlyWithLua provides powerful support for **Dear ImGui** floating windows. Starting with FlyWithLua 2.8.18, script authors have access to high-resolution scalable TrueType (`.ttf`) and OpenType (`.otf`) fonts, a modern **Named Font Registry**, and live mid-flight font reloading.

This guide explains both the **Modern Named Font Registry** (recommended for new scripts) and the **Legacy Slot System** (preserved for 100% backward compatibility).

1. Quick Comparison

Feature	Legacy Slot System	Modern Named Font Registry
Syntax	`imgui_push_font(1..9)`	`imgui.PushFont("Roboto-Regular-16")`
Font Identification	Arbitrary integer slot (1–9)	Human-readable string or alias
Adding New Fonts	Replaces slots 1–9 via INI	Drop into folder or add `Font.` in INI
Dynamic Sizing	Fixed to 3 predefined INI sizes	Any size at runtime: `imgui.PushFont("Roboto-Regular", 24)`
Missing Font Handling	Silently ignored (crashes on `PopFont`)	Warns & falls back to rescaled default font
Reloading Fonts	Requires full sim or plugin reload	**Live mid-flight reload** via FlyWithLua menu
Pop Function	`imgui.PopFont()`	`imgui.PopFont()`, `imgui.pop_font()`, or `imgui_pop_font()`

2. The Modern Named Font Registry (Recommended)

2.1 Using Named Fonts in Lua

To format text with a specific font weight and size, wrap your text calls between `imgui.PushFont()` and `imgui.PopFont()`:

```
-- Standard syntax (matching Dear ImGui):
imgui.PushFont("Roboto-Medium-20")
imgui.TextUnformatted("Cockpit Checklist")
imgui.PopFont()

-- Standard body text:
imgui.PushFont("Roboto-Regular-16")
imgui.TextUnformatted("All systems normal.")
imgui.PopFont()
```

> **NOTE**
> FlyWithLua supports all common casing styles interchangeably:
> - `imgui.PushFont(...)` / `imgui.PopFont()` (PascalCase, standard Dear ImGui)
> - `imgui.push_font(...)` / `imgui.pop_font()` (snake_case, FlyWithLua convention)
> - `imgui_push_font(...)` / `imgui_pop_font()` (global legacy alias)

2.2 Standard Bundled Fonts & Built-In Defaults

FlyWithLua includes high-quality TrueType fonts pre-baked into the shared font atlas:

Font Name / Alias	Style	Default Baked Sizes
`"Roboto-Light"`	Light / Clean (Proportional)	`13px`, `16px`, `20px` (e.g. `"Roboto-Light-13"`)
`"Roboto-Regular"`	Standard Regular (Proportional)	`13px`, `16px`, `20px` (e.g. `"Roboto-Regular-16"`)
`"Roboto-Medium"`	Semi-Bold / Header (Proportional)	`13px`, `16px`, `20px` (e.g. `"Roboto-Medium-20"`)
`"Roboto-Italic"`	Italic / Emphasis (Proportional)	`13px`, `16px`, `20px` (e.g. `"Roboto-Italic-16"`)
`"RobotoMono-Regular"`	Code / Monospace	`13px`, `16px`, `20px` (e.g. `"RobotoMono-Regular-16"`)
`"ProggyClean"`	Bitmap Monospace	`13px` fixed (Classic ImGui embedded font)
`"ProggyForever"`	Scalable Vector Monospace	Scalable default font
`"default"`	Active Default Font	Points to the primary default font

If you request a base name without a size (e.g. `imgui.PushFont("Roboto-Regular")` or `imgui.PushFont("RobotoMono-Regular")`), FlyWithLua automatically uses the primary size (`ImguiFontSize1`, default 13px).

2.2.1 Markdown Typography Font Wiring (`imgui.MD`)

When using the Markdown rendering engine (`imgui.MD`), FlyWithLua automatically connects text styles to the appropriate bundled TrueType fonts:

* **Headings (`#`, `##`, `###`):** Rendered with `Roboto-Medium` (scaled by heading level).
* **Body Text:** Rendered with `Roboto-Regular`.
* **Italic Text (*`italic`*):** Rendered with `Roboto-Italic`.
* **Inline Code (`code`) & Fenced Code Blocks (` ):** Rendered with `RobotoMono-Regular`. If `RobotoMono-Regular` is not present, it gracefully falls back to `ProggyForever`.

2.3 Dynamic Point-Size Rescaling at Runtime

You are not limited to pre-baked sizes. You can pass a point size as an optional second argument:

```
-- Dynamically scale Roboto-Regular to 26px:
imgui.PushFont("Roboto-Regular", 26)
imgui.TextUnformatted("26px Dynamic Heading")
imgui.PopFont()
```

2.4 Adding Your Own Fonts

You have two simple ways to add custom fonts:

Method A: Zero-Config Folder Drop-In (Simplest)

1. Copy any TrueType (`.ttf`) or OpenType (`.otf`) file into:

```
Resources/plugins/FlyWithLua/Custom_Fonts/
```

2. FlyWithLua automatically discovers the file, builds it into the font atlas at the 3 standard sizes (`13`, `16`, `20`), and registers it under its filename stem.
3. For example, dropping `Ubuntu-Bold.ttf` into the folder makes all of these immediately available:

* `"Ubuntu-Bold-13"`
* `"Ubuntu-Bold-16"`
* `"Ubuntu-Bold-20"`
* `"Ubuntu-Bold"` (primary size)
* Or dynamic scaling: `imgui.PushFont("Ubuntu-Bold", 32)`

Method B: Custom INI Aliases & Custom Sizes

You can define semantic font nicknames and custom pixel sizes in `Resources/plugins/FlyWithLua/fwl_prefs.ini`:

```
; ------------------------------------------------------------------------
; Custom Named Font Definitions
; Format: Font.<AliasName> = <FontFileName.ttf>, <SizeInPixels>
; ------------------------------------------------------------------------
Font.HUD        = DSEG7Classic-Regular.ttf, 28
Font.Title      = Roboto-Medium.ttf, 24
Font.TinyLabel  = Roboto-Light.ttf, 11
```

In your script, simply call:

```
imgui.PushFont("HUD")
imgui.TextUnformatted("124.850")
imgui.PopFont()

imgui.PushFont("Title")
imgui.TextUnformatted("Navigation Display")
imgui.PopFont()
```

2.5 Querying Available Fonts in Lua

Scripts can dynamically discover all registered font names at runtime using `imgui.get_font_list()`:

```
local fonts = imgui.get_font_list()
for index, font_name in ipairs(fonts) do
    imgui.PushFont(font_name)
    imgui.TextUnformatted(string.format("%s: The quick brown fox", font_name))
    imgui.PopFont()
end
```

---

3. The Legacy Slot System (100% Backward Compatible)

FlyWithLua preserves complete compatibility with scripts written for William Good's original 9-slot integer font system.

3.1 Legacy Usage

```
imgui_push_font(1) -- Select font slot 1
imgui.TextUnformatted("Text in Slot 1")
imgui.PopFont()

imgui_push_font(5) -- Select font slot 5
imgui.TextUnformatted("Text in Slot 5")
imgui.PopFont()
```

3.2 Legacy Slot Mapping Table

By default, the 9 integer slots are pre-configured as follows:

Slot Number	Font File	Default Size	Description
1	`Roboto-Light.ttf`	13px	Font 1, Size 1
2	`Roboto-Light.ttf`	16px	Font 1, Size 2
3	`Roboto-Light.ttf`	20px	Font 1, Size 3
4	`Roboto-Regular.ttf`	13px	Font 2, Size 1
5	`Roboto-Regular.ttf`	16px	Font 2, Size 2
6	`Roboto-Regular.ttf`	20px	Font 2, Size 3
7	`Roboto-Medium.ttf`	13px	Font 3, Size 1
8	`Roboto-Medium.ttf`	16px	Font 3, Size 2
9	`Roboto-Medium.ttf`	20px	Font 3, Size 3

3.3 Legacy INI Configuration (`fwl_prefs.ini`)

To alter the sizes or files assigned to slots 1–9, configure these keys in `fwl_prefs.ini`:

```
; Font sizes for slots (1, 4, 7), (2, 5, 8), and (3, 6, 9)
ImguiFontSize1 = 13
ImguiFontSize2 = 16
ImguiFontSize3 = 20

; Set to 1 to replace Roboto with custom fonts for slots 1-9
UseCustomFonts = 0

ImguiCustomFont1 = Roboto-Light.ttf   ; Used for slots 1, 2, 3
ImguiCustomFont2 = Roboto-Regular.ttf ; Used for slots 4, 5, 6
ImguiCustomFont3 = Roboto-Medium.ttf  ; Used for slots 7, 8, 9
```

> **TIP**
> Even if `UseCustomFonts = 1` is enabled to customize slots 1–9, FlyWithLua automatically keeps the standard bundled Roboto fonts loaded and accessible by name (`"Roboto-Regular-16"`, etc.) so that other community scripts never break!

---

4. Stack Safety & Crash Protection

In raw Dear ImGui, mismatched font calls can crash X-Plane. FlyWithLua incorporates rigorous safeguards:

4.1 Missing Font Fallback & Automatic Rescaling

If a script requests a font name or slot index that doesn't exist:

1. FlyWithLua extracts the requested size (e.g. from `"MissingFont-24"` or `imgui.PushFont("Ghost", 24)`).
2. It logs a friendly developer warning to `Log.txt`:

```
FlyWithLua Warning: imgui.PushFont: Font 'MissingFont-24' not found, falling back to default font @ 24px.
```

3. It **pushes the default font rescaled to the requested point size**.
4. **Why this matters:** Because a font was pushed, the script's subsequent `imgui.PopFont()` call succeeds without a stack underflow assertion, and your UI layout preserves its intended proportions.

4.2 Empty Stack Guard (`PopFont`)

If a script mistakenly calls `imgui.PopFont()` more times than `PushFont()`:

* Raw ImGui triggers an unrecoverable assertion (`IM_ASSERT(g.FontStack.Size > 0)`).
* FlyWithLua verifies `ctx->FontStack.Size > 0` before popping. If empty, it logs a warning and returns cleanly, completely preventing simulator crashes.

---

5. Live Mid-Flight Font Reloading

You **do not need to restart X-Plane** or reload all simulator plugins when adding fonts or modifying configurations!

Why a Reload is Needed (The Shared Font Atlas)

Dear ImGui renders text using a single, unified GPU texture known as the **Font Atlas**. In FlyWithLua, all floating windows share this single font atlas so that memory usage remains minimal and rendering stays ultra-fast. Because all available fonts and sizes are compiled into this shared atlas when FlyWithLua initializes, any time you drop a new font into `Custom_Fonts/` or change font sizes or aliases in `fwl_prefs.ini`, FlyWithLua needs to rebuild that shared atlas so your scripts can immediately use the new glyphs.

Step 1: Add or Configure Fonts
Drop a new .ttf or .otf font into Custom_Fonts/, or define custom aliases in fwl_prefs.ini.

↓

Step 2: Trigger Script Reload
In X-Plane, click **Plugins** → **FlyWithLua** → **'Reload all Lua script files'**.

↓

Step 3: Shared Font Atlas Rebuild
FlyWithLua re-scans font folders and compiles all active fonts into the single shared ImGui font atlas.

↓

Step 4: Live Script Refresh
Your Lua scripts re-evaluate mid-flight and floating windows re-open with newly loaded fonts rendered cleanly!

The 4-Step Font Workflow

1. **Add Your Font File:**

Copy any TrueType (`.ttf`) or OpenType (`.otf`) file into:

```
Resources/plugins/FlyWithLua/Custom_Fonts/
```

2. **(Optional) Configure Aliases or Custom Sizes:**

If you want a custom pixel size or a shorthand alias name, open `Resources/plugins/FlyWithLua/fwl_prefs.ini` and add your entry (e.g. `Font.HUD = MyFont.ttf, 28`). If you skip this, FlyWithLua automatically registers the font at standard sizes (`13`, `16`, `20`) using its filename stem.

3. **Trigger the Live Reload:**

In X-Plane's top menu bar, simply select:

Plugins → FlyWithLua → Reload all Lua script files

4. **Immediate Mid-Flight Refresh:**

Within a single simulator frame, FlyWithLua closes any open floating windows, re-scans your font folders, rebuilds the shared font atlas, and re-executes your scripts. Your windows re-open with your new fonts immediately active!

TIP
Scripting Tip for Smooth Reloads: Because reloading scripts closes and re-opens floating windows, having your script remember its open state or position ensures a seamless live-editing workflow while tweaking fonts mid-flight!

---

6. Complete Demo Script

A complete, working reference script is included in your FlyWithLua installation at:

[`Resources/plugins/FlyWithLua/Scripts (disabled)/imgui_named_fonts_demo.lua`](file:///Users/brat/Documents/FlyWithLua-pg-test/FlyWithLua/Scripts%20(disabled)/imgui_named_fonts_demo.lua)

Copy it to your `Scripts/` folder to explore all the features in real time!