

IWORLDINSTANCE INTERFACE

The `IWorldInstance` interface represents an instance of a "world" type plugin in Construct. It derives from `IObjectInstance`.

Methods

`GetLayer()`

Return the `ILayer` this instance belongs to.

`GetLayout()`

Return the `ILayout` this instance belongs to.

`GetBoundingBox()`

Returns an `SDK.Rect` representing the bounding box of the instance in the layout.

`GetQuad()`

Returns an `SDK.Quad` representing the bounding quad of the instance in the layout.

`GetColor()`

Returns an `SDK.Color` representing the premultiplied color of the instance. This combines the instance's color tint with its opacity in the alpha channel.

`SetOpacity(o)`

`GetOpacity()`

Set or get the alpha component of the instance's color, representing its opacity, in the 0-1 range.

SetX(x)

SetY(y)

SetXY(x, y)

GetX()

GetY()

GetXY()

Set and get the X and Y co-ordinates of this instance.

SetZ(z)

GetZ()

Set and get the Z position of this instance. Note this is relative to the Z elevation of the layer the instance is on.

SetXYZ(x, y, z)

GetXYZ()

Set and get the X, Y and Z co-ordinates of this instance.

GetTotalZ()

Get the total Z elevation of this instance, which is its own Z position added to the Z elevation of the layer it is on.

SetAngle(a)

GetAngle()

Set and get the angle of the instance, in radians.

SetWidth(w)

SetHeight(h)

SetSize(w, h)

GetWidth()

GetHeight()

Set and get the size of the instance, in pixels.

SetDepth(d)

GetDepth()

Set and get the depth (size on the Z axis) of the instance, in pixels. Note this is only applicable for 3D objects (2D objects have a depth of zero).

`SetOriginX(x)`
`SetOriginY(y)`
`SetOrigin(x, y)`
`GetOriginX()`
`GetOriginY()`

Set and get the current origin of the instance in the layout. Note this is normalized to a [0, 1] range, e.g. 0.5 is the middle.

`ApplyBlendMode(iRenderer)`

Sets the current blend mode of the given [IWebGLRenderer](#) according to the *Blend mode* property of the instance in Construct. This is only relevant if the plugin specifies that it supports effects. Use this in the `Draw()` method to set the correct blend mode.

`SetSampling(sampling)`

`GetSampling()`

Set or get a string of the instance's sampling mode, which is one of `"auto"`, `"nearest"`, `"bilinear"` or `"trilinear"`.

`GetActiveSampling()`

Get a string of the instance's active sampling mode. This is only different to `GetSampling()` when the sampling mode is `"auto"`: in this case the active sampling mode is inherited from the project, layout, layer, or hierarchy. This is the sampling mode with which this instance will be rendered.

You are here:

Search this manual:

[Community Help](#)

[Contact Us](#)

This manual entry was last updated on 12 Mar, 2026 at 10:55

