

TILEMAP SCRIPT INTERFACE

The `ITilemapInstance` interface derives from `IWorldInstance` to add APIs specific to the `Tilemap` plugin.

Tile numbers

Tiles in the tilemap are represented as a single 32-bit integer number and can be rotated and flipped. To support this they consist of two parts using a bitmask:

- The tile ID in the lower 29 bits - this is the number of the tile as shown in the Tilemap Bar when hovering the tile
- Tile flags in the upper 3 bits

There is also a special tile number `-1` indicating an empty tile.

Tile flags

The Tilemap script interface exposes the following flags and masks which can be used to manipulate tile numbers:

```
1 | ITilemapInstance.TILE_FLIPPED_HORIZONTAL = -0x80000000;  
2 | ITilemapInstance.TILE_FLIPPED_VERTICAL = 0x40000000;  
3 | ITilemapInstance.TILE_FLIPPED_DIAGONAL = 0x20000000;  
4 | ITilemapInstance.TILE_FLAGS_MASK = 0xE0000000;  
5 | ITilemapInstance.TILE_ID_MASK = 0x1FFFFFFF;
```

For example, to flip tile ID 2 horizontally, you would use bitwise OR combining the tile ID and the flag, e.g. `2 |`

`ITilemapInstance.TILE_FLIPPED_HORIZONTAL`. Similarly you can test if the bit is set using `tile & ITilemapInstance.TILE_FLIPPED_HORIZONTAL`.

You can also use the masks to extract each component of the tile number. For example `tile & ITilemapInstance.TILE_ID_MASK` will return just the tile ID, since it removes all the flag bits.

 Be sure to first check if the tile is the special value `-1` indicating an empty tile. This is a special value that doesn't use the bit representation so won't work when combined with flags or masks.

Tilemap APIs

`mapWidth`

`mapHeight`

`getMapSize()`

Read-only numbers representing the size of the tilemap in tiles. The method allows getting both values at the same time.

`mapDisplayWidth`

`mapDisplayHeight`

`getMapDisplaySize()`

Read-only numbers with the displayed size of the tilemap, in tiles. The method allows getting both values at the same time.

 This can differ from `mapWidth` and `mapHeight` if the Tilemap is resized smaller at runtime - in that case the display size will be smaller, but the map size will stay the same.

`tileWidth`

`tileHeight`

`getTileSize()`

Read-only numbers with the size of a tile in pixels. The method allows getting both values at the same time.

`getTileAt(x, y)`

Get the tile at a given position in tiles (i.e. (0, 0) is the top-left tile of the tilemap, regardless of the tilemap's position or the tile size). Returns `-1`

for empty tiles or tiles outside the tilemap; otherwise use bit operations to determine tile ID or flags separately.

setTileAt(x, y, tile)

Set the tile at a given position in tiles. Use -1 to set a tile empty; otherwise use bit operations to combine the tile ID and flags.

async replaceImage(blob)

Replace the current tilemap image with the contents of a **Blob** representing an image file such as a PNG image. The blob can be locally generated or retrieved from a URL, for example:

```
1 // Loading an image from a URL
2 const response = await fetch(url);
3 const blob = await response.blob();
4 await tmInst.replaceImage(blob);
```

You are here:

Search this manual:

[Community Help](#)

[Contact Us](#)

This manual entry was last updated on 13 Jul, 2023 at 13:48