

Lab 2 - Correction Key

Making sure NAT overload works for Outside net

- add the following line on asa
- `same-security-traffic permit inter-interface`

Outside to DMZ with UDP

- Create the following ACL:
- ```
access-list OUTSIDE extended permit udp 172.16.1.0 255.255.255.0 10.0.0.0 255.255.255.0
access-list OUTSIDE extended deny icmp 172.16.1.0 255.255.255.0 192.168.1.0 255.255.255.0
access-list OUTSIDE extended deny icmp 172.16.1.0 255.255.255.0 10.0.0.0 255.255.255.0
access-list OUTSIDE extended permit icmp 172.16.1.0 255.255.255.0 any
```

- Apply it to the outside interface
- `access-group OUTSIDE in interface outside`

### Inside to DMZ with TCP

- add modify the ACL to have the following lines
- ```
access-list INSIDE extended deny udp 192.168.1.0 255.255.255.0 10.0.0.0 255.255.255.0
access-list INSIDE extended deny icmp 192.168.1.0 255.255.255.0 10.0.0.0 255.255.255.0
access-list INSIDE extended permit tcp 192.168.1.0 255.255.255.0 10.0.0.0 255.255.255.0
access-list INSIDE extended permit icmp 192.168.1.0 255.255.255.0 any
```

- Make sure the ACL is applied to the inside interface

DMZ

- to allow these devices access to Outside and Internet we need to fix the OSPF neighbour adjacency with the ASA

- on DMZ-R's g0/0 interface change the hello-interval and dead-interval back to their default values
- currently they are modified to 11 and 400 respectively

HSRP

- On router 1 enable preempt in the standby process
- on R2 remove the standby 10 process and configure it correctly

- ```
standby 1 ip 192.168.1.15
standby 1 preempt
standby 1 priority 50
```