```
1. VirtualBox Network Setting
 2
      1)VirtualBox 환경설정 > 네트워크
 3
      2)새 NAT 네트워크 생성 > 네트워크 편집
 4
         -네트워크 이름: DockerNetwork
 5
         -네트워크 CIDR: 10.0.2.0/24
         -네트워크 옵션: DHCP 지원만 체크
 6
 7
         -포트 포워딩
 8
           --IPv4
 9
           --이름: docker-ubuntu
           --호스트 IP: 127.0.0.1
10
11
           --호스트 포트: 105
           --게스트 IP: 10.0.2.105
12
13
           --게스트 포트 : 22
14
15
16 2. Ubuntu Server Setting
17
      1)이름: docker-ubuntu
18
      2)종류: Linux
19
      3)버전: Ubuntu (64-bit)
20
      4) Memory: 2048 MB
21
      5)하드 디스크: 지금 새 가상 하드 디스크 만들기
22
      6)하드 디스크 파일 종류: VDI
23
      7)물리적 하드 드라이브에 저장 : 동적 할당
24
      8)파일 위치 및 크기: 50GB
      9)만들기 > 설정
25
26
      10)시스템 : 플로피 체크 해제, 프로세서 : 2
27
      11)저장소: 컨트롤러(IDE) -> 다운로드 받은 iso(ubuntu-20.04.2-live-server-amd64.iso)
28
29
    3. Ubuntu Sever Installation
30
      1)Language: English
31
32
      2)Keyboard configuration: Done
33
      3) Network connections: Done
34
      4)Configure proxy: Done
35
      5)Configure Ubuntu archive mirror: Done
36
      6) Guided storage configuration: Done
37
      7)Storage configuration: Done
38
      8) Confirm destructive action: Are you sure you want to continue? Continue
      9)Profile setup
39
40
         -Your name:
41
         -Your server's name: ubuntu-server
42
         -Pick a username : docker-ubuntu
43
         -Choose a password:
44
         -Confirm your password :
45
      10)SSH Setup: No Check, Done
46
      11)Featured Server Snaps: No Check, Done
47
      12)설치마치면 Reboot Now
48
49
50
    4. Post-Intallation Setting
51
      1)Network Manager Installation
52
         -$ sudo apt update
53
         -$ sudo apt install network-manager
54
         -$ sudo systemctl status network-manager
55
56
      2) View Current IP Address
57
         -$ ip a or $ ip addr
58
59
      3)Set Static IP Address
         -Oracle VM VirtualBox 관리자창에서
60
61
         -docker-ubuntu의 설정 > 네트워크 > 다음에 연결됨 : NAT 네트워크 | DockerNetwork로 변경 > 확인
62
63
         -$ ls /etc/netplan
64
           00-installer-config.yaml
65
66
         -$ sudo cp /etc/netplan/00-installer-config.yaml /etc/netplan/00-installer-config.yaml.bak
         -$ sudo nano /etc/netplan/00-installer-config.yaml
67
```

```
69
             [before]
 70
             network:
 71
                ethernets:
 72
                  enp0s3:
 73
                     dhcp4: true
 74
                version: 2
 75
 76
             [after]
 77
             network:
 78
                renderer: NetworkManager
 79
                ethernets:
 80
                  enp0s3:
 81
                     dhcp4: no
 82
                     addresses:
 83
                     - 10.0.2.105/24
 84
                     gateway4: 10.0.2.1
 85
                     nameservers:
 86
                        addresses: [8.8.8.8, 8.8.4.4]
 87
                version: 2
 88
 89
          -Save
 90
          -Test the new configuration
 91
             $ sudo netplan try
 92
 93
          -Run the new configurations.
 94
             $ sudo netplan apply
 95
 96
          -$ ip addr
 97
          -$ ping -c 4 8.8.8.8
 98
          -$ sudo apt update
 99
100
        4) View Current Hostname
101
          $ hostnamectl
102
103
        5)Change Hostname
104
          $ sudo nano /etc/hostname
105
             ubuntu-server.example.com
106
107
          $ sudo nano /etc/hosts
108
             127.0.0.1 localhost
109
             10.0.2.105 ubuntu-server.example.com
110
111
          $ ping -c 4 ubuntu-server.example.com
112
113
        6)SSH Server Installation
114
           $ sudo apt install openssh-server curl tree
115
116
          $ systemctl status sshd
117
118
          $ export HOST=ubuntu-server
119
120
          $ ssh $USER@$HOST
121
             - Are you sure you want to continue connecting (yes/no/[fingerprint])? yes
122
             - 확인 후 exit
123
124
        7)root 계정 비밀번호 설정(옵션)
125
           $ sudo passwd root
126
          [sudo] password for {{현재 로그인 계정}}:
127
          New password:
128
          Retype new password:
129
          passwd: passsword updated successfully
130
131
          -root 계정으로 전환
132
           $ su -
133
          Password:
134
          root@docker-ubuntu:~#
```

68

```
136
137
     5. Windows Host OS에서 Ubuntu Guest OS 연결하기
138
       1)PuTTY
139
          -Window > Appearance
140
            --Font settings : Courier New, 16-point
141
142
          -Window > Colours
143
            -- Default Foreground: 0, 0, 0
144
            --Default Background : 255, 255 ,255
145
146
          -Session
147
            --Host Name(or IP address): 127.0.0.1
148
            --Port: 105
            --Connection type : SSH
149
150
            --Saved Sessions : docker-ubuntu
151
152
            --Save
153
154
          -Open > 인증서에서 [예(Y)] Click
155
156
       2)XShell
157
          -파일메뉴 > 새로 만들기
158
            --연결
159
               이름: docker-ubuntu
160
               프로토콜 : SSH
161
               호스트: 127.0.0.1
162
               포트 번호 : 105
163
            --연결 > 사용자 인증
164
               사용자 이름: docker-ubuntu
165
               암호:
166
               방법: Password
167
            --확인
168
169
          -모든 세션 > docker-ubuntu double click
            -SSH 보안 경고 > 수락 및 저장
170
171
172
173
     6. Host OS에서 Guest OS 연결 후 작업
174
       1)IP Address 확인
175
          $ ip addr
176
177
       2)OS 확인하기
178
          $ cat /etc/os-release
179
            NAME="Ubuntu"
180
            VERSION="20.04.2 LTS (Focal Fossa)"
181
            ID=ubuntu
182
            ID_LIKE=debian
183
            PRETTY_NAME="Ubuntu 20.04.2 LTS"
            VERSION ID="20.04"
184
185
            HOME_URL="https://www.ubuntu.com/"
186
            SUPPORT_URL="https://help.ubuntu.com/"
187
            BUG_REPORT_URL="https://bugs.launchpad.net/ubuntu/"
            PRIVACY_POLICY_URL="https://www.ubuntu.com/legal/terms-and-policies/privacy-policy"
188
189
            VERSION_CODENAME=focal
190
            UBUNTU_CODENAME=focal
191
192
       3)Memory 확인
193
          $ free -h
194
195
       4)System Shutdown
196
          $ sudo shutdown now
197
198
199
     7. Ubuntu Virtual Machine에 Host-Only NIC 설치하기
200
       1)docker-ubuntu > 설정 > 네트워크
       2)어댑터2
201
```

135

```
202
       3)다음에 연결됨 : 호스트 전용 어댑터
203
       4)이름: VirtualBox Host-Only Ethernet Adapter
204
       5)확인 클릭
205
       6)Host OS에서 이더넷 어댑터 VirtualBox Host-Only Network 파악하기
206
          -Windows 10 > cmd > ipconfig /all
207
          -VirtualBox Host-Only Ethernet Adapter의 IPv4 확인하기
208
             --예)192.168.56.1
209
       7)docker-ubuntu Booting 후, enp0s8 Ip Address 확인하기
210
211
          -$ sudo nano /etc/netplan/00-installer-config.yaml
212
213
             network:
214
               renderer: NetworkManager
215
               ethernets:
216
                  enp0s3:
217
                    dhcp4: no
218
                    addresses:
                    - 10.0.2.105/24
219
220
                    gateway4: 10.0.2.1
221
                    nameservers:
222
                       addresses: [8.8.8.8, 8.8.4.4]
223
                  enp0s8:
                                        <--- 추가
224
                    dhcp4: true
                                        <---추가
225
               version: 2
226
227
          -Save
228
          -Test the new configuration
229
             $ sudo netplan try
230
231
          -Run the new configurations.
232
             $ sudo netplan apply
233
234
          -Restart network-manger service
235
             $ sudo systemctl restart network-manager
236
          - $ ip address
237
238
          - 예:192.168.56.101/24
```