SAS° ODS Layout Tip Sheet

Absolute Layout Example

```
options nocenter obs=5;
ods pdf file='absolute.pdf';
ods layout absolute
           x=0cm y=0cm
width=17cm height=23cm
    style={background=lightgray};
  ods region x=1cm y=1cm
             width=10cm height=10cm
      style={background=lightred};
    proc report data=sashelp.class
      column name age;
    run;
  ods region x=2cm v=2cm
             width=10cm height=10cm
      style={background=lightblue};
    proc report data=sashelp.cars
      nowd;
      column make model;
    run;
  ods region x=3cm v=3cm
             width=10cm height=10cm
      style={background=lightgreen};
    proc report data=sashelp.shoes
        nowd;
      column product sales;
    run;
ods layout end;
ods pdf close;
```

Gridded Layout Example

```
ods pdf file='gridded.pdf';
ods layout gridded
           columns=2 width=5in
           column gutter=.25in
    style={background=lightgray};
  ods region
      style={background=lightblue};
    proc means data=sashelp.class mean;
    run;
    proc report nowd
      data=sashelp.class(obs=5)
      nowd;
    run;
  ods region width=2in
      style={background=lightblue};
    proc print
      data=sashelp.class(obs=5
           keep=name age);
    run;
ods layout end;
ods pdf close;
```

The MEANS Procedure						Obs	Name	Age
	Variabl	e	Mean			1	Alfred	14
	Age		3.3157895			2	Alice	13
	Height Weight		2.3368421 0.0263158			3	Barbara	13
						4	Carol	14
Name	Sex	Age	Height	Weight		5	Henry	14
Alfred	М	14	69	112.5				
Alice	F	13	56.5	84				
Barbara	F	13	65.3	98				
Carol	F	14	62.8	102.5				
Henry	М	14	63.5	102.5				

SAS®

ODS Layout Tip Sheet

For complete information, refer to the Base SAS® documentation at

support.sas.com/base

information in one place, on one sheet of paper, so you don't have to search through the online documentation. It also gives you something to take home, type in, and try.

This tip sheet places frequently used

Creating custom reports that show your information in just the right way is now possible using ODS Layout. ODS Layout has two distinct forms, absolute and gridded. Each form is suited to different reporting tasks. The most important decision when using ODS Layout is selecting the type that best suits your report design. Absolute layout is valid for Printer destinations only. Gridded layout is valid for Printer, HTML, and SASReport.



SAS Institute Inc. +1 919 677 8000

sas.com/offices

World Headquarters

SAS and all other SAS Institute Inc. product or service names are registered trademarks or trademarks of SAS Institute Inc. in the USA and other countries. @ indicates USA registration. Other brand and product names are trademarks of their respective companies. Copyright © 2019, SAS Institute Inc. All rights reserved. 1901904.0319

SAS ODS Layout Tip Sheet

Common Layout Options and Values

The style= option and option values listed below are used by the layout and region options in this tip sheet.

dimension

indicates a positive integer or floating point value followed by one of the following units:

> **in** – inches cm – centimeters (2.54 cm = 1 inch) mm – millimeters (25.4 mm = 1 inch) % (pct) - percentage (percentage of container width or height for width= and height=) px - pixelspt – points (1/72 inch)

integer

indicates a positive integer.

style=style-element{style-attributes}

all layout and region statements accept the style= option. This statement allows you to specify a style element and style overrides.

(style= is pre-production in SAS 9.4)

Absolute Layout Syntax

ods layout absolute options;

x=dimension

specifies horizontal position of the layout, which extends to the right. If omitted, it defaults to 0.

v=dimension

specifies vertical position of the layout, which extends down. If omitted, it defaults to the current vertical position on the page.

Absolute Layout Syntax

(continued)

width=dimension

specifies horizontal width of the layout. If omitted, it defaults to the maximum horizontal space available on the page.

height=dimension

specifies vertical height of the layout. If omitted, it defaults to the maximum vertical space available on the page.

Absolute Layout Region Syntax

ods region options;

x=dimension

specifies horizontal position of the region within the layout, which extends to the right. If omitted, it defaults to 0.

v=dimension

specifies vertical position of the region within the layout, which extends down. If omitted, it defaults to 0.

width=dimension

specifies horizontal width of the region, and is restricted by the layout dimensions. If omitted, it defaults to the maximum horizontal space available in the layout container.

height=dimension

specifies vertical height of the region and is restricted by the layout dimensions. If omitted, it defaults to the maximum vertical space available in the layout container.

Gridded Layout Syntax

ods layout gridded options;

x=dimension

specifies horizontal position of the layout, which extends to the right of this position. If omitted, the layout container is centered on the page.

y=dimension

specifies vertical position of the layout, which extends down from this position. If omitted, it defaults to the current vertical position on the page.

width=dimension

specifies horizontal width of the layout. If omitted, it defaults to the maximum horizontal space needed to display all regions.

height=dimension

specifies vertical height of the layout. If omitted, it defaults to the maximum vertical space needed to display all regions.

columns=integer

specifies fixed number of columns in the gridded layout. If omitted, it defaults to 1.

column widths=(dimension-1 ... dimension-n) specifies width of each column.

column gutter=dimension

specifies space between each column.

rows=integer

specifies fixed number of rows in the layout. If omitted, the number of regions created in the vertical direction is used

row heights=(dimension-1 ... dimension-n) specifies height of each row.

Gridded Layout Syntax

(continued)

row gutter=dimension

specifies space between each row.

order type=row major | column major indicates which direction the grid is populated. Printer destination only.

advance=explicit | proc | table | bygroup specifies which output type advances to the next region.

Gridded Layout Region Syntax

ods region options;

width=dimension

specifies horizontal width of the region and is restricted by the layout dimensions.

height=dimension

specifies vertical height of the region and is restricted by the layout dimensions.

column=integer

specifies the current column position in the gridded layout.

column span=integer

specifies the number of columns that the region will occupy. The default value is 1.

row=integer

specifies the current row position in the gridded layout.

row span=integer

specifies the number of rows that the region will occupy. The default value is 1.