AIR GENERAL SETUP INSTRUCTIONS

AIR

Setup for a debian server running AIR platform.

AIR packages

AIR packages and configuration files will be located under `/var/air`.

Required packages

- `apt install htop` (optional)
- `apt install jackd2` `apt install ffmpeg`
- `apt install puredata`
- * `apt install icecast2`

Also install PD extra libraries:

apt install pd-3dp pd-ableton-link pd-ambix pd-arraysize pd-autopreset pdbassemu pd-beatpipe pd-boids pd-bsaylor pd-chaos pd-cmos pd-comport pd-creb pdcsound pd-cxc pd-cyclone pd-deken pd-deken-apt pd-earplug pd-ekext pd-ext13 pdextendedview pd-fftease pd-flext-dev pd-flext-doc pd-flite pd-freeverb pd-ggee pd-gil pd-hcs pd-hexloader pd-hid pd-iem pd-iemambi pd-iemguts pd-iemlib pdiemmatrix pd-iemnet pd-iemutils pd-jmmmp pd-jsusfx pd-kollabs pd-lib-builder pdlibdir pd-list-abs pd-log pd-lua pd-lyonpotpourri pd-mapping pd-markex pd-maxlib pd-mediasettings pd-mjlib pd-moonlib pd-motex pd-mrpeach pd-mrpeach-net pdnusmuk pd-osc pd-pan pd-pddp pd-pdogg pd-pdp pd-pdstring pd-pduino pd-plugin pdpmpd pd-pool pd-puremapping pd-purepd pd-purest-json pd-readanysf pd-rtclib pdscaf pd-sigpack pd-slip pd-smlib pd-syslog pd-tclpd pd-testtools pd-unauthorized pd-upp pd-vbap pd-wiimote pd-windowing pd-xbee pd-xsample pd-zexy

Configure Puredata

Configure Puredata paths under `File -> Preferences -> Path`:

Add paths:

- `/lib/puredata/extra`
- `/usr/lib/pd/extra`
- `/var/air/air-mixer`

Icecast

air user

Create air user: `useradd air`

```
### Add realtime permission
Edit `/etc/security/limits.conf` and add:
air - rtprio 100
air - nice -10
air - memlock unlimited
## Configure realtime permissions and limits for jack_recorder service
... by adding the following under the `[Service]` section:
LimitNICE=-10
LimitMEMLOCK=500000000
LimitRTPRIO=100
## VNC Server
Install XFCE: `apt install task-xfce-desktop`
Configure VNC server: https://www.digitalocean.com/community/tutorials/how-to-
install-and-configure-vnc-on-debian-11
N.B.: Configure the VNC server under `air` user.
Start the VNC server with `vncserver`
Kill the VNC server with `vn`
VNC server is not accessible directly via the internet. To access it, create a
`ssh` tunnel by running:
    ssh -L 5901:localhost:5901 root@air.ijs.si
and then pointing your VNC client to `localhost:5901`
## Ensure that jackd runs automatically
### jackd.service
Create `jackd.service` file in `/var/air/systemd`
. . .
[Unit]
Description=JACK audio connection kit
After=multi-user.target
[Service]
ExecStart=/usr/bin/jackd -ddummy
Type=simple
Restart=always
User=air
[Install]
WantedBy=multi-user.target
### Starting the service

    Symlink `/var/air/systemd/jackd.service` to `/usr/lib/systemd/system/`:
```

```
- `ln -s /var/air/systemd/jackd.service`
2. Start the service: `systemctl start jackd`
## AIR Core Mixer & Blender files
Copy AIR Core Mixer files (PD, etc) to `/var/air`
## Install .NET
Add package registry:
wget https://packages.microsoft.com/config/debian/12/packages-microsoft-prod.deb
-O packages-microsoft-prod.deb
sudo dpkg -i packages-microsoft-prod.deb
rm packages-microsoft-prod.deb
Install the SDK:
sudo apt-get update && \
  sudo apt-get install -y dotnet-sdk-7.0 dotnet-runtime-6.0 aspnetcore-runtime-
6.0
## Stream JACK to Icecast
ffmpeg -f jack -i ffmpeg -ar 48000 \
-content_type audio/mpeg
icecast://source:ZNxVwf5ElrTB3knRLH@127.0.0.1:8080/air.mp3
To test, you can:
1. Run `jack_metro -b 120` as user `air`
2. Connect the metro output to ffmpeg input: `jack_connect metro:120_bpm
ffmpeg:input_1` and `jack_connect metro:120_bpm ffmpeg:input_2`
Enjoy beeping sound at `http://air.ijs.si:8080/air.mp3`
## Caddy server
Used for reverse proxy tasks and serving recording files to the users of the
AirRecorder web app
1. Install caddy with `apt install caddy`
2. Remove `/etc/Caddyfile` and symlink caddyfile from `/var/air/caddy/Caddyfile`
## jack_recorder_server
The server that records jack inputs when instructed to do so.

    Symlink `/var/air/systemd/jackrecorder.service` to

`/usr/lib/systemd/system/`:
    - `cd /usr/lib/systemd/system/`
    - `ln -s /var/air/systemd/jackrecorder.service`
2. Start the service: `systemctl start jackrecorder`
## AirRecorder
```

- `cd /usr/lib/svstemd/svstem/`

A web interface for JACK recorder

- 1. Symlink `/var/air/systemd/airrecorder.service` to `/usr/lib/systemd/system/`:

 - cd /usr/lib/systemd/system/`ln -s /var/air/systemd/airrecorder.service`
- 2. Start the service: `systemctl start airrecorder`

Jacktrip

Jacktrip is used for producting audio in different locations connected via internet.

- Install jacktrip: `apt install jacktrip`
- 1. Symlink `/var/air/systemd/jacktrip.service` to `/usr/lib/systemd/system/`:

 - `cd /usr/lib/systemd/system/`
 `ln -s /var/air/systemd/jacktrip.service`
- 2. Start the service: `systemctl start jacktrip`