

LVM

1. Instalação

1.1. Pacote "lvm2" #apt-get install lvm2

2. Arquitetura

- 2.1. (PV)-Volume Físico (Phisical Volume)
 - 2.1.1. #pvcreate <particao> .Ex:: #pvcreate /dev/sdb1 #pvcreate /dev/sdc1
 - 2.1.2. #pvs ou pvdisplay
- 2.2. (VG) Grupo Volume (Volume Group)
 - 2.2.1. #vgcreate <vg-nome> <dispositivo>. Ex:: #vgcreate vg-group /dev/sdb1 #vgextend vg-group /dev/sdc1
 - 2.2.2. #vgs ou vgdisplay
- 2.3. (LV)-Volume Lógico (Logical Volume)
 - 2.3.1. #lvcreate -n <nome> -L <tamanho> <volume group>. Ex:: #lvcreate -n lv home -L 1G vg-group #lvcreate -n lv data -L 2G vg-group
 - 2.3.2. #lvs ou lvdisplay
 - 2.3.3. Formatar o volume lógico. Ex:: #mkfs.ext4 /dev/vg-group/lv home #mkfs.xfs /dev/vg-group/lv data

3. Manipulação

- 3.1. Montar partição
 - 3.1.1. #mount <dispositivo> <ponto montagem>. Ex:: #mkdir lv_home #mount /dev/vg-group/lv_home /lv_home
- 3.2. Aumentar LV
 - 3.2.1. #Ivextend -L <tamanho> <LV>. Ex:: #Ivextend -L +500M /dev/vg-group/lv home #resize2fs /dev/vg-group/lv home
- 3.3. Aumentar VG
 - 3.3.1. #vgextend <nome volume> <particao>. Ex:: #vgextend vg-group /dev/sdb2 #vgdisplay
- 3.4. Visualizar Estrutura