

Bank Interface - RBSLynkISO EMV Contact, Quickchip and Contactless

The RBSLynkISO bank interface is an integrated solution and is made to communicate with the RBSLynkISO server through the RBSLynkISO switch using Internet IP. A driver, named ApiRBSLynkISO.dll, needs to be installed and a configuration file created at each LOC SMS POS in order to get LOC SMS to work with the RBSLynkISO bank interface.

It is mandatory to always install the Bank and the pinpad option from the same version to work properly.

WARNING: Before upgrading and existing installation to V360 it is important to be aware of the changes that had been done in Version V360.

For more details click on link:

- [Bank Options changes with V360](#)
- [FSA/NACS code section](#)

IMPORTANT

In order to use SMS 3.6.0, you **MUST** be prepared to configure your store as EMV. The base options are all EMV versions. There is **no non-EMV** version in 3.6.0.

The **Bank_RbsLynkISO** option includes the driver, the configuration file, all functions and scripts.

Software key programming

To be able to work with the Bank_RBSLynkISO option, these modules must be programmed on the software key:

- Banks module **Security RBSLynkISO (121)** is required for the EFT and EBT transactions;
- Gifts module **Gift card RBSLynkISO (151)** is required for the gift card transactions;
- Gifts module **Gift card Blackhawk (151)** is required for the Blackhawk gift card transactions;
- Contactless module **Module RFID Contactless Interface (113)** is required for RFID transactions. (see the [Bank_RbsLynkISO Contactless](#) for more details)
- Others module **eWIC RBSLynkISO interface (196)** for the eWIC transactions.

Note that fees are related to these modules.

End-to-End Encryption (VSP)

If there is a need to setup for VSP encryption, the following docs should be consulted **in addition** to this document:

[RBSLynkISO \(EMV\) - VSP End to End Encryption](#) - This is hardware encryption. The LOC forms do not change for TAVE, just the pinpad programming from Verifone.

End-to-End Encryption (E2EE) Overview: [US Pinpad End to End Encryption](#);

Step by Step Install

- [Steps before installing RBSLynkISO EMV](#)
- [RBSLynkISO Communication](#)

- [Installation of RBSLynkISO Option](#)
- **[Specific Bank RBSLynkISO functions in V360](#)**
- [Installation of 2 banks](#)
- [Pinpad option Installation](#)
- [Bank Configuration](#)
- [Configuration of the Merchant ID and the Terminal ID's](#)
- [BIN Download](#)
- [FSA/NACS codes](#)
- [Troubleshooting](#)

Supported Transaction Types

Here is the list of the supported transactions with the RBSLynkISO bank:

- Debit (Chip and Swipe, no manual entry);
- Credit (Chip and Swipe);
- EBT Food Stamps and EBT Cash;
- eWIC
- Fleet cards (including Wright Express, Voyager, Visa Fleet, Master Card Fleet, Fuel Lynk, Fleet One, Fuelman).
- [Check processing with Certegy \(Check verification, Check guarantee and Electronic Check Conversion \(ECA\)\)](#);
- [Gift cards: RBSLynkISO own gift cards](#);
- [Blackhawk Activation gift cards](#);
- [FSA](#);
- [eWIC Cards \(for certain states\)](#)

Features of RBSLynkISO

- [Fallback Allowance/Restriction](#);
- [No Signature under a certain amount EMV](#);
- [No signature under a certain amount Non EMV](#);
- [No bank receipt on specific tenders](#);
- [No bank receipt printed](#);
- [No bank receipt on Gift Card Activation and Recharge](#)
- [No Suspend/Backup on Gift Card Activation and Recharge](#)
- [Force printing of EBT and Gift card receipt on Balance Inquiry](#);
- [No prompt for the expiration date on EBT manual entry](#);
- [Disable the partial approval](#);
- [Swipe card restrictions](#);
- [SAF EMV \(Store and Forward\)](#);
- [End-to-End Encryption \(VSP\)](#);

- [Close batch with RBSLynkISO](#);

Steps before installing RBSLynkISO EMV

1. Set up the RBSLynkISO EMV account with WorldPay. Worldpay provides terminal IDs which are 8-digit length (leading zeros need to be added if less than 8-digits). This step requires some lead time, make appropriate arrangements before installing.
2. Get the RBSLynkISO server address for the TCP/IP.
3. Ensure that the SMS system is updated to the desired release version (SMS 3.6.0)
4. Ensure the chosen pinpad is EMV capable and is certified with SMS (See the document **US Supported Pinpads** grid on the LOC Portal - Home page - right hand column - scroll down.).
5. Order the pinpad(s) to be injected with the proper key (Validate the production key needed with your RBSLynkISO representative)
6. Ensure that Pinpad(s) are loaded with the correct packages (Forms, OS, etc) (See the document **US Supported Pinpads** grid on the LOC Portal - Home page - right hand column - scroll down.).
7. If the store is to use online eWIC via Worldpay, the **XChange_FTP** and **XChange_File** options should be installed on the backoffice server ONLY prior to installing the Bank_RBSLynkISO option.

WorldPay Profile Setup

Contact WorldPay and inform them that EMV is to be run in the store and that IDs are required for the desired terminals to be upgraded/installed.

This step will require some lead time with WorldPay. Do not proceed with the next step until the necessary IDs have been received from WorldPay.

RBSLynkISO Communications

From version 3.4.0.3, SSL communications are done using standard TLS 1.2 protocols for encryption. According to PCI Compliance 3.1, all bank communications must be done through TLS protocols (Ver. 1.0, Ver. 1.1, Ver 1.2), and must never fall back to SSL under any situation.
From release Version of V3.4.0.2, TLS 1.2 communication was added to the RBSLynkISO bank driver and visible through the bank log.

Install Bank_RBSLynkISO

Note for eWIC


If the store is to use online eWIC via RBSLynkISO, the **XChange_FTP** and **XChange_File** options **MUST be installed** on the backoffice server ONLY, prior to install the Bank_RBSLynkISO option.

The **Bank_RBSLynkISO** option must be installed:


- On all front-end workstations
- On the backoffice server, so that backups of the bank functions can be kept, if needed as this ensures that the Host has an updated list of totalizers and tenders and can run bank reports properly. However, **DO NOT** enable the bank driver on the backoffice server).

To install the Bank_RBSLynkISO option, follow the steps below:

1. From the **Launchpad** application, under the **Options** tab of the **Company setup** window, install the Bank_RBSLynkISO option as options are normally installed.
2. If WorldpayISO is the main bank that will process Debit and Credit transactions, PAYMENT1 must be selected




3. During the installation process, a prompt appears asking for the fleet cards selection. If the installation is for a gas site, select the proper fleet card setting required or select *No fleet card* and then click **GO**.



4. A prompt also appears for the installation of the eWIC module.

Note: the **XChange_FTP** and **XChange_File** options **MUST be installed** on the backoffice server ONLY, prior to install the Bank_RBSLynkISO option.

If the store accepts WIC cards, select Yes, otherwise select No and then click **GO**.



5. One of the important steps during the installation of the bank option, is to properly configure, by default, each EFT tenders function with its appropriate Cardtype=.

Critical Note:

It is **Mandatory** when upgrading a bank option or installing a Sample, to always verify that all your bank functions are configured with a Cardtype=.

When there are no card types configured in a bank tender function, SMS approves the transaction like an offline transaction and this information is never transmitted to the bank.

Failure to properly configure the bank functions means that the store stands to lose substantial revenues.

Verifying the EMV installation

To verify that the EMV portion was installed correctly, check for a file called \Storeman\xchdev\EMVAIDFct.ini. This is similar to the SETTING.INI, but for EMV. This file should NOT be modified as it is supplied by LOC and is required for EMV to work correctly.

Specific Bank RBSLynkISO functions in V360

A new specific range of functions is added to Option RBSLynkISO in V360.

Here is the list of the functions with their parameters:

Fct name	Fct number	Alpha parameters
RBSLynkISO	FCT 5780	=RBSLynkISO (section in function table)
EBT balance Info	FCT 5781	MSR=1 XCH=PayUtil PayTranCode=6 PayFunction=120 Payment=RBSLynkISO
FSA balance Info	FCT 5782	MSR=1 XCH=PayUtil PayTranCode=6 PayFunction=128 Payment=RBSLynkISO
BIN download	FCT 5786	SQI=Bank_RBSLynkISO_BINDownload Payment=RBSLynkISO
BIN Local treatment	FCT 5787	SQI=Bank_RBSLynkISO_BINLocalTreatment Payment=RBSLynkISO
BIN deploy	FCT 5788	SQI=Bank_RBSLynkISO_BINDeploy PAYMENU=1 Payment=RBSLynkISO
Print current totals	FCT 5791	SQI=TRS_POS_BANK_RPT JOB=PAYTOTAL PRINT=1 Payment=RBSLynkISO
Gift_card_functions_		Click on the link for Gift card functions and parameters

Installation of 2 banks

Important

- When you have 2 banks installed on the same lane, it is mandatory to have PAYMENT1 selection for the bank driver which will process the Debit and Credit tender transactions.
- Selection of Payment2 or anyone Payment available should be for the processing of the cards that are NOT Debit and Credit tender transactions. Gift cards with another bank provider for example.
- **Every card related to a tender function** needs to have a payment index associated with it, or else the driver in payment index 1 will be used.
Example: Installation of RBSLynkISO for Debit and Credit and BuypasIP for gift cards
Tender functions processing with RBSLynkISO (Payment1) will need to be configured with parameter Payment=RBSLynkISO
Tender functions processing with BuypasIP (Payment2) will need to be configured with parameter PAYMENT=BUYPASIP


Pinpad option Installation

If you are installing RBSLynkISO for the first time, the Verifone option must be install As First Load. .

It is mandatory to always install the Bank and the pinpad option from the same version to work properly.

Steps of the installation process

1. At the HTML selection prompt, Asynch application must be selected



2. At the Bank Driver selection prompt, you must always select the bank that will process the Debit and Credit transactions

Bank Configuration

Once the installation of the **Bank_RBSLynkISO** option is done, it needs to be configured.

Note:

Terminal ID for EMV MUST be 8 digits. If provided with a 6-digit number, add two leading zeroes (00) in front.

The RBSLynkISO configuration file is used to set the Bank interface configuration. To access and/or modify this configuration, use the INI editor (**Edit config files** option from the **Execute** pull-down menu in the **SMS Pro** application). The RBSLynkISO configuration file is located under the **Bank interface** sub-menu. The RBSLynkISO bank parameters are saved in the Storeman/XchPay/ApiRBSLynkISO.ini file.

Important Note:

It is mandatory to configure, accordingly, the MerchantType in the INI file.

Grocery Store: MerchantType = 5411

Fuel Store: MerchantType = 5542

PARAMETER NAME:
(SMS Pro application)

DESCRIPTION:

PARAMETER NAME:
(ApiRBSLynkISO.ini file)

<u>EFT Payment</u>		
Driver enabled:	When enabled, this parameter specifies that the current bank interface driver is in use. The Driver parameter contains the name of the driver and is ApiRBSLynkISO.dll. Note Driver is NOT enabled on the backoffice server.	Storeman\Office\Setup.ini: [PAYMENT] Driver=ApiRBSLynkISO.dll
Debug log:	This parameter is enabled by default. This creates a bank log file named ApiRBSLynkISO.sls in the Storeman\Log folder. This log is necessary for troubleshooting. Note Logs are PCI compliant.	[General] Debug=
Two Drawers	When the lane is configured with 2 drawers, this parameter must be enabled	Storeman\XchPay\ApiRbsLynkISO.ini [Bank] Two Drawers=
Print Gift Card Stub	This parameter determines if the ACTIVATION of the GIFT card bank stub will be printed or not. If the parameter is enabled, the ACTIVATION of the GIFT bank stub will be printed. If the parameter is Disabled, the ACTIVATION of the GIFT bank stub will NOT be printed.	Storeman\XchPay\ApiRbsLynkISO.ini [Bank] PrintGCStub=
Emv Signature Amount Limit	This parameter determines the amount under which the signature is not required on EMV credit cards.	[Bank] EmvSigReqAmount=
<u>RBSLynkISO Default ID</u>		
Merchant ID:	This parameter is MANDATORY and should contain the Merchant ID number provided to you by RBSLynk. This Merchant ID is the same for every lane.	[Bank] MerchantId=
Merchant Type	It is mandatory to configure, accordingly, the Merchant Type parameter in the INI file. 5411 should be configured in this parameter when the store is a General Retail Store (Grocery) 5542 should be configured in this parameter when the store is a FUEL store.	[Bank] MerchantType=
Merchant Zip Code:	This parameter contains the zip code of the merchant.	[Bank] MerchantZip=
Terminal ID:	This parameter is MANDATORY and should contain the Terminal ID number provided to you by RBSLynk. This Terminal ID is different for each lane and for EMV MUST be 8 digits. Pad with two leading zeroes (00) if necessary. (ex. 00123456) Note This parameter is read in the case where the value of the Terminal ID parameter of the RBSLynkISO ID for Lane xxx is not set. It allows RBSLynkISO to set a Terminal Default ID for all customers to be used.	[Bank] TermID=
Check Digit:	This parameter contains the check digit information, used for the communication.	[Bank] CheckDigit=

	This check digit is provided by RBSLynkISO. Note This parameter is read in the case where the value of the Check Digit parameter of the RBSLynkISO ID for Lane xxx is not set. It allows RBSLynkISO to set a Default Check Digit for all customers to be used.	
Blackhawk Store Number	This parameter contains the store number provided by Blackhawk for card activation.	[Bank] BlackhawkStoreNo=
<u>RBSLynkISO ID for Lane XXX</u>		
Terminal ID:	This parameter is MANDATORY and should contain the Terminal ID number provided to you by RBSLynkISO. This Terminal ID is different for each lane and for EMV MUST be 8 digits. Pad with two leading zeroes (00) if necessary. (ex. 00123456) Note This parameter is read before the Terminal ID parameter of the RBSLynkISO Default ID section. In the case where this value is not set, RBSLynkISO is allowed to set a Terminal Default ID for all customers to be used.	[Term_XXX] TermID=
Check Digit:	This parameter contains the check digit information, used for the communication. This check digit is provided by RBSLynkISO. Note This parameter is read before the Check Digit parameter of the RBSLynkISO Default ID section. In the case where this value is not set, RBSLynkISO is allowed to set a Default Check Digit for all customers to be used.	[Term_XXX] CheckDigit=
Batch Date:	This parameter contains the date of the current batch (not editable).	In the Windows Registry.
<u>Manual Card Verification</u>		
Enter Address:	This parameter specifies that the system will prompt the operator to enter the address of the cardholder on a manual credit card transaction. It is enabled by default.	[Bank] AVS=
Enter Zip:	This parameter specifies that the system will prompt the operator to enter the zip code of the customer on a manual credit card transaction. It is enabled by default.	[Bank] ZIP=
Enter CVV code:	This parameter specifies that the system will prompt the operator to enter the card verification value code of the customer's card on a manual credit card transaction. It is enabled by default.	[Bank] CVV=
Request Card present:	This parameter specifies that the system will prompt the operator to confirm that the card is physically present at the transaction time on a manual credit card transaction. It is enabled by default.	[Bank] CardPresent=
<u>Pre-Auth Setup</u>		
Send 1\$ Pre-Auth Amount:	When enabled, this parameter sets the pre-authorized amount sent to the bank to \$1.00 (checked). It is used only for the payment at the pump.	[Bank] OneDollarsPreAuth=

	See the pre-authorized amounts table for more details.	
<u>Reverse Transaction on Error</u>		
Reverse on AVS or Zip error:	When enabled, this parameter will automatically reverse the transaction if the AVS and/or zip code of the customer does not match the billing address on file at the credit card company.	[Bank] AVSReject=
Reverse on CVV error:	When enabled, this parameter will automatically reverse the transaction if the CVV of the card does not match with the file at the credit card company.	[Bank] CVVReject=
<u>Network 1</u>		
Host Name 1:	This parameter contains the HTTPS address of the host server, on the primary network. Its default value is <i>tptrans.lynksystems.com</i> and should not required to be changed.	[Network1] HostName=
Host Port:	This parameter contains the Host port used for the communication, on the primary network. Its default value is 6661.	[Network1] HostPort=
Timeout:	This parameter contains the number of seconds before timing out if there is no response from the bank, on the primary network. Its default value is 35 seconds.	[Network1] HostTimeout=
<u>Network 2 *</u>		
Host Name 1:	This parameter contains the HTTPS address of the host server, on the second network.	[Network2] HostName=
Host Port:	This parameter contains the Host port used for the communication, on the second network.	[Network2] HostPort=
Timeout:	This parameter contains the number of seconds before timing out if there is no response from the bank, on the second network.	[Network2] HostTimeout=
<u>BIN Lookup</u>		
	Refer to the BIN file configuration section.	
<u>WIC State Support</u>		
	Refer to the eWIC configuration topic.	
	This parameter sets the pre-authorized amount sent to the bank to \$1.00 (checked). It is used only for the payment at the pump. See the pre-authorized amounts table for more details.	[Bank] OneDollarsPreAuth=

Configuration of the Merchant ID and the Terminal ID's

For EMV: WorldPay requires you to enter 8 digits, if provided 6 digits, you need to add leading zeros .i.e. 00113139

World Pay will give to the store a Var Sheet that will contain the Merchant ID and the Terminal ID's . Remember that each lane will be configured with the same Merchant ID, but each lane will have his own individual Terminal ID.

Here is an example of the information the store will get from World Pay:

BASIC TERMINAL INFORMATION

Terminal ID: 4301LK113139

Check Digit: X

MERCHANT INFORMATION

Merchant Nbr: 542xxxxxxxxx22

Note

The Terminal ID number is usually the 6-digit numbers after LK. Only these 6-digit numbers must be configured in the INI file:
Terminal ID: 4301LK113139
Or in the case of EMV, 8 digits 00113139

BIN file with RBSLynkISO

As of December 2019, Worldpay BIN Server was decommissioned without notice to LOC or clients.

IMPORTANT: As of May 2021, there is NO BIN FILE AVAILABLE from Worldpay yet.

The process and the fees for SFTP had not been clearly established by Worldpay. Worldpay is working on a new bin file which will be more available for smaller customers. **No ETA** has been given by Worldpay on when the Bin file will be available to the merchant.

Important Process to follow with Worldpay

An Account, User Name and Password is required from Worldpay.

The merchant or dealer must contact their Worldpay representative to start a project.

The global.txt file defines the layout of these BINs:

- Debit;
- EBT;
- eWIC;
- Visa;
- Master Card;
- American Express;
- Discover;
- Dinners;
- JCB;

Important Note:

1- The download of the Bin File from Worldpay will be possible only from the Back office store SERVER and then can be deployed from the Back office Server to the lanes. The refresh of the bin file on Worldpay side will be done every Monday at 8:00 AM.

2- The download of the file can be done only once per store since the Bin file will be deleted automatically after the download.

Installation, Configuration and Process

The installation of the Bank RbsLynkISO option will need to be done on the server and all the lanes. New functions, Tasks and files will be added for Bin File at installation process.

Configuration

Configuration of the Bin Lookup will need to be done on the Server.

To access and/or modify this configuration, use the INI editor (**Edit config files** option from the **Execute** pull-down menu in the **SMS Pro** application). The RBSLynkISO configuration file is located under the **Bank interface** sub-menu. The RBSLynkISO bank parameters are saved in the Storeman/XchPay/ApiRBSLynkISO.ini file.

Even though the bank must be enabled on the server, it will not required to add another node to the license key. Although, on the server, we are not sending any bank requests to Worldpay, therefore, we need to initialize the DLL when SMS runs to be able to download the Bin file. This requires that a MID and TID be defined in the INI on the 901. It can be one of the ones from any lanes in the store. The only time the Server needs its own MID and TID is if 901 is used to process EFT transactions sales, it will then also

need a node on the license key as well.

User Name and Password provided by Worldpay must be configured in the Bin Lookup setion.
Next refresh date is the

BIN LOOKUP	
Host Name	mft.ftpsllc.com
Host Port	22
User Name	
Password	
Root Folder	Inbox
Next Refresh	20200513 (YYYYMMDD)

Setting.ini

The setting.ini file must be updated manually on all the lanes.

This is the file SMS checks when a card is swiped. In order to configue SMS to do a BIN Lookup, the Setting.ini file located in the \Storeman\Office\ directory needs to be modified by adding the following entries under the [CARDS] section located at the top of the file, as follows:

[CARDS]

0*=@1

1*=@1

2*=@1

3*=@1

4*=@1

5*=@1

6*=@1

7*=@1

8*=@1

9*=@1

If there are conflicting entries between the Setting.ini file and the BIN file, the entries in the Setting.ini file are followed when assigning a BIN range to an SMS function. If getting CREDIT CARD as a choice on the pinpad to confirm the card type, this is because the card in question was not found in the BIN file nor in the Setting.ini file.

If you do not want the card to process as Credit when bin range is not found, you can configured the NotFound parameter in the setting.ini to Error. This configuration will send the error message Cardtype Not Accepted at the POS screen.

NOTFOUND=ERROR

Scheduler Taks


Task Bin Download #145 and Task Bin Deploy #150 will be configured by default at installation process.

Bin Download Task 145

The Bin Download task is an SMS TASK. If any modification has to be done to the Task, you will need to reload SMS to apply the change.

This TASK can be performed ONLY on the Server and ONLY once a week.

Important Note: SMS must be ruuning for this TASK to process the Bin Download. The GlobalBin.txt file will be downloaded in the Storeman, Xchpay, Data folder.



Here is an example of the Bin Download process from the 901 Bank log.


```
<ApiRBSISO ts="11:03:36.485" id="0" cap="BinUpdate date" dat="20200513"/>
<ApiRBSISO ts="11:03:36.485" id="0" cap="Start Bin Update" dat="Update Date=20200513"/>
<ApiRBSISO ts="11:03:36.485" id="0" cap="GetBinFile" dat="Host: mft.ftpsllc.com"/>
<ApiRBSISO ts="11:03:36.485" id="0" cap="GetBinFile" dat="Port: 22"/>
<ApiRBSISO ts="11:03:36.485" id="0" cap="GetBinFile" dat="User: YOUR USER"/>
<ApiRBSISO ts="11:03:36.485" id="0" cap="GetBinFile" dat="Pass: YOUR PASSWORD"/>
<ApiRBSISO ts="11:03:36.485" id="0" cap="GetBinFile" dat="Root: Inbox"/>
<ApiRBSISO ts="11:03:36.485" id="0" cap="GetBinFile" dat="Start"/>
<ApiRBSISO ts="11:03:36.485" id="0" cap="SFTP" dat="Process Starting"/>
<ApiRBSISO ts="11:03:36.501" id="0" cap="SFTP" dat="Execute"/>
<ApiRBSISO ts="11:03:36.563" id="0" cap="PAY Status" dat="Start"/>
<ApiRBSISO ts="11:03:36.563" id="0" cap="PAY Status" dat="40"/>
<ApiRBSISO ts="11:03:36.563" id="0" cap="PAY Response" dat="Start"/>
<ApiRBSISO ts="11:03:36.563" id="0" cap="PAY Response Bypass"
dat="/TARGET=901 /DATE=05/20/2020 /TIME=000000 /PAYTERMID=901 /PAYSTOREID=001 /TASK=BINDOWNLOAD /XCH=PAYHAN
<ApiRBSISO ts="11:03:36.563" id="0" cap="PAY Response" dat="-----End_request-----"/>
<ApiRBSISO ts="11:03:36.907" id="0" cap="SFTP" dat="KeyValidate. Server key received (RSA). Fingerprint is
8a:18:37:60:d5:af:3e:02:ef:21:d5:4d:15:08:e9:c5"/>
<ApiRBSISO ts="11:03:37.391" id="0" cap="SFTP" dat="Authentication succeeded"/>
<ApiRBSISO ts="11:03:38.110" id="0" cap="SFTP" dat="Connected"/>
<ApiRBSISO ts="11:03:38.329" id="0" cap="SFTP" dat="Root Directory opened"/>
<ApiRBSISO ts="11:03:38.391" id="0" cap="OnDirectoryReady" dat="Start"/>
<ApiRBSISO ts="11:03:38.391" id="0" cap="SFTP" dat="Starting file download, &quot;LOCS_P0OURBUP_20200518&quot;"/>
<ApiRBSISO ts="11:03:38.532" id="0" cap="SFTP" dat="Progressing... (0/87342300)"/>
<ApiRBSISO ts="11:03:43.547" id="0" cap="SFTP" dat="Progressing... (4866048/87342300)"/>

<ApiRBSISO ts="11:05:11.532" id="0" cap="SFTP" dat="Progress done (87342300)"/>
<ApiRBSISO ts="11:05:11.610" id="0" cap="OnDirectoryReady" dat="Done"/>
<ApiRBSISO ts="11:05:11.672" id="0" cap="OnDownloadDone" dat="File ready LOCS_P0OURBUP_20200518"/>
<ApiRBSISO ts="11:05:11.672" id="0" cap="OnDownloadDone" dat="Reading"/>
<ApiRBSISO ts="11:05:56.641" id="0" cap="OnDownloadDone" dat="Sorting"/>
<ApiRBSISO ts="11:06:11.922" id="0" cap="OnDownloadDone" dat="Saving"/>
<ApiRBSISO ts="11:06:22.610" id="0" cap="OnDownloadDone" dat="GlobalBin.txt is updated"/>
<ApiRBSISO ts="11:06:22.610" id="0" cap="OnDownloadDone" dat="Done"/>
<ApiRBSISO ts="11:06:22.844" id="0" cap="SFTP" dat="Execute done"/>
```

Bin Deploy Task 150

The Bin Deploy will be performed by the 901 Launchpad of the Back Office Server only.

This will deployed the BinFile.txt to all the lanes. This Task must be scheduled to run after the Bin download Task.



Here an example of the L-WIN log of the process of the Bin Deploy from the server to the lane,

Server log:

```
<mime From="001901" To="PAL" Date="2020-05-23T11:33:39T11:33:39" Subject="BIN FILE DEPLOY" X-Priority="">
<msg>MSG: This is an auto-transfer message
Destination directory for attachment
*MIMESET[TAR_PATH=*RUNXchPay\Data]
*MIMESET[TAR_OPT=]
*MIMESET[TAR_FILE=]
Files attached:
E:\CYCLE3509ARbsBINServer\XchPay\Data\GlobalBin.txt
</msg>
</mime> </locmsg>
```

Lane log:

```
<locmsg ts="11:33:38.950" op="O7">
<mime From="001901" To="PAL" Date="2020-05-23T11:33:38T11:33:38" Subject="BIN FILE DEPLOY" X-Priority="">
<msg>This is an auto-transfer message
Destination directory for attachment
*MIMESET[TAR_PATH=*RUNXchPay\Data]
*MIMESET[TAR_OPT=]
*MIMESET[TAR_FILE=]
Files attached:
E:\CYCLE3509ARbsBINServer\XchPay\Data\GlobalBin.txt
```

FSA/NACS codes with RBSLynkISO

NACS (National Association of Convenience Stores) codes are used by Gas stations to identify what is being charged to a fleet credit card.

FSA (Flexible Spending Account) codes are used by Pharmacies to identify categories (Optical, Dental, Prescription, Clinic, Over-the-counter) that are charged to an FSA Credit Card (Benefits card).

In previous Versions, the Report code field was used to store the NACS/FSA codes. Often this conflicted with other report codes used by the customer.

In version V3.6.0 a new dedicated field has been added for the NACS/FSA code in the Main window of the Maintenance Price View in SMS_Pro along with a new FSA/NACS look-up table.

Wherever this bank option is installed, during the upgrade to 3.6, the Report codes on each item will be copied to the new FSA/NACS code field.

If the Store's Server does not have the bank installed, there is a process during the upgrade to ensure those codes get pushed from the lane to the server.

Deploy Price Change from Host (Head Office)

To Prevent a Price Change deployed from host wiping out the NACS codes in the stores, follow the procedure below if it hasn't

already been done.

1. It is strongly recommended that the bank option be installed on the Store Server and the Host PC so that all installations have the correct list of Functions and totalizers.
2. If not already done, update the host NACS Code field for EACH item which requires the FSA or NACS code.
3. If the FSA/NACS codes are not to be maintained from the host, skip steps 1 and 2 above and exclude the Store server from accepting updates from the Host for that field. Each store server needs a setting for this.

Modify the Host_Store.ini file located in the Office directory on each Store Server.

Make the following changes to stop the host from overwriting the NACS field:
Add F2931 to the existing Execute_Exclude line:

```
[OBJ_CHG]
Execute_Exclude=F2119,F2931
```

Add the following lines to the [FOBJ_BAT] section (They do not exist by default):

```
[FOBJ_BAT]
Change_Exclude=F2931
Execute_Exclude=F2931
```

Click on this link ([Setup FSA](#)) to get all the needed information for FSA configuration with Bank RBSLynkISO.

EMV Fallback to MSR Restriction

A new regulation has been established by the banks concerning Fallback to MSR.
It is now forbidden to do a FallBack to Swipe when the chip of the EMV card is defective.

[Bank]
AllowFallback=0



OE: Fallback not allowed

No signature under a certain amount for EMV credit cards

NOTE OF LIABILITY:

This feature is **NOT** to be used without confirmation from your processor. When setting this feature, merchant may be liable for the **No Signature Under a Certain Amount** transactions. An amount higher than \$25.00 should **NOT** be set.

The parameter **EmvSigReqAmount** should be configured in the MAX Limit section of the bank interface INI. An amount below which the signature prompt will be ignored on the pinpad. Reload SMS to apply the change.
This amount must be determined by the merchant.

The RBSLynkISO configuration file can be used to configure the **EmvSigReqAmount** parameter. To access and/or modify this configuration, use the INI editor (**Edit config files** option from the **Execute** pull-down menu in the **SMS Pro** application). The RBSLynkISO configuration file is located under the **Bank interface** sub-menu.

In the bank driver logs the message "Signature Skipped by Merchant Limit" appears as confirmation this rule was applied.

NOTE: EMV Credit transactions greater than this amount will require a signature on the pinpad.

For example, *EMVSigReqAmount=50* means that all transactions under \$50.00 will not require a signature on the pinpad.

Important note

For EMV, even though the alpha parameter SCANSIGN=1 is part of the specific tender functions, it will not override the **EMVSigReqAmount** parameter.

No signature under a certain amount Non-EMV only

NOTE OF LIABILITY:

This feature is **NOT** to be used without confirmation from your processor. When setting this feature, merchant may be liable for the **No Signature Under a Certain Amount** transactions. An amount higher than \$25.00 should **NOT** be set.

If a card is swiped, it is possible to configure the pinpad not to prompt for the signature under a certain amount.

To do so, follow these steps:

1. On the lane, open the Setup.ini file located under the \Storeman\Office\ directory.
2. In the [SIGCAP] section, add the **AmountMinimum** parameter with the amount under which the signature will not be required.
For example, *AmountMinimum=25* means that all transactions under \$25.00 will not require a signature on the pinpad.
3. Restart the **SMS** application.

WARNING: If the alpha parameter SCANSIGN=1 is part of the specific tender functions, it will override the **AmountMinimum** parameter.

Gift cards with RBSLynkISO

RBSLynkISO supports its own gift cards only.

Before performing gift card transactions

Before being able to perform gift card transaction, you should:

- Get the confirmation from World Pay that the gift cards are activated on the customer profile;
- Be sure the RBSLynkISO gift card module is programmed on the software key;
- If another gift card program was installed before, be sure the **Setup.ini[GIFTCARD]Driver** parameter is empty.

Supported gift card transactions

Here is the list of the supported transactions with the gift cards:

- Activation (swipe only, manual is not supported);
- Deactivation;
- Inquiry;
- Recharge;
- Redeem.

Gift card functions

At the installation of the Bank_RBSLynkISO option in V360, specific gift card functions are installed and configured with the required alpha parameters.

Here are the functions that require a button at the POS:

Function name	Function number	Alpha parameter
Gift card balance info	5796	MSR=1 XCH=PayUtil PayTranCode=6 PayFunction=117
Gift card recharge	5797	MSR=1 CardType=T PayTranCode=200 Payment=RBSLynkISO ADDREG=CREDIT
Gift card activation	5798	MSR=1 CardType=T PayTranCode=201 Payment=RBSLynkISO ADDREG=CREDIT
Gift card deactivation	5799	MSR=1 CardType=T PayTranCode=205 Payment=RBSLynkISO ADDREG=DEBIT
Gift card used	117	CardType=T MSR=1 CHG=0 PaySubType=RBS CardType=T MSR=1 CHG=0 BEHAVIOR=CARD_GIFT

	Note: To be able to do Partial Approval on Gift Card, parameter Paypartial=1 must be added manually to function 117
--	--

By default, the system prompts for the expiration date on manual gift card transactions. To not get prompted for the expiration date on manual gift card transactions, add the alpha parameter EXPIRY=0 in the Gift card used function (117).

By default, the system prompts for the signature on the pinpad on gift card transactions. To not get prompted for the signature on the pinpad, add the alpha parameter SCANSIGN=0 in the function Gift card used function (117).

By default, the system is configured to disallow partial payment with gift cards (PayPartial=0 alpha parameter in the Gift card used function (117)). In this case, the error message Insufficient Funds is displayed. To allow partial payment on gift card, set the PayPartial alpha parameter to 1 (PayPartial=1) in the Gift card used function (117).

No bank receipt on Gift Card Activation and Recharge

When the parameter **Print Gift Card Stub** is enabled, the Gift card Activation and / or Recharge is printed. If the parameter is disabled, the receipt does **NOT** print. To access and/or modify this configuration, use the INI editor (**Edit config files** option of the **Execute** pull-down menu in the **SMS Pro** application). The RBSLynkISO configuration is located under the **Bank interface** sub-menu.

No Suspend/Backup on Gift Card Activation and Recharge

A new parameter can be added in System.ini to stop the suspend/ backup of an Activation or a Recharge of a gift card transaction. A configuration needs to be done in Storeman, Office, System.ini.

In the [Client] section add this parameter:

StopSuspendAfterEft=1

Mask Gift Card on report

To mask the gift cards on the reports, the system must be configured accordingly. In the **Others** part of the *setup.ini* file (from the INI Editor in the **SMS Pro** application), the Gift card and Private card parameters should be enabled. All applications should be restarted for the change to take effect.

Blackhawk gift cards with RBSLynkISO

An instore test script needs to be run with Blackhawk to be able to use it with RBSLynkISO and LOC SMS. Contact Blackhawk for the test script procedures, and this requirement must be completed for each RBSLynkISO installation supporting Blackhawk with LOC SMS.

Types of gift card transactions supported:

- Activation.

Blackhawk store number

Blackhawk store number must be configured in the [RBSLynkISO configuration file](#), under the **RBSLynkISO Default ID** section. This Blackhawk store number is provided by Blackhawk.

Blackhawk documentation

Refer to the links below for more details.

[Blackhawk with SMS](#) document for all required information on Blackhawk Items with SMS.

[Blackhawk through Bank Interface](#) document for all required information on Blackhawk configuration with the bank.

Check Services with RBSLynkISO

NOTE: CASHBACK on checks of any type (ECA included) is NOT allowed by the bank.

RBSLynkISO does not support all Worldpay check service types. Here are the service types supported:

Service	Description
---------	-------------

type	
ECA/ECC	This service type means that the MICR information is used to make a one-time electronic DEBIT payment from the customer's account -- an electronic fund transfer. The check itself is not the method of payment.
Verification:	This service type means that Certegy, the check approving institution, verifies the MICR data on the check and confirm if the check is good or not. It is the responsibility of the store to collect the money.
Guarantee:	This service type means that Certegy verifies the MICR data and guarantees the store will get the money. If the check bounces, Certegy will pay the store and go after the check writer.
Full MICR 1 (FM1):	This data entry requirement means that the MICR data suffices for Certegy to approve the check.
Full MICR 2 (FM2):	This data entry requirement means that in addition to the MICR data, the driver's license and the state code are required to approve the check.

Depending on the check service type and the data entry requirements set in the Customer profile at Worldpay, the check configuration needs to be done accordingly in LOC SMS.

Each service may be set for FM1 or FM2 at Worldpay. Follow the configuration which matches what your client agreed with Worldpay.

Electronic check conversion (ECA/ECC) with RBSLynkISO

"Electronic check conversion is a process in which a check is used as a source of information-- the check, account and financial institution numbers are used to make a one-time electronic DEBIT payment from an account, an electronic fund transfer. The check itself is not the actual method of payment. The cashier runs the check through a machine and hands the voided check back to the customer with the receipt."

In addition to the configuration that needs to be done in LOC SMS, the ECA/ECC check must also be configured in the customer's profile at the bank.

There are two (2) possible configurations for ECA/ECC on the customer's profile at the bank:

1. Full MICR 1 (FM1);

This configuration requires the phone number to be entered on each ECA/ECC transaction (must be a 10-digit number). If the phone number is not present in the transaction, the check will be declined at the POS and the cashier will be prompted that the phone number is missing.

2. Full MICR 2 (FM2).

This configuration requires the driver ID, the phone number and the state code to be entered on each ECA/ECC transaction.

For ECA/ECC there is no difference in SMS configuration for FM1 or FM2. It is a procedural training for cashiers to supply the correct ID information in the Check processing window in SMS.

The total amount of the ECA/ECC check transactions will be available on the Certegy Web site. This amount will not be provided by RBS World Pay in the close batch.

Cash back on checks is NOT allowed by RBS World Pay. Any cash back amount entered will be overwritten by the bank. Only the amount of the transaction will be sent to Certegy.

Note: Worldpay required the entry of the phone number on all ECA check transactions.

Refer to the **How to run an ECA transactions at the POS** topic in the SMSUsers help file for details on how to perform the ECA/ECC transactions at the POS.

ECA/ECC check configuration

To configure the ECA checks, follow these steps:

1. In the **Check** function (102), set these alpha parameters: CardType=K MICR=1 PARSE=CHK BEHAVIOR=BANK_CHK VAL=1;

2. In the **Risk level** table, set the **Checks Accept** field to 1 (*Accept with limits*).

Electronic signature with ECA check

Since SMS does not support the Electronic signature to be printed on the receipt, the customer will have to sign on the Merchant copy. Adding the parameter Scansign=1 in your function 138 will prompt the customer to sign on the pinpad. However, you have to be aware that in a case of chargeback, this copy of EJ can be declined by the bank.

Printing of NACHA Agreement

the Nacha Agreement will be printed on the customer receipt as well as the bank receipt.

Business Checks

All business checks will be returned as TCK (check verification) by the bank. The message "Keep the check for deposit" will prompt on the POS screen. All business checks must be deposited by the store at the bank.

Configuration for Check Guarantee and Check Verification (Non ECA Check)

Check Guarantee Full MICR 1

Certegy guarantees that the store will get the money. In LOC SMS, only the MICR data is necessary to approve the check transaction.

The **Check** function (102) should be configured with these alpha parameters:

CardType=K MICR=1 PARSE=CHK VAL=1 BEHAVIOR=BANK_CHK PAYSUBTYPE=C30

Check Guarantee Full MICR 2

Certegy guarantees that the store will get the money. In LOC SMS, in addition to the MICR data, the driver's license and the state code are required to approve the check transaction.

The **Check** function (102) should be configured with these alpha parameters:

CardType=K MICR=1 PARSE=CHK VAL=1 BEHAVIOR=BANK_CHK PAYSUBTYPE=C40

Check Verification Full MICR 1

Certegy verifies the MICR data on the check and confirms if the check is good or not. In LOC SMS, only the MICR data is necessary to approve the check transaction.

The **Check** function (102) should be configured with these alpha parameters:

CardType=K MICR=1 PARSE=CHK VAL=1 BEHAVIOR=BANK_CHK PAYSUBTYPE=V30

Check Verification Full MICR 2

Certegy verifies the MICR data on the check and confirms if the check is good or not. In LOC SMS, in addition to the MICR data, the driver's license and the state code are required to approve the check transaction.

The **Check** function (102) should be configured with these alpha parameters:

CardType=K MICR=1 PARSE=CHK VAL=1 BEHAVIOR=BANK_CHK PAYSUBTYPE=V40

The **Debit card enable** parameter is used to tell the system to accept debit cards (checked) or not (unchecked). Since it may happen the pinpads provided to the store are not injected with the right keys, the combo card (Credit-Debit) is causing issues at the point of sale in this situation. So to bypass the debit on the combo card, the **Debit card enable** parameter can be disabled (unchecked). In this case, the transaction will be automatically tendered with credit when the customer will use a combo card.

The same parameter is used to bypass the debit on the combo card on the payment at the pump.

Close batch with RBSLylnkISO

The closing of the batch is automatically done at 04:00AM at the bank every day.

As per RBS World Pay, the merchant may choose to end the business day at a specific time other than 04:00AM. This time should be provided when the merchant is registered with RBS World Pay. The merchant terminal cutoff must be a valid 24-hour time from 00:00 to 23:59. The cutoff time specified is the time on the RBS World Pay host when the merchant wishes to end the business day. If the merchant cutoff time is 04:00AM or earlier (00:00 thru 04:00), the new business day is today's date. If the merchant cutoff is after 04:00AM (04:01 thru 23:59), the new business day is tomorrow's date.

Additionally, a merchant may choose to manually close the day. The merchant may close the day at any time BEFORE the specified or default cutoff time. If the day close message has not been received by the specified cutoff time, the RBS World Pay Host will close the merchant's business day upon receipt of the first transaction at or after the specified or default cutoff time. It will be possible to do the Close batch before manually at each lane or automatically by scheduling the Automatic Bank Close job (250) in the Scheduler at each lane. A report of the closing batch can be sent to the printer.

NOTE: The End of Shift receipt will also show eWIC transactions (as of 3.4.1.5) but the Bank COUNT of the transactions will be DOUBLE the SMS count for eWIC. This is because they count the balance inquiry the system uses to grab the prescription as a transaction even though it is not a financial transaction.

Tenders	Count	Total
BANK Credit Card	3	22.98
SMS Credit Card	3	22.98
Diff.	0	0.00
BANK eWIC	2	60.40
SMS eWIC	1	60.40
Diff.	1	0.00
Bank Total	5	83.38
SMS Total	4	83.38
Diff.	1	0.00

Bank name: RBSLYNK ISO
 Job type: PAYCLOSE
 Operator: Programmer
 Date: 2016-12-21 10:08:24
 Store: 053 Ter: 901
 Bank Term: 801197
 Batch#: 20161221
 BANK TOTALS

Scheduling the Automatic Bank Close job

Take note that RBS Worldpay must be aware of the terminals cutoff time.

To configure the Automatic Bank Close job (250) in the Scheduler, follow these steps:

1. The **Host target** field MUST be set to *SMS*.

L_SMS is the application that will execute the Automatic Bank Close job and not L_WIN, so be sure L_SMS is up and running on every lane.

2. Keep 901 in the **Exec. target** field.
3. Enter 1 in the **Every x days** field.
4. Check the **Execute manually** field.
5. The **Last date** field has to be set with the previous date at which the task has to be executed.
6. Click on the **Apply** button to save the changes.

The date of the next execution of this task is shown in the **Next date** field.

The OUTPUT=RECEIPT command tells the system to print the report of the closing batch on the receipt printer.

The Close batch process can be run manually at each lane using the function 952, named *End of Shift*. It is also possible to schedule the Automatic bank close job (250) to run at each lane. If scheduled, the OUTPUT value in the **Command** field needs to be modified to be equal to *NUL* instead of *RECEIPT* (OUTPUT=NUL) if the report should NOT be printed at the lane.

Automatic close batch on the payment at the pump

The configuration of the Automatic bank close job (250) is the same on the payment at the pump, except the OUTPUT command should be set to NUL (OUTPUT=NUL) if there is no printer configured on the PAP terminal.

Print current totals

It is possible to get the bank totals during the day by using the Print current totals function (5791) at the POS. Remember that this function will NOT close the batch; it will only give the current totals of the current batch.

Close batch done on the bank side

In the case where the bank is closing the batch on their side every day, the Close batch job still need to be executed once in a while (e.g. once a month) at the lanes.

When running the Close batch job, all files standing in the \Storeman\Office\DBS\ directory of the lane are deleted. These files are not needed anymore once the transaction is closed. Leaving them in the \Storeman\Office\DBS\ directory would create issues such as a directory too big or old receipts are printed on recent transactions.

The Close batch job can be executed manually at each lane using the End of Shift function (952), or it can be scheduled through the Automatic bank close job (250) at each lane. If the Close batch is executed automatically, the OUTPUT value in the Command field has to be modified to be equal to NUL instead of RECEIPT (OUTPUT=NUL). This will avoid printing the report at the lane.


Note

If the execution of the Close batch returns an error, the \Storeman\Office\DBS\ directory is not cleaned up (the files stay there). So it is important to verify the size of that directory.

Automatic bank close is not running

If the Automatic bank close job is not running, verify this information:

- The **Host target** field in the job 250 is set to *SMS*.
- L_SMS is up and running on the lane when the job is to be executed.
- The **TargetTrsRun** parameter in the Startup.ini file is set to *SMS* on the lane.
- In the Launchpad of the lane, company setup, clock tab, clock section, verify that "Transaction Scheduler Target" is configured to SMS.



Close batch is not running with suspended transactions

By default, LOC SMS is configured to not close the batch when there are suspended transactions on the lane. If there is an error message saying that the batch cannot be closed because of suspended transactions, here are the two (2) options available:

1. Close the suspended transactions;
2. Allow the system to close the batch even if there are suspended transactions.

To configure the system to allow the close batch even if there are suspended transactions, follow these steps:

1. In the INI Editor in the **SMS Pro** application, access the **Customer** part of the System.ini file;
2. Under the **POS behavior** section, unchecked the **EndOfShiftBackup** and **EndOfShiftSuspend** parameters, depending on the function used to backup the transactions;
3. Restart the LOC SMS applications.

No bank receipt printed

By default, the bank receipt is printed.

To do not print the bank receipt, follow these steps:

1. In the **SMS Pro** application, open the INI Editor (**Edit config files** option from the **Execute** pull-down menu, **Bank interface** section of the **Others** link of the **Setup INI** sub-menu);
2. Enable (check ON) the parameter **No drawer receipt**.
3. Restart the LOC SMS applications.

Note

This configuration has to be done on every lane.

Force printing of EBT and Gift card receipt on Balance Inquiry

When the parameter NoDrawerReceipt is set to 1 in the setup.ini, by default the printing of the Bank stub will be disabled for all the EFT transactions. To force the printing of the Balance Inquiry on EBT and Gift card transactions configure the EBT and Gift card Balance Inquiry functions with the parameter STUB=1

No bank receipt on specific tenders

To control the printing of the bank receipt on specific tenders, the STUB alpha parameter has to be set to 0 (STUB=0) in each tender function for which no bank receipt should be printed.

Disable the partial approval

By default, the partial approval is enabled in the bank driver itself. This means that if the remaining balance left on the card does not cover the entire amount of the transaction, only the available amount will be taken from the card and there will be a balance left to pay.

To disable the partial approval, follow these steps:

1. Set the PAYPARTIAL alpha parameter to 0 (PAYPARTIAL=0) in the Debit function (103), in all specific Credit functions, in the Gift card function (117) and/or the EBT function, depending on which situations you do not want to allow the partial approval;
2. Restart the LOC SMS applications.

If the parameter PAYPARTIAL=0 is not configured in the functions, the operator will be prompted with this message on the POS screen when the remaining balance of the card will not cover the entire amount of the transaction.

```
Partial Amount $xxx.xx Confirmation
DO YOU ACCEPT THIS AMOUNT?
YES NO
```

When the operator will select YES, the partial amount the transaction will be completed and the balance of the transaction will need to be pay with another type of payment.

When the operator will select NO, the transaction will not be completed and the transaction will have to be paid with another type of payment.

Note

This configuration has to be done on every lane.

No prompt for the expiration date on EBT manual entry

THIS SHOULD NOT BE USED WITH EMV

By default, the system asks for the expiration date when the EBT function is used manually.

For the system does not prompt for the expiration date on a manual EBT entry, follow these steps:

1. Set the EXPIRY alpha parameter to 0 (EXPIRY=0) in the EBT function;
2. Restart the LOC SMS applications.

Note

This configuration has to be done on every lane.

Swipe card restrictions

In this particular case, the merchant does not want to accept Amex swipe card in their store. To be able to decline this card type at the POS, a change needs to be done in the Setting.ini file. All bin ranges related to AMEX will need to be changed as in this example:

Change 34*=132 to 34*=error

When a card is swiped and bin range of the card cannot be found in the setting.ini, it will be sent to the bank with payfunction=104. To avoid this situation, you can configure the parameter **NOTFOUND=** in the setting.ini to:

NOTFOUND=error

This way, when this card is used at the POS, the error "Card type not accepted" will be displayed to the operator and the transaction will not be sent to the bank.

Troubleshooting

Here are some errors that may occurred, with their solutions.

Getting a 902 error

This is an error returned by the bank. It can be related to a faulty ID configuration (see the [Merchant ID and Terminal ID section](#)) or if a manual transaction was attempted on a Debit card (manual entries on Debit cards are not allowed).

This error should be reported to the RBS World Pay support center to get solved.

To know what is the exact error and report it accordingly to the RBS World Pay report center, follow these steps:

1. Edit the RBSLynkISO.sls log file located in the \Storeman\Log\ directory;
2. Do a search for 902NH;

The result of the search brings you to the transaction line on which the error occurred.

3. Look for the field DE44.

This will give the error code associated to the 902 error. This is the error that should be reported to the RBS World Pay support center.

Here is an example:

```
<ApiRBSFuel
ts="09:46:15.953" id="1" cap="ParseResponse" dat="Exit MsgType=[0210] BitMap=[323804000B518008] DE3=[000000] DE4=[000000000001] DE7=[0223094615] DE11=[000014] DE12=[094613] DE13=[120223] DE22=[022] DE37=[46359 ] DE39=[902] DE40=[NHCGR02000] DE42=[5429298048257351048287] DE44=[91204DENIED 902] DE48=[/S12='SMS V3.20.1020100510' /S14='008L' ] DE49=[840] DE61=[0000100071000840]"/>
```

```
<ApiRBSFuel
ts="09:46:15.953" id="1" cap="CheckEditorError" dat="Weird=Error 91204:invalid Manufacturer Code"/>
```

Getting a NO RESPONSE error

A 'NO RESPONSE' could be due to several issues

1) SMS asks windows to connect to the Worldpay server (tptrans.lynksystems.com) but windows cannot resolve the name to an IP.

The error in the log is:

WSocketResolveHost: Cannot convert host address 'tptrans.lynksystems.com', Error #11004 Network=1"/>

A Search of this Windows error give:

"This specific Winsock error implies some type of Names Resolution issue within the network environment. The POS software does not directly perform any type of Names Resolution, it simply asks the Operating System to perform all Names Resolution, and this error is being returned by the Operating System to the software. Therefore, if the machine is being entered by its Host Name or FQDN (fully qualified domain name), try using the IP address instead. This may resolve the issue. "

Although the IP might work better, it is better for your network to find out why the domain name cannot be resolved in the first place.

Please work on your network end or with your ISP to resolve this.

2) Get connected to the Host computer but the Worldpay server software does not give a response to the Credit request.

3) Get connected to the Host computer but the Worldpay Server's link to the issue is down so they cannot get an authorization.

Looking into the RBSLynkISO log at the transaction (PAYINVOICE=Trs #)

HR 0014 Call Certegy Rep

This decline code is coming from Certegy (14) and indicates an invalid station ID number. This means the merchant number presented does not exist in the Certegy's master file, or it represents a merchant who has been suspended or cancelled.

In this specific case, Certegy has to refresh the account. It was probably set up for a while back and had not been used since, so the account went dormant.

Getting the error Gift card not activated on the key

Here are the points to verify when getting the Gift card not activated on the key error message:

- Verify that the gift card module 151 has been programmed on the key;
- Verify that the Company name has been configured properly on the key;
- Verify that the Gift card functions are all set with CardType=T.

Getting the error Cashback Not Allowed on Gift Activation or Recharge

This error means that your the gift bin range for Activation and/or Recharge are not configured correctly in the setting.ini. Changes had been done in Version V360 and now required to add the specific bank function for Gift to the paytrancode section.

Paytrancode code 200 for Recharge and Paytrancode 201 for Activation.

For example, Setting.ini should have this configuration:

For Recharge

```
[CARDS_200]
603225*=5797
```

For Activation

```
[CARDS_201]
603225*=5798
```


Gift driver is invalid

This error occurs when loading LOC SMS, on a new bank installation over an old one. It is related to a wrong configuration in the Setup.ini file of the terminal.

Since the gift driver is not used anymore with RBSLynkISO, the [GiftCard] section in the Setup.ini file should not be set to a bank driver (dll).

GIFTNET not loaded

This error occurs on an activation of a gift card. It is usually related to a wrong configuration of the gift card functions.

Refer to the [Gift card configuration section](#) to review the configuration of the gift cards.

Invalid card error on Gift transactions

When the Host is returning Invalid card error with a PayHostCode 002 or 003, a verification of the customer profile with Worldpay will need to be done to fix the issue.

Gift cards shown with weird characters in the electronic journal

In this specific situation, the gift card numbers are shown with weird characters in the electronic journal (encrypted).

Visa	CC	*****6019****
Debit card	DC	*****8874****
Debit card	DC	*****6687****
Debit card	DC	*****8897****
Gift card used	PC	EaY0"O::YÁa,p*—luWnó pðy
Gift card used	PC	EaY0"O::YÁa,"00.\$"Ábè A)=l
Gift card used	PC	EaY0"O::YÁa,&Er,K60A!c?
Gift card used	PC	[Rhs3

This occurs when the passphrase set on the lane is not the same as the one set on the server. The Private card passphrase in the **Launchpad** application MUST be the same on the server and all lanes.

Gift Card last 4 digits shown with weird characters in the electronic journal on the workstation

When the passphrase is set in the **Launchpad** application, the resulting entry is added in the Windows registry where it is again encrypted. This setting is local so every machine that needs to have access to these un-encrypted numbers is in need to have those settings added to its registry. This is usually done on the backoffice server at the installation time, but rarely done on the workstations.

Here is how to do it on the workstations:

1. On the workstation, make a shortcut for the **Launchpad** application that will need access to un-encrypted card numbers;
2. Use that Launchpad shortcut to open the **Launchpad** application locally on the workstation;
3. Under the **Security** tab, set the passphrase (the passphrase MUST be the SAME as the one set on the server);
4. Once done, close the **Launchpad** application, and delete the shortcut;
5. Restart (reboot) the workstation.

Once this is done, the encryption passphrase would have been added to the workstation's registry, thus enabling the user to see the last 4 digits of the cards in the needed reports.

Note

By default, the gift card numbers are masked in the log files and the electronic journal.

0021 Denied on EBT

This error indicates that the configuration of the customer profile for EBT is wrong at the Bank. The Bank needs to be called.

91270 error Denied on EBT

This error indicates an issue with the TID in the customer profile at the bank. Worldpay support will need to be involve to fix this issue.

I/O Error, Re-Try on Certegy Check

This error indicates an issue on the bank side (no more details about it).

Duplicated receipts printed with wrong bank information

When the Close Batch process is not running, all files standing in the \Storeman\Office\DBS\ directory of the lanes are NOT deleted. These files are not needed anymore once the transactions are closed. Leaving them in the \Storeman\Office\DBS\ directory would create issues such as a directory too big or old receipts printed on recent transactions.

CVV=1 does not prompt to enter the CVV code at the POS on manual credit card transactions

For the POS prompts to enter the CVV, the alpha parameter Behavior_Card_Credit must be configured in the tender functions. By default, if it configured during the installation of the bank option. Be sure it has not been removed.

Card not supported by the merchant

It is possible for the merchant to do not accept specific cards for payments. To decline specific card types at the POS, changes are required in the Setting.ini file.

For example, to decline the Amex cards, this information needs to be set for the bin ranges related to the Amex cards:

34*=error

This way, when an Amex card will be used at the POS, the error *Invalid Card Type* will be returned to the operator.

SMS prompts for restart on EFT transactions

Here is the error that pops up on the POS screen on an EFT transaction: "The application has experienced an internal error and must be restarted to avoid a data loss".

It has been found that there was a TAB instead of spaces between the 104 and the AMEX card configuration in the Setting.ini file.

Invalid Response returned by the bank on a swiped credit card

This kind of error can be related to a type of card that is not supported on the profile of the customer. If the type of card is not supported, it needs to be deleted from the Setting.ini file.

Error HR-042: No further W/D via Worldpay

This error is coming back from the issuer of the card. The card issuer put a restriction on the card saying that they cannot use the card. The owner of the card will have to call his card issuer.

Blackhawk declines with 054 - Date mismatch

This error indicates that the Blackhawk Store ID number has not been configured in the INI file of the bank interface. This number is provided by Blackhawk.

Blackhawk declines with 030 - Invalid Trs

This kind of error could be related to a wrong configuration of the Blackhawk Store number. This should be verify with Worldpay and Blackhawk.

005 Do Not Honor error on FSA transaction

You will get this error when trying to pay a transaction with an FSA card on which there is no FSA products. To validate that the FSA items had been sent in the packet, you can verify that field DE121 is part of the bank request data.

Here is an example from a bank log:

```
<ApiRBSISO ts="09:51:21.835" id="1" cap="Request Data" dat="MsgType=[0200] Bitmap=[F23C048009418008] DE1=[*****0080] DE2=[16*****5934] DE3=[*****] DE4=[*****007284] DE7=[1226095121] DE11=[***017] DE12=[095117] DE13=[141226] DE14=[1804] DE22=[012] DE25=[00] DE37=[9446 ] DE40=[NHCGR02***] DE42=[5429298033393404121479] DE48=[0381220SMS V3.3.***201206201404013L150219] DE49=[840] DE61=[016***11***71***840] DE121=[081A5312*****0072845412*****0072845512*****5612*****5712*****]"/>
```

BD Invalid Response

This type of error can be related to:

- 1- The EMV options did not installed properly. Verify in the sample.ini if you have the Bank installed with Yes for EMV.
- 2- Verify that your Terminal ID's must be configured with two leading zeroes. EX: 00123456
- 3- You can also force an Update EMV Config. with function 7608.

User Documentation

There is User Documentation on the EMV transactions and the different screens the customer and cashiers will see.

You see the **Verifone User Doc** or the **Equinox User Doc** inside the SMSUsers.chm help file.