

Range Breakout EA Inputs:

The Range Breakout EA waits for the market to form a range between two times of day, then places pending orders to trade the breakout in either direction. It comes with full control over volume, targets, stops, trailing, daily trade limits and range filters.

Trading Volume Modes:

VOLUME_FIXED > Uses a fixed lot size for every trade.

VOLUME_MANAGED > Uses "Fixed Lots" per each "Fixed Lots Per x Money" amount of money in the account.

VOLUME_PERCENT > Lot size is calculated so the set percentage of the account is lost if the initial SL is hit.

VOLUME_MONEY > Lot size is calculated so the set amount of money is lost if the initial SL is hit.

TP / SL Calculation Modes:

CALC_MODE_OFF > No TP/SL is placed.

CALC_MODE_FACTOR > Distance is a multiple of the current range.

CALC_MODE_PERCENT > Distance is a percentage of the range high (for buys) or low (for sells).

CALC_MODE_POINTS > Distance is set in points (one point = the smallest price change for the symbol).

Trailing Stop Modes:

TSL_MODE_OFF > Trailing / break-even stop is inactive.

TSL_MODE_PERCENT > Distance is a percentage of the position open price.

TSL_MODE_POINTS > Distance is set in points.

<General Settings>

Timeframe Range Calculation: Chart timeframe used for range calculation. Always use PERIOD_M1 for live trading; only change it in the tester if you do not have enough M1 data.

Trading Volume: Mode used to calculate the lot size for each trade (see Trading Volume Modes above).

Fixed Lots: Lot size for VOLUME_FIXED and VOLUME_MANAGED.

Fixed Lots Per x Money: Base money amount for VOLUME_MANAGED.

Risk Percentage of Balance: Risk percent for VOLUME_PERCENT.

Risk Money: Risk amount for VOLUME_MONEY.

Order Buffer Points (0 = No Buffer): Pending orders are placed this many points above and below the range.

Target Calc Mode: Calculation mode for the TP distance (entry to TP).

Target Value: Value for the TP calculation based on the Target Calc Mode.

Stop Calc Mode: Calculation mode for the SL distance (entry to SL).

Stop Value: Value for the SL calculation based on the Stop Calc Mode.

<Time Settings>

Range Start Hour: Hour for the start time of the daily range.

Range Start Minute: Minute for the start time of the daily range.

Range End Hour: Hour for the end time of the daily range.

Range End Minute: Minute for the end time of the daily range.

Delete Orders Hour: Hour at which unfilled pending orders expire.

Delete Orders Minute: Minute at which unfilled pending orders expire.

Close Positions: Decides whether open positions are closed at the close time.

Close Positions Hour: Hour at which open positions are closed.

Close Positions Minute: Minute at which open positions are closed.

<Trailing Stop Settings>

BE Stop Calc Mode: Calculation mode for the break-even stop.

BE Stop Trigger Value: The break-even stop activates once a trade is more than this value in profit.

BE Stop Buffer Value: How far into profit the stop loss is moved once break-even activates.

TSL Calc Mode: Calculation mode for the classic trailing stop.

TSL Trigger Value: The trailing stop activates once a trade is more than this value in profit.

TSL Value: Distance the trailing stop is kept behind the current market price.

TSL Step Value: The stop loss is only modified if it moves at least this distance above the previous SL.

<Trading Frequency Settings>

Max Long Trades: Maximum number of buy trades on a single day.

Max Short Trades: Maximum number of sell trades on a single day.

Max Total Trades: Maximum number of trades on a single day.

<Range Filter Settings>

Min Range Points: Ranges smaller than this many points are ignored.

Min Range Percent: Ranges smaller than this percentage are ignored.

Max Range Points: Ranges larger than this many points are ignored.

Max Range Percent: Ranges larger than this percentage are ignored.

<More Settings>

Range Color: Color of the range object drawn on the chart.

Order Comment: Comment attached to every order the EA places.

Magic Number: Unique number identifying this EA's trades. Use a different one for every EA on the same account.

Chart Comment: Activates or deactivates the info comment in the upper-left corner of the chart.

Debug Mode: Activate to print more information about the current EA state in the Experts journal.

Note: The default inputs are not a recommendation and are not necessarily the best settings. Different symbols require different inputs. Always test in the Strategy Tester and on a demo account first. All the best and good trades :)