#### **Overview of Ceramics**

- Define ceramic materials
- Find a few common examples of ceramic materials, with the correponding crystal structures.
- What are the types of bonds typically found in ceramic materials?
- What are typical applications of ceramic materials?

# **Key Mechanical Properties**

- Strength
- Compressive strength (higher than metals and polymers)
- Tensile strength (typically low due to brittleness)
  - Hardness
- High hardness (suitable for wear-resistant applications)
  - Elasticity
- High elastic modulus (stiffness)
- Low ductility (little to no plastic deformation)

# Linear elasticity

Hooke's law

$$\varepsilon_{xx} = \frac{\sigma_{xx}}{E}$$

Poisson's ratio

$$v = -\frac{\varepsilon_{yy}}{\varepsilon_{xx}}$$

$$\varepsilon_{yy} = -\nu \, \varepsilon_{xx} = -\nu \frac{\sigma_{xx}}{E} \qquad \varepsilon_{zz} = -\nu \, \varepsilon_{xx} = -\nu \frac{\sigma_{xx}}{E}$$

The maximum elastic strain that can be achieved in a polycrystalline ceramic prior to failure is typically 0.1% or so.

Ceramic fibers and bulk single crystals specially prepared to be nearly flaw free may have elastic tensile strains at fracture as great as 1%.

## Response to shear loads and pressure

Application of shear stress  $\sigma_{xy} = \sigma_{yx}$ 

- Shear modulus or rigid modulus  $\gamma_{xy} = \gamma_{yx} = \frac{\sigma_{xy}}{u}$
- Bulk modulus B:

$$B = -V \left(\frac{\partial p}{\partial V}\right)_T$$
 or  $B = -V \frac{dp}{dV}$ 

## Elastic Moduli of Polycrystalline Ceramics

Substance	Young's Modulus (GPa)	Shear Modulus (GPa)
$\overline{\text{Al}_2\text{O}_3}$	402.8	163.0
$Dy_2O_3$	170.5	
$Er_2O_3$	186.3	
MgO	310.9	133.4
$ThO_2$	261.0	100.6
TiO <sub>2</sub>	284.2	111.5

### Variation of elastic constants with temperature

- Elastic constants of single crystals generally decrease slowly with increasing temperature
- As the temperature is decreased toward absolute zero, the slope of the curve of elastic constant as a function of temperature approaches zero, as required by the third law of thermodynamics.
- As the temperature increases toward the Debye temperature, the slope approaches a constant for many ceramics.

$$E = E_0 - bT \exp\left(\frac{-T_0}{T}\right)$$

## Elastic properties of ceramics with porosity

Many ceramics have some degree of porosity.

Mechanical properties such as elastic moduli, strength, and toughness decrease

with increasing porosity.

$$\frac{E}{E_0} = 1 - bP$$

E is the elastic modulus of the porous material

E<sub>o</sub> is the elastic modulus of the fully dense material

P is the porosity

b is the shape factor that accounts for pore geometry

where, P is the pore size

An important class of porous solids not properly regarded as solids with distributed porosity is the class of cellular solids (Homework: read about Cellular solids).

Defect-free solids are much stronger than the *real* solids (with defects) usually encountered.

## Permanent deformation: creep

Here permanent deformation begins when stress is applied, slows down in rate, but continues for a long time before ultimate failure.

Transient and steady-state creep, Generally occur in <u>polycrystalline ceramics</u> at <u>low stresses</u> and sufficiently <u>high temperature</u>.


### Fracture Behavior

## **Brittleness**

- Lack of plastic deformation before failure
- Sudden, catastrophic fracture under stress

# **Crack Propagation**

- Stress concentration at flaws or cracks
- Role of microcracks in failure



Micrograph showing pullout of bridge in wake of crack. (From Swanson et al., 1987)

## Linear elastic fracture mechanics


- The strength of polycrystalline ceramics is usually much less than that of a corresponding perfect single crystal
- Understanding the strength of real polycrystalline ceramics requires understanding the behavior of microcracks under stress.
- Linear elastic fracture mechanics is a very useful theory that treats a crack in a continuous body while avoiding the detail of what happens on an atomic scale.

## Concept of stress concentration

- Stress concentrations are usually discussed in terms of a thought experiment in which a flaw is introduced into a body that was originally under uniform stress.
- Consider a sample initially under a uniform tensile stress,  $\sigma$ . If an elliptical flaw whose maximum length is perpendicular to the tensile stress is introduced, the stress will change, especially near the end of the flaw
- The equation of the ellipse defining the crack is

$$\frac{x^2}{c^2} + \frac{y^2}{b^2} = 1$$

• The radius of curvature at the end of the major axis of the ellipse is given by  $b^2$ 



σ

Elliptical crack in plate subjected to uniaxial tensile stress  $\sigma$ .

Two-dimensional view of a sample with a flaw of length 2c in the x direction and a dimension 2b in the y direction

The maximum normal stress that appears anywhere in the plate is at the "tips" of the crack  $(x = \pm c)$  and is in the y direction  $(\sigma_{yy})$ , that is, it is in the same direction as the externally applied stress  $\sigma$ .

This is given by: 
$$\underline{\sigma_{yy}} = \sigma \left( 1 + \frac{2c}{b} \right) = \sigma \left[ 1 + 2 \left( \frac{c}{\rho} \right)^{1/2} \right]$$
 develops because of presence of crack

This last expression of this equation contains only two characteristics of the elliptical crack: the length c and the radius of curvature at the end of the crack perpendicular to the initial stress,  $\rho$ .

To a good first approximation only the length of the crack perpendicular to the applied stress and the radius of curvature at the end of that length determine the maximum stress.

## Toughness ----- Area under stress-strain curve until the fracture

## Low Fracture Toughness

 Ceramics are prone to fracture under impact or stress in comparison with metals and polymers

# Methods to Improve Toughness

- Toughening mechanisms (e.g., adding fibers, controlling grain size)
- Crack tip shielding by crack bridging (second-phase ductile ligament bridging)

## Influence of Temperature

### Thermal Shock Resistance

- Rapid temperature changes can cause fracture
- Applications requiring thermal stability (e.g., space shuttle tiles)

## **High-Temperature Strength**

Ceramics maintain strength at high temperatures (better than metals)