

Inventory Management System (IMS)

Standard Operating Procedure & User Manual

Prepared For: Agile Tech Solutions

System: Agile Tech IMS — Asset, Inventory & User Management Platform

Document Type: Standard Operating Procedure (SOP) / User Manual

Version: 1.1

Status: Final — Client Release

CONFIDENTIAL — For authorized internal use only

Document Control

Version History

Version	Date	Author	Description
1.0	2026-09-08	Agile Tech Solutions — Implementation Team	Initial release. Documents the IMS platform as implemented in the current codebase: asset lifecycle, master data (Department, Sub Department, Type, Subtype, Brand), the Type → Subtype → Parameters configuration model, Excel import/export, roles & permissions, centre/location scoping, dashboard, reports, and search.
1.1	2026-09-22	Agile Tech Solutions — Implementation Team	Updated to match the codebase as of 2026-09-21: the Vendor module and Asset Category were removed; Roles & Permissions are now configured separately per Centre; Global Search adds an Access Accounts result group; and a new Asset unassignment alert notification was added.
1.2	2026-09-23	Agile Tech Solutions — Implementation Team	Updated Section 9 (Asset Assignment & Status) and Section 15 (Validations) to match the current codebase and UI, with new screenshots: the Assign Asset workflow now documents multi-select assignment/unassignment from the User directory (Section 9.2), the per-user Asset History tab is documented in full (Section 9.3), and a new Client-Side Form Validation reference (Section 15.1) documents the shared real-time Name/Email/Phone validation (validation.js) and the letters-only Name Picker used across Department, Sub Department, Brand and other forms.

Purpose of this Document

This manual documents the Inventory Management System (IMS) exactly as it is built and configured today. Every field name, validation rule, permission, and workflow described in this document was verified directly against the application's source code and live screens. No feature described here is planned, assumed, or aspirational — if it is in this manual, it exists in the system.

Audience

- Administrators responsible for configuring master data, roles, and centres.
- Asset Managers, Admins, Auditors, and Viewers who use the system day-to-day.
- New employees being onboarded to the IMS platform.
- IT/Support staff troubleshooting user-reported issues.

Table of Contents

Document Control	2
Version History	2
Purpose of this Document.....	2
Audience.....	2
Table of Contents	3
1. System Overview and Purpose.....	6
1.1 What the System Does	6
1.2 Who Uses It	6
2. Login and Navigation	7
2.1 Logging In.....	7
How to Use	7
Validation & Errors	7
2.2 Signing Out	8
2.3 Navigation Layout.....	8
Sidebar Groups	9
Top Bar	10
3. User Roles & Permissions	11
3.1 Roles	11
3.2 How to Access.....	11
3.3 How to Use	12
3.4 Modules Governed by Permissions	13
4. Dashboard	14
4.1 Period Filter	15
4.2 Stat Cards.....	16
4.3 Charts and Panels	16
5. Master Data Modules.....	17
6. Asset Type → Subtype → Parameters Workflow	18
6.1 Step 1 — Define Parameters on the Asset Type	18
Required / Optional Fields.....	19
Validation	19
6.2 Step 2 — Create a Subtype and Fill In Values.....	19
Required / Optional Fields.....	20
Validation	20
6.3 Different Types Carry Different Parameters.....	20
6.4 How This Appears on the Asset Form	20
7. Brand, Department & Sub Department.....	21

7.1 Department	21
Purpose.....	21
How to Access	21
How to Use	21
Required / Optional Fields.....	21
Validation Rules	22
Example	22
7.2 Sub Department	22
Purpose.....	22
How to Access	22
How to Use	22
Required / Optional Fields.....	23
Validation Rules	23
Example	23
7.3 Brand	24
Purpose.....	24
How to Access	24
How to Use	24
Required / Optional Fields.....	24
Validation Rules	25
Example	25
8. Asset Creation & Editing.....	26
8.1 How to Use	26
8.2 Required / Optional Fields.....	27
8.3 Validation Rules.....	27
8.4 Asset Details Page.....	27
9. Asset Assignment & Status	28
9.1 Assigning an Asset from the Asset Form	28
9.2 Assigning an Asset from the User Directory	28
9.3 Assignment History.....	28
9.4 Asset Status Values.....	29
10. Warranty & AMC	30
How to Use	30
Where Coverage Is Surfaced	30
11. Asset Import / Export	31
11.1 Bulk Asset Import & Export	31
Column Structure (per Type sheet)	31

Import Behaviour	31
Example Import Errors.....	31
11.2 Bulk Asset Subtype Import & Export	32
11.3 Reading the “Expected CSV Columns” Panel.....	32
12. Centre / Location Workflow	33
12.1 For Access Accounts (Manager/Admin/Auditor/Viewer).....	33
12.2 For Administrators.....	33
13. Search, Filters and Reports.....	34
13.1 Global Search.....	34
13.2 Asset List Filters	34
13.3 Reports	34
Coverage Filter Options (Warranty and AMC, independently)	35
14. Notification & SMTP Settings	36
14.1 Notification Settings	36
Purpose.....	36
How to Access	36
How to Use	36
Available Alert Events.....	36
Validation Rules.....	37
14.2 SMTP Settings.....	37
Purpose.....	37
How to Access	37
How to Use	37
Required / Optional Fields.....	37
Validation Rules.....	38
Example	38
15. Validations and Common Errors.....	38
15.1 Client-Side Field Validation (Real-Time)	38
15.2 Server-Side Validation Messages	39
16. Complete Recommended Workflow	41
17. FAQ and User Best Practices	42
Best Practices	42

1. System Overview and Purpose

The Agile Tech Inventory Management System (IMS) is a web-based platform for tracking an organization's physical assets — laptops, desktops, printers, cameras, and any other equipment type an administrator configures — from the moment they are added to inventory through assignment, warranty/AMC coverage, and eventual retirement.

1.1 What the System Does

- Maintains a master catalogue of Asset Types, Subtypes, Brands, Departments and Sub Departments.
- Lets each Asset Type define its own set of Subtype Parameters (e.g. RAM, Processor, Storage for Laptops; Print Type, Paper Size, Connectivity for Printers) — different Types can have completely different parameter sets.
- Records every physical Asset against a Type, an optional Subtype (which carries its own fixed Brand and configured parameter values), a Department/Sub Department, and an assigned user.
- Tracks Warranty and AMC (Annual Maintenance Contract) coverage per asset, with dashboard alerts for coverage expiring within 30/60/90 days.
- Supports bulk Excel import and export of both Assets and Asset Subtypes, one worksheet per Asset Type, with the same Type/Subtype/Brand/Parameter validation as the manual forms.
- Enforces role-based permissions per module and per action (View, Create, Update, Delete, Assign, Import, Export, Download, Verify, Restore).
- Scopes almost all data — Assets, Types, Subtypes, Brands, Departments, Sub Departments, Users, Notifications, Backups, Audit Logs — to a Centre/Location (currently Noida and Lucknow), so each centre only ever sees its own records.
- Provides a live Dashboard, a filterable Reports module, and an instant global search across Assets and Users.

1.2 Who Uses It

Account Type	Logs in as	Typical Use
Super Admin	Super Admin (separate Admin login, not an Access Account)	Full unrestricted access to every module, every Centre, and Roles & Permissions configuration.
Asset Manager	Access Account (User, role = Asset Manager)	Day-to-day asset creation, assignment, import/export, master data upkeep.
Admin	Access Account (User, role = Sub admin)	Administrative operations delegated by the Administrator, scoped by Roles & Permissions.
Auditor	Access Account (User, role = Auditor)	Read/verify-oriented access for compliance and audit review, per configured permissions.
Viewer	Access Account (User, role = Viewer)	Read-only access to permitted modules.

Note: “Administrator” is a separate account type (the Admin model) from the four dashboard roles above (which are User accounts). An Administrator always has full access to every module and every Centre; the four roles are governed entirely by whatever is configured on the Roles & Permissions screen (Section 3).

2. Login and Navigation

2.1 Logging In

Purpose: authenticate into the system as either an Administrator or an Access Account.

How to access: open the application URL — you are redirected to /login automatically if not already signed in.




Figure 2.1 — Login screen

How to Use

1. Enter the account's Email address.
2. Enter the Password.
3. Click Sign In.
4. On success you are redirected to the first module your account has permission to view — normally the Dashboard.

Validation & Errors

- Email is required and must be a valid email format.
- Password is required.
- An incorrect email/password combination shows: “Invalid email or password.”
- An account whose Status is not Active, or an Access Account with login disabled, cannot sign in even with the correct password.
- If a valid account has no permission granted to any module at all, login is rejected with: “Your account does not have access to any module. Contact an administrator.”

Note: Repeated invalid login attempts against a non-existent Administrator email are written to the Audit Log as a blocked LOGIN FAILED event.

2.2 Signing Out

Click the account menu (top-right, showing your name/initials) and choose Logout. This ends the session and records a LOGOUT audit entry.

2.3 Navigation Layout

After login, the interface has a fixed left sidebar and a top bar. The sidebar is grouped into collapsible sections; only groups and items your account has View permission for are shown.




Figure 2.2 — Dashboard, showing the full sidebar navigation

Sidebar Groups

Group	Contains
Workspace	Dashboard

Asset Management	Department, Sub Department, Type, Subtype, Brand, Assets
User Management	Users (the employee/asset-holder directory)
Access Accounts	Manager, Admin, Auditor, Viewer login-account lists
Data & Audit	Reports, Audit Logs, Backup & Recovery
Administration	Roles & Permissions, Settings

Top Bar

- Global search box — searches Assets and Users as you type (Section 13).
- Select Centre — visible to Administrators only; switches the active Centre/Location (Section 12).
- Fullscreen toggle and Notifications bell.
- Account menu — profile initials, name, role, and Logout.
- “Recently Opened” — the sidebar remembers the last pages you visited for quick return.

3. User Roles & Permissions

Access to every module in the system is controlled by a permission matrix: for each Role, and each Module, up to ten possible actions can be independently switched on or off: View, Create, Update, Delete, Assign, Import, Export, Download, Verify, Restore. Not every module exposes every action — only the actions relevant to that module are shown.

3.1 Roles

Internal Role Name	Displayed As	Notes
Administrator	Administrator / Super Admin	Not managed on this screen — always has full access to everything, in every Centre.
Asset Manager	Manager	Typically the broadest of the four configurable roles.
Sub admin	Admin	Administrative operations delegated by the Administrator.
Auditor	Auditor	Read/compliance-oriented access.
Viewer	Viewer	Read-only access.

3.2 How to Access

Sidebar → Administration → Roles & Permissions. Requires the roles_permissions module View permission (Administrators always have it). Editing (not just viewing) also requires a specific Centre to be selected — each Centre keeps its own separate permission set per role (Section 12).

Agile Tech SOLUTIONS

RECENTLY OPENED

- Roles & Permissions
- Reports
- Users

WORKSPACE

- Dashboard
- Asset Management
- User Management
- Access Accounts
- Data & Audit
- Administration
 - Roles & Permissions
 - Settings

Search assets, tickets, users...

Select Centre

SB Screenshot Bot Super Admin

Roles Permissions

ENTERPRISE WORKSPACE

Roles & Permissions

Control module access and View, Create, Update, Delete, Assign, Import, and Export actions for every dashboard role.

Manager
 Create, assign, update, import, and maintain asset operations
 Database permissions

Admin
 Manage business modules and system operations
 Database permissions

Auditor
 Read-only operational and compliance access
 Database permissions

Viewer
 View permitted dashboard information
 Database permissions

Manager Permissions
Changes apply to all active Manager login accounts immediately

Save All Permissions

MODULE	VIEW	CREATE	UPDATE	DELETE	ASSIGN	IMPORT	EXPORT	DOWNLOAD	VERIFY	RESTORE
Dashboard Module permission	☒	N/A	N/A	N/A	N/A	N/A	N/A	N/A	N/A	N/A
Departments Module permission	☒	☒	☒	☐	N/A	☐	☐	N/A	N/A	N/A
Sub Departments Module permission	☒	☒	☒	☐	N/A	☐	☐	N/A	N/A	N/A
Asset Types Module permission	☒	☒	☒	☐	N/A	☐	☐	N/A	N/A	N/A
Asset Subtypes Module permission	☐	☐	☐	☐	N/A	☐	☐	N/A	N/A	N/A
Brands Module permission	☒	☒	☒	☐	N/A	☐	☐	N/A	N/A	N/A
Assets Module permission	☒	☒	☒	☒	☒	☒	☒	☐	☐	☐
User Directory Module permission	☒	☐	☐	☐	☐	☐	☐	N/A	N/A	N/A
Asset Manager Module permission	☐	☐	☐	☐	N/A	☐	☐	N/A	N/A	N/A
Admin Module permission	☒	☒	☒	☐	N/A	☐	☐	N/A	N/A	N/A
Auditor Module permission	☒	☒	☒	☐	N/A	☐	☐	N/A	N/A	N/A
Viewer Module permission	☒	☒	☒	☐	N/A	☐	☐	N/A	N/A	N/A
Notifications & Alerts Module permission	☒	N/A	☒	☒	N/A	N/A	N/A	N/A	N/A	N/A
Reports Module permission	☒	☒	N/A	☐	N/A	N/A	☒	N/A	N/A	N/A
Audit Logs Module permission	☐	N/A	N/A	N/A	N/A	N/A	☐	N/A	N/A	N/A
Backup & Recovery Module permission	☐	☐	☐	☐	N/A	N/A	N/A	☐	☐	☐
Settings Module Access Module permission	☒	N/A	N/A	N/A	N/A	N/A	N/A	N/A	N/A	N/A
Settings: Basic Module permission	☒	N/A	N/A	N/A	N/A	N/A	N/A	N/A	N/A	N/A
Settings: Advanced Module permission	☒	N/A	☐	N/A	N/A	N/A	N/A	N/A	N/A	N/A
Roles & Permissions Module permission	☐	N/A	☐	N/A	N/A	N/A	N/A	N/A	N/A	N/A
Administrators Administrator accounts only	☐	N/A	N/A	N/A	N/A	N/A	N/A	N/A	N/A	N/A

View is the module-access switch and is required for every other action. Administrator retains unrestricted access.

© 2026 Agile Tech Solutions

Figure 3.1 — Roles & Permissions screen

3.3 How to Use

1. Click one of the four role cards (Manager, Admin, Auditor, Viewer) to load its permission grid.
2. For each module row, tick the actions that role should be allowed to perform.
3. The View column is the master switch for that module — ticking any other action without View still restricts the role, since every other action check also confirms View.

4. For the two Settings sub-modules (Settings: Basic, Settings: Advanced), a role also needs the parent Settings Module Access box ticked or those permissions have no effect.
5. Click Save All Permissions to apply the changes immediately to every active login of that role.

3.4 Modules Governed by Permissions

Module Key	Label	Available Actions
dashboard	Dashboard	View
departments / sub_departments	Departments / Sub Departments	View, Create, Update, Delete, Import, Export
types / sub_types	Asset Types / Asset Subtypes	View, Create, Update, Delete, Import, Export
brands	Brands	View, Create, Update, Delete, Import, Export
assets	Assets	View, Create, Update, Delete, Assign, Import, Export
faculty	User Directory	View, Create, Update, Delete, Assign, Import, Export
access_accounts_asset_manager / _sub_admin / _auditor / _viewer	Access Accounts (per role)	View, Create, Update, Delete, Import, Export
notifications	Notifications & Alerts	View, Update, Delete
reports	Reports	View, Create, Export
audit_logs	Audit Logs	View, Export
backup	Backup & Recovery	View, Create, Update, Delete, Download, Verify, Restore
settings / settings_basic / settings_advanced	Settings	View (Advanced also has Update)
roles_permissions	Roles & Permissions	View, Update

Note: Each Access Account role tab (Manager/Admin/Auditor/Viewer) is governed by its own module key (access_accounts_asset_manager, etc.), so a role can be permitted to manage some Access Account tabs and not others.

Note: Every module and record in the system that carries a Centre value is still filtered by the signed-in user's own Centre regardless of permissions — permissions control what actions are allowed, Centre scoping controls which records are visible. See Section 12.

4. Dashboard

Purpose: a single landing page summarising asset inventory, coverage risk, user activity, and recent system events. Every card and chart only appears if your account has View permission on the underlying module (Assets, Users, Notifications, Reports, Audit Logs).

How to access: Sidebar → Dashboard, or automatically after login.




Figure 4.1 — Dashboard overview

4.1 Period Filter

The Day / Week / Month toggle (or a custom From–To date range) controls the System Activity chart and the activity total; it does not affect the asset counts, which are always current totals.

4.2 Stat Cards

Card	Meaning
Total Assets	Count of all Asset records.
Active Assets	Assets with Status = Active.
In Stock	Assets with Status = In Stock.
Maintenance	Assets with Status = Under Maintenance.
Assigned Assets	Assets with a non-empty Assigned To.
Unassigned Assets	Assets with a blank Assigned To.
Users	Count of records in the User Directory (Faculty).
Access Accounts	Count of login-enabled User accounts in the current Centre.
Unread Alerts	In-app notifications not yet marked read.
AMC Due (30d)	Assets whose AMC Expiry falls within the next 30 days.
Warranty Due (30d)	Assets whose Warranty Expiry falls within the next 30 days.

Every card is clickable and opens the matching filtered list.

4.3 Charts and Panels

- Asset Distribution — donut chart of assets grouped by Asset Type.
- Asset Status Overview — bar chart across Active / In Stock / Under Maintenance / Retired.
- System Activity — donut of Audit Log actions within the selected period.
- Coverage Forecast — Warranty vs AMC expiries bucketed into Expired / Due in 30 days / 31–60 days / 61–90 days.
- Recent Assets, Notifications & Alerts, Audit Activity — the five/six most recent records of each.
- Upcoming AMC & Warranty — coverage expiring within 60 days.
- Expired Assets — coverage that has already lapsed.

5. Master Data Modules

Five master data modules sit under Asset Management. Each follows the same pattern: a searchable, paginated directory table, an Add/Edit modal, a auto-generated Code, a Status of Active/Inactive, and (except Assets themselves) CSV/Excel Import and Export. Detailed field-by-field instructions for Department, Sub Department and Brand are in Section 7; Type and Subtype — the more involved two — have their own dedicated Section 6.

Module	Route	Code Prefix	Depends On	Import/Export
Department	asset-management/departments	DT	—	CSV
Sub Department	asset-management/sub-departments	ST	Department	CSV
Asset Type	asset-management/types	TE	—	CSV (with Subtype Parameters column)
Asset Subtype	asset-management/sub-types	SY	Asset Type, Brand	CSV (flat) and Excel workbook, one sheet per Type
Brand	asset-management/brands	BD	—	CSV

Note: Codes are generated automatically the moment a record is saved and cannot be typed in manually on the form — the Code field on Add/Edit is always shown read-only as “{PREFIX}-Auto” until saved.

6. Asset Type → Subtype → Parameters Workflow

This is the configuration model that drives everything else in the system: what specification fields an Asset shows, what a bulk Excel sheet's columns look like, and what gets validated on import. It has three layers:

Layer	Defines	Example
Asset Type	A category of equipment, plus the list of Subtype Parameter names that apply to every Subtype under it.	Type “Laptop” with parameters RAM, Processor, Storage.
Asset Subtype	A specific model/variant under a Type, with its own Brand and one fixed value per parameter the Type defines.	Subtype “Business Laptop” under Laptop, Brand Dell, RAM = 16GB, Processor = i7, Storage = 512GB SSD.
Asset	One physical unit. Selecting a Type and Subtype pulls in the Subtype's Brand and displays its parameter values as read-only reference — they are not retyped per asset.	Asset “John's Laptop”, Type Laptop, Subtype Business Laptop → shows Dell / 16GB / i7 / 512GB SSD automatically.

Note: Parameter values live on the Subtype, not on the Asset. If two assets share the same Subtype, changing that Subtype's configured value (e.g. correcting a typo in Processor) changes what is displayed for every asset using it.

6.1 Step 1 — Define Parameters on the Asset Type

How to access: Sidebar → Asset Management → Type → Add Type (or Edit an existing one).

The screenshot shows the 'Asset Types Directory' in the Agile Tech Solutions system. The sidebar on the left has 'Type' selected under 'Asset Management'. The main area shows a table with two entries:

TYPE	CODE	ASSETS	STATUS	ACTIONS
Computer Added 08 Sep 2026	TE-007	0	Active	[View] [Edit] [Delete]
Laptop Added 21 Aug 2026	TE-001	1	Active	[View] [Edit] [Delete]

Below the table, it says 'Showing 1 to 2 of 2 entries' with pagination controls.

Figure 6.1 — Asset Types directory

1. Enter the Type Name (e.g. “Laptop”) and, optionally, a Description.
2. In the Subtype Parameters section, click + Add Parameter to add one blank row per parameter name you want this Type to carry (e.g. RAM, then Processor, then Storage).
3. Use the × button next to a row to remove a parameter you no longer need.
4. Set Status (Active/Inactive) and click Create Type / Save Changes.

Required / Optional Fields

Field	Required?	Notes
Name	Required	Max 255 characters.
Code	Auto-generated	Prefix TE, read-only.
Description	Optional	Max 2000 characters.
Subtype Parameters	Optional	Any number of free-text parameter names; blank rows are discarded and duplicate names are collapsed to one on save.
Status	Required	Active or Inactive.

Validation

- Name is required.
- Status must be Active or Inactive.
- Parameter rows left blank when saving are silently dropped — they do not produce an error.

Example: Type “Printer” with parameters Print Type, Paper Size, Connectivity.

6.2 Step 2 — Create a Subtype and Fill In Values

How to access: Sidebar → Asset Management → Subtype → Add Subtype.

The screenshot displays the 'Asset Subtypes' directory in the Agile Tech Solutions Enterprise Workspace. The left sidebar shows the navigation menu with 'Subtype' selected under 'Asset Management'. The main content area features a table titled 'Asset Subtypes Directory' with 1 record available. The table has columns: SUBTYPE, CODE, ASSET TYPE, ASSETS, STATUS, and ACTIONS. The single entry is 'Laptop' (SY-002) with 0 assets and an 'Active' status. Above the table, there is a search bar, a 'Show 10 entries' dropdown, and buttons for 'Export' and 'Import'. A '+ Add Subtype' button is in the top right corner of the table area. The bottom of the page shows 'Showing 1 to 1 of 1 entries' and a pagination control.

Figure 6.2 — Asset Subtypes directory

1. Enter the Subtype Name (e.g. “Business Laptop”).
2. Select the Asset Type it belongs to — this immediately loads that Type's configured parameter list.
3. Select the Brand (from the Brand master — Section 7.3).
4. Leave Required field in asset forms and imports ticked if every one of this Type's parameters must have a configured value before this Subtype can be used (see Section 14).
5. Under Subtype Parameters, type a value into each field shown (these fields are generated from the selected Type; if the Type has no parameters configured, you'll see a message to configure the Type first).

6. Set Status and Save.

Required / Optional Fields

Field	Required?	Notes
Name	Required	Max 255 characters.
Code	Auto-generated	Prefix SY, globally unique, read-only.
Asset Type	Required	Must be an existing Type.
Brand	Required	Must be an existing Brand.
Required field in asset forms and imports	Optional (default: checked)	Governs the completeness check described in Section 14.
Subtype Parameters (one field per Type parameter)	Optional per field	Free text; blank is allowed unless completeness is enforced.
Description	Optional	Max 2000 characters.
Status	Required	Active or Inactive.

Validation

- Name, Asset Type and Brand are required.
- Only parameters that belong to the selected Type are ever saved against the Subtype — stray values are ignored.

Example: Subtype “Sample Printer” under Type Printer, Brand HP, Print Type = Laser, Paper Size = A4, Connectivity = WiFi.

6.3 Different Types Carry Different Parameters

Because parameters are defined per Type, two Subtypes under different Types never share a parameter list unless the Types themselves share parameter names.

Type	Subtype	Parameters
Laptop	Business Laptop	RAM, Processor, Storage
Desktop	Office Desktop	RAM, Processor, Graphics
Printer	Sample Printer	Print Type, Paper Size, Connectivity

6.4 How This Appears on the Asset Form

On Add/Edit Asset, selecting a Type filters the Subtype dropdown to only that Type's Subtypes. Once a Subtype is chosen, a read-only Subtype Parameters panel appears showing every parameter the Type defines together with the value configured on that Subtype. The asset's Brand is not picked separately — it is taken automatically from the selected Subtype.

Note: If a Type has no Subtypes yet, the Subtype field simply has nothing to select — the Asset can still be created against the Type alone, with Brand left unset until a Subtype exists.

7. Brand, Department & Sub Department

7.1 Department

Purpose

Represents the top level of the organisational structure that Assets and Users belong to (e.g. Finance, IT, Transport). Every Sub Department and every Asset is linked to one Department.

How to Access

Sidebar → Asset Management → Department.

How to Use

1. Click Add Department.
2. Enter Name and, optionally, Description.
3. Set Status.
4. Click Create Department.

The screenshot shows the 'Departments Directory' page in the Agile Tech Solutions system. The sidebar on the left contains navigation links for 'Department', 'Subtype', 'Type', 'Dashboard', 'Asset Management', 'User Management', 'Access Accounts', 'Data & Audit', and 'Administration'. The main content area has a search bar and a table of departments. The table has columns for 'DEPARTMENT', 'CODE', 'SUB DEPARTMENTS', 'ASSETS', 'STATUS', and 'ACTIONS'. The table lists 11 departments, all with a status of 'Active'.

DEPARTMENT	CODE	SUB DEPARTMENTS	ASSETS	STATUS	ACTIONS
Anusandhan Added 21 Aug 2026	DT-002	2	0	Active	[Edit] [Delete]
CC First Floor Added 21 Aug 2026	DT-003	2	0	Active	[Edit] [Delete]
CC Ground Floor Added 21 Aug 2026	DT-004	6	0	Active	[Edit] [Delete]
Chintan Added 21 Aug 2026	DT-005	6	0	Active	[Edit] [Delete]
Dispatch Added 21 Aug 2026	DT-006	1	0	Active	[Edit] [Delete]
Electric Deptt Added 21 Aug 2026	DT-007	1	0	Active	[Edit] [Delete]
Electric Room Added 21 Aug 2026	DT-008	1	0	Active	[Edit] [Delete]
Exchange Added 21 Aug 2026	DT-009	1	0	Active	[Edit] [Delete]
Health Centre Added 21 Aug 2026	DT-010	1	0	Active	[Edit] [Delete]
LIBRARY Added 21 Aug 2026	DT-011	1	0	Active	[Edit] [Delete]

Figure 7.1 — Department directory

Required / Optional Fields

Field	Required?	Notes
Name	Required	Max 255 characters.

Code	Auto-generated	Prefix DT.
Description	Optional	Max 2000 characters.
Status	Required	Active or Inactive.

Validation Rules

- Name is required.
- A Department in use by Sub Departments or Assets cannot be deleted — the system shows “This Department is in use and cannot be deleted.”

Example

Department “Samadhan”.

7.2 Sub Department

Purpose

A finer subdivision within a Department, used for more precise asset ownership and reporting (e.g. Transport under Samadhan).

How to Access

Sidebar → Asset Management → Sub Department.

How to Use

1. Click Add Sub Department.
2. Enter Name and select the parent Department.
3. Optionally add a Description, set Status, and Save.

Agile Tech SOLUTIONS

RECENTLY OPENED

- Sub Department
- Department
- Subtype

WORKSPACE

- Dashboard
- Asset Management
 - Department
 - Sub Department
 - Type
 - Subtype
 - Brand
 - Assets
- User Management
- Access Accounts
- Data & Audit
- Administration

Asset Management / Sub Departments

ENTERPRISE WORKSPACE

Sub Departments

Organize asset ownership within each department.

Sub Departments Directory
55 records available

+ Add Sub Department

Show 10 entries

Search sub departments...

Export Import

SUB DEPARTMENT	CODE	DEPARTMENT	ASSETS	STATUS	ACTIONS
Accounts Added 21 Aug 2026	ST-001	Samadhan	0	Active	
Admission Office Added 21 Aug 2026	ST-002	Chintan	0	Active	
AIRC Added 21 Aug 2026	ST-003	Anusandhan	0	Active	
ALUMNI Added 21 Aug 2026	ST-004	PGP	0	Active	
Anusandhan Added 21 Aug 2026	ST-005	Anusandhan	0	Active	
BOARD ROOM Added 21 Aug 2026	ST-006	Samadhan	0	Active	
CAO Room Added 21 Aug 2026	ST-007	Samadhan	0	Active	
Classroom Added 21 Aug 2026	ST-008	PGP (OLD)	0	Active	
Dean Faculty Office Added 21 Aug 2026	ST-009	Chintan	0	Active	
Dean Programme Added 21 Aug 2026	ST-010	Chintan	0	Active	

Showing 1 to 10 of 55 entries

Showing 1 to 10 of 55 entries < 1 >

© 2026 Agile Tech Solutions

Figure 7.2 — Sub Department directory

Required / Optional Fields

Field	Required?	Notes
Name	Required	Max 255 characters.
Department	Required	Must be an existing Department.
Code	Auto-generated	Prefix ST.
Description	Optional	Max 2000 characters.
Status	Required	Active or Inactive.

Validation Rules

- Name and Department are required.
- On the Asset form, the Sub Department dropdown is filtered to the currently selected Department's own Sub Departments only.

Example

Sub Department “TRANSPORT” under Department “Samadhan”.

7.3 Brand

Purpose

The manufacturer/vendor master. Every Asset Subtype is tied to exactly one Brand, and that Brand flows through to every Asset that uses the Subtype.

How to Access

Sidebar → Asset Management → Brand.

How to Use

1. Click Add Brand.
2. Enter Name; optionally Country and Support Contact.
3. Optionally upload a Brand Logo (JPG/PNG/WebP, up to 2 MB).
4. Set Status and Save.




Figure 7.3 — Brand directory

Required / Optional Fields

Field	Required?	Notes
Name	Required	Max 255 characters.
Code	Auto-generated	Prefix BD.
Country	Optional	Max 100 characters.
Support Contact	Optional	Max 255 characters (email or phone).
Brand Logo	Optional	JPG, PNG or WebP, up to 2 MB.
Status	Required	Active or Inactive.

Validation Rules

- Name is required.
- Logo file, if provided, must be an image under 2 MB.

Example

Brand “Dell”, Country “United States”.

8. Asset Creation & Editing

Purpose: register a physical asset in inventory and keep its identification, ownership, and coverage details up to date.

How to access: Sidebar → Asset Management → Assets → Add New Asset (or the pencil icon on an existing row to edit).

Figure 8.1 — Add New Asset form

8.1 How to Use

1. Enter the Asset Name.
2. Select Type. The Asset ID field is generated automatically from the asset name's first and last character plus a running sequence (e.g. AST-OR-001) — it cannot be typed.
3. Select Subtype (optional, filtered to the chosen Type). Once selected, the Subtype's configured parameters and their values are displayed as read-only reference underneath, and Brand is set automatically from the Subtype.
4. Enter Serial Number and FR Number (both required, Serial Number must be unique).
5. Select Department, then Sub Department (filtered to that Department).
6. Select Installation Date.
7. Optionally search and select Assigned To from the user directory.
8. Select Status.
9. Optionally attach an Asset Image (JPG/PNG/WebP up to 4 MB).

10. Optionally switch on Warranty and/or AMC and enter their expiry dates (Section 10).
11. Optionally add a Description.
12. Click Create Asset / Save Changes.

8.2 Required / Optional Fields

Field	Required?	Notes
Name	Required	Max 255 characters.
Type	Required	Must be an existing, Active Asset Type.
Subtype	Optional	Must belong to the selected Type; sets Brand automatically.
Brand	Set automatically	Taken from the selected Subtype; not entered directly.
Serial Number	Required	Must be unique across all Assets.
FR Number	Required	Max 255 characters.
Department	Required	Must be an existing, Active Department.
Sub Department	Required	Must belong to the selected Department.
Installation Date	Required	Valid date.
Assigned To	Optional	Free-text, populated by searching the user directory.
Status	Required	Active, In Stock, Under Maintenance, or Retired.
Asset Image	Optional	JPG, PNG or WebP, up to 4 MB.
Warranty Expiry	Optional	Only entered when the Warranty toggle is switched on.
AMC Expiry	Optional	Only entered when the AMC toggle is switched on.
Description	Optional	Max 5000 characters.

8.3 Validation Rules

- Name, Type, Serial Number, FR Number, Department, Sub Department, Installation Date and Status are all required.
- Serial Number must be unique — duplicate entries are rejected.
- Sub Department must belong to the selected Department, or the save is rejected.
- Subtype, if selected, must belong to the selected Type.
- Asset Tag/ID is never entered manually — it is always generated by the system.

Example: Name “Office Hour”, Type Laptop, Subtype Laptop (Brand Dell), Department Samadhan, Sub Department TRANSPORT, Serial Number 2354yrtjfd → Asset ID auto-generated as AST-OR-001.

8.4 Asset Details Page

Opening an Asset shows its full profile: identification fields, the Subtype's configured parameters and values, coverage dates, and (if permitted) a Delete Asset action in a clearly marked Danger Zone.

9. Asset Assignment & Status

9.1 Assigning an Asset from the Asset Form

The Assigned To field on Add/Edit Asset is a search box over the user directory. Typing filters the list live; selecting a name (or leaving it blank for Unassigned) sets that value directly on the asset.

9.2 Assigning an Asset from the User Directory

How to access: Sidebar → User Management → Users → open a user → Assign Asset (requires the faculty module's Assign permission).

1. Open Assign Asset for the user, and optionally set Filter by Asset Type to narrow the list.
2. Under “Available Assets to Add”, check one or more assets (only currently unassigned assets are listed). To remove an asset the user already holds, uncheck it under “Already Assigned to this User”.
3. Click Save Assignment Changes.

Assignment and unassignment are both handled in a single save, and multiple assets can be added to or removed from a user at once. For each newly checked asset, Assigned To is set to the user's name and its Status changes from In Stock to Active (any other status is left unchanged); for each unchecked asset, Assigned To is cleared and its Status reverts from Active to In Stock. Every assignment and unassignment is written to that user's Asset Assignment History and to the system Audit Log, and triggers a corresponding “asset assigned” or “asset unassigned” notification.

Note: An asset already assigned to someone is not offered again until it is unassigned.




Figure 9.1 — Assign Asset modal: check multiple available assets to add them, or uncheck an already-assigned asset to remove it, then Save Assignment Changes.

9.3 Assignment History

Sidebar → User Management → Users → open a user (eye icon) to reach their Asset History page. It shows Total Assignments and Current Assets stat cards, a Current Assigned Assets table (every asset presently held, with type, serial number, assigned date and assigned by), and a full Assignment History table below it covering

every past and current assignment (asset, department, assigned/unassigned date, assigned/unassigned by) — searchable and exportable to CSV. A user can hold, and this page will list, any number of currently assigned assets at once.

Agile Tech SOLUTIONS

RECENTLY OPENED

- Users

WORKSPACE

- Dashboard
- Asset Management
- User Management
 - Users
- Access Accounts
- Data & Audit
- Administration

Search assets, tickets, users...

Noida

SA Super Admin

Users / #12 / Asset History

ENTERPRISE WORKSPACE

Divya Reddy

User profile, current assets and complete assignment history.

DI Divya Reddy

USR-0011 divya.reddy@iiml.ac.in 9714502958

Back Export History

Total Assignments 4

Current Assets 4

Current Assigned Assets

4 currently assigned

ASSET	ASSET TAG	TYPE	SERIAL NUMBER	ASSIGNED AT	ASSIGNED BY
Epson EcoTank L14150	AST-SY-PR-02-0002	—	SN-SY-PR-02-0002	18 Sep 2026 05:42 AM	System (backfill)
Canon imageCLASS MF445dw	AST-SY-PR-01-0003	—	SN-SY-PR-01-0003	18 Sep 2026 05:42 AM	System (backfill)
Deleted Asset	—	—	—	18 Sep 2026 05:42 AM	System (backfill)
Deleted Asset	—	—	—	18 Sep 2026 05:42 AM	System (backfill)

Assignment History

4 assignment records

Active

Search asset, tag, type, serial, department or assigned by.

#	ASSET	ASSET TAG	TYPE	SERIAL NUMBER	DEPARTMENT	ASSIGNED AT	UNASSIGNED AT	ASSIGN
1	Epson EcoTank L14150	AST-SY-PR-02-0002	—	SN-SY-PR-02-0002	Facilities & Maintenance	18 Sep 2026 05:42 AM	Current	System
2	Canon imageCLASS MF445dw	AST-SY-PR-01-0003	—	SN-SY-PR-01-0003	Facilities & Maintenance	18 Sep 2026 05:42 AM	Current	System
3	Deleted Asset	—	—	—	—	18 Sep 2026 05:42 AM	Current	System
4	Deleted Asset	—	—	—	—	18 Sep 2026 05:42 AM	Current	System

© 2026 Agile Tech Solutions

Figure 9.2 — Asset History page for a user with multiple currently assigned assets.

9.4 Asset Status Values

Status	Meaning
In Stock	Not yet assigned or deployed; the default for newly received assets.
Active	In active use — set automatically when an unassigned/In Stock asset is assigned.
Under Maintenance	Temporarily out of service for repair.
Retired	Decommissioned and no longer in active inventory rotation.

10. Warranty & AMC

Every asset can optionally track two independent coverage periods: manufacturer Warranty and Annual Maintenance Contract (AMC). Both are entirely optional — the Add/Edit Asset form shows them as two switchable cards under “Warranty & AMC”, add coverage only when it applies.

How to Use

1. On the Asset form, switch on Warranty and/or AMC.
2. Enter the corresponding Expiry Date.
3. Switching a toggle back off clears its date.

Where Coverage Is Surfaced

- Dashboard: AMC Due (30d) and Warranty Due (30d) stat cards, the Coverage Forecast chart (Expired / Due in 30 days / 31–60 days / 61–90 days), Upcoming AMC & Warranty panel (next 60 days), and Expired Assets panel.
- Assets list: a Coverage Due (30 days) filter for Warranty or AMC.
- Reports: Warranty and AMC filters with Available / Expiring (30 days) / Expired / No Coverage / Any Coverage options (Section 13).

Note: Both fields are plain optional dates — there is no reminder configuration beyond the fixed 30/60/90-day dashboard buckets and the Reports filters.

11. Asset Import / Export

Two independent bulk workflows exist: bulk Assets (Excel, one worksheet per Asset Type) and bulk Asset Subtypes (Excel, also one worksheet per Asset Type). Both reuse the exact same Type/Subtype/Brand master-data validation as the manual forms — nothing typed in a spreadsheet bypasses those checks.

11.1 Bulk Asset Import & Export

How to access: Assets list → Export / Import buttons.

Export and the sample download both open a Select Asset Types dialog (all types checked by default = “All”) before generating an .xlsx workbook with one sheet per selected Type.

Column Structure (per Type sheet)

Column	Required on Import?	Notes
Asset Tag	Optional	Leave blank to create a new asset; enter an existing tag to update that asset instead.
Name	Required	
Asset Type	Required	Must match an existing Type, and must match the sheet it's on.
Subtype Code	Optional	Must belong to the sheet's Type.
Brand	Required	Must match an existing Brand.
Department	Required	Must match an existing Department.
Sub Department	Required	Must belong to the given Department.
Serial Number	Required	
FR Number	Required	
Installation Date	Required	Accepts YYYY-MM-DD, DD/MM/YYYY, DD-MM-YYYY, DD.MM.YYYY or MM/DD/YYYY — normalized automatically.
... one column per that Type's configured Subtype Parameters ...	Optional	Value must match the selected Subtype's configured value if both are present.
Assigned To	Optional	
Status	Required	Active, In Stock, Under Maintenance, or Retired.
Warranty Expiry / AMC Expiry	Optional	Same flexible date formats as Installation Date.
Notes	Optional	

Import Behaviour

- Asset Tag blank → a new asset is created with an auto-generated tag.
- Asset Tag matches an existing asset → that asset is updated in place (never duplicated).
- Asset Tag provided but not found → a new asset is created using that exact tag.
- Every row is validated independently; valid rows are saved even if other rows in the same file fail — failing rows are listed with the sheet name, row number, and a plain-language reason.

Example Import Errors

- Row 12: Invalid Subtype Code: LAP-999
- Row 15: Subtype LAP-002 does not belong to Asset Type Desktop

- Row 18: Brand “XYZ” does not exist

11.2 Bulk Asset Subtype Import & Export

How to access: Asset Subtypes directory → Export / Import. Import also opens a Select Asset Types dialog (“All” by default) before downloading a sample; the resulting workbook has one sheet per selected Type.

Column	Required?	Notes
Name	Required	
Code	Optional	Leave blank to create a new Subtype; enter an existing Code to update it.
Brand	Required	Must match an existing Brand.
Status	Required	Active or Inactive.
Description	Optional	
... one column per that sheet's Type's configured parameters ...	Optional	

Because each sheet is dedicated to one Type, a Laptop sheet's Ram/Processor/cpu columns never mix with a Printer sheet's Color Support/Print Speed columns — there is no shared “parameter_values” text column to fill in.

11.3 Reading the “Expected CSV Columns” Panel

The Type and Subtype master modules also support a simpler flat CSV import (separate from the Excel workbook flows above), reached from their own Import buttons. Hover the (i) icon in that panel for a plain-language explanation of the column format, including that the Type module's Parameters column uses a pipe character (|) to separate multiple parameter names in one cell (e.g. RAM|Processor|Storage).

Note: Download Sample always reflects the live, current configuration — if you add a parameter to a Type, the next sample download for that Type includes the new column automatically.

12. Centre / Location Workflow

The system currently supports two Centres: Noida and Lucknow. Nearly every record type — Assets, Asset Types, Asset Subtypes, Brands, Departments, Sub Departments, the User directory, Notifications, Backups, and Audit Logs — carries a Centre value and is automatically filtered to it.

12.1 For Access Accounts (Manager/Admin/Auditor/Viewer)

- Each Access Account is created against exactly one Centre (set when the account is created).
- That user only ever sees and creates records in their own Centre — there is no Centre selector for them.

12.2 For Administrators

- A Select Centre dropdown appears in the top bar, offering All, Noida, and Lucknow.
- Choosing Noida or Lucknow scopes every screen to that Centre's records only, and any record the Administrator creates while that Centre is selected is automatically stamped with it.
- Choosing All removes the Centre filter, showing every record from every Centre at once.
- Certain create/update actions (for example, adding a User or Access Account, or editing Roles & Permissions) require the Administrator to have a specific Centre selected — with All selected, the system responds “Please select a specific Centre before performing this action.”

Note: *Switching Centre does not move or duplicate data — it only changes which existing records the current view shows.*

13. Search, Filters and Reports

13.1 Global Search

The search box in the top bar searches live as you type (minimum 2 characters), across three groups, each limited to 5 results:

Group	Matches On
Assets	Asset Tag, Name, Serial Number, FR Number.
Users	Name, Email, Unique ID, Contact number.
Access Accounts	Name, Email, Unique ID, Contact number — Manager/Admin/Auditor/Viewer login accounts, each only shown if your role has View on that role's Access Accounts module.

Clicking a result opens that Asset's detail page, or — for a login-enabled user — that user's Access Account list filtered to them; a non-login user opens the User Directory instead.

13.2 Asset List Filters

- Search — Name, Asset Tag, Serial Number, or FR Number.
- Type, Department, Status.
- Installation Date range (From/To).
- Assigned filter — Assigned only or Unassigned only.
- Coverage Due (30 days) — Warranty or AMC expiring within the next 30 days.
- Sortable by Name, Serial Number, Installation Date, or Created date; page size of 10/25/50/100.

13.3 Reports

How to access: Sidebar → Data & Audit → Reports.

Agile Tech SOLUTIONS

RECENTLY OPENED

- Reports
- Users
- Brand

WORKSPACE

- Dashboard
- Asset Management
- User Management
- Access Accounts
- Data & Audit
 - Reports
 - Audit Logs
 - Backup & Recovery
- Administration

Search assets, tickets, users...

Select Centre

SB Screenshot Bot Super Admin

Home / Reports

ENTERPRISE WORKSPACE

Asset Reports

Filter and fetch asset records across ownership, classification, status, warranty, and AMC coverage.

Asset Report Builder

Choose one or more filters to fetch matching records

CLASSIFICATION

Type: All types | Brand: All brands | Status: All statuses

OWNERSHIP & ASSIGNMENT

Department: All departments | Sub Department: All sub departments | Assigned To: All assignments

COVERAGE

Warranty: All warranty records | AMC: All AMC records

Empty filters include every value in that field.

Fetch Report

Build your asset report

Select filters above and click Fetch Report to view live database records.

© 2026 Agile Tech Solutions

Figure 13.1 — Reports screen

1. Choose any combination of filters: Asset Type, Brand, Department, Sub Department, Assigned To, Status, Warranty coverage, AMC coverage.
2. Click Generate Report to run the filters and show a paginated result with summary counts (Total, Assigned, Warranty Due, AMC Due).
3. Export to CSV or Export to Excel to download the exact filtered result set.

Coverage Filter Options (Warranty and AMC, independently)

Option	Meaning
Available	Expiry date is more than 30 days away.
Expiring	Expiry date falls within the next 30 days.
Expired	Expiry date is in the past.
No Coverage	No expiry date set.
Any Coverage	An expiry date is set, regardless of when.

Note: Every report export is written to the Audit Log and triggers a system notification recording the filters used and the number of matching records.

14. Notification & SMTP Settings

Sidebar → Administration → Settings. Both tabs sit under the Settings: Advanced permission (settings_advanced) — a role needs the parent Settings module access box ticked as well as this sub-permission, or the tabs do not appear. View-only access shows the saved configuration with every field disabled; Update access is required to save changes.

14.1 Notification Settings

Purpose

Controls, per system event, whether an in-app notification and/or an email alert is sent, independently of one another. Preferences are scoped per Centre — each Centre keeps its own on/off switches for the same list of events.

How to Access

Sidebar → Administration → Settings → Notification Settings tab.

How to Use

1. For each Alert row, toggle the In-app switch and/or the Email switch.
2. For the two expiry alerts (AMC, Warranty), the fixed lead time — 30 days before expiry — is shown next to the alert name and is not editable from this screen.
3. Click Save Preferences to apply the changes.
4. Click Advanced Rules to open the full Notifications & Alerts centre for finer-grained alert rules (requires the notifications module View permission).

Available Alert Events

Event	Fires When	Default In-app	Default Email
AMC expiry alert	30 days before an asset's AMC coverage expires.	On	On
Warranty expiry alert	30 days before an asset's warranty expires.	On	On
New user alert	A User is created in the User Directory.	On	On
Deleted user alert	A User is deleted.	On	On
New access account alert	An Access Account (Manager/Admin/Auditor/Viewer) is created.	On	On
Deleted access account alert	An Access Account is deleted.	On	On
Asset assignment alert	An Asset is assigned to a user.	On	On
Report generation alert	A Report is generated or exported.	On	On
Asset unassignment	An Asset is unassigned from a	On	On

alert	user.		
Backup completed alert	A Backup finishes successfully.	On	On
Backup failure alert	A Backup fails.	On	On
Backup health alert	The scheduled backup health check finds an issue.	On	On

Validation Rules

- Both switches can be off at once — the event still occurs, it simply is not surfaced.
- Email alerts are only actually delivered if SMTP Settings are Enabled with a working configuration — see Section 14.2.

Note: Turning Email on for an alert here does not itself add recipients — emails go to the Alert Recipient Emails configured on the SMTP Settings tab.

14.2 SMTP Settings

Purpose

Configures the outgoing mail server used for every notification email the system sends. Settings saved here are stored in the database and override the server's MAIL_* environment defaults at runtime, without requiring a redeploy.

How to Access

Sidebar → Administration → Settings → SMTP Settings tab.

How to Use

1. Turn on Enable email delivery to activate these settings for notification emails.
2. Enter SMTP Host and Port (e.g. smtp.office365.com, port 587).
3. Optionally enter a Username and Password for the mail account.
4. Choose Encryption — TLS, SSL, or None.
5. Enter From Name and From Email — shown as the sender on outgoing alert emails.
6. Enter one or more Alert Recipient Emails, separated by commas, semicolons, or spaces.
7. Click Save SMTP Settings.
8. Click Send Test Email to confirm delivery before relying on the configuration.

Required / Optional Fields

Field	Required?	Notes
Enable email delivery	—	Master switch; while off, no notification emails are sent regardless of other fields.
SMTP Host	Required if enabled	Max 255 characters.

Port	Required if enabled	Numeric, 1–65535.
Username	Optional	Max 255 characters.
Password	Optional	Stored encrypted; leave blank on edit to keep the saved password.
Encryption	Optional	TLS, SSL, or None.
From Name	Required if enabled	Max 255 characters.
From Email	Required if enabled	Must be a valid email address.
Alert Recipient Emails	Required if enabled	Comma/semicolon/space-separated list, max 2000 characters.

Validation Rules

- Host, Port, From Name, From Email, and Alert Recipient Emails are only mandatory while Enable email delivery is on — they can be left blank while it is off.
- Send Test Email requires the configuration to already be Enabled with a Host and at least one recipient saved, otherwise the system responds “Enable SMTP and provide a host and notification recipient first.”

Example

Host smtp.office365.com, Port 587, Encryption TLS, From Name “Agile Tech Solutions IIM”, From Email alerts@agiletechsolutions.com, Recipients admin@agiletechsolutions.com, assets@agiletechsolutions.com.

Note: The password field never re-displays a saved password — it always shows as blank with a “Saved — leave blank to keep” placeholder, and is only replaced if a new value is typed.

15. Validations and Common Errors

A consolidated reference of validation messages you may encounter and what causes them.

15.1 Client-Side Field Validation (Real-Time)

A shared script (validation.js) runs live on every Add/Edit form across Assets, Users, Backups and Settings, and a separate Name Picker component is used for name fields on Department, Sub Department, Brand and similar master-data forms. Both validate as you type, before the form is even submitted.

- **Name fields (name="name"):** up to 50 characters; an inline error appears the moment the limit is exceeded.
- **Name Picker fields** (e.g. Department Head, Sub Department Manager): letters and spaces only, 3–50 characters — enforced live as you type via a type-ahead combo box.
- **Email fields (type="email"):** must match a standard name@domain.tld pattern.
- **Phone / Contact fields (name="contact" or "phone"):** non-digit characters are stripped automatically as you type, and the field must end up exactly 10 digits.
- **Any field marked required:** the browser blocks submission and shows an inline “Please fill out this field” prompt on the first empty required field.

Agile Tech SOLUTIONS

RECENTLY OPENED

- Assets
- Users

WORKSPACE

- Dashboard
- Asset Management
 - Department
 - Sub Department
 - Type
 - Subtype
 - Brand
- Assets
- User Management
- Access Accounts
- Data & Audit
- Administration

Add New Asset
Register an asset and capture its ownership and coverage details.

Asset Information
Identification, assignment and lifecycle details

Asset ID
AST-XX-001
Uses asset name's first and last character

Asset Name *
Enter asset name
Please fill out this field.
Canon Image...
Cisco Catalyst 9200
Dell OptiPlex 7020
Dell PowerEdge R740
Epson EB-X05
Epson EcoTank L14150

Type *
Select type

Subtype
Select subtype

Department *
Select department

Assigned To
Search users...
Search and pick from the user directory

FR Number *
Enter FR number

Installation Date *
dd/mm/yyyy

Asset Image
Choose File | No file chosen
JPG, PNG or WebP up to 4 MB

Warranty & AMC
Optional — add coverage only when it applies to this asset.

Warranty
Track manufacturer warranty

AMC
Track annual maintenance contract

Description
Add configuration, installation or handover details

Cancel | Create Asset

© 2026 Agile Tech Solutions

Figure 15.1 — Required-field validation on the Add Asset form.

15.2 Server-Side Validation Messages

If a rule above is bypassed (e.g. the request is submitted directly) or the issue can only be detected on the server, one of the following messages is returned instead:



ASSET MANAGEMENT SYSTEM

Welcome back

Enter your details to access your workspace.

Invalid email or password.

Email address

superadmin@ilm.com

Password

Enter your password

Remember me

Log in →




Figure 15.2 — Server-side validation error shown on the Login screen.

Message	Where	Cause / Fix
Invalid email or password.	Login	Wrong credentials, or the account is Inactive / login-disabled.
Your account does not have access to any module. Contact an administrator.	Login	The account exists but has no View permission on any module.
Please select a specific Centre before performing this action.	Various (Administrators)	Centre selector is set to All; pick Noida or Lucknow first.
This asset is no longer available for assignment.	Assign Asset	Someone else was assigned this asset in the meantime, or it changed Type.
Asset Type “...” does not exist.	Asset bulk import	The Asset Type column value does not match any existing Type name.
Asset Type “...” does not match this sheet's Asset Type “...”.	Asset bulk import	The row's Asset Type column disagrees with the sheet it is on.
Invalid Subtype Code: ...	Asset / Subtype bulk import	The Subtype Code column value does not match any existing Subtype.
Subtype ... does not belong to Asset Type ...	Asset / Subtype bulk import	The Subtype exists but under a different Type than the sheet.
Brand “...” does not exist.	Asset / Subtype bulk import	The Brand column value does not match any existing Brand — brands are never auto-created.
... value “...” does not match the configured value “...” for Subtype “...”.	Asset bulk import	A parameter column's value disagrees with what is configured on that row's Subtype; fix the sheet or the Subtype configuration.
Parameter “...” is required for Subtype “...” but has no configured value.	Asset bulk import	The Subtype has “Required field” checked but one of its Type's parameters was left blank on the Subtype itself — fill it in on the Subtype form first.
... must be a recognized date ...	Asset bulk import	The date column could not be parsed in any supported format — use YYYY-MM-DD, DD/MM/YYYY, DD-MM-YYYY, DD.MM.YYYY, or MM/DD/YYYY.
This {record} is in use and cannot be deleted.	Any master module	Another record (Sub Department, Asset, etc.) still references it.
Serial Number must be unique / Asset Tag ‘...’ already exists.	Asset form / import	Another asset already uses that Serial Number or Asset Tag.

16. Complete Recommended Workflow

The order below sets up master data in the sequence each step depends on, then moves into day-to-day operation.

1. Administrator selects the correct Centre (or All, for cross-centre setup).
2. Configure Roles & Permissions for the four dashboard roles.
3. Create Departments, then their Sub Departments.
4. Create Brands.
5. Create Asset Types and define each one's Subtype Parameters.
6. Create Asset Subtypes under each Type, selecting Brand and filling in every parameter value.
7. Create Access Accounts (Manager/Admin/Auditor/Viewer) and add Users to the User Directory.
8. Add Assets one at a time, or prepare and import a bulk Asset workbook (download the sample for the relevant Types first).
9. Assign assets to users, either from the Asset form or from the user's Assign Asset action.
10. Add Warranty/AMC coverage where it applies.
11. Use the Dashboard and Reports to monitor coverage expiry, assignment status, and system activity on an ongoing basis.
12. Use Export (Assets, Subtypes, or Reports) whenever data needs to leave the system for offline review or another system.

17. FAQ and User Best Practices

Q: Why can't I type the Asset ID or a master record's Code myself?

A: Both are generated automatically when the record is saved, using a fixed prefix per module (e.g. TE for Types, SY for Subtypes, DT for Departments) so codes stay unique and consistent.

Q: Why is the Brand field missing from the Asset form?

A: Brand is no longer chosen directly on an Asset. It comes from the Subtype you select, since every Subtype already has its own fixed Brand.

Q: I selected a Type but no Subtypes appear — why?

A: That Type has no Subtypes configured yet. Create at least one Subtype under it (Section 6.2), or leave Subtype blank and create the Asset against the Type alone.

Q: Why does my bulk import say a value “does not match the configured value”?

A: The parameter value typed in your sheet disagrees with what is saved on that Subtype's own configuration. Update the Subtype record (or correct the sheet) so both agree.

Q: Can I import a brand new Asset Type or Brand through the Asset import?

A: No. Types and Brands are never created automatically during import — they must already exist in their own master modules first.

Q: What happens if I re-import a file with the same Asset Tag or Subtype Code?

A: The matching Asset or Subtype is updated in place, not duplicated. Leave the Tag/Code column blank to always create a new record instead.

Q: Why can't I see records another Centre created?

A: Almost all data is scoped to a Centre. As an Access Account you only see your own Centre; as an Administrator, switch Select Centre to All to see everything.

Q: Why don't my permission changes seem to apply to a user I'm testing with?

A: Permissions are checked live from the Roles & Permissions table by Role, not cached per user session in a way that requires re-login — double-check the correct role tab was saved.

Q: An asset I assigned still shows Status “Under Maintenance” — is that a bug?

A: No. Assignment only auto-changes Status from In Stock to Active; any other status (including Under Maintenance) is left exactly as it was.

Best Practices

- Set up Departments, Brands, and Asset Types/Subtypes completely before bulk-importing Assets — imports validate against these masters and never create them automatically.
- Keep Subtype parameter values accurate and complete; they are shown as the specification of record on every asset that uses that Subtype.
- Use Download Sample before every bulk import so the column set always matches your current configuration exactly.
- Reserve the All Centre view for genuinely cross-centre administrative work; do day-to-day data entry with a specific Centre selected so new records are stamped correctly.
- Review the Dashboard's Coverage Forecast and Reports' Warranty/AMC filters regularly so coverage renewals are never missed.

- Grant the narrowest permission set a role actually needs — View alone for reference-only roles, and reserve Delete/Import for the accounts that truly require them.