

Partner Integration Guide



Table of Contents

Executive Summary.....	3
Setting Up a Test Account & Production Account.....	4
Solo Card Reader Simulator.....	6
Cloud API Integration Guide.....	7
1. Overview.....	7
2. Requirements & Considerations.....	8
3. Authorisation.....	9
3.1 Option 1: API Keys.....	9
3.2 Option 2: Authorisation Code Flow.....	10
3.2.1 Refresh Token Flow.....	12
4. Affiliate Key.....	13
4.1 What is an Affiliate Key?.....	13
4.2 Create Your Affiliate Key.....	13
4.2.1 Option A:.....	13
4.2.2 Option B:.....	14
4.3. Using Affiliate Key with Cloud API.....	14
5. Steps to Integrate Cloud API.....	15
5.1 Prepare the Solo Card Reader.....	15
5.2 Generate the Pairing Code.....	15
5.3 Pair the Card Reader to the Merchant Account.....	16
5.4 Wait for Confirmation.....	17
6. REST APIs.....	17
6.1 Readers API.....	17
6.1.1 Create a Reader Checkout.....	17
6.1.2 List Readers.....	19
6.1.3 Create a Reader.....	20
6.1.4 Retrieve a Reader.....	20
6.1.5 Update a Reader.....	20
6.1.6 Delete a Reader.....	21
6.1.7 Create a Reader Terminate Action.....	21
7. Checkout Status.....	22
7.1 Webhook.....	22
7.2 Polling Transactions API.....	23
8. Tipping (Optional).....	23
9. Updating the Firmware.....	24
10. Lock the Solo Screen.....	25
11. Unlock the Solo Screen.....	25
12. Last Steps.....	26
13. Customer Support Reference Guide.....	26

13.1 FAQs.....	27
13.2 Step-by-Step Guides for Your Customers.....	28

Executive Summary

This guide provides a comprehensive overview and **step-by-step instructions** to integrate **Cloud API** with your system. It covers all essential aspects of the integration process, including how to implement Cloud API, the authentication flows, and the use of the affiliate key for partner and merchant attribution.

You will find a detailed explanation of the Cloud API capabilities, system requirements, pairing procedures, and how to set up both **test and production accounts**. Additionally, recommendations and known limitations are discussed to ensure smooth integration and optimal performance.

Whether you are a developer, partner manager, or sales engineer, this document equips you with the necessary information and practical steps to successfully implement Cloud API and manage and launch your integration effectively.

Setting Up a Test Account & Production Account

Before starting the Cloud API integration, we recommend using a **test account** during the implementation, and not a production account. Production accounts undergo regular checks and any behaviour such as using your own card, or sending multiple payments, can trigger the account to be investigated, and possibly be closed.

Transactions processed with test accounts will always be successful. However, please note that the card that you used will never be charged. Thus, no test cards are needed, you can just any card.

In order to get a test account, contact us directly to issue one for you at integration@sumup.com or your partner manager. Test accounts never expire.

Once the integration is finalised, please replicate all the settings you made in your **test account** in your **production account**, and make sure the integration is nested in that account, and not in the test account.

If you haven't registered a production account yet, please do so via the landing page, or alternatively you can also sign up via me.sumup.com. The flow is the same as the regular merchant onboarding. You'll be asked for business details, personal information, and ID verification. If you're not the company's authorised representative, we will also need a power of attorney and the managing director's proof of identity.

Although in some cases, you may never take a payment using your production account, and you are only acting as an integrator, a production account where you have replicated the integration setup is still needed.

A few considerations:

- Only the administrator of the production account has access to the entirety of the SumUp account, including the possibility to make integration changes. No other member

(subaccount) will be able to make such changes. Thus, you may need to share the credentials with the developer.

- By default, when using a test account, all transactions will be successful. To test **unsuccessful transactions**, please introduce 11€ (or equivalent). Nevertheless, if a transaction is unsuccessful (*failed*), you will **not** have visibility **of the cause of the error** (insufficient funds, denied by the issuing bank, etc).

Solo Card Reader Simulator

You should either receive a Solo card reader from your partner manager or, alternatively, you can also use the Solo virtual terminal [simulator](#), which enables you to test the integration without the need of a physical device. Please note that the physical device is the same as the one to process real transactions, as there are no test devices.

With the simulator, you will be able to replicate successful and failed transactions only with your test accounts.



The tipping feature is not available with the Solo reader simulator.

SumUp card readers are **linked to the country of the SumUp account used for the first transaction**, and cannot be used with a SumUp account from a different country after that.

Thus, please make sure you test with card readers that have only been used with SumUp accounts of the same country as your test account.

Cloud API Integration Guide

1. Overview

The Cloud API solution enables initiating transactions from a system running on any platform (Windows, iOS, Linux, Android, web-based, etc.) and processes payments through the SumUp Solo card reader.

Key advantages of this integration include:

- Compatibility with any operating system and platform
- Ability to process simultaneous transactions to multiple Solo card readers
- No distance limitation between POS device and Solo card reader; remote transactions supported
- No Bluetooth connection required
- PCI compliance ensuring secure and compliant transactions

Supported features of Cloud API:

- Debit, credit, and installment transactions
- Pairing multiple Solo card readers to a single SumUp account
- Naming each Solo card reader for a smoother checkout experience
- Webhooks for real-time transaction result updates
- Wi-Fi and mobile data connectivity

2. Requirements & Considerations

- Compatible exclusively with Solo card reader
 - Firmware version of the Solo card reader must be 3.3.18.X or higher (latest firmware is recommended)
 - The Solo card reader should be **logged out** of any SumUp account before connecting it with Cloud API
 - We highly recommend to have the card reader charging continuously, maintaining a minimum battery level of 5% for successful transactions.
 - To receive notifications on incidents affecting SumUp systems, subscribe to the official status page [here](#)
 - Solo does not support WiFi networks with hidden SSID, nor 5GHz. However, should you need to open traffic just to certain routes, please note that the primary services used by Solo are hosted under [sumup.com](#). We also rely on public DNS (8.8.8.8 + 8.8.4.4) and NTP servers. Assuming those public services remain accessible, then allowing sumup.com should be sufficient to handle all of Solo's networking use-cases
 - The minimum amount to process a transaction is:
 - Eurozone - 1 EUR
 - BG - 2 BGN
 - CZ - 30 CZK
 - DK - 8 DKK
 - HU - 1 HUF
 - NO - 10 NOK
 - PL - 1 PLN
 - RO - 5 RON
 - SE - 10 SEK
 - We do not provide test cards, however, our test accounts allow you to perform testing without incurring any actual charges.
-

3. Authorisation

To start processing payments via the Solo card reader, and have access to other public APIs, it is necessary that you obtain an access token. At the moment, SumUp offers two methods of obtaining such a token. The choice of method that you choose to follow will depend on what works best for you.

Please note: The decision to go for one flow over the other would be solely up to you and your business needs.

3.1 Option 1: API Keys

API keys allows you to access all the public REST APIs that SumUp offers, as it has all the permissions enabled by default, and it does not expire.

Each merchant can create their own keys in the [API keys](#) page, once logged in.

Please note: It is not possible to create API keys on behalf of your merchants. This will have to be performed by the merchants.

You can find a step-by-step guide with pictures at the end of this document under the section **13.2 Step-by-Step Guides for Your Customers**

In the API key section, there are two types of keys listed:

Public key Public key
Secret key Secret key (only visible once you have created an API key)

Only the keys marked in grey, i.e., *secret keys*, are the ones to be used. The token has a `sup_sk_` prefix.

Keep your API keys confidential as they grant full API access.

Lastly, make sure that you either save the .txt file containing your API key upon creation, or that you copy it and store it. It will not be shown again after closing the window.

Example of an authenticated API call using an API key:

None

```
curl https://api.sumup.com/v0.1/me -H 'Authorization: Bearer sup_sk_XXX'
```

3.2 Option 2: Authorisation Code Flow

This flow allows applications to request permission to act on behalf of SumUp merchants.

- The access token obtained using this flow needs to be passed in the authorisation header similar to API keys.
- When requesting an access token, include these scopes:
 - `payments` (must be enabled by SumUp, please contact integration@sumup.com)
 - `transactions.history`
 - `user.app-settings`
 - `user.profile`
 - `readers.read`
 - `readers.write`

Please note: The access token is always valid for a limited time, i.e. 3600 seconds (1 hour). However, the refresh token is valid for 6 months once it is generated. A new refresh token will also be issued when a valid refresh token is used within 30 days prior to the expiration (150 to 180 days time frame) of the valid refresh token. The new token will be valid for another 6 months. See details below on how to use the Refresh Token flow.

Good to know:

- If the password of the SumUp account is changed, this will trigger the token to expire before the expiration date.
- In case of any system wide changes, this can also trigger token expiration.


Example authenticated request using an access token:

None

```
curl https://api.sumup.com/v0.1/me -H 'Authorization: Bearer at_classic_XXX'
```

Process:

- Redirect users to <https://api.sumup.com/authorize> with required parameters.
- Users authorise the app with requested scopes; on acceptance, the server redirects to your app with an authorisation code.



*Language selection is available on the bottom left of the screen. Additionally, adding a custom logo is possible by providing **Logo URL** in your OAuth2 app settings.*

- Exchange the authorization code at <https://api.sumup.com/token> to receive access and refresh tokens.

Example Token Response:

```
None
{
  "access_token":
  "565e2d19cef68203170ddadb952141326d14e03f4ccbd46daa079c26c910a864",
  "refresh_token":
  "d180031bfe9bac36c336e5746637810272546865e9c9586012f462a56f3fe9af",
  "token_type": "Bearer",
  "expires_in": 3600
}
```

The `access_token` authorises API calls. Use the `refresh_token` to renew expired tokens without user interaction.

3.2.1 Refresh Token Flow

To refresh an access token, send a request to <https://api.sumup.com/token> with the `refresh_token`.

- Refresh tokens are valid for 6 months by default.
- After expiry, a new authorisation flow is required.
- Using a refresh token within 30 days before expiry issues a new refresh token valid for another 6 months.
- Invalid refresh tokens due to password changes or scope modifications require user reauthorization.

Handle failed refresh attempts gracefully by prompting users to log in again.

4. Affiliate Key

4.1 What is an Affiliate Key?

An affiliate key is one unique credential linked to a SumUp merchant account. It serves two primary purposes:

- **Partner Authentication:** Ensures that partner applications can authenticate with SumUp.
- **Merchant Attribution:** Associates all merchant accounts linked to the affiliate key with the partner.

Since the affiliate key is used to authenticate your app, **only one is necessary per partner**. Please **use one single affiliate key for all your integrations** and avoid having multiple. Once created, an affiliate key cannot be deleted nor changed.

4.2 Create Your Affiliate Key

Follow either option A or option B below to set up your affiliate key.

4.2.1 Option A:

1. Log into me.sumup.com
2. Click your account name (top-right corner)
3. Select Settings
4. Scroll down and select Toolkit under the 'For developers' section
5. Log in to the developers portal with your SumUp credentials
6. In the top-right corner, go to Account and select Affiliate Keys
7. In the Affiliate key field, enter your Application ID. You can associate multiple Application IDs with the same affiliate key. If unsure, request this information from your development team.
8. Click Add Application ID

9. Your new affiliate key will appear at the top of the Application IDs list.

4.2.2 Option B:

1. Log in to developer.sumup.com/affiliate-keys with your SumUp account credentials
2. Navigate to Account > Affiliate Keys
3. Enter the Application ID in the Affiliate Keys field (request from your dev team if unsure)
4. Click Add Application ID
5. The newly created affiliate key will appear at the top of the list

4.3. Using Affiliate Key with Cloud API

The affiliate key is included in the *Create a Reader Checkout* API request. This request includes an **affiliate** section with two fields:

- **app_id**: The application ID discussed above
- **key**: The unique affiliate key assigned to each SumUp account and mandatory for merchant checkout requests

Example checkout request snippet:

```
None
{
  "affiliate": {
    "app_id": "your_application_id",
    "key": "your_affiliate_key"
  },
  "checkout": {
    "amount": 10.00,
    "currency": "EUR",
    "description": "Test Transaction"
  }
}
```

Note: The `app_id` and `key` must match the values in the affiliate key section of the SumUp account settings.

5. Steps to Integrate Cloud API

5.1 Prepare the Solo Card Reader

If logged in with your SumUp account on the Solo card reader, log out:

- Drag the top middle arrow down to open the menu
- Tap Settings > About > Logout

5.2 Generate the Pairing Code

In order to initiate a payment on the Solo card reader, the device must be enrolled with the merchant account. This enrollment process is the reader pairing.

The pairing process starts on the card reader side by generating the pairing code.

Requirements:

- Both your application and the Solo card reader must be connected to the internet (not necessarily the same network)
- Pairing code expires after 5 minutes—restart if necessary

Steps:

1. Open menu
2. Go to Connections > API or Cloud API > Connect
3. The device displays an 8-9 character pairing code
4. Use this code to pair the Solo card reader to your system
5. Upon success, you receive a reader ID

5.3 Pair the Card Reader to the Merchant Account

Make this HTTP POST call with the pairing code and replace merchant_code with your merchant ID, which is the ID which starts with “M” that you will find on the top right corner of your SumUp [dashboard](#):

None

```
POST https://api.sumup.com/v0.1/merchants/:merchant_code/readers
```

Example request:

None

```
{
  "pairing_code": "918MPQHZ",
  "name": "Frontdesk",    // optional
  "meta": {}             // optional custom metadata
}
```

Successful Response:

None

```
{
  "id": "rdr_3MSAFM23CK82VSTT4BN6RWSQ65",
  "name": "Frontdesk",
  "status": "processing",
  "device": {
    "identifier": "200100010001",
    "model": "solo"
  },
  "created_at": "2023-05-09T14:50:20.214Z",
  "updated_at": "2023-05-09T14:52:58.714Z"
}
```

The pairing process is initiated and awaiting device confirmation.

5.4 Wait for Confirmation

After pairing, the card reader shows a confirmation screen and transitions to idle.

To unpair your Solo card reader from your system, please jump to section **6.1.6 Delete a Reader** or visit the following [link](#).

6. REST APIs

The following APIs are exclusive to our Cloud API integration.

For additional features, such as [refunds](#), [receipts](#), and [retrieve merchant](#) information, or [retrieve merchant profile](#) (using each merchant's OAuth token to retrieve profile information), among others, please refer to the full catalog of [REST APIs](#). You can add any of those to your integration alongside the mandatory Cloud APIs described here.

For a smooth user experience, we recommend integrating as many REST APIs as possible into your system. This allows transaction insights, refunds, etc. directly in your environment without having to switch to the SumUp app or SumUp dashboard. The SumUp app and dashboard are built for the standard merchant journey and can't be customised for integration users, so keeping everything in your system helps avoid confusion.

6.1 Readers API

6.1.1 Create a Reader Checkout

Starts a payment on the card reader.

Endpoint:

```
None
POST
https://api.sumup.com/v0.1/merchants/:merchant_code/readers/:reader_id/checkout
```

Example request:

```
None
{
  "description": "Some custom description",
```

```

"total_amount": {
  "value": 123,
  "currency": "EUR",
  "minor_unit": 2
},
"return_url": "https://webhook.site/1811d2d7-b68b-4af0-91e5-78424a554d2d",
"card_type": "credit",          // optional
"installments": 1,             // optional
"affiliate": {                 // optional
  "app_id": "com.example.app",
  "key": "1994f9e6-d463-4007-aa14-3642107b2713",
  "foreign_transaction_id": "UNIQUE ID"
}
}

```

Successful response:

```

None
{
  "data": {
    "client_transaction_id": "f4f42e17-768e-4cc0-adf8-53aaed17874b"
  }
}

```

Notes:

- Transactions time out after 60 seconds
- To cancel before timeout, use the Create a Reader Terminate Action API

6.1.2 List Readers

Lists all readers paired to a SumUp merchant account (only Solo card readers connected via Cloud API).

Endpoint:

None

GET https://api.sumup.com/v0.1/merchants/:merchant_code/readers

Example response:

None

```
{
  "items": [
    {
      "id": "rdr_3MSAFM23CK82VSTT4BN6RWSQ65",
      "name": "Frontdesk",
      "status": "paired",
      "device": {
        "identifier": "200100010001",
        "model": "solo"
      },
      "meta": {},
      "created_at": "2023-01-18T15:16:17Z",
      "updated_at": "2023-01-20T15:16:17Z"
    }
  ]
}
```

6.1.3 Create a Reader

Pairs a new card reader.

Endpoint:

None

POST https://api.sumup.com/v0.1/merchants/:merchant_code/readers

6.1.4 Retrieve a Reader

Retrieves the details of an existing card reader.

Endpoint:

None

GET https://api.sumup.com/v0.1/merchants/:merchant_code/readers/:reader_id

6.1.5 Update a Reader

Updates the information of a specific card reader.

Endpoint:

None

PATCH https://api.sumup.com/v0.1/merchants/:merchant_code/readers/:reader_id

Example Request:

None

```
{
  "name": "Frontdesk 2",
  "meta": {
    "custom": "value"
  }
}
```

6.1.6 Delete a Reader

Unpairs and deletes a card reader.

Endpoint:

None

DELETE https://api.sumup.com/v0.1/merchants/:merchant_code/readers/:reader_id

Note: Deleting requires generating a new pairing code to reconnect.

Alternatively, you can also unpair the card reader via the SumUp dashboard:

<https://me.sumup.com/en-gb/readers>

Disconnect a Card Reader

After unpairing the card reader by calling the [Delete a Reader API](#), please follow these steps on the device:

- Turn on the Solo card reader
- Open menu > Connections > API / Cloud API > Disconnect

6.1.7 Create a Reader Terminate Action

Stops the current transaction on a target card reader. Having the latest firmware is recommended.

Endpoint:

None

POST

https://api.sumup.com/v0.1/merchants/:merchant_code/readers/:reader_id/terminate

7. Checkout Status

Currently, there are two ways to get the transaction status: Via webhook or polling the Transactions API.

7.1 Webhook

SumUp notifies your POS using the `return_url` from the Create Reader Checkout request whenever transaction status changes.

Example webhook payload:

```
None
{
  "id": "5158cc37-6cc0-4592-acc3-523311546446",
  "event_type": "solo.transaction.updated",
  "payload": {
    "client_transaction_id": "f4f42e17-768e-4cc0-adf8-53aaed17874b",
    "merchant_code": "M1234567",
    "status": "failed",
    "transaction_id": "1eee2e01-60a0-68cd-be40-27916874b8b3"
  },
  "timestamp": "2024-03-15T15:24:54.868301Z"
}
```

- Webhooks provide limited transaction details. For full details, call the [Transactions API](#).
- Implement a timeout; if webhook does not arrive, fallback to polling the API.
- Possible statuses: `Successful` or `Failed`.

7.2 Polling Transactions API

Fetch transaction status programmatically; start polling 6-7 seconds after initiating a transaction.

Endpoint:

None

GET

```
https://api.sumup.com/v2.1/merchants/:merchant_code/transactions?client_transaction_id=YOUR_CLIENT_TRANSACTION_ID
```

Example Response:

None

```
{
  "id": "1ee25b10-fa6a-6399-93b0-654a9c6bb80b",
  "transaction_code": "TDA9DPHA7F",
  "merchant_code": "MERCHANT_CODE",
  "amount": 1.23,
  "currency": "EUR",
  "timestamp": "2023-07-18T21:21:29.748Z",
  "status": "SUCCESSFUL",
  "payment_type": "POS",
  "entry_mode": "contactless",
  "client_transaction_id": "4b787723-ea5c-4579-9b6c-1f50bdac2cec",
  "internal_id": 4866711358
}
```

Note: Transactions API may return **404 - Not Found** immediately after checkout due to processing delays.

8. Tipping (Optional)

Note: Feature availability may vary by market—please consult SumUp.

Example request with tipping:

```
None
{
  "description": "Cloud API transaction demo",
  "total_amount": {
    "value": 1000,
    "currency": "EUR",
    "minor_unit": 2
  },
  "tip_rates": [
    0.1,
    0.2,
    0.3
  ],
  "affiliate": {
    "app_id": "com.example.app",
    "key": "sup_afk_XXXXXXXXXXXXXXXXXXXX",
    "foreign_transaction_id": "UNIQUE ID"
  }
}
```

9. Updating the Firmware

Starting version 35, firmware updates will be downloaded in the background. The card reader will only restart if no transaction is processed in the span of 5 min.

- During firmware rebooting, no transactions can be processed
- We recommend the card reader to be connected via Wi-Fi for firmware updates; however, updates via mobile data are also possible
- Firmware update notifications appear:
 - Every 6 hours
 - After reboot

10. Lock the Solo Screen

Any Solo card reader with firmware version 34, and above, offers the possibility to lock the screen, preventing customers from unauthorized use.

To lock the Solo screen, please do the following:

- Go to menu > Settings > Security Lock > Enable the option

11. Unlock the Solo Screen

To unlock the screen, please tap three times on the screen.

12. Last Steps

Once the integration is complete, please email integration@sumup.com and CC your partner manager with the following information:

1. Test account merchant ID (MID) or email associated with the test account
2. Production merchant ID (MID) or email associated with the production account
3. The authorisation flow used to obtain the access token
4. In case you are using the authorisation code flow, please email us at integration@sumup.com to enable the restricted scopes
5. Affiliate key implemented in the production account's checkout
6. REST APIs implemented alongside the Cloud API integration

For troubleshooting purposes concerning the integration or any merchant issue, please always include the following information:

1. Merchant ID or email linked to the SumUp account affected
2. Transaction ID and/or date and amount of transaction, if relevant
3. Serial number of the card reader, if relevant

13. Customer Support Reference Guide

The SumUp App and [SumUp dashboard](#) are designed for general merchant use and are not customised for integration merchants. By implementing the [REST APIs](#), you can customize the experience and display the necessary data directly within your own system.

Whether or not you decide to implement additional APIs, we strongly recommend creating a Help Center article that clarifies where information can be found and explain, at least, how to connect the card reader to your system.

13.1 FAQs

For ease of use, we have collected a set of frequently asked questions to help address common scenarios.

Battery: Continuous API connectivity can drain the battery quickly, therefore, we recommend having the readers plugged continuously. Maintaining a charge above 5% ensures smooth, uninterrupted transactions. Transactions processed with a battery level of 5%, or below, will be unsuccessful and *will not be shown* on the transaction history

Error Visibility: Currently, we do not expose detailed information regarding the causes of transaction failures. Some errors, such as not having permission to `readers.delete` or `readers_checkout_create` are not to be interpreted as such, as the error might lay within the body, URL, header or HTTP method of the request.

Minimum Transaction Amount: The minimum amount to process a transaction is:

- Eurozone - 1 EUR
- BG - 2 BGN
- CZ - 30 CZK
- DK - 8 DKK
- HU - 1 HUF
- NO - 10 NOK
- PL - 1 PLN
- RO - 5 RON
- SE - 10 SEK

Network Compatibility: The Solo card reader does not support Wi-Fi networks with hidden SSID, nor 5GHz network.

Refunds: Refunds can only be processed when there are sufficient funds available in the SumUp account balance. Payouts that have already been transferred to a bank account cannot be used to cover refunds. This means that immediately after a payout, refunds may not be possible until new transactions increase the available outstanding balance. SumUp will never withdraw funds from a customer's bank account to fund a refund. For more information, please visit the following [link](#).

Solo Printer: Our Solo printers only work when the Solo card reader is used in standalone mode, not with Cloud API. It prints only transaction receipts, not fiscally compliant receipts. If inclusion of this information on invoices generated by an external system is required, it can be enabled by implementing the [Receipt API](#).

VAT: At the moment, if VAT is added to transactions with Cloud API, this won't be sent in a separate field to the card reader, nor will this piece of information be retrievable using the APIs.

13.2 Step-by-Step Guides for Your Customers

The following visuals and links are intended to help you provide clear guidelines to your customers as these are one of the few steps they will need to do on their own.


Pairing the Solo Reader

Please find a step-by-step guide [here](#).


Generating API Keys

To generate an API key, please refer to steps below:

- Go to developer.sumup.com
- Click on “Log in” in the top right corner
- Enter your SumUp credentials to log in

A screenshot of the SumUp login page. The page has a white background with the SumUp logo in the top left corner. The main heading is "Log in". Below it, there is a link "New to SumUp? Register". The login form consists of two input fields: "Email address" with the placeholder text "you@example.com" and "Password" with a toggle icon for visibility. Below the password field is a link "Forgot your password?". A blue "Next" button is located at the bottom right of the form.

- Once logged in, go to Account and click on API keys



- Name your API key and click on “Create”

API keys

API keys are static authorization tokens that allow you to call SumUp APIs on your behalf. Read more about API keys in our [authorization guide](#).

Type	Name	Token	Created At	Options
Public key	Public API Key	sup_pk_0oFptJlelwlk3Nvu10N73Jdri58hLSI2h	13/04/2023	

Name your API key

Cancel+ Create

- Important: Copy or save your API key file appearing on your screen

Copy your API Key now.

SumUp doesn't store your app API keys. If you lose your API key, you'll need to revoke it and get a new one.

API key

Download *.txtNext

Once generated, please insert the API key in the partner's platform where your partner instructed you.