Richco International Inc.

Heat Prevention Plan

I. INTRODUCTION

Richco's heat-illness prevention plan is provided as a resource to our employees and is not designed to address all work site scenarios and heat stress hazards.

This plan is designed to protect our employees from developing heat-related illnesses in healthy, physically fit workers. It is not designed to meet state, local or other regulatory requirements regarding heat stress. It is not designed to protect workers with medical conditions or pre-existing conditions that put them at risk of heat stress.

Richco will medically screen our employees prior to working in hot environments, especially when physical exertion is required.

Richco's five (5) key areas of heat-illness prevention are as outlined below.

1. **Training workers and supervisors** on heat-illness prevention strategies, as well as recognizing and reporting the signs and symptoms of heat-related illnesses.
2. **Monitoring weather and workplace conditions**.
3. **Conducting a heat hazard assessment** of common environmental and work-related heat stress factors, when appropriate.
4. **Implementing heat-illness prevention strategies** to reduce heat stress. This includes:
    a. Reducing worker exposures to heat-stress conditions.
    b. Establish an acclimatization program to help workers adapt to working in the heat.
    c. Ensuring workers are provided adequate water, shade, and rest periods.
    d. Monitoring workers for early signs and symptoms of heat stress, including the use of physiological measures of body temperature, recovery heart rate and/or body weight.
5. **Planning for heat-related medical emergencies** and ensuring victims receive prompt medical attention.

PURPOSE

This heat-illness prevention plan was developed to provide supervisors and workers with training and tools to help protect them from heat-related exposures and illnesses.

SCOPE

Each work site and job task can be unique and contain several heat stress hazards that must be addressed prior to the beginning work and during work activities. Supervisors and workers are responsible for assessing these hazards and taking necessary corrective actions to reduce heat-related illnesses.

COMPANY POLICY

Richco International Inc. is dedicated to protecting employees from on-the-job illnesses and injuries. All employees have the responsibility to work safely on the job. The purpose of this plan is to supplement our existing safety and health program and to ensure employees recognize heat stress hazards and act appropriately to address those hazards. The general approach addresses five (5) key areas of heat-illness prevention, as outlined below.

Main Elements of Heat-Illness Prevention Plan

Control	Description
1. Train supervisors and workers	Train supervisors and workers on heat-illness prevention strategies, as well as to recognize and report the signs and symptoms of heat-related illnesses.
2. Monitor weather and workplace conditions	Monitor weather workplace conditions and take preventative measures to protect workers when the temperatures exceed 70 °F (21 °C).
3. Conduct a heat hazard assessment when temperatures exceed 70 °F	Determine an effective wet-bulb globe temperature (WBGT-Effective) and use established recommended alert limits (non-acclimatized workers) and exposure limits (acclimatized workers) to determine the level of risk to heat stress.
4. Implement heat-illness prevention strategies	Implement appropriate heat-illness prevention strategies based on established risk levels for heat stress.
5. Plan for heat-related medical emergencies	Ensure adequate supervision, first aid and medical services are readily available in the event a worker suffers from a heat illness.

Employee Training and Responsibilities

Each employee will be trained in heat-illness prevention and will strictly adhere to the recommended practices, except when doing so would expose him/her to a greater hazard. If, in the employee's opinion, this is the case, the employee is to notify their supervisor of their concern and have the concern addressed before proceeding.

Employer Responsibilities

On the job, it is the responsibility of the Safety Manager to implement this Heat-Illness Prevention Plan. Continual observational safety checks of work operations and the enforcement of the safety policy and procedures shall be regularly enforced. The supervisor is responsible for correcting any unsafe practices or conditions immediately.

It is the responsibility of the employer to ensure that all employees understand and adhere to the policies and procedures of this plan. It is also the responsibility of the employee to bring to management's attention any unsafe or hazardous conditions or practices that may cause injury to either themselves or any other employees. The Safety Manager must approve any changes to the Heat-Illness Prevention Plan.

Designated Safety Manager: Lorenzo Casto

Supervisors: Darren Richardson
Denis Richardson

TRAINING

To ensure workers are prepared to work safely under hot conditions, all employees and supervisors who may be exposed to heat stress and heat-related illnesses will receive training in the following:

Elements of the Company's Heat-Illness Prevention Plan

1. Training
2. Monitoring
3. Hazard Assessment
4. Heat-Illness Prevention Strategies
5. Emergency Preparedness

Risk Factors for Heat Stress

Environmental risk factors for heat stress

1. Temperature
2. Humidity
3. Air movement
4. Radiant heat (e.g., sun exposure)

Work-related risk factors for heat stress

1. Physical exertion
2. Clothing

Personal risk factors for heat stress

1. Age
2. Physical fitness
3. Acclimatization
4. Medical conditions
6. Medications
7. Alcohol and/or drug use
8. Caffeine

How the Body Handles Heat

1. Increased heart rate
2. Increased blood circulation to skin
3. Evaporative cooling from sweating

The importance of acclimatization.

1. Reduces risks of dehydration and salt loss
    a. Sweating and evaporative cooling becomes more efficient.
    b. Salt loss becomes more efficient.
2. Core body temperature is maintained more efficiently.
3. Reduces strain on the heart.
    a. Blood circulation to skin becomes more efficient.
    b. Recovery heart rate improves.
4. The human body needs to acclimate to hot environments, typically 10-14 days.
    a. Gradually increase exposure to hot environment over 7-14 days
    b. Avoid prolonged exertion during hottest times of day.
    c. Schedule heavy exertion for cooler parts of day
5. Acclimatized workers will need 2-3 days of re-acclimatization if they stop working under heat stress conditions for more than a week.

The importance of consuming water throughout the work shift

1. One cup (8 oz.) of cool water or an electrolyte replacement fluid every 15-20 minutes; four cups of water every hour.
2. Increased water intake may be needed to account for increased physical exertion and/or sweating.
3. However, too much water intake can be dangerous and lead to headache, nausea, vomiting and/or mental confusion.
4. Physiological monitoring may be necessary under extreme conditions.
    a. If sweat is not trapped within clothing, then we can monitor body weight, which should not drop below 1.5% of starting body weight.
    b. Urine color is another indicator of potential dehydration.
        i. Normal urine should be pale yellow.
        ii. Use a urine color chart to help determine if you are properly hydrated. Some diets, medications and illnesses may affect results.

The importance of rest breaks and shade throughout the work shift

1. Prolonged physical exertion and muscle activity increases the body's core temperature and reduces the body's ability to cool itself. Short rest breaks are necessary to allow blood to flow to the skin to be cooled.
2. Rest breaks slow down the buildup of heat in the body from prolonged muscle activity.
3. Rest breaks are also important for the heart and allow your heart rate to recover from sustained heat stress and physical exertion.
4. Rest breaks in the shade will help with cooling, especially if there is air movement with cool air.

Heat-Related Illnesses

The following information needs to be covered in training on heat-related illnesses, including cause, preventative measures, signs, and symptoms, first aid treatment and reporting requirements.

Heat Rash

1. Cause: Skin irritation due to excessive sweating.
2. Preventative measures:
    a. Wear loose fitting clothing that allows sweat to dissipate
    b. Wear freshly laundered clothing each day
    c. Avoid working in sweat-soaked clothing for prolonged periods (e.g., changing at breaks as needed)
    d. Wash sweat-soaked areas with mild soap and water and dry thoroughly at breaks and after your shift ends.

3. Signs and symptoms:
    a. Itchy and painful clusters of red blisters
    b. Common to the neck, chest, groin, armpits and creases of the elbows and knees
4. First aid treatment:
    a. Move person to a cool location.
    b. Have a person take a cool shower.
    c. Thoroughly dry the skin following shower
    d. Continue to ensure skin is cleaned and dried frequently, especially before and after shifts.
    e. Seek medical treatment if rash persists for more than two days or if rash becomes infected.
5. Reporting: Report to supervisor and safety manager

Heat Cramps

1. Cause: Depletion of salt and water in body due to excessive sweating. This is a precursor to more serious heat exhaustion and/or heat stroke.
2. Preventative measures:
    a. Acclimatization of heat helps reduce salt and water loss.
    b. Drink adequate amounts of water throughout the day
    c. Salt your food to taste.

3. Signs and symptoms:
    a. Muscle cramps, spasms and/or pain
    b. Common to major muscles used for work (e.g., arms, legs, abdominal and back muscles)
4. First aid treatment:
    a. Move person to a cool location.
    b. Provide a person with an electrolyte replacement fluid to replace lost salt and water.
    c. Seek medical treatment if cramps persist or other heat-illness symptoms develop (e.g., elevated body temperature, elevated heart rate, headache, dizziness, etc.)

5. Reporting: Report to supervisor and safety manager

Heat Syncope

1. Cause: Prolonged standing or sudden rising from a sitting or resting (supine) position; dehydration can be a contributing factor
2. Preventative measures:
    a. Acclimatization to heat helps reduce dehydration
    b. Drink adequate amounts of water throughout the day
    c. Break up long periods of standing with small rest breaks
    d. Rise slowly from sitting or resting positions

3. Signs and symptoms:
    a. Light-headedness or dizziness
    b. Fainting

4. First aid treatment:
    a. If he/she is only slightly dizzy and able to move, have two people assist and carefully move to a cool location and have the person lay down on their back with feet elevated above heart level; provide small amounts of water.
    b. If dizziness persists, request immediate first aid and/or medical attention.
    c. If he/she fainted, then secure the area, elevate his/her feet above heart level and request immediate first aid and/or medical attention; do not allow him/her to get up quickly or walk about.

5. Reporting: Report to supervisor and safety manager

Heat Exhaustion

1. Cause: The body's inability to cool itself, often due to a combination of several factors (e.g., high temperatures, humidity, physical exertion, dehydration, clothing that blocks sweat evaporation and/or alcohol use). This is a serious condition that can lead to a life-threatening heat stroke.
2. Preventative measures:
    a. Acclimatization to heat helps reduce dehydration.
    b. Drink adequate amounts of water throughout the day
    c. Take small rest breaks in the shade to allow the body to recover from heavy physical exertion and heat exposure.
    d. Protect skin against sunburn, which reduces body's ability to cool itself.
    e. If possible, perform heavier physical labor towards the cooler part of the day (e.g., early morning or evening)
3. Signs and symptoms:
    a. Elevated core body temperature of 100.4 to 102.2 °F (38 to 39 °C); oral temperature 99.6 to 101.4 °F
    b. Weak, but rapid pulse (elevated heart rate)
    c. Cool, moist skin (person may appear pale with clammy skin)
    d. Excessive sweating
    e. Headache and possible irritability
    f. Fatigue or weakness
    g. Dizziness and/or feeling faint.
    h. Nausea and/or vomiting.
    i. Decreased urine output

4. First aid treatment:
    a. Seek immediate medical care (call 911)
    b. Immediately help the person cool off
        i. Move to a cool location
        ii. Remove or loosen unnecessary clothing
        iii. Have them drink small amounts of cool water
        iv. Spray skin with cool water and fan rapidly to increase evaporation and cooling
        v. Monitor body temperature and continue cooling efforts until body temperature returns to a normal temperature below 99 °F (37 °C).
        vi. Implement additional heat stroke treatments if body temperature does not decrease below 100 °F (37.8 °C) after 30 minutes or increases above 102 °F (38.9 °C).

5. Reporting: Report to supervisor and safety manager

Heat Stroke

1. Cause: Body is unable to cool itself and regulate core body temperature. This is a serious and life-threatening condition that requires immediate medical attention (call 911).
2. Preventable measures: Same as for heat exhaustion
3. Signs and symptoms:
    a. Elevated core body temperature above 104 °F (40 °C); oral temperature above 103.2 °F
    b. Hot, dry skin or heavy sweating
    c. Mental confusion, agitation and/or irrational behavior
    d. Clumsiness
    e. Slurred speech
    f. Fainting or a loss of consciousness
    g. Seizures or convulsions

4. First aid treatment:
    a. Call 911 and seek immediate medical attention for the victim; do not wait as their life depends on getting immediate medical care.
    b. Provide immediate and aggressive cooling to their body.
        i. Elevate feet above heart level.
        ii. Remove or loosen unnecessary clothing.
        iii. Pack ice in groin and armpit areas
        iv. Soak skin with cool water and fan rapidly and vigorously to increase cooling of skin.
        v. As an alternative, immerse them in a tub of cool water or spray the body with large amounts of cool water.
        vi. Do not give person fluids to drink, especially are unconscious.
        vii. Monitor body temperature and continue cooling efforts until body temperature returns to a normal temperature below 99 °F (37 °C).
    c. Administer CPR as needed, if blood circulation or breathing stops, until emergency medical services arrive

5. Reporting: Report to supervisor and safety manager

Rhabdomyolysis

1. Cause: Sometimes caused by a combination of heat stress and prolonged physical exertion, muscle starts to break down and die, releasing proteins and electrolytes into the bloodstream. This is a potentially life-threatening condition affecting the kidneys that require immediate medical attention.
2. Preventative measures:
    a. Same as for heat exhaustion and heat stroke.
    b. Avoid overexertion, such as lifting objects heavier than you can comfortably lift or straining muscles to a point where they can no longer function properly.
    c. Those with diabetes, thyroid conditions or muscular dystrophy are at greater risk.
    d. Those with a viral infection, such as flu, HIV or herpes, are at greater risk.
    e. Use of alcohol and illegal drugs, such as heroin, cocaine and amphetamines can increase the risk.
    f. Some medications, such as antipsychotics or statins, can increase the risk.
3. Signs and symptoms:
    a. Muscle cramps, pain and/or loss of range
    b. Joint pain and/or stiffness
    c. Swelling of muscles
    d. Weakness and a decreased ability to perform physical exertion for even a small amount of time.
    e. Dark urine (similar to tea or cola in color)
    f. If kidney damage and/or failure occurs the following life-threatening indicators may be observed:
        i. Shortness of breath
        ii. Irregular heartbeat
        iii. Swelling in the legs and feet
        iv. Seizures
        v. Coma

4. First aid treatment:

    a. Seek immediate medical care for the victim (IV fluids and treatments to combat toxic proteins in blood are needed to prevent kidney failure)

5. Reporting: Report to supervisor and safety manager

Heat-illness prevention strategies

When Risk Level is High Incorporate Physiological Monitoring

1. Oral Temperature
    a. It is important to make sure the thermometer is stored in a cool environment and not exposure to temperatures above 95 °F.
    b. Readings should not be taken be taken within 15-minutes of consuming hot or cool liquids and foods or if breathing heavy (mouth breathing).
    c. Oral temperatures should not exceed 99.5 °F.
    d. As a precautionary measure, when the oral temperature is elevated above 99.1 °F, adjust the work-rest schedule to increase the frequency and duration of rest breaks or take other preventative measures.
2. Heart Rate Recovery
    a. The method involves taking an initial pulse rate reading at the beginning of a scheduled rest break. With the worker sitting and resting, an initial pulse rate reading is collected (P1) and if the pulse rate is above 110 bpm, then pulse rate readings are collected at a two-minute (P2) and four-minute (P3) interval.
    b. If the pulse rate does not drop to below 110 bpm during the test, then this indicates heat stress conditions are above an acceptable level. The resting heart rate is too high, which indicates the work rate is too high for the individual.
    c. With a starting pulse rate above 110 bpm, if the difference between two-minute intervals is less than 10 bpm, then this also indicates heat stress conditions are above an acceptable level. The heart rate is not effectively recovering at rest, which also indicates the work rate is too high for the individual. It could also indicate dehydration.
    d. There can be variation among individuals, and some may exhibit much lower or higher resting pulse rates. A qualified medical provider should examine individuals with pre-work pulse rates above 100 bpm when at normal rest. High resting pulse rates could be indicative of an underlying medical condition.

3. Additional Measures to Help Reduce Dehydration

    a. Body Weight
        i. Assumes that the worker is wearing clothing that will allow sweat to evaporate from the skin and not be trapped within the clothing (e.g., chemical protective and impermeable suits can trap sweat).
        ii. Use a reliable scale that can read body weight within ± 0.25 lbs.
        iii. If body weight reduces by more than 1.5%, then not likely taking in enough water to replace the water lost due to sweating.

b. Urine Color
    i. Urine color can be a good indicator of potential dehydration, which can lead to heat stress and heat-related illnesses.
    ii. In some cases, underlying diseases, medications or even some foods may affect urine color.
    iii. Check urine color against a color chart.
    iv. Normal urine should be a pale yellow. Darker color indicates potential dehydration.

Engineering Controls

1. Reduce physical exertion and physical demands of work through use of powered tools and equipment, especially for tasks involving heavy lifting.
2. Reduce radiant heat loading from the sun or other sources of radiant heat (e.g., furnaces, combustion engines and compressors, hot surfaces, heated transfer lines, windows receiving intense sun, etc.). One effective method is to place line-of-sight, reflective barriers between the heat source and workers. Another method is to insulate hot surfaces, such as furnaces.
3. If air temperatures are below 95 °F, then increase air speed across skin of workers using fans or air movers, to increase evaporative cooling from skin.
4. If air temperatures are above 95 °F, then reduce air speed across skin of workers, to reduce convective heat transfer from air to skin.
5. If humidity is below 50%, then evaporative coolers and portable fans with water mist systems can be used to effectively cool the air by about 10 to 20 °F.
6. Decrease humidity to below 50% to increase evaporative cooling from sweating.

Administrative Controls

1. Adjust work schedule to ensure workers are acclimated to work in hot conditions.
2. Schedule work or work requiring heavy physical exertion during the coolest parts of the day.
3. Modify the work-rest schedule to shorten heat exposure periods by including frequent rest breaks. Shorter, more frequent breaks are more effective than longer, less frequent rest breaks.
4. Encourage adequate water intake at frequent intervals to prevent dehydration (e.g., one 8-ounce cup of cool water or an electrolyte replacement fluid every 15-20 minutes).
    a. The supervisor or foreman is responsible for making sure drinking water is provided, plus:
        i. Ensure that water containers are clean and sanitary prior to filling.
        ii. Ensure water containers are filled at a sanitary location.
        iii. Provide sufficient disposable cups and a place for disposing cups.
        iv. Ensure workers do not share cups and dispose of used cups.
        v. Prohibit workers from opening the cooler top to fill cups and instead have workers use the provided spigot.

b. Pure and cool potable water is made available to workers at no additional cost.
    i. We do not use water from irrigation, sprinklers, or firefighting systems.
    ii. We do not use water from a garden hose, as it may contain contaminants from the hose and/or bacteria and other microbes.
c. Water quantities need to be sufficient and at least 1 quart per worker per hour for the entire shift.
d. Locate water containers as close as practicable at all times.
e. Encourage workers to frequently drink water and not wait until thirsty.

5. Provide a shaded and/or air-conditioned space nearby for rest and water breaks.
6. Train workers on the recognition of the signs and symptoms of heat-induced illness and on heat-illness prevention strategies.
7. Alert workers to extreme heat events or heat stress conditions and provide a short review of the heat-illness prevention strategies for the day.
8. Work in pairs (buddy system) and monitor each other for signs and symptoms of heat stress or illness.
9. Avoid caffeine and alcohol before and during working in a hot environment.
10. Report illnesses or medical conditions that may put them at risk of heat stress (e.g., diarrhea, fever, infection, etc.)
11. Medically screen for work in hot environments.

Protective Clothing and Equipment Controls

1. Provide clothing designed to keep the body cool, such as air, cooled fluid or ice-cooled conditioned clothing.
2. Provide reflective clothing to reduce radiant heat loading from the sun or hot surfaces radiating heat.
3. If air temperatures are below 95 °F and worker is protected from radiant heat, then decrease clothing coverage or layers (when feasible) to increase evaporative cooling from skin. Caution: Do not remove clothing designed to protect workers from chemical, mechanical, or other hazards without conducting a proper evaluation to address those hazards.
4. If air temperatures are above 95 °F, then increase clothing coverage to reduce air speed across skin of workers, which can help reduce convective heat transfer from air to skin.

MONITORING WEATHER AND WORKPLACE CONDITIONS

The Safety Manager and supervisors are responsible for monitoring the daily weather and workplace conditions to determine if workers will be exposed to temperatures greater than 70 °F (21 °C). The National Weather Service (www.weather.gov) should be used to monitor weather conditions. Public weather observation alternatives include Intellect (www.intellicast.com) and Weather Underground (www.wunderground.com). Use the closest weather station to the worksite location.

If the temperatures exceed 70 °F (21 °C) for more than an hour during the work shift, then a heat hazard assessment needs to be performed. The following additional weather information is required for the heat hazard assessment.

- Air temperature (°F)
- Humidity (%)
- Wind speed (mph)
- Barometric pressure (inches)
- Longitude and latitude
- Cloud cover

HEAT HAZARD ASSESSMENT

When weather or workplace conditions exceed 70 °F (21 °C), a heat hazard assessment will be conducted to consider environmental and work factors associated with heat stress and heat-related illnesses. Temperature, humidity, wind speed and solar irradiance are environmental factors that will also be considered. Work factors include metabolic work rate (physical exertion) and clothing. These factors are all accounted for using an effective wet-bulb globe temperature (WBGT-Effective).

Use of a heat index, which only considers temperature and humidity, is not recommended. The heat index does not consider wind speed, radiant heat,

Clothing and metabolic heat from physical exertion, which are all factors that can contribute to heat stress and heat-related illnesses.

HEAT-ILLNESS PREVENTION STRATEGIES

When the HQ is above 1.0, heat-illness prevention controls need to be implemented to protect workers. The heat-illness prevention strategies are broken down into five (5) steps:

1. First, implement controls aimed at reducing the hazard quotient (HQ).
2. Second, when the risk level is high, very high or severe, then incorporate physiological monitoring (e.g., body temperature and/or heart rate) as a precautionary measure to identify heat stress before a more serious condition or illness arises.
3. Third, implement engineering controls to reduce heat stress conditions.
4. Fourth, implement administrative controls to address acclimatization issues and/or reduce heat stress conditions.
5. Fifth, provide workers personal protective clothing and equipment to reduce heat stress conditions.

The heat-illness prevention strategies vary slightly for unacclimated workers. If workers have not worked in a hot environment within the previous week, then those workers must be placed in an acclimatization program designed to gradually acclimate them to work in a hot environment.

Implement Controls to Reduce Hazard Quotient and Risk Level

The first step in the heat-illness prevention strategy is to evaluate those factors used in the heat hazard assessment and determine what changes could be made to reduce the hazard quotient (HQ) to a value below 1.0, a low risk level. Examples of effective controls include:

1. Suspend activities during the hottest part of the day and change to work schedule to cooler times of the day.
2. Provide shade or shelter from the sun.

3. When feasible, eliminate the use of chemical vapor-barrier coveralls, such as encapsulating suits and whole-body chemical protective suits during hottest parts of day.
4. When feasible, eliminate double clothing layers.
5. When feasible, use mechanical and powered equipment to reduce worker physical exertion, especially heavy physical exertion. This includes the use of forklifts, portable power tools etc.
6. When feasible, change the work-rest schedule to ensure workers receive adequate rest breaks, which will decrease accumulation of body heat.
7. If air temperatures are below 95 °F (skin temperature) and air velocities are less than 1-2 mph, then increasing the air velocity at workers using portable fans can be an effective control to increase cooling. Caution: If air temperatures are above 95 °F, then heat will be added to workers by convection, which puts them at risk of heat stress.
8. When feasible, adjust work clothing to lighter, more breathable cotton fabrics or change coveralls to a more breathable material.

Implement Engineering Controls

When the risk level is moderate or above, then implementation of effective engineering controls are recommended over administrative or protective clothing controls. The following are examples of effective engineering controls.

1. Reduce physical exertion and physical demands of work through use of powered tools and equipment, especially for tasks involving heavy lifting.
2. Reduce radiant heat loading from the sun or other sources of radiant heat (e.g., compressors, hot surfaces, heated transfer lines, windows receiving intense sun, etc.). One effective method is to place line-of-sight, reflective barriers between the heat source and workers. Another method is to insulate hot surfaces, such as furnaces.
3. If air temperatures are below 95 °F, then increase air speed across skin of workers using fans or air movers, to increase evaporative cooling from skin.
4. If air temperatures are above 95 °F, then reduce air speed across skin of workers, to reduce convective heat transfer from air to skin.
5. If humidity is below 50%, then evaporative coolers and portable fans with water mist systems can be used to effectively cool the air by about 10 to 20 °F.
6. Decrease humidity to below 50% to increase evaporative cooling from sweating.

MEDICAL EMERGENCIES

When workers are exposed to heat stress conditions, it is critical to ensure adequate supervision, first aid and medical services are readily available in the event a worker suffers from a heat illness. This includes ensuring adequate first aid supplies are available and supervisors and workers are trained on what to do if a co-worker suffers from a heat-related illness.

First Aid Supplies

The following first aid supplies for heat-induced illnesses need to be on hand.

1. Reliable oral thermometer for checking body temperature.
2. Reliable instrument or timer for checking heart rate.
3. Cool water or electrolyte replacement fluids.
4. Cold packs or ice packs for treatment of heat stroke.
5. Spray bottles with water or an available water source for treating heat stroke.

First Aid Providers

Each work site should have at least one person trained to administer first aid. The location, physical address and phone number of the nearest hospital or emergency medical services must be obtained prior to the beginning of work activities under hot conditions. The following emergency response information must be obtained prior to the beginning of work activities.

1. Names, locations and phone numbers of all first aid trained supervisors or key personnel on site.
2. Phone numbers for on-site or local medical emergency services.
3. Address, phone number and directions from site to closest emergency medical services (e.g., hospital).
4. Physical address and detailed directions for emergency medical services. If the site is a remote location, then check with emergency medical services to ensure they can find the location. Some providers may require GPS coordinates.

First Aid Guidelines

It is important that all supervisors and workers know how to recognize the signs and symptoms of heat stress, when to call for emergency medical assistance and what steps they need to take to help the victim of heat stress until emergency services arrive.

ENFORCEMENT

Constant awareness of and respect for heat stress hazards, and compliance with all safety rules are considered conditions of employment. The supervisor, as well as individuals responsible for safety and personnel, reserve the right to issue disciplinary warnings to employees, up to and including termination, for failure to follow the guidelines of this program.

INCIDENT INVESTIGATIONS

All incidents that result in a worker suffering from a heat-related illness, regardless of their nature, shall be investigated and reported to management. It is an integral part of any safety program that documentation take place as soon as possible so that the cause and means of prevention can be identified to prevent a reoccurrence.