

USER GUIDE

Upyog Margdarshika (Hinglish)

XV Digital Access Control - Command Center and Gatekeeper phone app

Version test • Created by Team XV

Choose language / Bhasha chuniye: [\[English \]](#) [\[Hinglish \]](#)

Click a language to open that guide. Every page has the same switch at the top, and every chapter has a link to the same chapter in the other language.

Kisi bhi bhasha par click kijiye. Har page ke upar yahi switch hai, aur har chapter mein doosri bhasha ke usi chapter ka link hai.

USER GUIDE - English

Switch to: [Hinglish](#)

Contents

- [1. The main window](#)
- [2. First-time setup \(do this once\)](#)
- [3. Live Feed](#)
- [4. Personnel Registry and soldiers](#)
- [5. Vehicle Fleet](#)
- [6. Transit Times - watching vehicles between locations](#)
- [7. History and route chart](#)
- [8. Accounts & Devices](#)
- [9. Audit Trail](#)
- [10. Export tab and reports](#)
- [11. ID Card Studio and Card Register](#)
- [12. Visitors and temporary passes](#)
- [13. Leave, TD and overdue alerts](#)
- [14. Comms Center](#)
- [15. Settings](#)
- [16. Backup, restore, lock and administrator password](#)
- [17. Cloud Link \(phones over the internet\)](#)
- [18. The phone app \(for the RP at the gate\)](#)
- [19. If something does not work](#)

1. The main window


Read this chapter in: [Hinglish](#)

The Command Center is the server of your base. It keeps the encrypted records, talks to the gate phones and shows everything that happens at the gates.

1. Left side: live counts (people inside, vehicles on base, location flags, total events), the gate stations and the paired phones.
2. Top buttons: Add Soldier, Add Vehicle, Import / Export, ID Card Studio, Visitors, Leave & Overdue, Local Wi-Fi & Pair Device, Comms, the lock and refresh buttons.
3. Tabs: Live Feed, Personnel Registry, Vehicle Fleet, Transit Times, Accounts & Devices, Audit Trail, Export, Settings, Help and About.
4. The search box at the top right filters the tab you are looking at.

Note: The server keeps running when the window is locked.

Screen: live feed



2. First-time setup (do this once)

Read this chapter in: [Hinglish](#)

Before the gate phones can work, the server needs the posts of your base, an account for each Request Point (RP) and a paired phone.

1. Open Settings > Station & General > Open Station & General Settings (Stations & Settings).
2. Under LOCATIONS type the ID (for example LOC07) and the name, then press Add / Update. Do the same for GATES (for example G02).
3. Open the Accounts & Devices tab and press + Create Operator. Give the RP a name, an ID and a password.
4. Press Pair Terminal (or the top button Local Wi-Fi & Pair Device). A QR code appears.
5. On the phone open the XV Gatekeeper app, choose to pair, and scan the QR code. The phone appears under Paired Terminals.
6. Add your people and vehicles (chapters 4 and 5), or import them from a file.

Note: The phone and the PC must be on the same Wi-Fi for local pairing. For pairing over the internet use Cloud Link (chapter 17).

Note: Operators who register themselves on the phone must be approved in Accounts & Devices before they can sign in.

Screen: stations settings

Stations & Settings

Locations and gates appear in the terminal's sign-in screen. Nothing is pre-filled — add the real posts of your base.

LOCATIONS

LOC07 Location 07

Remove

LOC08 Location 08

Remove

Add a location: ID (e.g. LOC07) then name (e.g. Location 07 Main Hub)

Add / Update

GATES

G02 Gate 02

Remove

Add a gate: ID (e.g. G02) then name (e.g. Gate 02 Primary)

Add / Update

SERVER

COMMAND CENTER NAME (SHOWN ON TERMINALS)

HTTPS PORT (TERMINALS MUST BE RE-PAIRED AFTER A CHANGE)

☒ Operators who self-register must be approved here

Cancel

Save Settings

Screen: pair device

Pair a Terminal (Local Wi-Fi & Internet)

On the phone: open XV Access Control → 'PC Server Connection' → 'Scan PC Pairing QR'. The QR is valid for 10 minutes and works once.



Pairing code **7SWGQ9EZ**
Expires in 09:58 • single use

THIS PC'S ADDRESSES ON THE LOCAL NETWORK

No network adapter is connected. Connect this PC to the same Wi-Fi/router as the terminals.

INTERNET ADDRESS INCLUDED IN THE QR

Not configured — terminals will connect on the local network only. Set it up in Cloud Link.

Copy pairing text

New QR

Done

3. Live Feed

Read this chapter in: [Hinglish](#)

Every gate scan arrives here at once, newest first. Each card shows who or which vehicle, where, when and who recorded it.

1. Use the filter chips: All Events, Personnel, Vehicles, Entries, Exits, Location Flags.
2. A vehicle exit that has a destination shows a line such as 'To Location 08 - approx 30 min - ON THE WAY'. If the vehicle is late the line turns red: 'NOT REACHED'.
3. A red Location Flag means the person or vehicle was scanned at a location other than the one it was expected at.
4. Press Export CSV to save the feed as a spreadsheet.

Note: Every card shows a green line 'Recorded by server' with the time the server stored it and its sequence number. The phone shows RECORDED BY SERVER with the server number only after the server confirms the entry; until then it says NOT RECORDED YET and keeps retrying. Every card is also written to the Audit Trail and cannot be edited.

Screen: live feed

Server: localhost:8443 | DB: SQLCipher Encrypted | [+ Add Soldier](#) | [+ Add Vehicle](#)

[Import / Export](#) | [ID Card Studio](#) | [Visitors](#) | [Leave & Overdue](#) | [Local Wi-Fi & Pair Device](#)

[Comms](#) | [🔒](#) | [🔄](#)

BASE PRESENCE TELEMETRY Live Sync

Inside Facility **1** 3 currently outside

Fleet On-Base **0** 1 tactical units registered

Location Flags **0** Cross-location alerts record

Total Events **7** Today: 2 in • 1 out

GATE STATION NETWORK 0/1 ONLINE

G02 Gate 02 STANDBY Op: Unassigned

2 In 1 Out 0 Flags

PAIRED TERMINALS 0 active

No terminals paired

Click 'Local Wi-Fi & Pair Device' and scan the ID with the Y

REAL-TIME GATE AUDIT STREAM 7 events

Refreshed: 09:34:30 • every record below was received from a paired terminal and acknowledged by this server

[All Events](#) | [Personnel](#) | [Vehicles](#) | [Entries](#) | [Exits](#) | [Location Flags](#) | [Export CSV](#)

V-014 CI-TEST-0001 08:04:27 08 Oct

Location 07 • Gate 02 Stayed: 2h 30m

Op GK-01 • Terminal CI-TERMINAL • Seq #7

To Location 08 • approx 30 min • NOT REACHED, 1h 00m late

✓ Recorded by server 08 Oct 09:34:27 • Seq #7

Manifest: P-002 1 aboard

P-002 CI Test Driver 05:34:27 08 Oct

Location 07 • Gate 02 PERSON

With vehicle V014 • Op GK-01 • Terminal CI-TERMINAL • Seq #6

✓ Recorded by server 08 Oct 09:34:27 • Seq #6

Server XV-940F5B27 • TLS fingerprint 53d292f02250445c... • Internet access OFF (LAN only) • Data: D:\a_temp\xyshot

4. Personnel Registry and soldiers

Read this chapter in: [Hinglish](#)

The list of all soldiers and staff with their rank, number, unit, photo and card status.

1. Press + Add Soldier. Fill rank, name, army number, company, platoon, section, mobile and the other fields, add a photo, then save.
2. To change a record, open the person from the registry and edit it. To see where the person has been, press History.
3. To add many people at once press Import / Export, choose the soldier file (CSV or Excel) and import. The window tells you how many were added or updated and lists any rows with errors.
4. To save the registry press Import / Export and export soldiers. You can choose all, one company or a selection.

Note: A suspended person is refused at every gate until the status is made active again.

Screen: personnel

Server: localhost:8443 | DB: SQLCipher Encrypted + Add Soldier + Add Vehicle

Multi-Gate Telemetry • Encrypted Local Server (TLS + AES-256-GCM)

Import / Export ID Card Studio Visitors Leave & Overdue Local Wi-Fi & Pair Device

Comms

BASE PRESENCE TELEMETRY Live Sync

Inside Facility 1 3 currently outside

Fleet On-Base 0 1 tactical units registered

Location Flags 0 Cross-location alerts record

Total Events 7 Today: 2 in • 1 out

GATE STATION NETWORK 0/1 ONLINE

G02 Gate 02 STANDBY Op: Unassigned

2 In 1 Out 0 Flags

PAIRED TERMINALS 0 active

No terminals paired

Server XV-940F5B27 • TLS fingerprint 53d292f02250445c... • Internet access OFF (LAN only) • Data: D:\a_temp\xyshot

Live Feed (7) Personnel Registry (4) Vehicle Fleet (1) Transit Times Accounts & Devices Audit Trail Export

MILITARY & CIVIL

Company-wise registry with printable QR ID cards, custom fields and full movement history. Tick cards to export selected personnel.

+ Add Soldier Details Export Selected Reports ID Cards Card Register Import / Export

Select Company All Companies View Detailed Cards Sort by ID (default)

All (2) Alpha (1) Bravo (1) Charlie (0) Delta (0) SP (0) HQ (0) Select all shown

ALPHA COMPANY 1 personnel • 1 inside

☐ CT P-001 Alpha Co **CI Test Soldier** Major • Test record Active

Service No Unit CI-0001 CI Test Unit

5. Vehicle Fleet


Read this chapter in: [Hinglish](#)

All registered vehicles with registration, type, model, company and status. A badge shows how many are on the way and how many have not reached.

1. Press + Add Vehicle and enter the registration, military registration, type, model, company and status.
2. Open a vehicle to see its History: every entry and exit, the driver and co-driver, and its route chart.
3. Import many vehicles from a CSV file with Import / Export.

Note: The vehicle details appear at the top of every vehicle route chart and export.

Screen: vehicles



6. Transit Times - watching vehicles between locations

Read this chapter in: [Hinglish](#)

When a vehicle leaves a gate the guard can enter where it is going and about how many minutes it should take. The server watches the clock. It never assumes the vehicle arrived: only a gate scan, the destination RP or this server can say so.

1. On the phone the guard enters the destination and approximate minutes when recording the vehicle exit. If the pair of locations already has a standard time the server uses it.
2. Open the Transit Times tab. VEHICLES ON THE WAY lists every open trip with its due time.
3. STANDARD TIME BETWEEN LOCATIONS: press + Time Between Locations to save a standard time for a pair of locations.
4. AVERAGE TIME TAKEN shows the average, fastest and slowest time of all vehicles for each pair, and compares it with the standard.
5. Press + Add Trip to record a trip by hand (a vehicle that left without a gate record).
6. If a vehicle is late, a NOT REACHED pop-up appears on the server and the destination RP's phone gets a notice with the vehicle and the time it left.
7. In the pop-up press Reached... and enter the time taken; or Stopped / moved... and enter the place and time taken; or the cross to close it.
8. A closed pop-up comes back after 15 minutes with a sound until the trip is resolved.
9. Each late trip card shows what happened to the notice sent to the destination RP: SENT / IN TRANSIT (the phone has not received it), RECEIVED (the phone fetched it) or SEEN (the RP closed or answered it).
10. Press Export Transit Report for a PDF, Excel or CSV of all trips.

Note: A scan of the vehicle at the destination closes the trip as REACHED. A scan at another location closes it as MOVED ELSEWHERE.

Note: The phone is only told the vehicle and the time it left. It never receives route times or the route chart.

Screen: transit times

Server: **localhost:8443** | DB: **SQLCipher Encrypted**

+ Add Soldier **+ Add Vehicle**

Import / Export

ID Card Studio

Visitors

Leave & Overdue

Local Wi-Fi & Pair Device

Comms

XV DIGITAL ACCESS CONTROL **PC SERVER ACTIVE**

Multi-Gate Telemetry • Encrypted Local Server (TLS + AES-256-GCM)

BASE PRESENCE TELEMETRY **Live Sync**

Inside Facility

1

3 currently outside

Fleet On-Base

0

1 tactical units registered

Location Flags

0

Cross-location alerts record

Total Events

7

Today: 2 in • 1 out

GATE STATION NETWORK **0/1 ONLINE**

G02 Gate 02

STANDBY

Op: Unassigned

2 In

1 Out

0 Flags

PAIRED TERMINALS **0 active**

No terminals paired

Click 'I need Wi-Fi & Pair Device' and scan the QR with the Y

Live Feed (7) **Personnel Registry (4)** **Vehicle Fleet (1)** **Transit Times** **Accounts & Devices** **Audit Trail** **Export**

VEHICLE TRANSIT TIMES **1 NOT REACHED**

How long vehicles take between locations. A vehicle is never marked as reached by itself: only a gate scan, the destination RP or this server can record it.

+ Add Trip

+ Time Between Locations

Export Transit Report

VEHICLES ON THE WAY

CI-TEST-0001 **V-014**

NOT REACHED • 1h 0m Late

From

Going to

Left at

Approx. time

Expected by

RP notice: not sent yet

Location 07

Location 08

08 Oct 08:04

30 min

08 Oct 08:34

Reached...

Stopped / moved...

History

STANDARD TIME BETWEEN LOCATIONS

The vehicle is watched against these times. If the pair is missing, the RP is asked for an approximate time when the vehicle leaves.

Server XV-940F5B27 • TLS fingerprint 53d292f02250445c... • Internet access OFF (LAN only) • Data: D:\a_temp\xyshot

Screen: add trip

Add a vehicle trip manually

For a vehicle going to a new place, or one whose exit was not entered with a destination. The server watches the trip and alerts if the vehicle does not arrive in time.

VEHICLE

CI-TEST-0001 — V-014

LEFT FROM (LOCATION)

LOC07 — Location 07

GOING TO (PICK A LOCATION, OR TYPE A NEW PLACE)

DEPARTURE DATE

10/8/2026

DEPARTURE TIME (HH:MM)

09:34

APPROXIMATE TIME TO REACH (MINUTES)

A new place is not in the Transit Times list, so enter the approximate time yourself to get an alert if the vehicle is late.

ALREADY REACHED? TIME TAKEN (MINUTES). LEAVE BLANK IF THE VEHICLE IS STILL ON THE WAY.

Cancel **Save Trip**

Screen: transit alert


1 VEHICLE NOT REACHED

Closing this window with X only hides it. It returns, with a sound, after 15 minutes until each vehicle is closed below.

CI-TEST-0001
Supply Truck

LATE 1h 0m

Location 07 → Location 08
 Left 08 Oct 08:04 • expected by 08:34 (30 min)

Reached...

Stopped / moved to another location...

Open Transit Times

Screen: close trip

Close trip • CI-TEST-0001
 Location 07 → Location 08 • left 08 Oct 08:04. The vehicle is only recorded as reached when you enter it here.

WHAT HAPPENED TO THE VEHICLE?
☒ It reached Location 08
☐ It stopped on the way
☐ It moved to another location instead

TIME TAKEN TO REACH THE DESTINATION (MINUTES)

It left at 08:04; 90 minutes have passed since then. Enter the minutes from departure until the event, not from now.

REMARKS (OPTIONAL)

Cancel

Save

7. History and route chart

Read this chapter in: [Hinglish](#)

Open History for any person or vehicle to see every record and a route chart: the places visited, the time spent at each, the travel between them and what happened on each trip.

1. Press History on a person or vehicle.
2. Read the chart from top to bottom: LEFT, TRAVEL (with REACHED, NOT REACHED, MOVED ELSEWHERE or STOPPED), ARRIVED with the time stayed.
3. For vehicles the driver and co-driver are shown, and a line tells you when the driver changed.
4. Press Export Route... for a one-page PDF to print or a colour-coded Excel file.
5. Press + Add Record in a person's history to add a missing entry or exit by hand, with the reason and remarks.

Note: Entering a record by hand needs the administrator password if one is set, and is written to the audit trail.

Screen: vehicle history route

Movement History • V-014

Every entry and exit recorded for this credential, newest first.

VEHICLE DETAILS

REGISTRATION	VEHICLE ID	TYPE	MODEL	COMPANY	STATUS
CI-TEST-0001	V-014	Supply Truck	Test Model	Alpha	ACTIVE

2 records • total recorded time on site: 2h 30m

ROUTE CHART

LEFT Wed 07 Oct 21:54

Location 07
Trip entered by the server operator

TRAVEL Wed 07 Oct 21:54 REACHED

→ **Location 08**
To Location 08 • REACHED in 42 min (approx 30 min) • entered by the server

LEFT Wed 07 Oct 23:34

Location 08
Trip entered by the server operator

TRAVEL Wed 07 Oct 23:34 REACHED

→ **Location 07**
To Location 07 • REACHED in 31 min (approx 25 min) • entered by the server

ARRIVED Thu 08 Oct 05:34

Location 07 • Gate 02
Stayed 2h 30m

Export Route...

Close

Screen: add history record

+ Add Record to History • G-001

ENTRY / EXIT update who is inside, exactly like a gate scan. Other types (Leave, Duty, Course...) are dated history entries. Types are configured in Stations & Settings.

CI Test Visitor • VISITOR • Visitors Co • currently OUTSIDE

RECORD TYPE

ENTRY

DATE

10/8/2026

TIME (HH:MM)

09:34

LOCATION

LOC07 — Location 07

GATE

G02 — Gate 02

REASON (ENTRY / EXIT)

Cancel

Save Record

8. Accounts & Devices


Read this chapter in: [Hinglish](#)

The RP accounts that may sign in on the phones, and the phones that are paired.

1. + Create Operator makes a new RP account.
2. Disable stops an account from signing in. Reset Password sets a new password. Delete removes the account.
3. Pair Terminal shows a new pairing QR code.
4. Under PAIRED TERMINALS you can see each phone, its location and when it last reported. Press Revoke Access on a phone to stop it and order it to erase its data.

Note: A revoked phone is told to wipe its stored data the next time it contacts the server.

Screen: accounts devices



9. Audit Trail

Read this chapter in: [Hinglish](#)

A tamper-evident log of every change, sign-in and gate record. Each entry is chained to the one before it.

1. Open the Audit Trail tab. Newest entries are first; the details are shown under each row.
2. Press Verify integrity. The server checks the whole chain and tells you if anything was edited, removed or truncated.
3. Press Export CSV to save the log.

Note: Run Verify integrity regularly and before you hand over the server.

Screen: audit

Server: **Localhost:8443** | DB: **SQLCipher Encrypted** | **+ Add Soldier** | **+ Add Vehicle**

XV DIGITAL ACCESS CONTROL • **PC SERVER ACTIVE**
Multi-Gate Telemetry • Encrypted Local Server (TLS + AES-256-GCM)

Import / Export | **ID Card Studio** | **Visitors** | **Leave & Overdue** | **Local Wi-Fi & Pair Device**

Comms | **🔒** | **🔄**

BASE PRESENCE TELEMETRY Live Sync

Inside Facility 1
3 currently outside

Fleet On-Base 0
1 tactical units registered

Location Flags 0
Cross-location alerts record

Total Events 7
Today: 2 in • 1 out

GATE STATION NETWORK 0/1 ONLINE

G02 Gate 02
STANDBY
Op: Unassigned
2 In • 1 Out • 0 Flags

PAIRED TERMINALS 0 active
No terminals paired
Click 'I need Wi-Fi & Pair Device' and scan the QR with the Y

SECURITY AUDIT TRAIL 20 entries
Every administrative change, sign-in and gate record is written to the encrypted audit log.

Verify integrity | **Export CSV**

08 Oct 2026 09:34:27	CI	SET_PHOTO	PERSON P001
08 Oct 2026 09:34:27	PC-ADMIN	ROTATE_QR_SECRET	persons P002
Replacement for lost card - CI test			
08 Oct 2026 09:34:27	PC-ADMIN	CARD_REPORTED_LOST	PERSON P002
CI test			
08 Oct 2026 09:34:27	PC-ADMIN	ADD_PERSON	PERSON G002
08 Oct 2026 09:34:27	PC-ADMIN	ADD_PERSON	PERSON G001
08 Oct 2026 09:34:27	GK-01	VEHICLE_EXIT	VEHICLE V014
MNF-CI-ENT-6PAP7A			
08 Oct 2026 09:34:27	GK-01	TRANSIT_OPENED	VEHICLE V014
LOC07 -> Location 08 (30 min)			
08 Oct 2026 09:34:27	GK-01	VEHICLE_ENTRY	VEHICLE V014
MNF-CI-ENT-6PAP7A			
08 Oct 2026 09:34:27	PC-ADMIN	TRANSIT_REACHED	VEHICLE V014
Location 08 -> Location 07 in 31 min (SERVER)			
08 Oct 2026 09:34:27	PC-ADMIN	TRANSIT_OPENED	VEHICLE V014

Server XV-940F5B27 • TLS fingerprint 53d292f02258445c... • Internet access OFF (LAN only) • Data: D:\a_temp\xyshot

10. Export tab and reports

Read this chapter in: [Hinglish](#)

All exports are in one place: movement reports, route charts and the transit report. Each has its own card.

1. Open the Export tab.
2. Choose the people, company or vehicles, the dates and the format (PDF, Excel or CSV), then press the export button of that card.
3. The heading of reports can be changed in Settings (Export heading template).
4. Route chart export has its own card, separate from the other exports.

Note: Exports need the administrator password if one is set.

Screen: export

XV DIGITAL ACCESS CONTROL
PC SERVER ACTIVE

Server: **localhost:8443** | DB: **SQLCipher Encrypted**
+ Add Soldier
+ Add Vehicle

Import / Export
ID Card Studio
Visitors
Leave & Overdue
Local Wi-Fi & Pair Device

Comms
🔒
🔄

BASE PRESENCE TELEMETRY
Live Sync

Inside Facility
1
3 currently outside

Fleet On-Base
0
1 tactical units registered

Location Flags
0
Cross-location alerts record

Total Events
7
Today: 2 in • 1 out

GATE STATION NETWORK
0/1 ONLINE

G02 Gate 02
STANDBY
Op: Unassigned

2 In
1 Out
0 Flags

PAIRED TERMINALS
0 active

No terminals paired
Click 'Local Wi-Fi & Pair Device' and scan the QR with the Y

EXPORT REPORTS
Choose who and what period to export, then pick a file format. CSV is data only; Excel and PDF print the heading below.

WHO

All Personnel

WHEN

This Month

☒ Include gate & history records (untick for roster only)

EXPORT HEADING
{Scope} is replaced with who this export covers -- e.g. "Capt John Doe", "Alpha Company", "2 Platoon". Also editable from Settings.

Movement History of {Scope}

Server XV-940F5B27 • TLS fingerprint 53d292f02258445c... • Internet access OFF (LAN only) • Data: D:\a_temp\xvshot

Screen: reports export

Reports & Export

Excel: summary sheet plus one colour-coded sheet per company (roster + records). PDF: printable A4 report. CSV: plain records for any software.

COMPANY

All Companies

FROM

9/8/2026

15

TO

10/8/2026

15

☒ Include gate & history records (untick for roster only)

Close

CSV

PDF

Excel

11. ID Card Studio and Card Register

Read this chapter in: [Hinglish](#)

Design and print ID cards with a genuine QR code, and keep a record of every card issued, re-issued, printed or lost.

1. Press ID Card Studio. Choose the people (one, a company, or a selection), adjust the design and print or save as PDF.
2. In Theme & Emblems > Card style pick Classic (formal armed forces card), Modern two sides (details on the front, QR on the back) or Modern one side (photo, details and QR together).
3. For the modern cards choose the colour, light or dark card, the wording, extra details (company, blood group and so on) and upload a logo: front and back logo on the two-sided card, left and right logo on the one-side card. A slider sets the logo size.
4. Open the Card Register to see each soldier's card number, issue date, last print and loss history.
5. If a card is lost press Report lost... The old card is refused at every gate at once and a new QR code is made for the next card.
6. Press Export company-wise... to save the register.

Note: Personnel QR codes never expire. A code changes only when the card is reported lost or re-issued.

Screen: id card studio

The screenshot displays the 'ID CARD STUDIO' interface. At the top, there's a header with the title 'ID CARD STUDIO' and a subtitle 'XV COMMAND CENTER'. Below this, a row of buttons includes 'Card Issue Log', 'Export data', 'Export cards (1)', 'Save PDF (1)', and 'Print cards (1)'. The main area is divided into two sections. On the left, the 'SELECT SOLDIERS' panel allows users to choose between 'Individual', 'Multiple', and 'Company' options, with sub-options for 'Platoon', 'Section', and 'Entire'. A search bar is present, and two soldier entries are listed: 'Major CI Test Soldier' (P001 • CI-0001 • Alpha) and 'Havildar CI Test Driver' (P002 • CI-0002 • Bravo). A status bar at the bottom of this panel indicates '1 card(s) selected for printing'. On the right, the 'CARD FRONT' preview shows a sample identity card for 'MAJOR CI TEST SOLDIER'. The card includes the Government of India emblem, the text 'GOVERNMENT OF INDIA • MINISTRY OF DEFENCE', and 'ARMED FORCES IDENTITY CARD'. It also displays the soldier's name, rank, and unit details, along with a QR code at the bottom.

Screen: card register

ID Card Register

Every card's issue, re-issue, print and loss history. Personnel QR codes never expire — a code changes only when the card is reported lost or re-issued, and then the old card is refused at every gate.

SEARCH (ID, army no, name, company)

Major CI Test Soldier CARD #1

P-001 • Army No: CI-0001 • Alpha

Issued 08 Oct 2026 • last printed never • QR: no expiry

History

Open in ID Card Studio

Report lost...

Havildar CI Test Driver CARD #2 LOST #1

P-002 • Army No: CI-0002 • Bravo

Issued 08 Oct 2026 • last re-issued 08 Oct 2026 09:34 • last printed never • QR: no expiry

History

Open in ID Card Studio

Report lost...

Close

Export company-wise...

12. Visitors and temporary passes

Read this chapter in: [Hinglish](#)

Day or temporary passes with a QR code that works only between 'valid from' and 'valid to'.

1. Press Visitors, then + New visitor pass.
2. Enter the visitor's name, mobile, organisation, ID proof, purpose and whom they are visiting. Set the dates or use Today until 18:00, Next 24 hours or 7 days.
3. Press Create pass (no print) to save the pass only, or Create & print pass to save it and open the printable pass.
4. Later you can press Print pass on any visitor, End pass now to stop a pass, or History to see where the visitor went.
5. Press Export visitors report... for a spreadsheet.

Note: Exits are always allowed, so nobody is trapped inside. A visitor still inside after the pass ends is flagged as overstay.

Screen: visitors

Visitors & Temporary Passes

Day / temporary passes with a QR that works only between 'valid from' and 'valid to'. Exits are always allowed, so nobody is trapped inside. Visitors still inside after the pass ends are flagged as overstay.

All passesInside nowValid nowEnded / expired

CI Test Visitor VALID

G001 • ID proof: CI test ID

Purpose: CI test visit • Visiting: P001

Valid 08 Oct 2026 09:29 → 08 Oct 2026 17:34

Print pass

History

End pass now

CI Ended Visitor ENDED

G002 • ID proof: CI test ID

Purpose: CI test visit • Visiting: P001

Valid 08 Oct 2026 04:34 → 08 Oct 2026 08:34

Print pass

History

End pass now

Close

Export visitors report...

+ New visitor pass

Screen: new visitor pass

New Visitor Pass

The QR on the pass works at every gate only inside the validity window.

VISITOR'S FULL NAME

MOBILE NUMBER

ORGANISATION / ADDRESS

ID PROOF (TYPE AND NUMBER, E.G. AADHAAR 1234 5678 9012)

PURPOSE OF VISIT

VISITING (PERSON / OFFICE)

VALID FROM

10/8/20261509:34

Cancel

Create pass (no print)

Create & print pass

13. Leave, TD and overdue alerts


Read this chapter in: [Hinglish](#)

People who left with an expected return date are tracked. When the date passes the server raises an alert.

1. The phone asks for an expected return date for the reasons you choose in Stations & Settings (for example Proceeding on Leave, TD).
2. Press Leave & Overdue to see everyone who is out. Use the chips Everyone out or Overdue only.
3. When someone is overdue, a pop-up appears on the PC: for example 'Havildar Name has not returned from leave', with the reason and the due date.
4. Any entry of that person closes the absence automatically.
5. Settings > Leave & Overdue Alerts: choose which Locations or RPs also get the alert on their phone. Only those phones receive it.

Note: By default the alert is shown on the PC only.

Screen: leave overdue



14. Comms Center

Read this chapter in: [Hinglish](#)


Messages, alerts, calls and SOS between the server and the paired phones.

1. Press Comms and choose a terminal on the left.
2. Type a message and press Send, or press Send ALERT to ring the phone even when its app is in the background.
3. Broadcast alert to all terminals... sends one alert to every phone.
4. Under each message you sent you see its real status: sent, in transit (the phone is offline), received (the phone has it) or seen (the person opened it). The phone shows the same for what it sends.
5. An SOS from a phone appears on the PC at once with the sender and the place.

6. Voice and video calls with a terminal are listed in the conversation, with missed calls in red.

Note: Messages are encrypted end to end.

Screen: comms center



15. Settings

Read this chapter in: [Hinglish](#)

Everything that controls how the server behaves.

1. QUICK STATUS shows the current data sharing, internet access, auto-lock, outbound block, self-registration, administrator password and heading template.
2. Station & General: locations, gates, server name, port, custom fields, movement reasons, data protection, diagnostics and maintenance.
3. Cloud Link: lets phones reach the PC over the internet (chapter 17).
4. Leave & Overdue Alerts: who else receives the leave alert on the phone.
5. Press Save Settings after any change.

Note: If you change the HTTPS port, the phones must be paired again.

Screen: settings

Server: **localhost:8443** | DB: **SQLCipher Encrypted**

+ Add Soldier

+ Add Vehicle

Import / Export

ID Card Studio

Visitors

Leave & Overdue

Local Wi-Fi & Pair Device

Comms

XV DIGITAL ACCESS CONTROL

Multi-Gate Telemetry • Encrypted Local Server (TLS + AES-256-GCM)

PC SERVER ACTIVE

BASE PRESENCE TELEMETRY

Live Sync

Inside Facility

1

3 currently outside

Fleet On-Base

0

1 tactical units registered

Location Flags

0

Cross-location alerts record

Total Events

7

Today: 2 in • 1 out

GATE STATION NETWORK

0/1 ONLINE

G02 Gate 02

STANDBY

Op: Unassigned

2 In 1 Out

0 Flags

PAIRED TERMINALS

0 active

No terminals paired

Click 'Local Wi-Fi & Pair Device' and scan the QR with the Y

LIVE FEED (7)

PERSONNEL REGISTRY (4)

VEHICLE FLEET (1)

TRANSIT TIMES

ACCOUNTS & DEVICES

AUDIT TRAIL

EXPORT

COMMAND CENTER SETTINGS

Station setup, data protection, connectivity and maintenance for this Command Center.

QUICK STATUS

Data sharing with terminals

Internet access

Auto-lock

Outbound internet block

Self-registration approval

Administrator password

Export heading template

MINIMAL

Disabled (LAN only)

OFF

ON

Required

Not set

Movement History of {Scope}

Station & General

Locations, gates, server name, custom fields, movement reasons, data protection, diagnostics and maintenance.

Open Station & General Settings

Server XV-940F5B27 • TLS fingerprint 53d292f02250445c... • Internet access OFF (LAN only) • Data: D:\a_temp\vxshot

Screen: stations settings

Stations & Settings

Locations and gates appear in the terminal's sign-in screen. Nothing is pre-filled — add the real posts of your base.

LOCATIONS

LOC07 Location 07

Remove

LOC08 Location 08

Remove

Add a location: ID (e.g. LOC07) then name (e.g. Location 07 Main Hub)

Add / Update

GATES

G02 Gate 02

Remove

Add a gate: ID (e.g. G02) then name (e.g. Gate 02 Primary)

Add / Update

SERVER

COMMAND CENTER NAME (SHOWN ON TERMINALS)

runnervmf6oq

HTTPS PORT (TERMINALS MUST BE RE-PAIRED AFTER A CHANGE)

8443

☒ Operators who self-register must be approved here

Cancel

Save Settings

XV Digital Access Control • User Guide • Team XV • Page 20 of 46

16. Backup, restore, lock and administrator password

Read this chapter in: [Hinglish](#)

Protect and recover your data.

1. Two backup methods:
2. ENCRYPTED FULL BACKUP: Create encrypted backup... Choose a file and a password. It holds the whole database and settings, encrypted. Restore from backup... asks for the same password and replaces all data. Do this only on purpose.
3. GRANULAR BACKUPS: Export and import individual data types (personnel, vehicles, accounts, devices, settings) as JSON files. Useful for selective recovery, migration, or replication to other systems.
4. Set an administrator password in Settings. It is then asked before exports, manual records and other sensitive actions.
5. Press the lock button at the top to lock the screen. The gate server keeps running. Enter the administrator password to unlock.
6. Auto-lock locks the screen after the idle time set in Settings.

Note: Keep backup passwords safe. Without them the backups cannot be opened.

17. Cloud Link (phones over the internet)

Read this chapter in: [Hinglish](#)

Lets a phone outside the base Wi-Fi reach the server through a secure tunnel.

1. Open Settings > Cloud Link.
2. Enter the secure web addresses (URLs) of the gate server and the comms server given by your tunnel.
3. Pair the phone again with the new QR code. The phone then works on mobile data too.
4. Turn internet access off again to return to local Wi-Fi only.

Note: All traffic is encrypted (TLS with AES-256-GCM messages) even over the internet.

Screen: cloud link

Cloud Link — Internet Connection Setup

Terminals always try the local network first and fall back to the internet address below. Every request stays end-to-end encrypted (AES-256-GCM with each terminal's own key) even when a tunnel or relay handles TLS.

☐ **Allow terminals to connect over the internet**

When off, this PC refuses every connection that does not come from a private (LAN / VPN) address.

CONNECTION METHOD

PORT_FORWARD

Port forwarding: on your router forward TCP 8443 → this PC's LAN address port 8443. Use a static public IP or a free DDNS name (e.g. DuckDNS) as the public host.

⚠ Least private option — this opens a port directly to the whole internet (still TLS + AES-256-GCM protected, but scannable and reachable by anyone). VPN or Tunnel expose nothing at all to the open internet and are safer where they're an option.

RESTRICT INTERNET CONNECTIONS TO KNOWN NETWORKS (OPTIONAL)

ALLOWED INTERNET ADDRESS RANGES, ONE PER LINE — E.G. 203.0.113.0/24 (BLANK = ALLOW ANY ADDRESS)

Only affects connections from outside the local network / VPN — LAN terminals are never blocked by this. Leave blank unless you know the exact networks your remote terminals connect from.

PUBLIC HOST (DDNS NAME, PUBLIC IP OR VPN IP)

PUBLIC PORT

Export details...

Cancel

Save

18. The phone app (for the RP at the gate)

Read this chapter in: [Hinglish](#)

The XV Gatekeeper app on the phone is used by the RP to record entries and exits.

1. Sign in with the RP account made in Accounts & Devices, and choose the location and gate.
2. Scan a card QR. The app shows the person and asks Entry or Exit. For an exit choose the reason; for leave or TD enter the expected return date.
3. For a vehicle, scan the vehicle QR, then the driver and everyone on board, and confirm. On a vehicle exit enter the destination and the approximate minutes.
4. If the destination is a location of your base, the RP there is told when the vehicle has not reached. The RP can then press Reached..., enter the time taken, or say it stopped or moved to another place.
5. Records made without network are kept on the phone and sent when the server is reachable again.
6. The SOS button sends an emergency alert with the position to the server.
7. Shift handover passes unsent records to the next phone over Bluetooth or a Wi-Fi hotspot.
8. Language (English or Hindi) and dark mode are in the app's settings.

Note: If a phone is lost, revoke it in Accounts & Devices. It erases its data on the next contact.

19. If something does not work

Read this chapter in: [Hinglish](#)

Quick checks.

1. A phone cannot connect: check the PC and phone are on the same Wi-Fi, the PC firewall allows the app, and the phone is not revoked.
2. A phone shows the wrong time or is refused: set the correct date and time on the phone.
3. A scan is refused: open the person in the Personnel Registry and check the status is active and the card was not reported lost.
4. A pop-up does not come back: open the Transit Times tab and resolve or snooze the trip.
5. Anything unexpected: look at the Audit Trail for the exact entry and time.

USER GUIDE - Hinglish

Is guide ko English mein padhne ke liye: [English](#)

Chapters

- [1. Main window](#)
- [2. Pehli baar setup \(sirf ek baar\)](#)
- [3. Live Feed](#)
- [4. Personnel Registry aur soldiers](#)
- [5. Vehicle Fleet](#)
- [6. Transit Times - gaadiyon ko locations ke beech dekhna](#)
- [7. History aur route chart](#)
- [8. Accounts & Devices](#)
- [9. Audit Trail](#)
- [10. Export tab aur reports](#)
- [11. ID Card Studio aur Card Register](#)
- [12. Visitors aur temporary passes](#)
- [13. Leave, TD aur overdue alerts](#)
- [14. Comms Center](#)
- [15. Settings](#)
- [16. Backup, restore, lock aur administrator password](#)
- [17. Cloud Link \(internet par phones\)](#)
- [18. Phone app \(gate par RP ke liye\)](#)
- [19. Kuch kaam na kare to](#)

1. Main window


Yeh chapter English mein: [English](#)

Command Center aapke base ka server hai. Yeh encrypted records rakhta hai, gate ke phones se baat karta hai aur gate par jo bhi hota hai woh sab dikhata hai.

1. Left side: live counts (andar kitne log, base par kitni gaadiyan, location flags, total events), gate stations aur paired phones.
2. Upar ke buttons: Add Soldier, Add Vehicle, Import / Export, ID Card Studio, Visitors, Leave & Overdue, Local Wi-Fi & Pair Device, Comms, lock aur refresh button.
3. Tabs: Live Feed, Personnel Registry, Vehicle Fleet, Transit Times, Accounts & Devices, Audit Trail, Export, Settings, Help aur About.
4. Upar right ka search box usi tab ko filter karta hai jo aap dekh rahe hain.

Dhyan dijiye: Window lock hone par bhi server chalta rehta hai.

Screen: live feed



2. Pehli baar setup (sirf ek baar)

Yeh chapter English mein: [English](#)

Gate phones kaam kar sakein, isse pehle server ko base ke posts, har Request Point (RP) ka account aur ek paired phone chahiye.

1. Settings > Station & General > Open Station & General Settings (Stations & Settings) kholiye.
2. LOCATIONS mein ID (jaise LOC07) aur naam likhiye, phir Add / Update dabaiye. GATES (jaise G02) ke liye bhi yahi kijiye.
3. Accounts & Devices tab kholiye aur + Create Operator dabaiye. RP ka naam, ID aur password dijiye.
4. Pair Terminal dabaiye (ya upar ka button Local Wi-Fi & Pair Device). Ek QR code aayega.
5. Phone mein XV Gatekeeper app kholiye, pair chuniye aur QR scan kijiye. Phone Paired Terminals mein dikhega.
6. Apne log aur gaadiyan add kijiye (chapter 4 aur 5) ya file se import kijiye.

Dhyan dijiye: Local pairing ke liye phone aur PC ka same Wi-Fi par hona zaroori hai. Internet se pairing ke liye Cloud Link use kijiye (chapter 17).

Dhyan dijiye: Jo operator phone par khud register karte hain, unhe sign in se pehle Accounts & Devices mein approve karna padta hai.

Screen: stations settings

Stations & Settings

Locations and gates appear in the terminal's sign-in screen. Nothing is pre-filled — add the real posts of your base.

LOCATIONS

LOC07 Location 07

Remove

LOC08 Location 08

Remove

Add a location: ID (e.g. LOC07) then name (e.g. Location 07 Main Hub)

Add / Update

GATES

G02 Gate 02

Remove

Add a gate: ID (e.g. G02) then name (e.g. Gate 02 Primary)

Add / Update

SERVER

COMMAND CENTER NAME (SHOWN ON TERMINALS)


HTTPS PORT (TERMINALS MUST BE RE-PAIRED AFTER A CHANGE)

☒ Operators who self-register must be approved here

Cancel

Save Settings

Screen: pair device



3. Live Feed

Yeh chapter English mein: [English](#)

Har gate scan yahan turant aata hai, sabse naya sabse upar. Har card batata hai kaun ya kaunsi gaadi, kahan, kab aur kisne record kiya.

1. Filter chips use kijiye: All Events, Personnel, Vehicles, Entries, Exits, Location Flags.
2. Destination wali vehicle exit par ek line dikhti hai jaise 'To Location 08 - approx 30 min - ON THE WAY'. Gaadi late ho to line laal ho jati hai: 'NOT REACHED'.
3. Laal Location Flag ka matlab hai ki person ya gaadi us location par scan hui jahan use hona chahiye tha uske alawa kisi aur jagah.
4. Feed ko spreadsheet mein save karne ke liye Export CSV dabaiye.

Dhyan dijiye: Har card par hara line 'Recorded by server' dikhta hai, jisme server ne kab save kiya aur uska sequence number hota hai. Phone par RECORDED BY SERVER aur server number tabhi dikhta hai jab server entry confirm kar de; tab tak NOT RECORDED YET likha rehta hai aur phone dobara koshish karta rehta hai. Har card Audit Trail mein bhi likha jata hai aur badla nahi ja sakta.

Screen: live feed

Server: localhost:8443 | DB: SQLCipher Encrypted | [+ Add Soldier](#) | [+ Add Vehicle](#)

[Import / Export](#) | [ID Card Studio](#) | [Visitors](#) | [Leave & Overdue](#) | [Local Wi-Fi & Pair Device](#)

[Comms](#) | [🔒](#) | [🔄](#)

BASE PRESENCE TELEMETRY Live Sync

Inside Facility: 1 (3 currently outside)

Fleet On-Base: 0 (1 tactical units registered)

Location Flags: 0 (Cross-location alerts record)

Total Events: 7 (Today: 2 in • 1 out)

GATE STATION NETWORK 0/1 ONLINE

G02 Gate 02: STANDBY, Op: Unassigned, 2 In, 1 Out, 0 Flags

PAIRED TERMINALS 0 active

No terminals paired

REAL-TIME GATE AUDIT STREAM 7 events

Refreshed: 09:34:30 • every record below was received from a paired terminal and acknowledged by this server

[All Events](#) | [Personnel](#) | [Vehicles](#) | [Entries](#) | [Exits](#) | [Location Flags](#) | [Export CSV](#)

V-014 CI-TEST-0001 08:04:27 08 Oct

+ Location 07 • Gate 02

Op GK-01 • Terminal CI-TERMINAL • Seq #7

Stayed: 2h 30m

🚨 To Location 08 • approx 30 min • NOT REACHED, 1h 00m late

✓ Recorded by server 08 Oct 09:34:27 • Seq #7

Manifest: P-002 1 aboard

P-002 CI Test Driver 05:34:27 08 Oct

+ Location 07 • Gate 02

With vehicle V014 • Op GK-01 • Terminal CI-TERMINAL • Seq #6

✓ Recorded by server 08 Oct 09:34:27 • Seq #6

PERSON

Server XV-940F5B27 • TLS fingerprint 53d292f02258445c... • Internet access OFF (LAN only) • Data: D:\a_temp\xyshot

4. Personnel Registry aur soldiers

Yeh chapter English mein: [English](#)

Sabhi soldiers aur staff ki list: rank, number, unit, photo aur card ka status.

1. + Add Soldier dabaiye. Rank, naam, army number, company, platoon, section, mobile aur baaki fields bhariye, photo lagaiye aur save kijiye.
2. Record badalne ke liye registry se person kholiye aur edit kijiye. Person kahan-kahan gaya yeh dekhne ke liye History dabaiye.
3. Ek saath bahut log add karne ke liye Import / Export dabaiye, soldier file (CSV ya Excel) chuniye aur import kijiye. Window batati hai kitne add ya update hue aur kin rows mein galti thi.
4. Registry save karne ke liye Import / Export dabaiye aur soldiers export kijiye. Aap all, ek company ya selection chun sakte hain.

Dhyan dijiye: Suspended person ko har gate par tab tak mana kiya jata hai jab tak status wapas active na ho.

Screen: personnel

Server: localhost:8443 | DB: SQLCipher Encrypted + Add Soldier + Add Vehicle

Import / Export ID Card Studio Visitors Leave & Overdue Local Wi-Fi & Pair Device

Comms

BASE PRESENCE TELEMETRY Live Sync

Inside Facility 1 3 currently outside

Fleet On-Base 0 1 tactical units registered

Location Flags 0 Cross-location alerts record

Total Events 7 Today: 2 in • 1 out

GATE STATION NETWORK 0/1 ONLINE

G02 Gate 02 STANDBY Op: Unassigned

2 In 1 Out 0 Flags

PAIRED TERMINALS 0 active

No terminals paired

Server XV-940F5B27 • TLS fingerprint 53d292f02250445c... • Internet access OFF (LAN only) • Data: D:\a_temp\xyshot

Live Feed (7) Personnel Registry (4) Vehicle Fleet (1) Transit Times Accounts & Devices Audit Trail Export

MILITARY & CIVIL

Company-wise registry with printable QR ID cards, custom fields and full movement history. Tick cards to export selected personnel.

+ Add Soldier Details Export Selected Reports ID Cards Card Register Import / Export

Select Company All Companies View Detailed Cards Sort by ID (default)

All (2) Alpha (1) Bravo (1) Charlie (0) Delta (0) SP (0) HQ (0) Select all shown

ALPHA COMPANY 1 personnel • 1 inside

☐ CT P-001 Alpha Co **CI Test Soldier** Major • Test record Active

Service No Unit CI-0001 CI Test Unit

5. Vehicle Fleet


Yeh chapter English mein: [English](#)

Sabhi registered gaadiyan: registration, type, model, company aur status. Ek badge batata hai kitni raaste mein hain aur kitni abhi tak pahunchi nahi.

1. + Add Vehicle dabaiye aur registration, military registration, type, model, company aur status bhariye.
2. Gaadi kholkar uski History dekhiye: har entry aur exit, driver aur co-driver, aur uska route chart.
3. Import / Export se CSV file se bahut saari gaadiyan import kijiye.

Dhyan dijiye: Gaadi ki details har vehicle route chart aur export ke upar dikhti hain.

Screen: vehicles



6. Transit Times - gaadiyon ko locations ke beech dekhna

Yeh chapter English mein: [English](#)

Jab gaadi gate se niklti hai to guard bata sakta hai ki woh kahan ja rahi hai aur lagbhag kitne minute lagenge. Server ghadi dekhta rehta hai. Woh kabhi yeh nahi maanta ki gaadi pahunch gayi: sirf gate scan, destination RP ya yeh server hi bata sakta hai.

1. Phone par guard vehicle exit likhte waqt destination aur lagbhag minute bharta hai. Agar un do locations ka standard time pehle se hai to server wahi use karta hai.
2. Transit Times tab kholiye. VEHICLES ON THE WAY mein har khula trip uske due time ke saath dikhta hai.
3. STANDARD TIME BETWEEN LOCATIONS: do locations ka standard time save karne ke liye + Time Between Locations dabaiye.
4. AVERAGE TIME TAKEN har jodi ke liye sabhi gaadiyon ka average, sabse tez aur sabse dheema time dikhata hai, aur standard se compare karta hai.
5. Haath se trip likhne ke liye + Add Trip dabaiye (jo gaadi bina gate record ke nikli).
6. Gaadi late ho to server par NOT REACHED pop-up aata hai aur destination RP ke phone par gaadi aur uske nikalne ke time ka notice jata hai.
7. Pop-up mein Reached... dabakar lagne wala time likhiye; ya Stopped / moved... dabakar jagah aur lagne wala time likhiye; ya cross se band kijiye.
8. Band kiya hua pop-up 15 minute baad awaaz ke saath wapas aata hai, jab tak trip resolve na ho.
9. Har late trip ke card par dikhta hai ki destination RP ko bheje notice ka kya hua: SENT / IN TRANSIT (phone ko abhi nahi mila), RECEIVED (phone ne le liya) ya SEEN (RP ne band ya jawab diya).
10. Saare trips ka PDF, Excel ya CSV banane ke liye Export Transit Report dabaiye.

Dhyan dijiye: Destination par gaadi ka scan trip ko REACHED kar deta hai. Kisi aur location par scan ho to trip MOVED ELSEWHERE ho jata hai.

Dhyan dijiye: Phone ko sirf gaadi aur uske nikalne ka time bataya jata hai. Usse route ke times ya route chart kabhi nahi bheje jate.

Screen: transit times

XV DIGITAL ACCESS CONTROL
PC SERVER ACTIVE

Server: localhost:8443 | DB: SQLCipher Encrypted
 + Add Soldier
+ Add Vehicle

Import / Export
ID Card Studio
Visitors
Leave & Overdue
Local Wi-Fi & Pair Device

Comms
🔒
🔄

BASE PRESENCE TELEMETRY
Live Sync

Inside Facility
1
 3 currently outside

Fleet On-Base
0
 1 tactical units registered

Location Flags
0
 Cross-location alerts record

Total Events
7
 Today: 2 in • 1 out

GATE STATION NETWORK
0/1 ONLINE

G02 Gate 02
STANDBY
 Op: Unassigned
 2 In • 1 Out • 0 Flags

PAIRED TERMINALS
0 active
 No terminals paired
(Click 'Local Wi-Fi & Pair Device' and scan the QR with the Y...)

LIVE FEED (7)
PERSONNEL REGISTRY (4)
VEHICLE FLEET (1)
TRANSIT TIMES
ACCOUNTS & DEVICES
AUDIT TRAIL
EXPORT

VEHICLE TRANSIT TIMES
1 NOT REACHED
+ Add Trip
+ Time Between Locations
Export Transit Report

How long vehicles take between locations. A vehicle is never marked as reached by itself: only a gate scan, the destination RP or this server can record it.

VEHICLES ON THE WAY

CI-TEST-0001
V-014
 NOT REACHED • 1h 0m Late

From	Location 07
Going to	Location 08
Left at	08 Oct 08:04
Approx. time	30 min
Expected by	08 Oct 08:34

RP notice: not sent yet
Reached...
Stopped / moved...
History

STANDARD TIME BETWEEN LOCATIONS
 The vehicle is watched against these times. If the pair is missing, the RP is asked for an approximate time when the vehicle leaves.

Server XV-940F5B27 • TLS fingerprint 53d292f02250445c... • Internet access OFF (LAN only) • Data: D:\a_temp\XVshot

Screen: add trip

Add a vehicle trip manually

For a vehicle going to a new place, or one whose exit was not entered with a destination. The server watches the trip and alerts if the vehicle does not arrive in time.

VEHICLE
 CI-TEST-0001 — V-014

LEFT FROM (LOCATION)
 LOC07 — Location 07

GOING TO (PICK A LOCATION, OR TYPE A NEW PLACE)

DEPARTURE DATE
 10/8/2026

DEPARTURE TIME (HH:MM)
 09:34

APPROXIMATE TIME TO REACH (MINUTES)

A new place is not in the Transit Times list, so enter the approximate time yourself to get an alert if the vehicle is late.

ALREADY REACHED? TIME TAKEN (MINUTES). LEAVE BLANK IF THE VEHICLE IS STILL ON THE WAY.

Cancel
Save Trip

Screen: transit alert

1 VEHICLE NOT REACHED

Closing this window with X only hides it. It returns, with a sound, after 15 minutes until each vehicle is closed below.

CI-TEST-0001
Supply Truck

LATE 1h 0m

Location 07 → Location 08
 Left 08 Oct 08:04 • expected by 08:34 (30 min)

Reached...

Stopped / moved to another location...

Open Transit Times

Screen: close trip

Close trip • CI-TEST-0001
 Location 07 → Location 08 • left 08 Oct 08:04. The vehicle is only recorded as reached when you enter it here.

WHAT HAPPENED TO THE VEHICLE?
☒ It reached Location 08
☐ It stopped on the way
☐ It moved to another location instead

TIME TAKEN TO REACH THE DESTINATION (MINUTES)

It left at 08:04; 90 minutes have passed since then. Enter the minutes from departure until the event, not from now.

REMARKS (OPTIONAL)

Cancel

Save

7. History aur route chart

Yeh chapter English mein: [English](#)

Kisi bhi person ya gaadi ki History kholiye: har record aur ek route chart dikhega: kin jagahon par gaye, har jagah kitna ruke, beech ka safar aur har trip mein kya hua.

1. Person ya gaadi par History dabaiye.
2. Chart upar se neeche padhiye: LEFT, TRAVEL (REACHED, NOT REACHED, MOVED ELSEWHERE ya STOPPED ke saath), ARRIVED aur kitna time ruke.
3. Gaadiyon ke liye driver aur co-driver dikhte hain, aur driver badalne par ek line batati hai.
4. Print ke liye ek page ka PDF ya rang-bhara Excel file chahiye to Export Route... dabaiye.
5. Chhooti hui entry ya exit haath se jodne ke liye person ki history mein + Add Record dabaiye, reason aur remarks ke saath.

Dhyan dijiye: Haath se record likhne ke liye administrator password lagta hai (agar set hai) aur woh audit trail mein likha jata hai.

Screen: vehicle history route

Movement History • V-014

Every entry and exit recorded for this credential, newest first.

VEHICLE DETAILS

REGISTRATION	VEHICLE ID	TYPE	MODEL	COMPANY	STATUS
CI-TEST-0001	V-014	Supply Truck	Test Model	Alpha	ACTIVE

2 records • total recorded time on site: 2h 30m

ROUTE CHART

LEFT Wed 07 Oct 21:54

Location 07
Trip entered by the server operator

TRAVEL Wed 07 Oct 21:54 REACHED

→ **Location 08**
To Location 08 • REACHED in 42 min (approx 30 min) • entered by the server

LEFT Wed 07 Oct 23:34

Location 08
Trip entered by the server operator

TRAVEL Wed 07 Oct 23:34 REACHED

→ **Location 07**
To Location 07 • REACHED in 31 min (approx 25 min) • entered by the server

ARRIVED Thu 08 Oct 05:34

Location 07 • Gate 02
Stayed 2h 30m

Export Route...

Close

Screen: add history record

+ Add Record to History • G-001

ENTRY / EXIT update who is inside, exactly like a gate scan. Other types (Leave, Duty, Course...) are dated history entries. Types are configured in Stations & Settings.

CI Test Visitor • VISITOR • Visitors Co • currently OUTSIDE

RECORD TYPE

ENTRY

DATE

10/8/2026

TIME (HH:MM)

09:34

LOCATION

LOC07 — Location 07

GATE

G02 — Gate 02

REASON (ENTRY / EXIT)

Cancel Save Record

8. Accounts & Devices

Yeh chapter English mein: [English](#)

Woh RP accounts jo phones par sign in kar sakte hain, aur jo phones paired hain.

1. + Create Operator naya RP account banata hai.
2. Disable account ko sign in karne se rokta hai. Reset Password naya password set karta hai. Delete account hata deta hai.
3. Pair Terminal naya pairing QR code dikhata hai.
4. PAIRED TERMINALS mein har phone, uski location aur aakhri baar kab report kiya yeh dikhta hai. Kisi phone par Revoke Access dabane se woh ruk jata hai aur use apna data mitane ka order jata hai.

Dhyan dijiye: Revoke kiya hua phone server se agli baar judte hi apna saved data mita deta hai.

Screen: accounts devices

9. Audit Trail

Yeh chapter English mein: [English](#)

Har badlav, sign-in aur gate record ka ek tamper-proof log. Har entry pichli entry se judi hoti hai.

1. Audit Trail tab kholiye. Nayi entries upar hoti hain; details har row ke neeche dikhti hain.
2. Verify integrity dabaiye. Server poori chain check karta hai aur batata hai ki kuch badla, hataya ya kaata gaya to nahi.
3. Log save karne ke liye Export CSV dabaiye.

Dhyan dijiye: Verify integrity niyamt roop se chalaiye aur server ko kisi ko saunpne se pehle bhi.

Screen: audit

Server: localhost:8443 | DB: SQLCipher Encrypted | + Add Soldier | + Add Vehicle

Import / Export | ID Card Studio | Visitors | Leave & Overdue | Local Wi-Fi & Pair Device

Comms | [Lock Icon] | [Refresh Icon]

BASE PRESENCE TELEMETRY Live Sync

Inside Facility: 1 (3 currently outside)

Fleet On-Base: 0 (1 tactical units registered)

Location Flags: 0 (Cross-location alerts record)

Total Events: 7 (Today: 2 in • 1 out)

GATE STATION NETWORK 0/1 ONLINE

G02 Gate 02: STANDBY, Op: Unassigned, 2 In, 1 Out, 0 Flags

PAIRED TERMINALS 0 active

No terminals paired

SECURITY AUDIT TRAIL 20 entries

Every administrative change, sign-in and gate record is written to the encrypted audit log.

Verify integrity | Export CSV

08 Oct 2026 09:34:27	CI	SET_PHOTO	PERSON P001
08 Oct 2026 09:34:27	PC-ADMIN	ROTATE_QR_SECRET	persons P002
Replacement for lost card - CI test			
08 Oct 2026 09:34:27	PC-ADMIN	CARD_REPORTED_LOST	PERSON P002
CI test			
08 Oct 2026 09:34:27	PC-ADMIN	ADD_PERSON	PERSON G002
08 Oct 2026 09:34:27	PC-ADMIN	ADD_PERSON	PERSON G001
08 Oct 2026 09:34:27	GK-01	VEHICLE_EXIT	VEHICLE V014
MNF-CI-ENT-6PAP7A			
08 Oct 2026 09:34:27	GK-01	TRANSIT_OPENED	VEHICLE V014
LOC07 -> Location 08 (30 min)			
08 Oct 2026 09:34:27	GK-01	VEHICLE_ENTRY	VEHICLE V014
MNF-CI-ENT-6PAP7A			
08 Oct 2026 09:34:27	PC-ADMIN	TRANSIT_REACHED	VEHICLE V014
Location 08 -> Location 07 in 31 min (SERVER)			
08 Oct 2026 09:34:27	PC-ADMIN	TRANSIT_OPENED	VEHICLE V014

Server XV-940F5B27 • TLS fingerprint 53d292f02258445c... • Internet access OFF (LAN only) • Data: D:\a_temp\xvshot

10. Export tab aur reports

Yeh chapter English mein: [English](#)

Sabhi exports ek jagah: movement reports, route charts aur transit report. Har ek ka apna card hai.

1. Export tab kholiye.
2. Log, company ya gaadiyan, dates aur format (PDF, Excel ya CSV) chuniye, phir us card ka export button dabaiye.
3. Reports ka heading Settings mein badla ja sakta hai (Export heading template).
4. Route chart export ka apna alag card hai, baaki exports se alag.

Dhyan dijiye: Exports ke liye administrator password lagta hai (agar set hai).

Screen: export

XV DIGITAL ACCESS CONTROL
PC SERVER ACTIVE

Server: localhost:8443 | DB: SQLCipher Encrypted
 + Add Soldier
+ Add Vehicle

Import / Export
ID Card Studio
Visitors
Leave & Overdue
Local Wi-Fi & Pair Device

Comms
🔒
🔄

BASE PRESENCE TELEMETRY
Live Sync

Inside Facility
1
3 currently outside

Fleet On-Base
0
1 tactical units registered

Location Flags
0
Cross-location alerts record

Total Events
7
Today: 2 in • 1 out

GATE STATION NETWORK
0/1 ONLINE

G02 Gate 02
STANDBY
Op: Unassigned

2 In
1 Out
0 Flags

PAIRED TERMINALS
0 active

No terminals paired
Click 'Local Wi-Fi & Pair Device' and scan the QR with the Y

LIVE FEED (7)
PERSONNEL REGISTRY (4)
VEHICLE FLEET (1)
TRANSIT TIMES
ACCOUNTS & DEVICES
AUDIT TRAIL
EXPORT

EXPORT REPORTS

Choose who and what period to export, then pick a file format. CSV is data only; Excel and PDF print the heading below.

WHO

All Personnel

WHEN

This Month

☒ Include gate & history records (untick for roster only)

EXPORT HEADING

{Scope} is replaced with who this export covers -- e.g. "Capt John Doe", "Alpha Company", "2 Platoon". Also editable from Settings.

Movement History of {Scope}

Server XV-940F5B27 • TLS fingerprint 53d292f02250445c... • Internet access OFF (LAN only) • Data: D:\a_temp\xvshot

Screen: reports export

Reports & Export

Excel: summary sheet plus one colour-coded sheet per company (roster + records). PDF: printable A4 report. CSV: plain records for any software.

COMPANY

All Companies

FROM

9/8/2026

15

TO

10/8/2026

15

☒ Include gate & history records (untick for roster only)

Close

CSV

PDF

Excel

11. ID Card Studio aur Card Register


Yeh chapter English mein: [English](#)

Asli QR code ke saath ID card design aur print kijiye, aur har card ka issue, re-issue, print aur kho jane ka record rakhiye.

1. ID Card Studio dabaiye. Log chuniye (ek, company ya selection), design badaliye aur print kijiye ya PDF save kijiye.
2. Theme & Emblems > Card style mein Classic (formal card), Modern two sides (front par details, back par QR) ya Modern one side (photo, details aur QR ek hi taraf) chuniye.
3. Modern cards ke liye rang, light ya dark card, likhawat, extra details (company, blood group aadi) chuniye aur logo upload kijiye: two-sided card par front aur back logo, one-side card par left aur right logo. Slider se logo ka size badlen.
4. Card Register kholkar har soldier ka card number, issue date, aakhri print aur kho jane ka itihis dekhiye.
5. Card kho jaye to Report lost... dabaiye. Purana card har gate par turant mana ho jata hai aur agle card ke liye naya QR code ban jata hai.
6. Register save karne ke liye Export company-wise... dabaiye.

Dhyan dijiye: Personnel QR codes kabhi expire nahi hote. Code tabhi badalta hai jab card lost report ho ya re-issue ho.

Screen: id card studio



Screen: card register

ID Card Register

Every card's issue, re-issue, print and loss history. Personnel QR codes never expire — a code changes only when the card is reported lost or re-issued, and then the old card is refused at every gate.

SEARCH (ID, army no, name, company)

Major CI Test Soldier CARD #1

P-001 • Army No: CI-0001 • Alpha

Issued 08 Oct 2026 • last printed never • QR: no expiry

History

Open in ID Card Studio

Report lost...

Havildar CI Test Driver CARD #2 LOST #1

P-002 • Army No: CI-0002 • Bravo

Issued 08 Oct 2026 • last re-issued 08 Oct 2026 09:34 • last printed never • QR: no expiry

History

Open in ID Card Studio

Report lost...

Close

Export company-wise...

12. Visitors aur temporary passes

Yeh chapter English mein: [English](#)

Din ya kuch samay ke passes jinka QR sirf 'valid from' aur 'valid to' ke beech kaam karta hai.

1. Visitors dabaiye, phir + New visitor pass.
2. Visitor ka poora naam, mobile, organisation, ID proof, aane ka purpose aur kisse milna hai yeh bhariye. Dates set kijiye ya Today until 18:00, Next 24 hours ya 7 days use kijiye.
3. Sirf pass save karna ho to Create pass (no print) dabaiye, ya save karke printable pass kholne ke liye Create & print pass.
4. Baad mein kisi bhi visitor par Print pass, pass band karne ke liye End pass now, ya visitor kahan gaya yeh dekhne ke liye History dabaiye.
5. Spreadsheet ke liye Export visitors report... dabaiye.

Dhyan dijiye: Exit hamesha allowed hai, isliye koi andar fansta nahi. Pass khatam hone ke baad bhi andar rehne wale visitor ko overstay mark kiya jata hai.

Screen: visitors

Visitors & Temporary Passes

Day / temporary passes with a QR that works only between 'valid from' and 'valid to'. Exits are always allowed, so nobody is trapped inside. Visitors still inside after the pass ends are flagged as overstay.

All passesInside nowValid nowEnded / expired

CI Test Visitor VALID

G001 • ID proof: CI test ID

Purpose: CI test visit • Visiting: P001

Valid 08 Oct 2026 09:29 → 08 Oct 2026 17:34

Print pass

History

End pass now

CI Ended Visitor ENDED

G002 • ID proof: CI test ID

Purpose: CI test visit • Visiting: P001

Valid 08 Oct 2026 04:34 → 08 Oct 2026 08:34

Print pass

History

End pass now

Close

Export visitors report...

+ New visitor pass

Screen: new visitor pass

New Visitor Pass

The QR on the pass works at every gate only inside the validity window.

VISITOR'S FULL NAME

MOBILE NUMBER

ORGANISATION / ADDRESS

ID PROOF (TYPE AND NUMBER, E.G. AADHAAR 1234 5678 9012)

PURPOSE OF VISIT

VISITING (PERSON / OFFICE)

VALID FROM

10/8/20261509:34

Cancel

Create pass (no print)

Create & print pass

13. Leave, TD aur overdue alerts


Yeh chapter English mein: [English](#)

Jo log expected return date ke saath nikle hain unhe track kiya jata hai. Date nikal jaye to server alert deta hai.

1. Phone un reasons ke liye expected return date poochta hai jo aap Stations & Settings mein chunte hain (jaise Proceeding on Leave, TD).
2. Leave & Overdue dabaiye aur dekhiye kaun bahar hai. Chips Everyone out ya Overdue only use kijiye.
3. Koi overdue ho to PC par pop-up aata hai: jaise 'Havildar Name has not returned from leave', reason aur due date ke saath.
4. Us person ki koi bhi entry absence apne aap band kar deti hai.
5. Settings > Leave & Overdue Alerts: chuniye kin Locations ya RPs ko yeh alert unke phone par bhi mile. Sirf unhi phones par jata hai.

Dhyan dijiye: By default alert sirf PC par dikhta hai.

Screen: leave overdue



14. Comms Center

Yeh chapter English mein: [English](#)


Server aur paired phones ke beech messages, alerts, calls aur SOS.

1. Comms dabaiye aur left se ek terminal chuniye.
2. Message likhkar Send dabaiye, ya Send ALERT dabaiye jisse phone app background mein ho tab bhi baje.
3. Broadcast alert to all terminals... har phone ko ek alert bhejta hai.
4. Aapke bheje har message ke neeche uska asli status dikhta hai: sent, in transit (phone offline hai), received (phone ke paas pahunch gaya) ya seen (kisi ne khola). Phone par bhi apne bheje ka yahi status dikhta hai.

5. Phone se SOS aate hi PC par bhejne wale aur jagah ke saath dikh jata hai.
6. Terminal ke saath voice aur video calls conversation mein dikhti hain, missed calls laal rang mein.

Dhyan dijiye: Messages end-to-end encrypted hote hain.

Screen: comms center



15. Settings

Yeh chapter English mein: [English](#)

Sab kuch jo server ke vyavhaar ko control karta hai.

1. QUICK STATUS mein abhi ki data sharing, internet access, auto-lock, outbound block, self-registration, administrator password aur heading template dikhte hain.
2. Station & General: locations, gates, server ka naam, port, custom fields, movement reasons, data protection, diagnostics aur maintenance.
3. Cloud Link: phones ko internet se PC tak pahunchne deta hai (chapter 17).
4. Leave & Overdue Alerts: leave alert phone par aur kise milega.
5. Koi bhi badlav ke baad Save Settings dabaiye.

Dhyan dijiye: HTTPS port badalne par phones ko dobara pair karna padega.

Screen: settings

XV DIGITAL ACCESS CONTROL
PC SERVER ACTIVE

Server: localhost:8443 | DB: SQLCipher Encrypted
 + Add Soldier
+ Add Vehicle

Import / Export
ID Card Studio
Visitors
Leave & Overdue
Local Wi-Fi & Pair Device

Comms
🔒
🔄

BASE PRESENCE TELEMETRY
Live Sync

Inside Facility
1
3 currently outside

Fleet On-Base
0
1 tactical units registered

Location Flags
0
Cross-location alerts record

Total Events
7
Today: 2 in • 1 out

GATE STATION NETWORK
0/1 ONLINE

G02 Gate 02
STANDBY
Op: Unassigned

2 In
1 Out
0 Flags

PAIRED TERMINALS
0 active

No terminals paired

Click 'Local Wi-Fi & Pair Device' and scan the QR with the Y

COMMAND CENTER SETTINGS
 Station setup, data protection, connectivity and maintenance for this Command Center.

QUICK STATUS

Data sharing with terminals	MINIMAL
Internet access	Disabled (LAN only)
Auto-lock	OFF
Outbound internet block	ON
Self-registration approval	Required
Administrator password	Not set
Export heading template	Movement History of {Scope}

Station & General
 Locations, gates, server name, custom fields, movement reasons, data protection, diagnostics and maintenance.

Open Station & General Settings

Server XV-940F5B27 • TLS fingerprint 53d292f02250445c... • Internet access OFF (LAN only) • Data: D:\a_temp\xvshot

Screen: stations settings

Stations & Settings

Locations and gates appear in the terminal's sign-in screen. Nothing is pre-filled — add the real posts of your base.

LOCATIONS

LOC07 Location 07

Remove

LOC08 Location 08

Remove

Add a location: ID (e.g. LOC07) then name (e.g. Location 07 Main Hub)

Add / Update

GATES

G02 Gate 02

Remove

Add a gate: ID (e.g. G02) then name (e.g. Gate 02 Primary)

Add / Update

SERVER

COMMAND CENTER NAME (SHOWN ON TERMINALS)

HTTPS PORT (TERMINALS MUST BE RE-PAIRED AFTER A CHANGE)

☒ Operators who self-register must be approved here

Cancel

Save Settings

16. Backup, restore, lock aur administrator password

Yeh chapter English mein: [English](#)

Apne data ko surakshit rakhiye aur wapas paiye.

1. Import / Export > ENCRYPTED BACKUP & RESTORE > Create encrypted backup... Ek file aur password chuniye. File mein poora database aur settings encrypted rehte hain.
2. Restore from backup... wahi password maangta hai aur is PC ka data badal deta hai. Yeh sirf soch samajhkar kijiye.
3. Settings mein administrator password set kijiye. Phir exports, haath ke records aur doosre sensitive kaam se pehle yeh poocha jata hai.
4. Screen lock karne ke liye upar ka lock button dabaiye. Gate server chalta rehta hai. Unlock ke liye administrator password daliye.
5. Auto-lock Settings mein set kiye gaye idle time ke baad screen lock kar deta hai.

Dhyan dijiye: Backup ka password surakshit rakhiye. Uske bina backup khul nahi sakta.

17. Cloud Link (internet par phones)

Yeh chapter English mein: [English](#)

Base ke Wi-Fi se bahar ke phone ko secure tunnel ke zariye server tak pahunchne deta hai.

1. Settings > Cloud Link kholiye.
2. Gate server aur comms server ke secure web addresses (URL) daliye jo aapke tunnel ne diye hain.
3. Phone ko naye QR code se dobara pair kijiye. Ab phone mobile data par bhi kaam karega.
4. Sirf local Wi-Fi par wapas aane ke liye internet access wapas off kijiye.

Dhyan dijiye: Internet par bhi saara traffic encrypted rehta hai (TLS aur AES-256-GCM messages).

Screen: cloud link

Cloud Link — Internet Connection Setup

Terminals always try the local network first and fall back to the internet address below. Every request stays end-to-end encrypted (AES-256-GCM with each terminal's own key) even when a tunnel or relay handles TLS.

☐ **Allow terminals to connect over the internet**

When off, this PC refuses every connection that does not come from a private (LAN / VPN) address.

CONNECTION METHOD

PORT_FORWARD

Port forwarding: on your router forward TCP 8443 → this PC's LAN address port 8443. Use a static public IP or a free DDNS name (e.g. DuckDNS) as the public host.

⚠ Least private option — this opens a port directly to the whole internet (still TLS + AES-256-GCM protected, but scannable and reachable by anyone). VPN or Tunnel expose nothing at all to the open internet and are safer where they're an option.

RESTRICT INTERNET CONNECTIONS TO KNOWN NETWORKS (OPTIONAL)

ALLOWED INTERNET ADDRESS RANGES, ONE PER LINE — E.G. 203.0.113.0/24 (BLANK = ALLOW ANY ADDRESS)

Only affects connections from outside the local network / VPN — LAN terminals are never blocked by this. Leave blank unless you know the exact networks your remote terminals connect from.

PUBLIC HOST (DDNS NAME, PUBLIC IP OR VPN IP)

PUBLIC PORT

Export details...

Cancel

Save

18. Phone app (gate par RP ke liye)

Yeh chapter English mein: [English](#)

Phone par XV Gatekeeper app RP ko entry aur exit record karne ke liye hai.

1. Accounts & Devices mein bane RP account se sign in kijiye aur location tatha gate chuniye.
2. Card ka QR scan kijiye. App person dikhata hai aur Entry ya Exit poochta hai. Exit ke liye reason chuniye; leave ya TD ke liye expected return date daliye.
3. Gaadi ke liye vehicle QR scan kijiye, phir driver aur saare saath baithe log, aur confirm kijiye. Vehicle exit par destination aur lagbhag minute daliye.
4. Agar destination आपके base ki location hai to wahan ke RP ko batata hai jab gaadi nahi pahunchi. RP phir Reached... dabakar lagne wala time likh sakta hai, ya bata sakta hai ki gaadi ruk gayi ya kisi aur jagah chali gayi.
5. Network na ho to bhi records phone mein rehte hain aur server milte hi bhej diye jate hain.
6. SOS button position ke saath emergency alert server ko bhejta hai.
7. Shift handover bina bheje records agle phone ko Bluetooth ya Wi-Fi hotspot se deta hai.
8. Bhasha (English ya Hindi) aur dark mode app ki settings mein hain.

Dhyan dijiye: Phone kho jaye to Accounts & Devices mein use revoke kijiye. Agli baar server se judte hi woh apna data mita dega.

19. Kuch kaam na kare to

Yeh chapter English mein: [English](#)

Jaldi ki jaanch.

1. Phone connect nahi ho raha: dekhiye PC aur phone same Wi-Fi par hain, PC firewall app ko allow karta hai, aur phone revoke nahi hua.
2. Phone ka time galat hai ya mana kiya ja raha hai: phone par sahi date aur time set kijiye.
3. Scan mana ho raha hai: Personnel Registry mein person kholkar dekhiye ki status active hai aur card lost report nahi hua.
4. Pop-up wapas nahi aata: Transit Times tab kholkar trip ko resolve ya snooze kijiye.
5. Kuch bhi anjaan ho to Audit Trail mein exact entry aur time dekhiye.