

Task 13

Implement a real-world AWS EC2 setup where **storage management, user access, connectivity troubleshooting, and S3 security** are all part of **one connected workflow**.

Task Description

1. EC2 Setup (Linux OR Windows)

- Launch **one EC2 instance** (Linux or Windows).
- Verify basic connectivity:
 - SSH for Linux / RDP for Windows.

2. Root Volume Extension

- Extend the **root volume** of the EC2 instance.
- Perform required OS-level steps to:
 - Increase filesystem size
 - Verify updated disk space

3. Attach and Use New Volume

- Create and attach **one additional EBS volume**.
- Format and mount the volume:
 - Linux: mount under /data
 - Windows: assign a new drive letter
- Store test files on the new volume.

4. User Management

- Create **OS-level users**:
 - Linux: one normal user and one sudo user
 - Windows: one standard user and one administrator
- Verify access permissions.

5. S3 Secure Configuration

- Create **one S3 bucket**.
- Enable:
 - Server-side encryption
 - Versioning


- Secure transport (HTTPS only)
- Upload logs or test files from EC2 to S3.

Solution:

1. Login to your AWS account with credentials and required verification.

(<https://signin.aws.amazon.com/>)

My account – AWS Management Console- Sign in



2. EC2 Setup (Amazon Linux)

2.1 Launch EC2 Instance

- Go to EC2 - Launch instance
- AMI: Amazon Linux 2
- Instance type: t2.micro (free tier)
- Key pair:
- Network:
 - VPC: default
 - Subnet: any public subnet
 - Auto-assign public IP: Enabled
- Security Group:
 - Allow SSH (22) from your IP

- Launch instance

EC2 > Instances > Launch an instance

Name and tags

Name

Bastion-public

Add additional tags

Application and OS Images (Amazon Machine Image)

An AMI contains the operating system, application server, and applications for your instance. If you don't see a suitable AMI below, use the search field or choose [Browse more AMIs](#).

Q Search our full catalog including 1000s of application and OS images

Recents

Quick Start

Amazon Linux

aws

macOS

Mac

Ubuntu

ubuntu

Windows

Microsoft

Red Hat

Red Hat

SUSE Linux

SUSE

Debian

debian

Browse more AMIs

Including AMIs from AWS, Marketplace and the Community

Amazon Machine Image (AMI)

Amazon Linux 2023 kernel-6.1 AMI

ami-0ced6a024bb18ff2e (64-bit (x86), uefi-preferred) / ami-01605b62a13170a53 (64-bit (Arm), uefi)

Virtualization: hvm ENA enabled: true Root device type: ebs

Description

Summary

Number of instances

1

Software Image (AMI)

Amazon Linux 2023 AMI 2023.10...[read more](#)

ami-0ced6a024bb18ff2e

Virtual server type (instance type)

t3.micro

Firewall (security group)

New security group

Storage (volumes)

1 volume(s) - 8 GiB

Cancel

Launch instance

Preview code

EC2 > Instances > Launch an instance

Amazon Linux 2023 AMI 2023.10.20260105.0 x86_64 HVM kernel-6.1

Architecture

64-bit (x86)

Boot mode

uefi-preferred

AMI ID

ami-0ced6a024bb18ff2e

Publish Date

2026-01-02

Username

ec2-user

Verified provider

Instance type

t3.micro

Family: t3 2 vCPU 1 GiB Memory Current generation: true On-Demand Linux base pricing: 0.0112 USD per Hour On-Demand SUSE base pricing: 0.0112 USD per Hour On-Demand Windows base pricing: 0.0204 USD per Hour On-Demand Ubuntu Pro base pricing: 0.0147 USD per Hour On-Demand RHEL base pricing: 0.04 USD per Hour

All generations

Compare instance types

Additional costs apply for AMIs with pre-installed software

Key pair (login)

You can use a key pair to securely connect to your instance. Ensure that you have access to the selected key pair before you launch the instance.

Key pair name - required

Bastion

Create new key pair

Summary

Number of instances

1

Software Image (AMI)

Amazon Linux 2023 AMI 2023.10...[read more](#)

ami-0ced6a024bb18ff2e

Virtual server type (instance type)

t3.micro

Firewall (security group)

New security group

Storage (volumes)

1 volume(s) - 8 GiB

Cancel

Launch instance

Preview code

EC2 > Instances > Launch an instance

Network settings

VPC - required

vpc-00f3cd51c8a211d4b (myvpc)

10.0.0.0/16

Subnet

subnet-036ba8f972ed7dea7

VPC: vpc-00f3cd51c8a211d4b Owner: 798974631771 Availability Zone: ap-south-1a (aps1-az1) Zone type: Availability Zone IP addresses available: 251 CIDR: 10.0.1.0/24

Public

Create new subnet

Auto-assign public IP

Enable

Firewall (security groups)

Create security group

Select existing security group

Security group name - required

Bastion

Description - required

launch-wizard-1 created 2026-01-16T05:48:09.293Z

Summary

Number of instances

1

Software Image (AMI)

Amazon Linux 2023 AMI 2023.10...[read more](#)

ami-0ced6a024bb18ff2e

Virtual server type (instance type)

t3.micro

Firewall (security group)

New security group

Storage (volumes)

1 volume(s) - 8 GiB

Cancel

Launch instance

Preview code

- Save changes

Before Extend

```
[ec2-user@ip-10-0-1-79 ~]$ df -h
Filesystem      Size  Used Avail Use% Mounted on
devtmpfs        4.0M  0    4.0M  0% /dev
tmpfs           459M  0    459M  0% /dev/shm
tmpfs           184M  432K  183M  1% /run
/dev/nvme0n1p1  8.0G  1.6G  6.5G  19% /
tmpfs           459M  0    459M  0% /tmp
/dev/nvme0n1p128 10M   1.3M  8.7M  13% /boot/efi
tmpfs           92M   0    92M   0% /run/user/1000
[ec2-user@ip-10-0-1-79 ~]$ lsblk
NAME            MAJ:MIN RM  SIZE RO TYPE MOUNTPOINTS
nvme0n1         259:0    0    8G  0 disk
├─nvme0n1p1     259:1    0    8G  0 part /
├─nvme0n1p127   259:2    0    1M  0 part
└─nvme0n1p128   259:3    0   10M  0 part /boot/efi
[ec2-user@ip-10-0-1-79 ~]$
```

Modify

The screenshot displays the AWS Management Console interface for an Elastic Block Store (EBS) volume. The left-hand navigation pane shows various AWS services, with 'Elastic Block Store' expanded to show 'Volumes', 'Snapshots', and 'Lifecycle Manager'. The main content area is titled 'Volumes (1/1) Info' and includes a table with one volume listed: 'vol-0838ea8fff670c512' of type 'gp3' and size '8 GiB'. Below the table, the 'Details' tab for this volume is active, showing various attributes and status checks.

Volume ID	Size	Type	Status check
vol-0838ea8fff670c512	8 GiB	gp3	Okay

Additional details shown in the console include:

- AWS Compute Optimizer finding:** Opt-in to AWS Compute Optimizer for recommendations. | [Learn more](#)
- Fast snapshot restored:** No
- Availability Zone:** ap-s1-az1 (ap-south-1a)
- Created:** Fri Jan 16 2026 11:21:15 GMT+0530 (India Standard Time)
- Multi-Attach enabled:** No
- Throughput:** 125
- Outposts ARN:** (empty)
- Managed:** (empty)
- Operator:** (empty)

EC2 > Volumes > vol-0838ea8fff670c512 > Modify volume

Modify volume [Info](#)

Modify the type, size, and performance of an EBS volume.

Volume details

Volume ID
vol-0838ea8fff670c512

Volume type [Info](#)
General Purpose SSD (gp3)

Size (GiB) [Info](#)
20
Min: 1 GiB, Max: 65536 GiB.

IOPS [Info](#)
3000
Min: 3000 IOPS, Max: 80000 IOPS.

Throughput (MiB/s) [Info](#)
125
Min: 125 MiB, Max: 2000 MiB, Baseline: 125 MiB/s.

[Cancel](#) [Modify](#)

Requested volume modification for volume vol-0838ea8fff670c512.
The volume is being modified.

Volumes (1) [Info](#)

Saved filter sets
Choose filter set [▼](#)

Last updated less than a minute ago [Recycle Bin](#) [Actions](#) [Create volume](#)

☐	Name ↗	Volume ID	Type	Size	IOPS	Throughput	Snapshot ID	Source volume ID	Created
☐		vol-0838ea8fff670c512	gp3	8 GiB	3000	125	snap-07e5239...	-	2026/01/16 11:21 GMT+5

After Extension

```
[ec2-user@ip-10-0-1-79 ~]$ df -h
Filesystem      Size  Used Avail Use% Mounted on
devtmpfs        4.0M   0  4.0M   0% /dev
tmpfs           459M   0  459M   0% /dev/shm
tmpfs           184M 432K  183M   1% /run
/dev/nvme0n1p1  8.0G  1.6G  6.5G  19% /
tmpfs           459M   0  459M   0% /tmp
/dev/nvme0n1p128 10M  1.3M  8.7M  13% /boot/efi
tmpfs           92M   0   92M   0% /run/user/1000
[ec2-user@ip-10-0-1-79 ~]$ lsblk
NAME        MAJ:MIN RM  SIZE RO TYPE MOUNTPOINTS
nvme0n1     259:0    0   20G  0 disk
├─nvme0n1p1 259:1    0    8G  0 part /
├─nvme0n1p127 259:2    0    1M  0 part
└─nvme0n1p128 259:3    0   10M  0 part /boot/efi
[ec2-user@ip-10-0-1-79 ~]$
```

3.2 Extend file system

Grow the partition

```
sudo growpart /dev/xvda 1
```

Resize filesystem

```
sudo xfs_growfs /
```

Verify

```
df -h
```

```
[ec2-user@ip-10-0-1-79 ~]$ lsblk
NAME        MAJ:MIN RM SIZE RO TYPE MOUNTPOINTS
nvme0n1     259:0    0 20G  0 disk
├─nvme0n1p1 259:1    0  8G  0 part /
├─nvme0n1p127 259:2    0  1M  0 part
└─nvme0n1p128 259:3    0 10M  0 part /boot/efi
[ec2-user@ip-10-0-1-79 ~]$ sudo growpart /dev/xvda 1
CHANGED: partition=1 start=24576 old: size=16752607 end=16777183 new: size=41918431 end=41943007
[ec2-user@ip-10-0-1-79 ~]$ sudo xfs_growfs /
meta-data=/dev/nvme0n1p1      isize=512    agcount=2, agsize=1047040 blks
=                               sectsz=4096   attr=2, projid32bit=1
=                               crc=1       finobt=1, sparse=0, rmapbt=0
=                               reflink=0    bigtime=1 inobtcount=1 nrext64=0
=                               exchange=0
data      =                    bsize=4096   blocks=2094075, imaxpct=25
=                               sunit=128     swidth=128 blks
naming    =version 2          bsize=16384  ascii-ci=0, ftype=1, parent=0
log       =internal log      bsize=4096   blocks=16384, version=2
=                               sectsz=4096   sunit=4 blks, lazy-count=1
realtime  =none              extsz=4096   blocks=0, rtextents=0
data blocks changed from 2094075 to 5239803
[ec2-user@ip-10-0-1-79 ~]$ df -h
Filesystem      Size  Used Avail Use% Mounted on
devtmpfs        4.0M   0  4.0M   0% /dev
tmpfs           459M   0  459M   0% /dev/shm
tmpfs           184M  432K  183M   1% /run
/dev/nvme0n1p1   20G   1.6G   19G   8% /
tmpfs           459M   0  459M   0% /tmp
/dev/nvme0n1p128 10M   1.3M   8.7M  13% /boot/efi
tmpfs           92M   0   92M   0% /run/user/1000
[ec2-user@ip-10-0-1-79 ~]$
```

4. Attach New EBS Volume and Use

4.1 Create and Attach Volume

- EC2 - Volumes - Create volume
- Size: 10 GiB
- AZ: same as EC2
- Attach volume to instance
- Device: `/dev/xvdbf`

EC2 > Volumes > Create volume

Volume settings

Volume type [Info](#)

General Purpose SSD (gp3)

Size (GiB) [Info](#)

10

Min: 1 GiB, Max: 65536 GiB.

IOPS [Info](#)

3000

Min: 3000 IOPS, Max: 80000 IOPS.

Throughput (MiB/s) [Info](#)

125

Min: 125 MiB, Max: 2000 MiB, Baseline: 125 MiB/s.

Availability Zone [Info](#)

aps1-az1 (ap-south-1a)

Snapshot ID - optional [Info](#)

Don't create volume from a snapshot

Encryption [Info](#)

Use Amazon EBS encryption as an encryption solution for your EBS resources associated with your EC2 instances.

EC2 > Volumes > vol-0498e42f881855f1c > Attach volume

Attach volume [Info](#)

Attach a volume to an instance to use it as you would a regular physical hard disk drive.

Basic details

Volume ID

vol-0498e42f881855f1c

Availability Zone

aps1-az1 (ap-south-1a)

Instance [Info](#)

i-0a8e89e9891315ddd
(B1ation-public) (running)

Only instances in the same Availability Zone as the selected volume are displayed.

Device name [Info](#)

/dev/xvdbf

Recommended device names for Linux: /dev/xvda for root volume, /dev/xvdf-p for data volumes.

ⓘ Newer Linux kernels may rename your devices to /dev/xvdf through /dev/xvdp internally, even when the device name entered here (and shown in the details) is /dev/sdf through /dev/sdp.

Cancel

Attach volume

Verify

```
[ec2-user@ip-10-0-1-79 ~]$ lsblk
NAME        MAJ:MIN RM  SIZE RO TYPE MOUNTPOINTS
nvme0n1      259:0    0   20G  0 disk
├─nvme0n1p1  259:1    0   20G  0 part /
├─nvme0n1p127 259:2    0    1M  0 part
├─nvme0n1p128 259:3    0   10M  0 part /boot/efi
nvme1n1      259:4    0   10G  0 disk
[ec2-user@ip-10-0-1-79 ~]$
```

Now create a file system

sudo mkfs -t xfs /dev/xvdf

```
[ec2-user@ip-10-0-1-79 ~]$ sudo mkfs -t xfs /dev/xvdf
Error accessing specified device /dev/xvdf: No such file or directory
Usage: mkfs.xfs
/* blocksize */          [-b size=num]
/* config file */        [-c options=xxx]
/* metadata */           [-m crc=0|1,finobt=0|1,uuid=xxx,rmapbt=0|1,reflink=0|1,
                          inobtcount=0|1,bigtime=0|1,autofsck=xxx]
/* data subvol */        [-d agcount=n,agsize=n,file,name=xxx,size=num,
                          (sunit=value,swidth=value|su=num,sw=num|noalign),
                          sectsize=num,concurrency=num]
/* force overwrite */    [-f]
/* inode size */         [-i perblock=n|size=num,maxpct=n,attr=0|1|2,
                          projid32bit=0|1,sparse=0|1,nrext64=0|1,
                          exchange=0|1]
/* no discard */         [-K]
/* log subvol */         [-l agnum=n,internal,size=num,logdev=xxx,version=n
                          sunit=value|su=num,sectsize=num,lazy-count=0|1,
                          concurrency=num]
/* label */              [-L label (maximum 12 characters)]
/* naming */             [-n size=num,version=2|ci,ftype=0|1,parent=0|1]]
/* no-op info only */    [-N]
/* prototype file */     [-p fname]
/* quiet */              [-q]
/* realtime subvol */    [-r extsize=num,size=num,rtdev=xxx]
/* sector size */        [-s size=num]
/* version */            [-V]
                          devicename
<devicename> is required unless -d name=xxx is given.
<num> is xxx (bytes), xxxs (sectors), xxxb (fs blocks), xxxk (xxx KiB),
      xxxm (xxx MiB), xxxg (xxx GiB), xxxt (xxx TiB) or xxxp (xxx PiB).
<value> is xxx (512 byte blocks).
[ec2-user@ip-10-0-1-79 ~]$
```

Create mount point

sudo mkdir /data

Mount volume

sudo mount /dev/xvdf /data

Persist after reboot

sudo blkid

sudo nano /etc/fstab

Add line

UUID=<UUID> /data xfs defaults,nofail 0 2

Verify

df -h

```
[ec2-user@ip-10-0-1-79 ~]$ sudo mount -a
[ec2-user@ip-10-0-1-79 ~]$ df -h
Filesystem      Size  Used Avail Use% Mounted on
devtmpfs        4.0M    0  4.0M   0% /dev
tmpfs           459M    0  459M   0% /dev/shm
tmpfs           184M  448K  183M   1% /run
/dev/nvme0n1p1  20G   1.6G   19G   8% /
tmpfs           459M    0  459M   0% /tmp
/dev/nvme0n1p128 10M   1.3M   8.7M  13% /boot/efi
tmpfs           92M    0   92M   0% /run/user/1000
[ec2-user@ip-10-0-1-79 ~]$
```

4.2 Store Test Files

```
sudo touch /data/testfile.txt
echo "EBS volume test data" | sudo tee /data/testfile.txt

ls -l /data
```

```
[ec2-user@ip-10-0-1-79 ~]$ ls -l /data
total 4
-rw-r--r--. 1 root root 21 Jan 16 06:28 testfile.txt
[ec2-user@ip-10-0-1-79 ~]$
```

5. User Management

5.1 Create normal user

```
sudo useradd devuser
sudo passwd devuser
Enter password
```

```
[ec2-user@ip-10-0-1-79 ~]$ sudo useradd devuser
[ec2-user@ip-10-0-1-79 ~]$ sudo passwd devuser
Changing password for user devuser.
New password:
Retype new password:
passwd: all authentication tokens updated successfully.
[ec2-user@ip-10-0-1-79 ~]$
```

5.2 Create sudo user

```
sudo useradd adminuser
sudo passwd adminuser
sudo usermod -aG wheel adminuser
```

```
[ec2-user@ip-10-0-1-79 ~]$ sudo useradd adminuser
[ec2-user@ip-10-0-1-79 ~]$ sudo passwd adminuser
Changing password for user adminuser.
New password:
Retype new password:
passwd: all authentication tokens updated successfully.
[ec2-user@ip-10-0-1-79 ~]$ sudo usermod -aG wheel adminuser
[ec2-user@ip-10-0-1-79 ~]$
```

5.3 Verify

Switch to devuser

su - devuser

After switching

Sudo ls

```
[ec2-user@ip-10-0-1-79 ~]$ su - devuser
Password:
[devuser@ip-10-0-1-79 ~]$ sudo ls

We trust you have received the usual lecture from the local System
Administrator. It usually boils down to these three things:

    #1) Respect the privacy of others.
    #2) Think before you type.
    #3) With great power comes great responsibility.

For security reasons, the password you type will not be visible.

[sudo] password for devuser:
devuser is not in the sudoers file.
[devuser@ip-10-0-1-79 ~]$ ls
[devuser@ip-10-0-1-79 ~]$
```

Switch to adminuser

su - adminuser

sudo yum update -y

```
[devuser@ip-10-0-1-79 ~]$ su - adminuser
Password:
[adminuser@ip-10-0-1-79 ~]$ yum update -y
Error: This command has to be run with superuser privileges (under the root user on most systems).
[adminuser@ip-10-0-1-79 ~]$ sudo yum update -y

We trust you have received the usual lecture from the local System
Administrator. It usually boils down to these three things:

    #1) Respect the privacy of others.
    #2) Think before you type.
    #3) With great power comes great responsibility.

For security reasons, the password you type will not be visible.

[sudo] password for adminuser:
Amazon Linux 2023 Kernel Livepatch repository
Dependencies resolved.
Nothing to do.
Complete!
[adminuser@ip-10-0-1-79 ~]$
```

6. Secure S3 Configuration

6.1 Create IAM Role for EC2

- IAM - Roles - Create role
- Trusted entity: EC2
- Permissions:
 - *AmazonS3FullAccess*
- Attach role to EC2 instance

Step 1: Select trusted entity

Step 2: Add permissions

Step 3: Name, review, and create

Select trusted entity

Trusted entity type

- ☒ **AWS service**
Allow AWS services like EC2, Lambda, or others to perform actions in this account.
- ☐ **AWS account**
Allow entities in other AWS accounts belonging to you or a 3rd party to perform actions in this account.
- ☐ **Web identity**
Allows users federated by the specified external web identity provider to assume this role to perform actions in this account.
- ☐ **SAML 2.0 federation**
Allow users federated with SAML 2.0 from a corporate directory to perform actions in this account.
- ☐ **Custom trust policy**
Create a custom trust policy to enable others to perform actions in this account.

Use case
Allow an AWS service like EC2, Lambda, or others to perform actions in this account.

Service or use case
EC2

Choose a use case for the specified service.

Use case

- ☒ **EC2**
Allows EC2 instances to call AWS services on your behalf.

task13

Allows EC2 instances to call AWS services on your behalf.

Summary

Creation date January 16, 2026, 12:14 (UTC+05:30)	ARN arn:aws:iam::798974631771:role/task13	Instance profile ARN arn:aws:iam::798974631771:instance-profile/task13
Last activity -	Maximum session duration 1 hour	

Permissions | Trust relationships | Tags | Last Accessed | Revoke sessions

Permissions policies (1)

You can attach up to 10 managed policies.

Policy name	Type	Attached entities
AmazonS3FullAccess	AWS managed	2

Modify IAM role

Attach an IAM role to your instance.

Instance ID
i-0a8e89e9891315ddd (Baton-public)

IAM role
Select an IAM role to attach to your instance or create a new role if you haven't created any. The role you select replaces any roles that are currently attached to your instance.

task13

[Create new IAM role](#)

[Cancel](#) [Update IAM role](#)

6.2 Create S3 Bucket

- S3 - Create bucket
- Settings:
 - Block public access: **Enabled**
 - Bucket versioning: **Enabled**
 - Default encryption: **SSE-S3**

Amazon S3 > Buckets > Create bucket

AWS Region

Asia Pacific (Mumbai) ap-south-1

Bucket type

General purpose

Recommended for most use cases and access patterns. General purpose buckets are the original S3 bucket type. They allow a mix of storage classes that redundantly store objects across multiple Availability Zones.

Directory

Recommended for low-latency use cases. These buckets use only the S3 Express One Zone storage class, which provides faster processing of data within a single Availability Zone.

Bucket name

my-task13-bucket

Bucket names must be 3 to 63 characters and unique within the global namespace. Bucket names must also begin and end with a letter or number. Valid characters are a-z, 0-9, periods (.), and hyphens (-). [Learn more](#)

Copy settings from existing bucket - optional

Only the bucket settings in the following configuration are copied.

Choose bucket

Format: s3://bucket/prefix

Object Ownership

Control ownership of objects written to this bucket from other AWS accounts and the use of access control lists (ACLs). Object ownership determines who can specify access to objects.

Object Ownership

ACLs disabled (recommended)

All objects in this bucket are owned by this account. Access to this bucket and its objects is specified using only policies.

ACLs enabled

Objects in this bucket can be owned by other AWS accounts. Access to this bucket and its objects can be specified using ACLs.

Object Ownership

Bucket owner enforced

Block Public Access settings for this bucket

Public access is granted to buckets and objects through access control lists (ACLs), bucket policies, access point policies, or all. In order to ensure that public access to this bucket and its objects is blocked, turn on Block all public access. These settings apply only to this bucket and its access points. AWS recommends that you turn on Block all public access, but before applying any of these settings, ensure that your applications will work correctly without public access. If you require some level of public access to this bucket or objects within, you can customize the individual settings below to suit your specific storage use cases. [Learn more](#)

Block all public access

Turning this setting on is the same as turning on all four settings below. Each of the following settings is independent of one another.

Block public access to buckets and objects granted through new access control lists (ACLs)

S3 will block public access permissions applied to newly added buckets or objects, and prevent the creation of new public access ACLs for existing buckets and objects. This setting doesn't change any existing permissions that allow public access to S3 resources using ACLs.

Block public access to buckets and objects granted through any access control lists (ACLs)

S3 will ignore all ACLs that grant public access to buckets and objects.

Block public access to buckets and objects granted through new public bucket or access point policies

S3 will block new bucket and access point policies that grant public access to buckets and objects. This setting doesn't change any existing policies that allow public access to S3 resources.

Block public and cross-account access to buckets and objects through any public bucket or access point policies

S3 will ignore public and cross-account access for buckets or access points with policies that grant public access to buckets and objects.

Bucket Versioning

Versioning is a means of keeping multiple variants of an object in the same bucket. You can use versioning to preserve, retrieve, and restore every version of every object stored in your Amazon S3 bucket. With versioning, you can easily recover from both unintended user actions and application failures. [Learn more](#)

Bucket Versioning

Disable

Enable

Default encryption

Server-side encryption is automatically applied to new objects stored in this bucket.

Encryption type

Secure your objects with two separate layers of encryption. For details on pricing, see [DSSE-KMS pricing](#) on the [Storage](#) tab of the [Amazon S3 pricing page](#).

Server-side encryption with Amazon S3 managed keys (SSE-S3)

Server-side encryption with AWS Key Management Service keys (SSE-KMS)

Dual-layer server-side encryption with AWS Key Management Service keys (DSSE-KMS)

Bucket Key

Using an S3 Bucket Key for SSE-KMS reduces encryption costs by lowering calls to AWS KMS. S3 Bucket Keys aren't supported for DSSE-KMS. [Learn more](#)

Disable


Enable

Bucket Policy



```
aws s3 ls s3://my-task13-bucket/logs/
```

```
[ec2-user@ip-10-0-1-79 ~]$ aws s3 ls s3://my-task13-bucket/logs/
2026-01-16 07:04:10      21 testfile.txt
[ec2-user@ip-10-0-1-79 ~]$
```


Verify it on Console:



Check /logs



Testfile.txt



EBS volume test data
