■ NetApp

Upgrade SnapCenter Server and plug-ins

SnapCenter Software 4.6

NetApp February 21, 2022

Table of Contents

Upgrade SnapCenter Server and plug-ir	S	 	 	 	 	 	 . 1
Configure SnapCenter to check for a	ailable updates	 	 	 	 	 	 . 1
Upgrade workflow		 	 	 	 	 	 . 1
Upgrade the SnapCenter Server		 	 	 	 	 	 . 1
Upgrade your plug-in packages		 	 	 	 	 	 . 4

Upgrade SnapCenter Server and plug-ins

Configure SnapCenter to check for available updates

SnapCenter periodically communicates with the NetApp Support Site to notify you of available software updates. You can also create a schedule to specify the interval in which you want to receive information about available updates.

Steps

- 1. In the left navigation pane, click **Settings**.
- In the Settings page, click Software.


The Available Software page displays the available plug-in packages, versions available, and their installation status.

- 3. Click **Check for updates** to see if any newer versions of plug-in packages are available.
- 4. Click **Schedule Updates** to create a schedule to specify the interval in which you want to receive information about available updates:
 - a. Select the interval in Check for updates.
 - b. Select the SnapCenter Server Admin Windows credential and click **OK**.

Upgrade workflow

Each release of SnapCenter contains an updated SnapCenter Server and plug-in package. Plug-in package updates are distributed with the SnapCenter installer. You can configure SnapCenter to check for available updates.

The workflow shows the different tasks required to upgrade the SnapCenter Server and the Plug-in packages.



Upgrade the SnapCenter Server

You can use the SnapCenter Server installer executable file to upgrade the SnapCenter Server.

What you will need

- The SnapCenter Server host must be up to date with Windows updates, with no pending system restarts.
- · You should ensure that no other operations are running before initiating the upgrade operation.
- You should back up the SnapCenter repository (MySQL) database after ensuring that no jobs are running.

This is recommended before upgrading SnapCenter Server and the Exchange plug-in.

For information, see Back up the SnapCenter repository.

• You should back up all the SnapCenter configuration files that you have modified either on the SnapCenter Server host or the plug-in host.

Examples of SnapCenter configuration files: SnapDriveService.exe.config, SMCoreServiceHost.exe.config, and so on.

About this task

- During upgrade, the host is automatically put into maintenance mode that prevents the host from running any scheduled jobs. After upgrade, the host is automatically pulled out of maintenance mode.
- During upgrade, a SQL script is executed to update the Exchange data in NSM database, which converts the DAG and host shortname to FQDN. This is applicable only if you are using SnapCenter Server with Exchange plug-in.
- Before initiating the upgrade operation, if you have manually placed the host in maintenance mode, post upgrade you need to manually bring the host out of maintenance mode by clicking Hosts > Activate Schedule.
- Supported upgrade paths:

If you are using	You can
4.0.x	 Directly upgrade to 4.1.x or 4.2.x
	 Upgrade to 4.3.x by first upgrading to 4.1.x or 4.2.x, and then upgrade to 4.3.x
	 Upgrade to 4.4.x by first upgrading to 4.2.x, and then upgrade to 4.4.x
	 Upgrade to 4.5 by first upgrading to 4.2.x, then upgrade to 4.4.x, and then upgrade to 4.5
	 Upgrade to 4.6 by first upgrading to 4.2.x, then upgrade to 4.4.x, and then upgrade to 4.6
4.1.x	 Directly upgrade to 4.2.x or 4.3.x
	 Upgrade to 4.4.x by first upgrading to 4.2.x or 4.3.x, and then upgrade to 4.4.x
	 Upgrade to 4.5 by first upgrading to 4.3.x and then upgrade to 4.5
	• Upgrade to 4.6 by first upgrading to 4.3.x, then upgrade to 4.5.x, and then upgrade to 4.6
4.2.x	Directly upgrade to 4.3.x or 4.4.x
	 Upgrade to 4.5 by first upgrading to 4.3.x or 4.4.x and then upgrade to 4.5
	 Upgrade to 4.6 by first upgrading to 4.4.x and then upgrade to 4.6

If you are using	You can
4.3.x	Directly upgrade to 4.4.x or 4.5
	 Upgrade to 4.6 by first upgrading to 4.5.x and then upgrade to 4.6
4.4.x	Directly upgrade to 4.5 or 4.6
4.5.x	Directly upgrade to 4.6

Steps

1. Download the SnapCenter Server installation package from the NetApp Support Site.

https://mysupport.netapp.com/site/products/all/details/snapcenter/downloads-tab

- 2. Create a copy of the web.config located at C:\Program Files\NetApp\SnapCenter WebApp.
- 3. Export the SnapCenter schedules related to plug-in host from windows task schedule so that you can use it to restore the schedules if upgrade fails.

```
md d:\\SCBackup``schtasks /query /xml /TN taskname >>
"D:\\SCBackup\\taskname.xml"
```

Create the SnapCenter MySQL database dump if the repository backup is not configured.

```
md d:\\SCBackup``mysqldump --all-databases --single-transaction --add-drop
-database --triggers --routines --events -u root -p >
D:\SCBackup\SCRepoBackup.dmp
```

When prompted, enter the password.

5. Initiate the SnapCenter Server upgrade by double-clicking the downloaded .exe file.

After you initiate the upgrade, all the prechecks are performed, and if the minimum requirements are not met, appropriate error or warning messages are displayed. You can ignore the warning messages and proceed with the installation. However, errors should be fixed.



SnapCenter will continue to use the existing MySQL Server repository database password provided during installation of the earlier version of SnapCenter Server.

6. Click Upgrade.

At any stage if you click the **Cancel** button, the upgrade workflow will be cancelled. It will not rollback the SnapCenter Server to previous state.

Best Practice: You should either log out and then log into SnapCenter, or close and then open a new browser to access SnapCenter GUI.

After you finish

- If the plug-in is installed using a sudo user, you should copy the sha224 keys available at
 C:\ProgramData\NetApp\SnapCenter\Package Repository\oracle_checksum.txt to update the /etc/sudoers file.
- You should perform a fresh discovery of resources on the hosts.

If the status of the host is displayed as stopped, you can wait for sometime and perform a fresh discovery. You can also change the value of **HostRefreshInterval** parameter (default value is 3600 seconds) to any value more than 10 minutes.

- If the upgrade fails, you should clean up the failed installation, reinstall the earlier version of SnapCenter, and then restore the NSM database to it's previous state.
- After upgrading the SnapCenter Server host, you must also upgrade the plug-ins before adding any storage system.

Upgrade your plug-in packages

The plug-in packages are distributed as part of the SnapCenter upgrade.

What you will need

- If you are a non-root user with access to the Linux machines, you should update the /etc/sudoers file with the latest checksum values before performing the upgrade operation.
- By default SnapCenter detects JAVA_HOME from the environment. If you want to use a fixed JAVA_HOME and if you are upgrading the plug-ins on a Linux host, you should manually add the SKIP_JAVAHOME_UPDATE parameter in the *spl.properties* file located at */var/opt/snapcenter/spl/etc/* and set the value to TRUE.

The value of JAVA_HOME gets updated when the plug-in is upgraded or when the SnapCenter plug-in loader (SPL) service restarts. Before upgrading or restarting the SPL, if you add the SKIP_JAVAHOME_UPDATE parameter and set the value to TRUE, the value of JAVA_HOME is not updated.

• You should have backed up all the SnapCenter configuration files that you have modified either on the SnapCenter Server host or the plug-in host.

Examples of SnapCenter configuration files: SnapDriveService.exe.config, SMCoreServiceHost.exe.config, and so on.

About this task

- The upgrade procedure places your Windows, Linux, or AIX host in "maintenance" mode, which prevents the host from running any scheduled jobs.
- · Supported upgrade paths:

 Directly upgrade to 4.1.x Upgrade to 4.2.x by first upgrading to 4.1.x then upgrade to 4.2.x Upgrade to 4.3.x by first upgrading to 4.1.x upgrade to 4.2.x, and then upgrade to 4.3.x Upgrade to 4.4.x by first upgrading to 4.1.x upgrade to 4.2.x, then upgrade to 4.3.x, an then upgrade to 4.4.x Upgrade to 4.5 by first upgrading to 4.1.x, tupgrade to 4.2.x, then upgrade to 4.3.x, the upgrade to 4.4.x, and then upgrade to 4.5. Upgrade to 4.6 by first upgrading to 4.1.x, tupgrade to 4.2.x, then upgrade to 4.3.x, the upgrade to 4.2.x, then upgrade to 4.3.x, the upgrade to 4.4.x, then upgrade to 4.3.x, the upgrade to 4.4.x, then upgrade to 4.5.x, an 	, then (, then d hen en
 then upgrade to 4.2.x Upgrade to 4.3.x by first upgrading to 4.1.x upgrade to 4.2.x, and then upgrade to 4.3.x Upgrade to 4.4.x by first upgrading to 4.1.x upgrade to 4.2.x, then upgrade to 4.3.x, an then upgrade to 4.4.x Upgrade to 4.5 by first upgrading to 4.1.x, tupgrade to 4.2.x, then upgrade to 4.3.x, the upgrade to 4.4.x, and then upgrade to 4.5 Upgrade to 4.6 by first upgrading to 4.1.x, tupgrade to 4.2.x, then upgrade to 4.3.x, the 	, then (, then d hen en
 upgrade to 4.2.x, and then upgrade to 4.3.x Upgrade to 4.4.x by first upgrading to 4.1.x upgrade to 4.2.x, then upgrade to 4.3.x, an then upgrade to 4.4.x Upgrade to 4.5 by first upgrading to 4.1.x, the upgrade to 4.2.x, then upgrade to 4.3.x, the upgrade to 4.4.x, and then upgrade to 4.5 Upgrade to 4.6 by first upgrading to 4.1.x, the upgrade to 4.2.x, then upgrade to 4.3.x, the 	then dhen en hen
 upgrade to 4.2.x, then upgrade to 4.3.x, an then upgrade to 4.4.x Upgrade to 4.5 by first upgrading to 4.1.x, the upgrade to 4.2.x, then upgrade to 4.3.x, the upgrade to 4.4.x, and then upgrade to 4.5 Upgrade to 4.6 by first upgrading to 4.1.x, the upgrade to 4.2.x, then upgrade to 4.3.x, the 	hen en hen
upgrade to 4.2.x, then upgrade to 4.3.x, the upgrade to 4.4.x, and then upgrade to 4.5 • Upgrade to 4.6 by first upgrading to 4.1.x, the upgrade to 4.2.x, then upgrade to 4.3.x, the	hen en
upgrade to 4.2.x, then upgrade to 4.3.x, the	en
then upgrade to 4.4.X, then upgrade to 4.5.X, and	d
4.1.x • Directly upgrade to 4.2.x	
Upgrade to 4.3.x by first upgrading to 4.2.x then upgrade to 4.3.x	, and
 Upgrade to 4.4.x by first upgrading to 4.2.x upgrade to 4.3.x, and then upgrade to 4.4.x 	
• Upgrade to 4.5 by first upgrading to 4.2.x, t upgrade to 4.3.x, then upgrade to 4.4.x, an then upgrade to 4.5	
Upgrade to 4.6 by first upgrading to 4.2.x, to upgrade to 4.3.x, then upgrade to 4.4.x, the upgrade to 4.5.x, and then upgrade to 4.6.	
4.2.x • Directly upgrade to 4.3.x	
 Upgrade to 4.4.x by first upgrading to 4.3.x then upgrade to 4.4.x 	, and
 Upgrade to 4.5 by first upgrading to 4.3.x, to upgrade to 4.4.x, and then upgrade to 4.5 	hen
• Upgrade to 4.6 by first upgrading to 4.3.x, t upgrade to 4.4.x, then upgrade to 4.5.x, an then upgrade to 4.6	
4.3.x • Directly upgrade to 4.4.x	
 Upgrade to 4.5 by first upgrading to 4.4.x, a then upgrade to 4.5 	and
• Upgrade to 4.6 by first upgrading to 4.4.x, t upgrade to 4.5.x, and then upgrade to 4.6	hen

If using are using	You can
4.4.x	 Directly upgrade to 4.5 Upgrade to 4.6 by first upgrading to 4.5.x, and then upgrade to 4.6
4.5.x	Directly upgrade to 4.6



For information about upgrading the SnapCenter Plug-in for VMware vSphere, see Upgrade SnapCenter Plug-in for VMware vSphere.

Steps

- 1. In the left navigation pane, click **Hosts** > **Managed Hosts**.
- 2. Upgrade the hosts by performing one of the following tasks:
 - If the Overall Status column displays "Upgrade available" for one of the hosts, click the host name and perform the following:
 - a. Click More Options.
 - b. Select **Skip prechecks** if you do not want to validate whether the host meets the requirements to upgrade the plug-in.
 - c. Click Upgrade.
 - olf you want to upgrade multiple hosts, select all the hosts, click , and then click **Upgrade > OK**.



All the plug-ins in the package gets selected, but only the plug-ins that were installed with the earlier version of SnapCenter are upgraded, and the remaining plug-ins are not installed. You must use the **Add plug-ins** option to install any new plug-in.

If you have not selected the **Skip prechecks** check box, the host is validated to see if it meets the requirements to install the plug-in. If the minimum requirements are not met, appropriate error or warning messages are displayed. After fixing the issue, click **Upgrade**.



If the error is related to disk space or RAM, you can update either the web.config located at C:\Program Files\NetApp\SnapCenter WebApp, or the PowerShell config files located at C:\Windows\System32\WindowsPowerShell\v1.0\Modules\SnapCenter\ to modify the default values. If the error is related to remaining parameters then you must fix the issue, and then validate the requirements again.

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.