Washing instructions

Getting it into the machine. Ironing is on the other sheet.
Generic front loader, 1–8 kg · Generic steam iron

LOADS — ONE LINE, ONE WASH

Bold pile names share one wash.

Cottons 60°	**White + White Socks**	~2:30
Cottons 60°	White Towels (on its own)	~2:30
Cottons 40°	**Coloured + Coloured Socks**	~2:15
Cottons 40°	Coloured Towels (on its own)	~2:15
Easy Care 40°	Microfibre Towels (on its own)	~1:30
Cottons 30°	**Dark + Black Socks +- Denim**	~2:00
Delicates / Silk cold	Raw Denim (on its own)	~0:45
Wool 30°	**Merino Wool + Cashmere Blend**	~0:40
Sportswear 30°	Synthetic Activewear (on its own)	~1:10
Sportswear 40°	Gym Socks (on its own)	~1:20
Wool cold	Wool Trainers (on its own)	~0:40
Easy Care 40°	Linen (on its own)	~1:30

The dials are drawn as they sit on the machine: twelve o'clock is Off, and the red pointer is where to turn it. Chips show every value the display steps through, filled in on the one you want.

1. White + White Socks

~2:30

NO SOFTENER **Cottons 60 °C · 1200 rpm**

WASH



Cottons
1 clockwise from Off

Temp	cold 20 30 40 [✓ 60] 90
Spin rpm	0 400 600 800 [✓ 1200] 1400
Buttons	Speed [✓ Eco] Easy Iron Extra Rinse

DETERGENT

White: Universal powder, full dose — the bleach in powder is what keeps whites from going grey

White Socks: Universal powder, full dose

WASH TOGETHER WITH

each other

DRYING

White: Tumble dry normal, or line dry in the sun — sunlight bleaches whites for free.

White Socks: Tumble dry normal.

NOTES

White: Wash whites on their own. One stray coloured sock is all it takes.

2. White Towels

~2:30

NO SOFTENER **Cottons 60 °C · 1400 rpm**

WASH



Cottons

1 clockwise from Off

Temp: cold 20 30 40 [✓ 60] 90

Spin rpm: 0 400 600 800 1200 [✓ 1400]

Buttons: Speed Eco Easy Iron [✓ Extra Rinse]

DETERGENT

Universal powder, full dose. Go lighter rather than heavier: excess detergent stiffens terry.

WASH TOGETHER WITH

nothing else — wash alone

DRYING

Tumble dry medium — the tumbling is what fluffs the pile back up.

NOTES

Never fabric softener: it coats the loops in silicone and the towel stops absorbing. White vinegar in the softener drawer once a month softens instead.

3. Coloured

~2:15

SOFTENER OK **Cottons 40 °C · 1200 rpm**

WASH



Cottons

1 clockwise from Off

Temp: cold 20 30 [✓ 40] 60 90

Spin rpm: 0 400 600 800 [✓ 1200] 1400

Buttons: Speed [✓ Eco] Easy Iron Extra Rinse

DETERGENT

Colour liquid detergent — no bleach, no optical brighteners

WASH TOGETHER WITH

Coloured Socks

DRYING

Line dry inside out, or tumble on low.

NOTES

Wash new or strongly dyed items separately for the first two or three washes.

4. Coloured Socks

~2:15

NO SOFTENER **Cottons 40 °C · 1200 rpm**

WASH



Cottons

1 clockwise from Off

Temp	cold 20 30 [✓ 40] 60 90
Spin rpm	0 400 600 800 [✓ 1200] 1400
Buttons	Speed [✓ Eco] Easy Iron Extra Rinse

DETERGENT

Colour liquid detergent

WASH TOGETHER WITH

Coloured

DRYING

Tumble dry low or line dry.

5. Coloured Towels

~2:15

NO SOFTENER **Cottons 40 °C · 1400 rpm**

WASH



Cottons

1 clockwise from Off

Temp	cold 20 30 [✓ 40] 60 90
Spin rpm	0 400 600 800 1200 [✓ 1400]
Buttons	Speed Eco Easy Iron [✓ Extra Rinse]

DETERGENT

Colour liquid detergent. Go lighter rather than heavier: excess detergent stiffens terry.

WASH TOGETHER WITH

nothing else — wash alone

DRYING

Tumble dry medium — the tumbling is what fluffs the pile back up.

NOTES

Never fabric softener — it kills absorbency. Run them at 60 °C every month or so if they start to smell.

6. Microfibre Towels

~1:30

NO SOFTENER **Easy Care 40 °C · 1200 rpm**

WASH



Easy Care
3 clockwise from Off

Temp: cold 20 30 [✓ 40] 60 90

Spin rpm: 0 400 600 800 [✓ 1200] 1400

Buttons: Speed Eco Easy Iron [✓ Extra Rinse]

DETERGENT

Liquid detergent, half dose. What doesn't rinse away stays in the split fibre and stops it picking anything up.

WASH TOGETHER WITH

nothing else — wash alone

DRYING

Air dry, or tumble on low. High heat fuses the split ends shut and the towel never absorbs again.

NOTES

Never fabric softener — it fills the split fibres with silicone and the towel is finished. Wash with microfibre only: the same split ends that make it absorbent grab cotton lint and never let go.

7. Dark + Black Socks + Denim

~2:00

NO SOFTENER **Cottons 30 °C · 800 rpm**

WASH



Cottons

1 clockwise from Off

Temp	cold 20 [✓ 30] 40 60 90
Spin rpm	0 400 600 [✓ 800] 1200 1400
Buttons	Speed Eco Easy Iron [✓ Extra Rinse]

DETERGENT

Dark: Liquid detergent for dark/black — optical brighteners are what leave that grey haze

Black Socks: Liquid detergent for dark/black

Denim: Liquid detergent for dark/black

WASH TOGETHER WITH

each other

DRYING

Dark: Line dry inside out, out of direct sun. Skip the dryer: heat fades black fastest.

Black Socks: Line dry, or tumble on low.

Denim: Hang by the waistband and air dry. A hot dryer shrinks them and destroys the elastane in stretch denim.

NOTES

Dark: Turn everything inside out. The extra rinse matters here — detergent residue dries as grey streaks on black.

Denim: Inside out, zips and buttons closed. Wash them far less often than you think.

8. Raw Denim

~0:45

NO SOFTENER **Delicates / Silk cold · 400 rpm**

WASH



Delicates / Silk
6 clockwise from Off

Temp: [✓ cold] 20 30 40 60 90

Spin rpm: 0 [✓ 400] 600 800 1200 1400

Buttons: Speed Eco Easy Iron Extra Rinse

DETERGENT

A capful of pH-neutral or denim-specific detergent. No bleach, no enzymes.

WASH TOGETHER WITH

nothing else — wash alone

DRYING

Hang inside out indoors, away from sun and radiators. Never tumble.

NOTES

Unwashed denim is meant to go months before its first wash. Gentler than the machine: a 45-minute cold soak in the bath, inside out, no agitation, no wringing — then roll in a towel to press the water out.

9. Merino Wool + Cashmere Blend ~0:40

NO SOFTENER **Wool 30 °C · 400 rpm**

WASH



Wool
7 clockwise from Off

Temp: cold · 20 · [✓ 30] · 40 · 60 · 90

Spin rpm: 0 · [✓ 400] · 600 · 800 · 1200 · 1400

Buttons: Speed · Eco · Easy Iron · Extra Rinse

DETERGENT

Merino Wool: Wool detergent, half dose. No enzymes, no proteases, no bleach — they eat the fibre.

Cashmere Blend: Wool or cashmere detergent, half dose. No enzymes, no proteases, no bleach.

WASH TOGETHER WITH

each other

DRYING

Merino Wool: Never tumble dry. Dry flat on a towel, away from radiators and sun — hung up it stretches and never comes back.

Cashmere Blend: Never tumble dry. Squeeze the water out, never wring, then dry flat on a towel away from any heat.

NOTES

Merino Wool: Turn inside out, wash with wool only, nothing with zips. Merino barely needs washing — air it overnight and wear it again.

Cashmere Blend: Inside out, and only ever with other wool. Cashmere pills where it rubs — that is the fibre behaving normally, not a fault; a cashmere comb takes it off. Check the blend first: a little nylon makes it tougher, silk makes it more delicate.

— *Icebreaker on merino*

10. Synthetic Activewear

~1:10

NO SOFTENER **Sportswear 30 °C · 800 rpm**

WASH



Sportswear
14 clockwise from Off

Temp: cold 20 [✓ 30] 40 60 90

Spin rpm: 0 400 600 [✓ 800] 1200 1400

Buttons: Speed Eco

Easy Iron

Extra Rinse

DETERGENT

A small dose of mild pH-neutral liquid detergent. Too much is what makes them smell.

WASH TOGETHER WITH

nothing else — wash alone

DRYING

Air dry on a hanger — dry within the hour. Tumble heat kills the stretch.

NOTES

Inside out. Never softener: it films over the fibres these rely on for wicking and stretch. A cup of white vinegar in the rinse resets a load that already smells. Covers tops, shorts and base layers — one fabric family, one wash. Mixed colours are fine in one run: at 30 °C the dyes on polyester barely move. The exception is a brand-new black or strong red piece, which can crock for a wash or two — give that its own run first.

— *Dirty Labs on synthetic activewear*

11. Gym Socks

~1:20

NO SOFTENER **Sportswear 40 °C · 1200 rpm**

WASH



Sportswear
14 clockwise from Off

Temp	cold 20 30 [✓ 40] 60 90
Spin rpm	0 400 600 800 [✓ 1200] 1400
Buttons	Speed Eco Easy Iron [✓ Extra Rinse]

DETERGENT
Liquid detergent, normal dose

WASH TOGETHER WITH
nothing else — wash alone

DRYING
Tumble dry low or line dry.

NOTES
Give them a 60 °C cotton run every few weeks — 40 °C keeps them clean but doesn't reset the smell.

12. Wool Trainers

~0:40

NO SOFTENER **Wool cold · 400 rpm**

WASH



Wool

7 clockwise from Off

Temp: [✓ cold] 20 30 40 60 90

Spin rpm: 0 [✓ 400] 600 800 1200 1400

Buttons: Speed Eco Easy Iron Extra Rinse

DETERGENT

A small amount of mild detergent — a wool detergent is ideal. No bleach.

WASH TOGETHER WITH

nothing else — wash alone

DRYING

Air dry only, somewhere with moving air: outside, by a window, or in front of a fan. Never the dryer and never a radiator — heat warps the sole and shrinks the wool upper.

NOTES

Pull the insoles and laces out first and wash those by hand. The shoes go in a mesh delicates bag or a pillowcase, on their own — a loose trainer batters the drum and everything in it.

13. Linen

~1:30

NO SOFTENER **Easy Care 40 °C · 800 rpm**

WASH



Easy Care

3 clockwise from Off

Temp: cold 20 30 [✓ 40] 60 90

Spin rpm: 0 400 600 [✓ 800] 1200 1400

Buttons: Speed Eco [✓ Easy Iron] Extra Rinse

DETERGENT

Mild liquid detergent, no bleach — bleach yellows linen and breaks the fibre down over time

WASH TOGETHER WITH

nothing else — wash alone

DRYING

Line dry, or tumble low and pull out a little damp — bone dry locks creases in.

NOTES

New linen sheds a little dye/lint for the first few washes — wash alone until it rinses clear, then fine with other 40 °C loads.

Durations are the machine's own estimates and vary with load.