Access

To access the elements of a container, you can use an iterator. If you use a begin and end iterator, you have a range, which you can further process. For a container `cont`, you get with `cont.begin()` the begin iterator and with `cont.end()` the end iterator, which defines a *half-open* range. It is *half-open* because the begin iterator belongs to the range, the end iterator refers to a position past the range. With the iterator pair `cont.begin()` and `cont.end()` you can modify the elements.

Iterator	Description
`cont.begin()` and `cont.end()`	Pair of iterators to iterate forward.
`cont.cbegin()` and `cont.cend()`	Pair of iterators to iterate const forward.
`cont.rbegin()` and `cont.rend()`	Pair of iterators to iterate backward.
`cont.crbegin()` and `cont.crend()`	Pair of iterators to iterate const backward.

Creation and deletion of a container

Now I can modify the container.

```
// containerAccess.cpp
#include <iostream>
#include <vector>
using namespace std;
```

```
struct MyInt{
  MyInt(int i): myInt(i){};
  int myInt;

};

int main(){
  std::vector<MyInt> myIntVec;
  myIntVec.push_back(MyInt(5));
  myIntVec.emplace_back(1);
  std::cout << myIntVec.size() << std::endl;         // 2

  std::vector<int> intVec;
  intVec.assign({1, 2, 3});
  for (auto v: intVec) std::cout << v << " ";        // 1 2 3
  cout << std::endl;

  intVec.insert(intVec.begin(), 0);
  for (auto v: intVec) std::cout << v << " ";        // 0 1 2 3
  cout << std::endl;

  intVec.insert(intVec.begin()+4, 4);
  for (auto v: intVec) std::cout << v << " ";        // 0 1 2 3 4
  cout << std::endl;

  intVec.insert(intVec.end(), {5, 6, 7, 8, 9, 10, 11});

  for (auto v: intVec) std::cout << v << " ";        // 0 1 2 3 4 5 6 7 8 9 10 11
  cout << std::endl;

  for (auto revIt= intVec.rbegin(); revIt != intVec.rend(); ++revIt)
     std::cout << *revIt << " ";                    // 11 10 9 8 7 6 5 4 3 2 1 0
  cout << std::endl;

  intVec.pop_back();
  for (auto v: intVec ) std::cout << v << " ";       // 0 1 2 3 4 5 6 7 8 9 10
  cout << std::endl;

  return 0;
}
```




Access the elements of a container