

Dejavu Engine Installation Guide - VMware ESXi

Once download is Completed, extract both the files ("Console\_VMDK.zip" & "Engine\_VMDK.zip")




Now Open VMware ESXi Web UI with "root" login Credentials to upload DejaVu console and DejaVu engine VMDK files into Data Store




### Create two directories:


- 1. DejaVu Console 2.0 Upload Extracted DejaVu Console\_VMDK\_2.0.vmdk File in Dejavu\_Console
- 2. DejaVu Engine 2.0 Upload Extracted DejaVu Engine2.0.vmdk File in Dejavu\_Engine




### Now create the new virtual machine



Set desired name - I have set it as "Dejavu\_Console\_Server"




# Select your data store to DejaVu VMDK file




Virtual Machine hardware Configuration for DejaVu engine server

- . 4 Core CPU
- . 32 GB RAM


Note: Delete the exiting hard disk and attach that VMDK as a hard disk




To add hard Disk, click on "Add hard disk"




## After you click on Add hard disk, select "Existing hard disk"



Once you Click on Existing hard disk, go to the datastore where you have uploaded that DejaVu Engine VMDK file & select the VMDK File




Now, go to the controller location and select the "IDE Controller 0" instead of "SCSI controller 0"




Two network cards are required for the Dejavu Engine. As shown in the screenshot below, click Add Network Adapter and then add another Network Adapter.

Note: Network Adapter 1 is the default, while Network Adapter 1 is a new one that we've added.




After configuring RAM, CPU and Hard disk Settings, click on **Next** 

Note: Remove CD/DVD Drive 1 From Virtual Machine Configuration




Virtual machine Configuration is done, click Finish. Power on the Virtual machine and DejaVu Engine should be running.




### DejaVu Engine is booting.





If you see this, then we are good. DejaVu Engine is up.







Dejavu Engine Default IP Address is: 192.168.56.102

Access URL: https://192.168.56.102

Default username : Set your username here Default password is : Set your password here




Once you enter the credentials, click on "Configure Management Interface" Tab and set up the IP Address reachable by Dejavu Console Server



Server will reboot to reflect the Changes after submitting the information.


Note: DejaVu Engine and Console management IP should be reachable by each other.




You should be able to access the Engine on the new IP




If you get to this page, Vyuha engine installation is task is completed



For Engine to authenticate Console, copy the Auth Key from the **Console** and use this key in Engine to establish connection.



## On Engine, enter "DejaVu Console Server IP", "Auth Key"



If you added correct IP Address and Auth key, then connection will be established.

Click on "Test Connection" and you will Get "API Connection Successful"

