Documentation

https://github.com/anarkila/DeveloperConsole

Table of contents

Getting Started	1
Adding and removing commands	
Console key inputs & navigation	
Calling commands	4
Default commands	
Command list generation	
Console.cs API	6
Logging	8
DeveloperConsole settings	8
Getting Console state info	12
How does it work?	14
Best Practices	14
Version History	15

Getting Started

- Drag & Drop DeveloperConsole.prefab into your scene
 Add [ConsoleCommand] to your methods like below. See *ConsoleExamples.cs* script for all examples.
- 3. Play your scene and press console key (default § or ½) to toggle Console.

```
using UnityEngine;
public class ExampleScript : MonoBehaviour {
      [ConsoleCommand("test")]
     private void Test() {
    Debug.Log("Called 'test' from Console!");
     [ConsoleCommand("test_int")]
     private void TestInt(int i) {
         // single parameter allowed types:
// single parameter allowed types:
// int, float, string, bool, double, char, string[], Vector2, Vector3, Vector4, Quaternion
Debug.Log(string.Format("Called 'test_int' with value: {0} from Console!", i));
      [ConsoleCommand("test_multi_int")]
     private void TestMultiInt(int i, int j) {
          // multi parameter allowed types:
// int, float, string, bool, double, char
Debug.Log(string.Format("Called 'test_multi_int' with value: {0} and {1} from Console!", i, j));
```

Adding and removing commands

Developer Console supports static, MonoBehaviour (instance), and Unity Coroutines methods (both public and private). Methods can contain either no parameters, single parameter or multiple parameters with certain rules.

Single parameter type support:

int, float, string, string[], bool, double, char, Vector2, Vector3, Vector4, Quaternion

Multi parameter supported types:

```
int, float, string, bool, double, char
```

Unity coroutines cannot contain multiple parameters because coroutines are started by calling method by its name and you can only pass one argument into it.

Methods with optional parameter are also supported.

Methods that contain multiple parameters with Vector2, Vector3, Vector4, Quaternion or string[] are currently not supported because character ',' (comma) is used to parse multiple parameters as well as types above. Developer Console will log warning (Editor only) and reason if the command cannot be registered.

Registering new commands

You can register new commands in two ways.

- 1) Add [ConsoleCommand("test")] attribute to your methods like above example.
- 2) Register new command with Console.RegisterCommand() method like below (see notes below!).
 - Console.RegisterCommand parameters:
 - Script reference (MonoBehaviour)
 - Method name (string)
 - o Command name (string)

Optional:

- default value (string) (default "")
 - would show as "{command} {default value}", example: "test.int 42" or "test_multi_int 4 5"
- o debugCommandOnly (bool) (default false)
 - if set to true command will only register in Editor and Development build
- isHiddenCommand (bool) (default false)
 - if set to true would not show in predictions
- hiddenCommandMinimalGUI (bool) (default false)
 - if set to true would not show in predictions (Minimal GUI only)

```
using UnityEngine;
public class Example : MonoBehaviour {
    private void Start() {
        Console.RegisterCommand(this, "ExampleRegister", "example.register");
    }
    public void ExampleRegister() {
        Debug.Log("Example Register called!");
    }
}
```

Notes:

Command name cannot contain characters whitespaces, '&' or ',' because these characters are reserved for parsing.

Instantiated objects with MonoBehaviour script that use [ConsoleCommand()] attribute(s) will not be registered. Use Console.RegisterCommand() and Console.RemoveCommand for objects that are instantiated runtime.

Use [ConsoleCommand()] attribute for all scripts that do not inherit from MonoBehaviour as Console.RegisterCommand() does not support non-MonoBehaviour command registering!

Multiple instances of same command is allowed, like in the example scenes all 3 cubes are disabled/enabled when command 'cube.enabled (bool)' is called, but same command but in different class or method is not allowed. If same command is found in different class or method, Developer Console logs warning (Editor only) and that command is ignored.

Removing commands

To remove any command during runtime, you can call *Console.RemoveCommand("commandName");* method. Just provide command name and command will be removed if it exists. Optionally, you can log whether command was found and was removed successfully (Editor only).

- Console.RegisterCommand parameters:
 - Command to remove (string)
 - o Log to console (bool)

```
using UnityEngine;
public class Example : MonoBehaviour {
    private void Start() {
        Console.RemoveCommand("quit");
        // with log
        //Console.RemoveCommand("quit", true);
    }
}
```

Console key inputs & navigation

You can change all key inputs to your liking through <u>DeveloperConsole settings</u>.

DeveloperConsole uses old Unity input system. All inputs are handled in ConsoleKeyInputs.cs script.

DeveloperConsole navigation is quite similiar to Windows Command Prompt or Linux Terminal.

Default keys:

Open/Close console – **Backslash** (§ or ½ key) Submit command – **Return** Search previously executed command – **Up Arrow** Next suggested command key – **Down Arrow** Next suggested command key Alt - **Tab**

Both suggested command keys only work if option 'Show Input Predictions' is set to true and only when the predictions/suggested panel is visible like below. If in this case either key Down Arrow or Tab is clicked then the next suggested commands gets filled to InputField. In this case it would be 'test_int'.

These suggested commands are also clickable with mouse, however the prediction/suggested panel will then close and the clicked suggestion will be filled to InputField.



Navigating previously executed commands works similiarly to Windows Command Prompt and Linux Terminal. First Up Arrow (Search previously executed command) must be clicked to start searching through previously executed commands. Down Arrow (Next suggested command key) can also be used to go opposite direction, but only after Up Arrow is clicked first. During searching previously executed commands, no input predictions are shown even if 'Show Input Predictions' is set to true. Input predictions / suggestions start appearing again when InputField is cleared completely.

Calling commands

To call added Console commands certain rules are applied due parsing.

To call command(s) that take no parameters:

{command name}

Example: test_method

Note. Empty space(s) before {command_name} is not allowed.

To call command(s) that take one parameter:

{command_name} {empty space} {parameter}

Example: test_int 5

To call command(s) that take two or more parameters:

{command_name} {empty space} {parameter} {comma} {parameter}...

Example: test_multi_int 5, 8

To call multiple commands in a row, add character '&' or '&&' with above rules.

https://github.com/anarkila/DeveloperConsole

{command_name} {empty space} {& or &&} {command_name} {empty space} {parameter}

Example: test_method && test_int 9 or test_method & test_int 9

Note. Option 'Allow Multiple Commands' must be enabled this to work (enabled by default).

Note. Character '&' cannot be passed as argument if option 'Allow Multiple Commands' is enabled.

Note. Input predictions are not shown at all if Console inputfield contains character '&'.

Default commands

Developer Console comes with few commands by default. If you wish to change, modify or delete them you can find them in *DefaultCommands.cs*, *DebugRenderInfo.cs* and *DeveloperConsole.cs* classes.

- help Print list of available commands
- quit Quit the application (works in Editor and Build)
- close Close console
- clear clear all Console messages
- reset Reset Console window position and size (Large GUI only)
- max_fps (int) Set <u>Application.TargetFrameRate</u>
- **console_style** Toggle GUI between Large and Minimal. This is only registered if option 'Allow GUI Change runtime' is set to true.
- scene_loadindex (int) Load scene asynchronously by scene build index
- scene_addloadindex (int) Load scene asynchronously additively by scene build index
- scene_loadname (string) Load scene asynchronously by scene name
- scene_unloadname (string) Unload scene asynchronously by scene name
- scene_unloadindex (int) Unload scene asynchronously by scene build index
- scene_information Print scene count and all scene names that are in project Build settings.
- empty Log empty line to console. This command is Editor only.
- debug_renderinfo Print rendering information: High and Avg FPS, highest draw call, batches, triangle and vertices count. This command is Editor only. The API (UnityStats.cs) only works in Editor.

Command list generation

To generate text file that contains all [ConsoleCommand] attribute commands, open Tools/Developer console and click 'Generate Command List' or click 'Generate Command List' button on DeveloperConsole.cs inspector.

Text file will be generated to YOUR_PATH/DeveloperConsole/Editor/ folder.

https://github.com/anarkila/DeveloperConsole

Console.cs API

Console.cs is simple static API to interact with the console programmatically.

Console.Log(): Logs message to Developer Console directly.

- Parameters:
 - String or System.Object
 - o (optional) Boolean forcelgnoreTimestamp

Console.LogEmpty(): Logs empty message to Developer Console without timestamp

Console.RegisterCommand(): Register new console command. See Adding and removing commands section.

- Parameters:
 - o MonoBehaviour script
 - String methodName
 - o String commandName
 - (optional) String defaultValue
 - o (optional) String info
 - o (optional) Boolean debugCommandOnly
 - o (optional) Boolean IsHiddenCommand
 - o (optional) Boolean HiddenCommandMinimalGUI

Console.RemoveCommand(): Remove console command by command name

- Parameters:
 - String commandToRemove
 - o Optional: Boolean logResult

Console.ExecuteCommand(): Execute console command. You can also build your own UI and call this method to execute Console command.

- Parameter:
 - String command

Console.lsConsoleOpen(): returns Boolean whether console is currently open.

Console.lsConsoleInitialized(): returns Boolean whether console is fully initialized.

Console.OpenConsole(): Open Developer Console

Console.CloseConsole(): Close Developer Console

Console.SetConsoleState(): Set Developer Console state (open or closed)

- Parameters:
 - o Boolean state

Console.IsConsoleEnabled(): Returns boolean whether Developer Console is enabled and can be opened with console open key. Default is true.

Console.EnableConsole(): Enable Developer Console. By default Console is enabled and can be opened if DeveloperConsole.prefab exists in the scene. This only need to be called if you have disabled console with Console.DisableConsole() or Console.SetConsoleEnabledState(false).

Console.DisableConsole(): Disable Developer Console from opening. If Console is open while this is called, it will be closed. To Enable Console again, call Console.EnableConsole() or Console.SetConsoleEnabledState(true).

Console.SetConsoleEnabledState(): Set Developer Console enabled state (enabled or disabled).

https://github.com/anarkila/DeveloperConsole

Console.AllowConsoleActivateKey(): Enable/disable listening default console activate key. If you disable listening default activate key then you must handle opening/closing console yourself (with above methods).

- Parameters:
 - o Boolean enabled

Console.ClearConsoleMessages(): Clear all Developer Console messages

Console.RebindConsoleActivateKey(): Rebind console activate key (default §)

- Parameters:
 - KeyCode newKey

Console.DestroyConsole(): Destroy Developer Console

Console.ResetConsole(): Reset Console Window size and position to default

Console.ShowInputPredictions(): Should show input predictions on console inputfield

- Parameters:
 - o Boolean showPredictions

Console.DisableUnityMessageLogging(): Disable all Debug.Log/LogError messages from logging to console window.

Console.GetCurrentUnityLogOption(): Get Current ConsoleLogOptions enum for Debug.Log/LogError messages.

Console.ChangeUnityLogOptions(): Change ConsoleLogOptions enum for Debug.Log/LogError messages.

Console.ChangeThreadedUnityLogOptions(): Change ConsoleLogOptions enum for threaded Debug.Log/LogError messages.

Console.GetCurrentThreadedUnityLogOption(): Get Current ConsoleLogOptions enum for threaded Debug.Log/LogError messages.

Console.SetSettings(): Set new ConsoleSettings.cs class

- Parameters:
 - ConsoleSettings newSettings

Console.GetSettings(): returns current settings (ConsoleSettings.cs class)

Console.GetGUIStyle(): returns current GUI style (ConsoleGUIStyle enum)

Console.SetGUIStyle(): Set Console style to use.

- Parameters:
 - ConsoleGUIStyle style

Console.SetGUITheme(): Set Console color theme to use.

- Parameters:
 - o ConsoleGUITheme theme

Console.SetCustomGUITheme(): Set custom Console color theme.

- Parameters:
 - ConsoleColors newColors

Console.GetAllConsoleCommands(): returns list of strings of all current console commands

Console.GetConsoleCommandsCount(): returns Console commands count (int)

Console.GetStaticConsoleCommandsCount(): returns static Console commands count (int)

https://github.com/anarkila/DeveloperConsole

Console.GetAllConsoleCommands(): returns list of strings of all current console commands

Console.GetAllConsoleCommandsWithInfos(): returns list of strings of all current console commands with info texts.

Console.GetConsoleMessagesArray(): returns string array of all current console messages

Console.GetConsoleMessagesList(): returns list of strings of all current console messages

Console.WriteMessagesToFile(): Writes all current console messages to .txt file. This .txt file will be created at project /Assets root folder. File name will be ConsoleMessage_{unixtimestamp}.txt. Note. This command only works in Windows Editor. Modify TextFileWriter.cs if you wish to add runtime and/or Mac/Linux support.

Console.RegisterConsoleStateChangedEvent: Register to receive console state change callback. See <u>Getting Console state info</u> section for usage.

Console.RegisterConsoleInitializedEvent: Register to receive callback when console is fully initialized.

In case your are unfamiliar with events see How to subscribe to and unsubscribe from events

Logging

By default, *Unity.Log* and *Debug.LogError* messages are redirected to Developer Console. This can be disabled and the level of logging of *Debug.LogError* can be controlled through <u>settings</u>.

To log messages directly to Console, you can use Console.Log() method from anywhere:

Console.Log("hello");

To log messages with certain Color, you can add optional Color parameter.


Console.log("hello", Color.Red);

There's also third optional parameter to force ignore timestamp even when option 'print message timestamps' is enabled:

Console.Log("hello", Color.red, true);

DeveloperConsole settings

Developer Console comes with few settings you can tweak. To change settings, modify DeveloperConsole.cs in the inspector which is attached to DeveloperConsole prefab gameobject.



Custom GUI: Whether to use custom GUI (tabs) or render default inspector view (default true)

GUI settings

Interface style: Modify GUI style, Large / Minimal (Default Large)

Interface theme: Select GUI theme (Dark, Red, Custom) (Default Dark)

Large GUI settings

Console Window Default Size: Developer Console default window size multiplier (Applies to Large GUI only) (Default 0.9)

Scroll Sensitivity: Developer Console scroll sensitivity (Default: 30)

Console Background Opacity: Developer Console message area background opacity (Applies to Large GUI only) (Default 55)

Reset Window Position On Enable: Whether to reset window position when console is opened (Applies to large GUI only) (Default false)

Reset Window Size On Enable: Whether to reset window size when console is opened (Applies to large GUI only) (Default false)

Force Console Inside Screen Bounds: Whether to force Console to be inside screen bounds when dragging and resizing console. If set to false and console was moved outside screen bounds, Console position and size will reset next time console is opened. (Applies to large GUI only) (Default false)

https://github.com/anarkila/DeveloperConsole

Scroll Rect Visibility: Whether to show Scroll Rect permanent or hidden when there's not enough messages to scroll through (default permanent)

Default Message Text Color: Default message text color (default white)

General settings

Include Console In Final Build: Whether to include Developer Console in final release build (Default false). Be careful whether you want to include in final release build. This is false by default, so you don't accidentally release this into the wild. You can and have permission to publish this for release builds but be careful to not include commands you don't want users to use!

Initialize Console On First Open: Whether to initialize Developer Console on first open instead of on DeveloperConsole.cs Awake(). This can be useful if you test play your game often, and rarely use Developer Console (default false).

Register Static Commands Only: Whether to register static commands only with [ConsoleCommand()] attributes and ignore all other (MonoBehaviour) [ConsoleCommand()] attributes (default false). See Adding and Removing Commands and Best Practises sections for more info.

Scan All Assemblies: Whether to scan all C# Assemblies when registering commands. Enabling this will increase command registration time significantly. You shouldn't have to enable this. If this option is enabled a warning is displayed (Editor only) (default false!)

Allow GUI Change runtime: Whether to allow changing between Large GUI and Minimal GUI runtime (default true)

Unity Log Option (applies to Large GUI only):

- Don't print logs:
 - o Don't print any Unity Debug.Log/LogError messages into Developer Console
- log with expections Editor only:
 - Print Debug.Log/LogError messages into Developer Console window with all exceptions but only in Editor.
- Log Expections With Stack Trace Editor Only
 - Print Debug.Log/LogError messages into Developer Console window with all exceptions and stack traces but only in Editor. Stack traces will print detailed error logs with script names and all.
- Log Without Expections
 - Print Debug.Log/LogError messages into Developer Console window with all exceptions (Editor and Build)
- Log Without Expections With Stack Trace (Default)
 - Print Debug.Log/LogError messages into Developer Console window with all exceptions and stack traces (Editor and Build). Stack traces will print detailed error logs with script names and all.

Unity Threaded Log Option (applies to Large GUI only): same as above options but for logs that come from other than main threads. *ListenThreadedLogs.cs* script handles listening threaded messages and safely 'moves' them into main thread so messages can printed to Developer Console.

Max Message count: How many messages will be shown in the Developer Console window before messages will start to recycle from the beginning (Applies to Large GUI only) (Default 128)

Commands Are Case Sensetive: Whether calling commands are case sensitive (Default false). **Allow Multiple Commands:** Whether to allow multiple commands to be executed in a row like below. See <u>Multiple Commands</u> section for more info (Default true)

https://github.com/anarkila/DeveloperConsole

Show Input Predictions: Whether to show inputfield predictions (Default true)

ShowContextMenuOnMessageRightClick: Whether to allow showing Context menu when message clicked. In this context menu you can copy the message content to clipboard, delete the message or clear all messages (Default false).

Allow Console Resize: Allow Console to be resized (Applies to large GUI only) (Default true)

Allow Console Window Drag: Allow Console to be dragged (Applies to large GUI only) (Default true)

Show Cursor On Enable: Whether to force cursor on when Console is opened. (Default true)

Hide Cursor On Disable: Whether to force cursor off when Console is closed. (Default true)

Scroll to bottom On Enable: Whether to scroll bottom when console is opened (Default true)

Clear Messages On Scene Change: Whether clear all console messages when scene is changed (Default false)

Print Message Timestamps: Whether to print message timestamp (Applies Large GUI only) (Default true)

Print Startup Help Text: Whether to show print 'type help and press enter to.." text on startup. (Default true)

Print Unrecognized Command Info: Whether to print unrecognized command info to console: "Command [command name] was not recognized." (Default true)

Print Commands Alphabetical Order: Whether to print commands in alphabetical order when command 'help' is called (Default true)

Print Command Info Texts: Whether to commands info texts when 'help' command called. Command info texts are optional parameter when adding [ConsoleCommand()] attribute (Default true)

Print Loaded Scene Name: Whether to print loaded scene name.

Print Initialization Time: Whether to print Console Initialization time when scene is loaded (default true).

Keep Track Of Messages: Whether to keep track of console messages. These messages can then be retrieved with Console API (default true).

Key Bindings

Console Toggle key: Keycode which activates/deactivates Developer Console (Default Backslash)

Console Submit key: Keycode which submits command (Default Return)

Console Search Command key: Keycode which searches previously (successfully) executed command (Default UpArrow)

Next Suggested Command Key: Keycode which fills next command from suggestions (Default DownArrow) – however if **Console Search Command key** clicked then this key goes reverse direction of that key. Similiar behaviour as Windows CMD or Linux Terminal.

Next Suggested Command Key Alt: Keycode which fills next command from suggestions alternative key (Default Tab)

Debug Settings

Print Message Count: Whether to print Debug.Log/LogError and Console.Log message count after exiting play mode (Editor only) (default true)

Print Play Button To Scene Time: Whether to print play button click to playable scene time (Default true)

Collect Render Info Editor: Whether to collect Unity rendering information such as highest draw call / batches count. This can be printed to console with command: 'debug.print.renderinfo'. This happens in DebugRenderInfo.cs class (Default true)

Clear Unity Console On Console Clear: Whether to Clear Unity console messages too when Developer Console 'clear' event called (Editor only) (Default false)

Print Log Type: Whether to print log type (Log, exception, Warning, Assert, Error) before message (Default false)

Getting Console state info

Developer Console comes with simple static API you can call everywhere to interact with console. This is intended if you need to know its state or change some settings during runtime.

If you need to know when Developer Console is opened or closed (for turning scripts on/off for example), you can do it two ways.

 Register to console event like below. Remember to unregister your event either in OnDisable or OnDestroy!

```
using UnityEngine;
public class Example : MonoBehaviour {
    private void OnEnable() {
        Console.RegisterConsoleStateChangeEvent += Callback;
    }
    private void OnDisable() {
        Console.RegisterConsoleStateChangeEvent -= Callback;
    }
    private void Callback(bool enabled) {
        Debug.Log("Console is open: " + enabled);
    }
}
```

2) If you want to check Developer Console state in Update() function (or anywhere) you can do the following.

```
using UnityEngine;
public class Example : MonoBehaviour {
    private void Update() {
        if (Console.IsConsoleOpen()) {
            return;
        }
        // Else do your work..
    }
}
```

If you need to know if Developer Console is fully initialized, you can either register to Console.RegisterConsoleInitializedEvent (like in the example below) or check by calling Console.IsConsoleInitialized() function.

```
using UnityEngine;
public class Example : MonoBehaviour {
    private void Start() {
        Console.RegisterConsoleInitializedEvent += ConsoleInitialized;
    }
    private void ConsoleInitialized() {
        Debug.Log("Developer Console is now fully initialized");
        // Unregister from the event
        Console.RegisterConsoleInitializedEvent -= ConsoleInitialized;
    }
}
```

Notes.

This event fires every time scene changes.

Since version 0.8.3 Developer Console should initialize relatively fast and should be fully initialized before any *Start()* function fires.

Developer Console 1.0.2

Documentation

https://github.com/anarkila/DeveloperConsole

How does it work?

DeveloperConsole.cs which is attached to DeveloperConsole prefab root gameobject, *Awake()* function calls ConsoleManager.cs initialization method. After this ConsoleManager.cs handles everything.

Every time new scene is loaded or unloaded (additively or single), ConsoleManager.cs handles looking for all [ConsoleCommand()] attributes via C# Reflection in the CurrentDomain Assembly. This work happens in two parts.

- 1) First part looks for all [ConsoleCommand()] attributes in the Unity C# Runtime assembly (<u>Assembly-CSharp</u>) and all static class commands are registered and cached. All other C# assemblies are ignored unless setting 'Scan All Assemblies' is set to true.
- 2) Second part handles registering MonoBehaviour instance commands and this done by looking for all the different MonoBehaviour scripts that have [ConsoleCommand()] attribute(s).

After all commands has been registered, final command lists are built, and all subscribers are notified that console is now fully initialized. If option *'Print Initialization Time'* is enabled then initialization times are printed to console, and it should look something like this:

Console Initialized. Initialization took 15 ms.

After commands has been registered, only one or two scripts run every frame.

- ConsoleKeyInputs.cs runs every frame and handles listening all key inputs.
- ListenThreadedLogs.cs also runs every frame (if option 'Unity threaded log option' is set to DontPrintLogs then this script is disabled) but most of the time it will just return before even doing anything.

Everything else is event based and does not run unless needed.

Best Practices

Performance

If your game relies heavily on additive scene un/loading or you change scenes often, consider enabling *'Register Static Commands Only'* option and use static class commands only for the best performance. Currently all MonoBehaviour commands are re-/registered when scene is loaded or unloaded while all static commands are cached on first load.

Consider keeping option 'Max Message Count' as small as you need. The default 128 is great starting point. After 128 messages has been reached, messages will start to recycle from the beginning. You can increase this as big as you want but consider that Console might get slow'ish with large number of messages (1K+) because Unity's VerticalLayoutGroup Component is pretty heavy UI with lots of child objects.

Logging

Avoid unnecessary Debug.Log/LogError or Console.Log calls. C# strings generate garbage and garbage collection in Unity is quite slow, thus it's recommended to remove all unnecessary ones. Avoid calling log messages in any Late/Fixed/Update() methods unless it's for short debugging purposes.

If you are only using Minimal GUI style, consider changing settings 'UnityPrintOption' and 'UnityThreadedPrintOption' ConsoleLogOptions enum to DontPrintLogs. By default, Debug.Log/LogError and Console.Log messages are still printed to Large GUI console even when it's not selected. Why? So you can toggle between them during runtime with command 'console.style'.

https://github.com/anarkila/DeveloperConsole

Version History

v 1.0.2

- Committed Unity .meta files to repository to fix missing references
- Renamed FillCommandKey option to NextSuggestedCommandKey
- Renamed FillCommandKeyAlt option to NextSuggestedCommandKeyAlt
- Filling from previous command(s) now keeps arguments
- Fix fill command previous command ordering issues
- Added option to keep track of failed/non-existing commands
- Added new option to allow keeping track of duplicate successfully executed commands
- Added editor check that EventSystem component exists in the scene to DeveloperConsole.cs (OnValidate).
- Added new option to allow initializing Developer Console on first open instead of DeveloperConsole.cs Awake function. This can be useful if you test play your game often, and only rarely use Developer Console.
- Fixed rare issue where InputField caretposition didn't move to the end of text correctly.
- Added ability to use down arrow to navigate reverse direction when browsing through previously executed commands. See <u>issue #6</u>.

v 1.0.1

- Simplified message pool logic
- Added optional context menu when message right clicked. In this menu you can copy the message to clipboard, delete the message, or clear all messages. This is not enabled by default.
- Code cleanup and fixed spelling mistakes
- Expanded runtime Console.cs API:
 - o Console.GetConsoleCommandsCount() Get registered console commands count
 - Console.GetStaticConsoleCommandsCount() Get registered static console commands count
 - o Console.GetConsoleMessagesArray() Get all current Console messages as string array
 - o Console.GetConsoleMessagesList() Get all current Console messages as list
 - Console.WriteMessagesToFile() Writes all current Console messages to .txt file (Windows Editor only)

v 1.0.0

- Bump version to 1.0.0
- Minor code changes: error checking and cleanup
- Fixed ConsoleLogOptions Expections spelling
- ConsoleLogOptions.LogExpectionsEditorOnly and
 - ConsoleLogOptions.LogExpectionsWithStackTraceEditorOnly now work properly.
- Expanded runtime Console.cs API:
 - o Console.lsConsoleEnabled() Whether console is currently enabled
 - o Console.EnableConsole() Enable Developer Console
 - Console.DisableConsole() Disable Developer Console from opening.
 - o Console.SetConsoleEnabledState() Set Developer console enabled state.
 - Console.ShowInputPrections() Should show input predictions on console inputfield
 - Console.DisableUnityMessageLogging() Disable showing all Debug.Log messages in console window
 - Console.GetCurrentUnityLogOption() Get ConsoleLogOptions for Debug.Log messages
 - o Console.ChangeUnityLogOptions() Ability to change ConsoleLogOptions runtime
 - Console.ChangeThreadedUnityLogOptions() Ability to change ConsoleLogOptions runtime
 - Console.GetCurrentThreadedUnityLogOption() Get ConsoleLogOptions for Threaded Debug.Log messages

Developer Console 1.0.2

Documentation

https://github.com/anarkila/DeveloperConsole

v 0.8.5

- Code cleanup and added comments
- Updated Editor generate text files utility script to list all parameters
- Added new color theme 'Darker'
- Fixed Console.OpenConsole and Console.CloseConsole methods to work in Awake/Start functions
- Fixed DeveloperConsoleEditor GUI to properly show all settings
- Improved Large GUI
- Adjusted 'Dark' theme colors
- Expanded Console.cs API:
 - o Added ExecuteCommand() method to execute commands
 - o Added ResetConsole() method to reset console size and position
 - o Added SetGUITheme() method to set Console GUI theme
 - o Added SetCustomGUITheme() method to to set custom Console GUI theme

v 0.8.4

- Added support for no domain/scene reload
- Added warnings if Console.cs methods were called from another thread.
- Added Ability to log messages with color
- Added multiple parameter support
 - o Only methods that don't contain Vector2, Vector3, Vector3 or String[] are supported.
- Fixed issue where command prediction would not show in minimal GUI
- Optimized console message pooling
- Optimized ConsoleCommand attribute registration performance for larger projects

v 0.8.3

- Improved ConsoleCommand attribute registration performance (from ~1500 ms to ~15 ms)
- Other minor performance improvements
- Logging and warning improvements
- Changed default command names
- Changed few settings defaults
- Added new settings

v 0.8.2

- Fixed issue where console took two button presses to open after closing console with top right X button
- Fixed issue where setting 'max message count' wouldn't increase max message count
- Reduced garbage collection in editor
- Minor performance improvements
- Improved Console window dragging
- Improved input prediction
- Added support for multiple commands (separated by '&' or '&&')
- Added support and option for threaded Debug.Log and Debug.LogError messages
- Added GUI themes (Dark, Red, Custom)
- Added more default scene un/loading commands
- Added optional info text parameter to ConsoleCommand. This info string is printed 'with 'help' command if setting 'print command info texts' is set to true (default true).
- Added more settings to tweak

Developer Console 1.0.2

Documentation

https://github.com/anarkila/DeveloperConsole

- Fixed issue where calling coroutine which no longer existed in the scene resulted in error
- Fixed issue where coroutine was started when gameobject was inactive
- Fixed issue where multiple DeveloperConsole prefabs where open at the same time
- Fixed issue where in editor DeveloperConsole would throw NullReferenceException if scene was entered and exited before console was initialized
- Renamed namespace to avoid any conflicts with other assets
- Prediction panel texts are now buttons and can now be clicked. Clicking prediction text will input that text into console inputfield
- Minor GUI improvements
- Minor performance improvements
- Made tabbed Inspector GUI for ConsoleInitializer.cs
- New settings:
 - o highlight color
 - o Setting for printing console commands in alphabetical order

v 0.8.0

Initial release