## **NAME**

kded5 - KDE daemon - triggers Sycoca database updates when needed.

#### **SYNOPSIS**

kded5 [--check]

## DESCRIPTION

**kded5** consolidates several small services in one process. These are mostly D–Bus services provided by KDED modules, but it also manages sycoca (a binary cache of servicetypes, MIME types and services used by KService) and KConfig update scripts as needed.

For sycoca, it monitors the directories containing .desktop files. When a file is added/removed, it waits 5 seconds (in case of a series of updates), and then launches **kbuildsycoca5** to update the sycoca.

For KConfig, it checks newly-installed update files, i.e. the \*.upd files used to update configuration files of users when the configuration file formats changes, and runs the KConfig update utility to perform the updates.

Those tasks are also run when **kded5** is started to ensure that the user configuration is up to date.

You do not normally need to run **kded5** directly; Plasma desktop sessions run it automatically, and it is started on demand when an application attempts to use a D–Bus interface provided by it or one of its modules.

#### **OPTIONS**

### --check

Check the sycoca database, updating it if necessary, and exit.

#### CONFIGURATION

**kded5** can be configured with the kded5rc ini-style configuration file. On UNIX® systems, this can be found at \$XDG\_CONFIG\_HOME/kded5rc; if \$XDG\_CONFIG\_HOME is not set, this defaults to ~/.config/kded5rc.

Configuration file entries are read on–demand, so changes can be made while **kded5** is running. However, all the current configuration options only really affect the startup behaviour of **kded5**.

The [General] section has the following options:

## CheckSycoca

Whether to update sycoca at startup (default: true).

## CheckUpdates

Whether to perform outstanding KConfig updates at startup (default: true).

## CheckFileStamps

Whether to check file timestamps when performing the initial sycoca update (default: **true**). See the documentation for **kbuildsycoca5** for more details.

## DelayedCheck

Whether to delay the initial sycoca update until about a minute after starting (default: false).

Each module also has a [Module-name] section in kded5rc, where name is the name of the module's desktop file without the .desktop extension. This contains an autoload option that specifies whether the module should be automatically loaded when kded5 is started (default: false). Note that this setting can also be changed via kded5's D-Bus interface.

## **SEE ALSO**

kbuildsycoca5(8), kdeinit5(8)

#### BUGS

Please use **KDE's bugtracker**<sup>[1]</sup> to report bugs.

## **AUTHORS**

**David Faure** <faure@kde.org>
Maintainer

# 

## NOTES

KDE's bugtracker
 https://bugs.kde.org