NAME

groupmems - administer members of a user's primary group

SYNOPSIS

```
groupmems –a user_name | –d user_name | [–g group_name] | –l | –p
```

DESCRIPTION

The **groupmems** command allows a user to administer their own group membership list without the requirement of superuser privileges. The **groupmems** utility is for systems that configure its users to be in their own name sake primary group (i.e., guest / guest).

Only the superuser, as administrator, can use **groupmens** to alter the memberships of other groups.

OPTIONS

The options which apply to the **groupmems** command are:

-a, --add user name

Add a user to the group membership list.

If the /etc/gshadow file exist, and the group has no entry in the /etc/gshadow file, a new entry will be created.

-d, --delete user_name

Delete a user from the group membership list.

If the /etc/gshadow file exist, the user will be removed from the list of members and administrators of the group.

If the /etc/gshadow file exist, and the group has no entry in the /etc/gshadow file, a new entry will be created.

-g, --group group_name

The superuser can specify which group membership list to modify.

-h, --help

Display help message and exit.

-l, --list

List the group membership list.

-p, --purge

Purge all users from the group membership list.

If the /etc/gshadow file exist, and the group has no entry in the /etc/gshadow file, a new entry will be created.

-R, --root CHROOT DIR

Apply changes in the *CHROOT_DIR* directory and use the configuration files from the *CHROOT_DIR* directory.

SETUP

The **groupmems** executable should be in mode 2710 as user *root* and in group *groups*. The system administrator can add users to group *groups* to allow or disallow them using the **groupmems** utility to manage their own group membership list.

```
$ groupadd –r groups
$ chmod 2710 groupmems
$ chown root.groups groupmems
$ groupmems –g groups –a gk4
```

CONFIGURATION

The following configuration variables in /etc/login.defs change the behavior of this tool:

MAX MEMBERS PER GROUP (number)

Maximum members per group entry. When the maximum is reached, a new group entry (line) is started in /etc/group (with the same name, same password, and same GID).

The default value is 0, meaning that there are no limits in the number of members in a group.

This feature (split group) permits to limit the length of lines in the group file. This is useful to make sure that lines for NIS groups are not larger than 1024 characters.

If you need to enforce such limit, you can use 25.

Note: split groups may not be supported by all tools (even in the Shadow toolsuite). You should not use this variable unless you really need it.

FILES

```
/etc/group
Group account information.
/etc/gshadow
secure group account information
```

SEE ALSO

chfn(1), chsh(1), passwd(1), groupadd(8), groupdel(8), useradd(8), userdel(8), usermod(8).