NAME

getline, getdelim – delimited string input

LIBRARY

Standard C library (libc, -lc)

SYNOPSIS

```
#include <stdio.h>
```

Feature Test Macro Requirements for glibc (see **feature_test_macros**(7)):

```
getline(), getdelim():
    Since glibc 2.10:
    _POSIX_C_SOURCE >= 200809L
    Before glibc 2.10:
    _GNU_SOURCE
```

DESCRIPTION

getline() reads an entire line from *stream*, storing the address of the buffer containing the text into**lineptr*. The buffer is null-terminated and includes the newline character, if one was found.

If *lineptr is set to NULL before the call, then **getline()** will allocate a buffer for storing the line. This buffer should be freed by the user program even if **getline()** failed.

Alternatively, before calling **getline()**, *lineptr can contain a pointer to a **malloc(3)**-allocated buffer *n bytes in size. If the buffer is not large enough to hold the line, **getline()** resizes it with **realloc(3)**, updating *lineptr and *n as necessary.

In either case, on a successful call, *lineptr and *n will be updated to reflect the b uffer address and allocated size respectively.

getdelim() works like **getline**(), except that a line delimiter other than newline can be specified as the *delimiter* argument. As with**getline**(), a delimiter character is not added if one w as not present in the input before end of file was reached.

RETURN VALUE

On success, **getline()** and **getdelim()** return the number of characters read, including the delimiter character, but not including the terminating null byte ('\0'). This value can be used to handle embedded null bytes in the line read.

Both functions return -1 on failure to read a line (including end-of-file condition). In the event of a failure, errno is set to indicate the error.

If *lineptr was set to NULL before the call, then the buffer should be freed by the user program even on failure.

ERRORS

EINVAL

Bad arguments (*n* or *lineptr* is NULL, or *stream* is not valid).

ENOMEM

Allocation or reallocation of the line buffer failed.

ATTRIBUTES

For an explanation of the terms used in this section, see **attributes**(7).

Interface	Attribute	Value
getline(), getdelim()	Thread safety	MT-Safe

STANDARDS

Both getline() and getdelim() were originally GNU extensions. They were standardized in POSIX.1-2008.

EXAMPLES

```
#define _GNU_SOURCE
#include <stdio.h>
#include <stdlib.h>
int
main(int argc, char *argv[])
    FILE *stream;
    char *line = NULL;
    size_t len = 0;
    ssize_t nread;
    if (argc != 2) {
        fprintf(stderr, "Usage: %s <file>\n", argv[0]);
        exit(EXIT_FAILURE);
    }
    stream = fopen(argv[1], "r");
    if (stream == NULL) {
       perror("fopen");
        exit(EXIT_FAILURE);
    }
    while ((nread = getline(&line, &len, stream)) != -1) {
        printf("Retrieved line of length %zd:\n", nread);
        fwrite(line, nread, 1, stdout);
    }
    free(line);
    fclose(stream);
    exit(EXIT_SUCCESS);
}
```

SEE ALSO

read(2), fgets(3), fopen(3), fread(3), scanf(3)