

Router WHC (DHCP, RIPv2, & Floating Static Route)

```
enable
configure terminal
```

```
! DHCP Pool for WHC PCs
ip dhcp pool WHC_LAN
network 6.6.1.0 255.255.255.0
default-router 6.6.1.1
dns-server 6.6.0.100
exit
```

```
! WHC LAN Interface
interface gig0/0
ip address 6.6.1.1 255.255.255.0
no shutdown
exit
```

```
! Connection to MOH
interface serial0/1/0
ip address 6.6.4.198 255.255.255.252
no shutdown
exit
```

```
! Connection to DDU
interface serial0/1/1
ip address 6.6.4.201 255.255.255.252
no shutdown
exit
```

```
! Backup Connection to CSC
interface serial0/2/0
ip address 6.6.4.213 255.255.255.252
no shutdown
exit
```

```
! Floating Static Route (Backup route to CSC network with Administrative Distance 130)
ip route 6.6.2.0 255.255.255.0 6.6.4.214 130
```

```
! Dynamic Routing (RIPv2)
router rip
version 2
no auto-summary
network 6.0.0.0
```

exit

Router DDU (DHCP & RIPv2)

enable

configure terminal

! DHCP Pool for DDU PCs

ip dhcp pool DDU_LAN

network 6.6.3.0 255.255.255.0

default-router 6.6.3.1

dns-server 6.6.0.100

exit

! DDU LAN Interface

interface gig0/0

ip address 6.6.3.1 255.255.255.0

no shutdown

exit

! Connection to WHC

interface serial0/1/0

ip address 6.6.4.202 255.255.255.252

no shutdown

exit

! Connection to RPP

interface serial0/1/1

ip address 6.6.4.205 255.255.255.252

no shutdown

exit

! Dynamic Routing (RIPv2)

router rip

version 2

no auto-summary

network 6.0.0.0

exit

Router RPP (No RIPv2, Static Routing Only)

enable

configure terminal

! RPP LAN Interface (/26 Subnet)

interface gig0/0

ip address 6.6.4.129 255.255.255.192

no shutdown

exit

! Connection to DDU

interface serial0/1/0

ip address 6.6.4.206 255.255.255.252

no shutdown

exit

! Exit-Interface Static Route (To MOH network directly out the serial port)

ip route 6.6.0.0 255.255.255.0 serial0/1/0

! Default Route (Next-hop pointing to DDU to reach the rest of the network)

ip route 0.0.0.0 0.0.0.0 6.6.4.205

exit