

ZICE_ARMS — Role Catalogue for Security

Oct 5, 2026 · @Arnav Johri

These are the role codes users request through ZICE_ARMS and the authorisation approvers need. The program does not map role codes to PFCG roles, so that mapping has to be done in S/4.

1. Normal and Cross Company roles

There are 22 requestable role codes, from table ZMM_PREP_ROLEDES.

- **Fields:** the organisational values the user must name on the request.
- **MM only:** the role is restricted to users of the MM discipline.
- **Who can approve:** "L3 and above" means an L3, IM or L1 approver.

Role	Description	Fields on request	MM only	Who can approve
M1	Indentor – Materials	Plant, Purch. group		L3 and above
M2	MRP Controller	Plant		L1 only
M4	Indentor – Services	Plant, Purch. group		L3 and above
M5	Indent Verifier for Services	Plant, Purch. group		L3 and above
M6	SES Creator	Plant, Purch. group		L3 and above
M7	SES Checker	Plant, Purch. group		L3 and above
M8	SES Approver	Plant, Purch. group, Approver level		L3 and above
M9	PO Materials Creator	Plant, Purch. group	Yes	L3 and above
M10	PO Services Creator	Plant, Purch. group		L3 and above
M11M	PO Approver – Materials	Plant, Purch. group, Approver level	Yes	L3 and above
M11S	PO Approver – Services	Plant, Purch. group, Approver level		L3 and above
M12	Stores – Receipt Section	Receipt location	Yes	IM or L1
M13	Stock Holder in MM Stores	Plant, Storage location	Yes	IM or L1

Role	Description	Fields on request	MM only	Who can approve
M14	Stock Incharge	Plant, Storage location	Yes	IM or L1
M15	Stock Verifier	Plant	Yes	IM or L1
M16	On-site Stores Transactions	Plant, Storage location		L3 and above
M17	C&F	Receipt location	Yes	IM or L1
M18	Disposal Stock Holder	Plant, Storage location	Yes	IM or L1
M19	Disposal Stock Incharge	Plant, Storage location	Yes	IM or L1
M20	Stock Verification Incharge	Plant		IM or L1
M21	Capital Indentor	—		L1 only
M22	All MM Display Roles (no SAP mail)	—		L3 and above

2. CRC roles

There are 32 active CRC role codes, from table ZMM_PREP_ROLECRC. Each one stands for an organisational unit. All need plant and purchasing group, except O7, which needs neither. C30 needs an L1 approver; every O code can be approved by L3 and above.

Role	Entity	Role	Entity
C30	Finance (L1 only)	O16	Exploration and Development
O1	Business Units	O17	Geology and Geophysics
O2	Director Office	O18	Corporate Planning and Strategy
O3	Business Development	O19	Operations
O4	Corporate Communication	O20	Drilling
O5	Company Secretary	O21	Corporate Support Services
O6	Strategic HR	O22	Engineering and Construction
O7	Project Finance	O23	Medical
O8	Technical and Management Cell	O24	Logistics
O9	Information Technology	O25	Maintenance

Role	Entity	Role	Entity
O10	Materials Management	O26	Vigilance
O11	Health Safety and Environment	O27	Security
O12	HR/ER	O28	Office of MD
O13	Legal	O29	Others
O14	Corporate Finance	O30	PR Approvals as per Designations
O15	Marketing	O31	SES Approvals – L3/L4

Inactive – do not map: M3, M3A, M3B, M11S, M11M (marked "NOT IN USE"). The ARMS screen still lists them, so a request that includes one of these should be rejected.

3. Approver authorisation

ARMS identifies an approver only by authorisation object **M_EINK_FRG**, field **FRGCO** (PO release code). It checks no other authorisation object and no role name. Without one of these values a user cannot approve in ARMS.

FRGCO value in the user's role	ARMS approval level
L1, DI, CS, MD	L1
IM	IM (I/C MM)
L2, L3	L3

- **Check order:** values are tested in the order shown and the first match wins. A user holding both IM and L3 is treated as IM.
- **Release group:** the check names only FRGCO, so FRGGR (release group) is not checked here.
- **PO release rights:** M_EINK_FRG is the standard purchase-order release object. A value granted only for ARMS approval also lets that user release POs if they have ME28/ME29N. Please confirm this is acceptable for each approver role.

4. Transaction codes and open points

Tcode	Who needs it (S_TCODE)	Note
ZICE_ARMS	All requesters and approvers	Current transaction

Tcode	Who needs it (S_TCODE)	Note
ZMM_ARMS	Nobody	Discontinued; shows a message and exits
ZMM_ARMS_CONNECT	Only if still called from another program	Display-only jump into a request

To confirm:

- ☐ Mapping of each ARMS role code above to the S/4 PFCG role(s).
- ☐ Which transaction the ICE core team uses to process requests (sets status PC/C), and who needs it.
- ☐ Whether L2 holders are meant to approve at the same level as L3.