SECTION 1 · SUBSECTION 1.5
PAGE LAYOUT: COLUMN GRID AND LANES

1.5.1 INTRODUCTION.

The page is laid out as a grid. Every row is measured first, then one matra width is chosen for the whole page, so a given cycle position sits in the same column in every row (figure 1.5-1). A pickup row occupies the columns of its own cycle positions and so ends up right-aligned.




Figure 1.5-1. Page Column Grid, Three Kinds Of Row

1.5.2 FUNCTIONAL DESCRIPTION.

TaalStave.preFormat() builds the contexts of a row and reports its widest packed matra. Page.format() fixes the matra width, assigns x from the ColumnGrid, reserves meend and tihai lanes on the rows they touch, then stacks the lanes of each row top to bottom (figure 1.5-2).

1.5.2.1 Column Position.

x(col) = left + col × W + bars × G, where bars counts the vibhag bars crossed. A bar stands before a column only when that column starts a vibhag and is not the first in its row.




Figure 1.5-2. Row Lanes And Matra Column

1.5.3 PERFORMANCE AND DESIGN DATA.

Table 1.5-1. Default Layout Parameters

Style key	Default
spacing.matraPad	7 PX
spacing.clusterGap	1 PX
spacing.vibhagGap	16 PX
spacing.swarToLyric	16 PX
spacing.lyricToMarker	6 PX
spacing.rowGap	30 PX
spacing.margin	44 PX
spacing.maxWidth	1000 PX
spacing.sectionGap	14 PX
fontSize.swar / lyric	24 / 21 PX
fontSize.kanScale	0.6 OF SWAR

NOTE

Rows never wrap. A page wider than maxWidth is scaled down as a whole (scale = maxWidth / width), so the bars still line up.

```
TUNE THE LOOK                    DEVELOPER
1 FACTORY - pass options.style
2 spacing.vibhagGap - bar room
3 spacing.maxWidth - page scale
4 fontSize.swar - swar size
5 script - devanagari | latin
6 textMode - path | text
  √ render - bars still align
```