AtiNAMatiC-Pitch — User Manual

Version 0.2.0 · Atij 666 Studio · Windows · macOS · Linux (VST3, CLAP, AU, LV2, Standalone)

1. What it is

AtiNAMatiC-Pitch is a one-knob pitch tool with three jobs:

- **Drop** — play drop-tuned parts without retuning: 0 to -7 semitones, always in whole semitones so it is always in tune.
- **Detune** — stereo "micro-shift" thickening: a voice a few cents up on the left, one a few cents down on the right, under your dry signal.
- **Octave** — an octave-below voice, filtered smooth, added under your playing.

It uses a pitch-synchronous granular shifter: a light pitch tracker finds the period of what you are playing and lines the grains up with the waveform, so single notes stay clean. Measured on steady notes: the shifted note is dominant, with by-products 35–41 dB down.

Honest limits: like any real-time shifter, full chords at large shifts (Drop -5 to -7, Octave) warble a little, because a chord has no single period to line up with. Single notes, riffs and small shifts are the cleanest. Drop and Octave also have a short inherent delay (the grain window, roughly 20–30 ms); Detune's delays are part of the effect.

2. Signal chain placement

```
Guitar -> [AtiNAMatiC-Pitch] -> ... -> Amp sim          (Drop, Octave: before the amp)
Amp sim -> Cab / IR -> [AtiNAMatiC-Pitch]               (Detune: after the amp, stereo)
```

Drop and Octave track best on a clean DI, so place them first. Detune works best after the amp. Mono in / stereo out is supported.

3. Controls

PITCH (big knob)

Its meaning depends on the mode; the readout under the knob shows the actual value.

Mode	Knob range	Readout
Drop	0 → -7 semitones (whole steps)	`-3 st`
Detune	0 → 25 cents each way	`12 cents`
Octave	octave-down level 0 → 100 %	`-1 oct 60 %`

MODE (switch)

Drop / Detune / Octave.

MIX (0–100 %)

Drop: wet/dry (100 % = only the shifted signal). Detune and Octave: how much of the added voice(s) you hear on top of the dry signal.

OUTPUT (-24 to +12 dB)

Final trim.

4. Meters

- **INPUT / OUTPUT** — peak level.
- Status: **IN TUNE**, **DROP -n ST**, **DETUNE +/-n CENTS**, **OCTAVE DOWN**.

5. Installation

Windows: run **AtiNAMatiC-Pitch-Setup-0.2.0.exe**, then rescan plug-ins. Manual install: copy `AtiNAMatiC-Pitch.vst3` to `C:\Program Files\Common Files\VST3\` and `AtiNAMatiC-Pitch.clap` to `C:\Program Files\Common Files\CLAP\`.

6. Tips

- Drop -2 st turns standard tuning into “D standard” for a song; -5 st into “B standard” for single-note riffs.
- Detune 8–15 cents after the amp is a classic stereo thickener on clean parts and leads.
- Octave at 30–50 % under a fuzzy lead gives a huge, organ-like low end.
- Double-click any knob to reset it; hold Shift while dragging for fine control.

AtiNAMatiC-Pitch v0.2.0 · Atij 666 Studio