
AtiNAMatiC-Hum — User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

1. What it is

Single-coil pickups, ground loops and nearby power supplies put a steady **hum** (50 or 60 Hz) and a harsher **buzz** (its upper harmonics) into your DI. An amp sim with lots of gain makes it much louder. A gate only hides it between notes; AtiNAMatiC-Hum removes it while you play.

- A cascade of true notches, each only about 2.5 Hz wide, at the mains frequency and its harmonics. Narrow enough that your notes pass.
- **Auto** works out whether your hum is 50 Hz or 60 Hz by itself.
- Measured: hum removed by about 15 dB (30 %), 22 dB (60 %) and 31–38 dB (100 %); a clean guitar with no hum loses only 0.2–0.3 dB.
- Zero latency.

2. Signal chain placement

```
Guitar -> [AtiNAMatiC-Hum] -> Gate -> ... -> Amp sim
```

Put Hum **first**, before the gate and before anything that adds gain.

3. Controls

HUM REMOVAL (big knob, 0–100 %, default 50 %)

Sets both how deep the notches cut (0 → -40 dB) and how many harmonics are treated (2 → 12). The low end of the knob (HUM) takes out the 50/60 Hz hum; higher settings (BUZZ) also remove the upper harmonics that make single-coil buzz.

MAINS (mode switch)

Mains	Use
Auto (default)	detects 50 Hz or 60 Hz from your signal (needs a second or two of hum to decide)
50 Hz	Europe, Asia, Africa, Australia, most of South America
60 Hz	North America, parts of South America, Japan (west), Korea, Taiwan, Philippines

OUTPUT (-24 to +12 dB)

Final trim.

4. Meters

- **INPUT** — peak level.
- **HUM** — energy of the hum series in your input.
- **REMOVED** — how much of it is being taken out, in dB.

- Status: **CLEAN**, **50 HZ HUM** / **60 HZ HUM**, or **... REMOVED**.

5. Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Hum-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Hum.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Hum.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Hum.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Hum-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Hum.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Hum.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Hum.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Hum.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Hum.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Hum-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.

6. Tips

- Start at 40–60 %; go higher only if you still hear buzz after the amp.
- If Auto picks the wrong mains on a near-silent signal, set 50 Hz or 60 Hz manually.
- Double-click any knob to reset it; hold Shift while dragging for fine control.

AtiNAMatiC-Hum v1.0.0 · Atij 666 Studio