ONE KNOB Series

23 one-knob plug-ins · Version 1.0.0

VST3 · CLAP · LV2 · AU (macOS) · Windows · macOS · Linux


Free and open source (GPL v3) · ATIJ STUDIO

Contents

1. AtiNAMatiC-Air
2. AtiNAMatiC-Bloom
3. AtiNAMatiC-Boost
4. AtiNAMatiC-Cab
5. AtiNAMatiC-Choke
6. AtiNAMatiC-Cohere
7. AtiNAMatiC-Dirt
8. AtiNAMatiC-Double
9. AtiNAMatiC-Feel
10. AtiNAMatiC-Gate
11. AtiNAMatiC-HitZone
12. AtiNAMatiC-Hum
13. AtiNAMatiC-Level
14. AtiNAMatiC-Mono
15. AtiNAMatiC-Pick
16. AtiNAMatiC-Pitch
17. AtiNAMatiC-Reach
18. AtiNAMatiC-Room
19. AtiNAMatiC-Sag
20. AtiNAMatiC-Slow
21. AtiNAMatiC-Squash
22. AtiNAMatiC-Strum
23. AtiNAMatiC-Tight

AtiNAMatiC-Air — User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

What's new in v0.2.0

- **Real depth on mono sources.** A guitar coming out of a mono amp sim has no side signal, so the old M/S widening produced no stereo image at all. Air now builds its depth from a short, mono-safe early-reflection pattern written only into the side channel (Studio: 2–12 ms, Room: 5–29 ms, lows below 150 Hz kept centred). Summing to mono gives exactly the dry-plus-EQ signal back. It is still not a reverb — there is no tail.
- The integer-step Haas delay (which zippered when the knob moved) is gone; the depth meter now shows the side-to-mid energy you actually hear.
- **New interface** — machined knob with a printed 0–10 scale, hardware-style mode switches that follow automation and preset recall, consistent value text ("72 %", "+1.5 dB"), resizable window (75–150 %, remembered per session). Double-click any knob to reset it; hold **Shift** while dragging for fine adjustment.

---

1. What it is

AtiNAMatiC-Air is a post-cab "amp-in-the-room" enhancer designed to sit **after** your amp/cab simulator (NAM, Helix Native, ML Sound Lab, IRs, etc.) in the signal chain. It restores three things that get lost when a cab is captured through a single microphone:

1. **Air** — high-shelf lift (10 kHz) plus a 5 kHz presence peak that brings the cab out of the speaker and into the room.
2. **Body** — a gentle 80 Hz peak (Room mode only) that adds the low-mid bloom you hear when standing in front of a real 4×12.
3. **Width & depth** — M/S widening plus a short, mono-safe early-reflection pattern in the side channel (more in Room mode), so even a mono amp sim gets a three-dimensional image.

It is **not** a reverb. It does not add tail. It re-creates the perceptual cues that make a recorded cab feel like a real amp in a real room.

---

2. Signal chain placement

```
Guitar → Amp Sim (NAM / Helix / etc.) → Cab / IR → ★ AtiNAMatiC-Air ★ → Reverb / Delay → Master
```

Always place AtiNAMatiC-Air after the cab/IR, never before. It is voiced for cab-coloured material, not raw amp distortion.

---

3. The Controls

AIR (large knob, centre)

The master macro. From 0 to 100% it simultaneously increases: - High-shelf gain at 10 kHz (0 → +5 dB) - Presence peak at 5 kHz (0 → +2 dB) - Body peak at 80 Hz (Room mode only, 0 → +2.5 dB) - Stereo widening (Studio: +0–40% sides · Room: +0–70% sides) - Early-reflection depth in the side channel (Studio: 2–12 ms, Room: 5–29 ms), mono-safe

Most users live between **30% and 65%**. Above 70% the widening becomes deliberately exaggerated for "WIDE" mix moments.

MODE (Studio / Room)

- **STUDIO** — Tighter, narrower, no body peak, a few very short reflections. Use for dry mixes, tight metal rhythms, double-tracked guitars where mono compatibility matters.
- **ROOM** — Adds the 80 Hz body peak and a longer early-reflection pattern that recreates the ear-distance cues of standing in a real room. Use for leads, ambient parts, and any track that needs to feel "live".

MIX (Wet/Dry)

0% = bypass, 100% = full wet. Default 100%. Lower it to blend in just a touch of air without changing the EQ balance of your dry cab.

OUTPUT (–24 to +12 dB)

Final makeup gain after all processing. Use to compensate for level changes the EQ + widening produces.

Activity Pill (bottom right)

Real-time indicator showing how much "air" is currently being applied:

Label	Meaning
DRY	Knob at 0, or no signal coming in
LIFT	Subtle enhancement (10–40%)
OPEN	Standard amp-in-room (40–70%)
WIDE	Wide-stereo / mix-bus mode (70–100%)

The LED brightens as you play and dims as the signal decays — it tracks both **the AIR knob position and the input level** so it idles dim when no notes are being played.

Activity Meter (INPUT / OUTPUT)

Two horizontal level bars showing peak input (post-cab) and post-processing output, with a dB scale below from –60 dB to 0 dB.

---

4. Quick-start presets (manual recipes)

Tight rhythm (mono-compatible)

- MODE: Studio · AIR: 35% · MIX: 100% · OUT: 0 dB

Standard rhythm (room feel)

- MODE: Room · AIR: 45% · MIX: 100% · OUT: −1 dB

Solo / lead

- MODE: Room · AIR: 65% · MIX: 100% · OUT: 0 dB

Ambient / clean

- MODE: Room · AIR: 80% · MIX: 100% · OUT: −2 dB

Mix-bus glue (parallel)

- MODE: Studio · AIR: 25% · MIX: 35% · OUT: 0 dB

---

5. Plug-in formats & install paths

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Air-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Air.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Air.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Air.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Air-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Air.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Air.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Air.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Air.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Air.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Air-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.

6. CPU / latency

- Processing is **zero-latency** (no oversampling, no FFT, no look-ahead).
- IIR filtering only: < 1 % CPU on a modern machine, even at 96 kHz.
- Safe to instantiate dozens of times in one session.

---

7. Troubleshooting

"The Activity Pill never lights up beyond DRY"
Make sure something is actually feeding the plug-in (NAM upstream, track armed/playing) and the AIR knob is above 0. The pill measures air × input level — both must be non-zero.

"It sounds harsh"
Drop AIR. Above 70% with a bright cab IR the 10 kHz shelf can stack up. Try 35–50% first.

"It feels narrower than expected"
Check that your DAW track (or the insert) is stereo. Air creates its depth from a mono source, but it needs a stereo output to put it in; on a mono track only the EQ is heard.

"Plug-in is missing after install"
Force a VST3 rescan in your DAW (see section 5). Some hosts cache old scan results.

"Mode switch produces a click"
Toggling MODE updates the body filter coefficients. The change is per-block so it should be inaudible during continuous playback; if you automate it, slope the automation across a few ms to be safe.

---

8. Credits

- Design & development: **Atij** (Atij 666 Studio)
- Built with **JUCE 8** (juce.com)
- Inspired by the room sound of every great cab anyone ever stood in front of

---


9. License & support

Personal & commercial use permitted on machines you own.
Bug reports / feature requests: see About dialog (click the title in the plug-in window).

AtiNAMatiC-Air is part of the AtiNAMatiC Series — a family of focused, hardware-flavoured guitar tools for the modern post-amp signal chain.

AtiNAMatiC-Bloom — User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

1. What it is

A loud amp **blooms**: hold a note or a chord and it seems to grow, fuller and richer, instead of just dying away. AtiNAMatiC-Bloom puts that in front of your amp model.

- On every pick attack Bloom remembers how loud the note started.
- While the note sustains, it gradually brings the decaying sustain back up toward that starting level — never above it — over the bloom time.
- As the note blooms, a little harmonic richness is blended in; in **Singing** mode an upper-mid resonance grows too, like an amp just before it feeds back.
- A new attack resets the bloom instantly, so the next pick is never boosted. Picks over a chord that is still ringing are caught too (the detector also watches the pick click above 4 kHz). Signals below about -50 dBFS are left alone, so decays into noise are never lifted.
- 6 ms latency, reported to your DAW. Bloom uses it to look ahead, so the bloom is already reset when the next pick arrives.

Measured on held notes: the attack is essentially unchanged, the sustain comes up by about +4 dB (50 %) to +8.6 dB (100 %), and peaks stay where they were.

2. Signal chain placement

```
Guitar -> Gate -> [AtiNAMatiC-Bloom] -> Boost / Dirt -> Amp sim -> Cab / IR
```

Place Bloom **before** the amp. It is most obvious on held chords, leads and clean or crunch tones; fast riffing barely triggers it (notes end before they bloom), which keeps rhythm parts tight.

3. Controls

BLOOM (big knob, 0–100 %, default 40 %)

How much of the drop between the attack and the sustain is brought back, up to +9 dB. 0 % (DECAY) is a clean pass-through.

TIME (mode switch)

Mode	Bloom time	Character
Swell	0.35 s	quick bloom, notes hold up
Sustain	0.9 s	slower, long sustaining notes
Singing	1.4 s	slow swell plus an upper-mid "about to feed back" resonance

MIX (0–100 %) and OUTPUT (-24 to +12 dB)

Blend with the dry signal and final trim.

4. Meters

- **INPUT / OUTPUT** — peak level.
- **BLOOM** — current bloom gain in dB.
- Status: **ATTACK**, **BLOOMING**, **SINGING**.

5. Latency and CPU

6 ms latency (look-ahead for the attack reset), reported to your DAW for automatic compensation. Very light on CPU.

6. Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Bloom-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Bloom.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Bloom.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Bloom.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Bloom-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Bloom.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Bloom.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Bloom.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Bloom.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Bloom.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Bloom-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.


7. Tips

- Leads: Singing at 50–80 % into a crunch amp gives that held-note swell.
- Pair with **Sag**: Sag squashes the attack, Bloom brings the sustain up — a very "alive" amp feel.
- Double-click any knob to reset it; hold Shift while dragging for fine control.

AtiNAMatiC-Bloom v1.0.0 · Atij 666 Studio

AtiNAMatiC-Boost — User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



Atij 666 Studio — Designed & developed by Atij

What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

What's new in v0.2.0

- **Constant loudness, clean at 0 %.** BOOST now stays within about ±1 dB across the whole sweep (it used to drop ~3 dB and lose ~10 dB of peak level at PUSH, and add +1.8 dB at 0 %). At CLEAN the curve is effectively linear.
- **4× oversampling** on the saturation stage removes the harsh aliasing that a following amp sim would otherwise amplify. This adds **38 samples** of latency (≈0.8 ms at 48 kHz), reported to your DAW for automatic compensation; the dry path of MIX is delay-matched.
- DC from the asymmetric (2nd-harmonic) bias is now removed, so there are no low-frequency thumps on note attacks.
- **New interface** — machined knob with a printed 0–10 scale, hardware-style mode switches that follow automation and preset recall, consistent value text ("72 %", "+1.5 dB"), resizable window (75–150 %, remembered per session). Double-click any knob to reset it; hold **Shift** while dragging for fine adjustment.

Overview

AtiNAMatiC-Boost adds life, punch, and harmonic clarity to any signal — designed to sit **before** your NAM amp sim (it is voiced to feed an amp model), though it also works anywhere you want musical saturation and presence.

Unlike a simple booster, it uses a three-stage soft-saturation engine with character modes and parallel mix control, so you can push the tone without destroying your dynamics.

System Requirements

	Minimum
OS	Windows 10 (64-bit) · macOS 10.15+ · Linux (Ubuntu 20.04+)
CPU	Any modern 64-bit processor
RAM	256 MB
Formats	VST3 · CLAP · LV2 · AU (macOS)
DAW	Any VST3 or CLAP host

Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Boost-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Boost.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Boost.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Boost.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Boost-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Boost.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Boost.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Boost.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Boost.lv2`	`/Library/Audio/Plug-Ins/LV2/`


The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Boost.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Boost-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.

Controls Reference



BOOST

Controls the drive into the saturation engine. Higher values push more harmonic content and add musical compression. The Spark Pill indicator shows the current harmonic activity level.

Range	Character
0 – 20 %	Transparent gain, subtle warmth
20 – 50 %	Natural harmonic enhancement — sweet spot for most signals
50 – 80 %	Noticeable saturation, aggressive presence
80 – 100 %	Heavy push, leads and solos

CHARACTER

Selects the tonal focus of the saturation engine:

Mode	Description
BALANCED	Flat character — enhances presence evenly across the spectrum
BRIGHT	High-frequency clarity shelf — adds edge and definition, ideal for single-coil pickups and clean tones
THICK	Low-mid weight shelf — fattens humbuckers and palm-muted riffs

MIX

Parallel blend between the dry signal (0 %) and fully processed signal (100 %). Use lower values (20–50 %) for New York–style parallel saturation — adds harmonic density while preserving the attack transients of the dry signal.

OUTPUT

Final output trim gain, range **−24 to +12 dB**. Use it to match perceived loudness after boosting, or to drive the next stage harder.

Activity Meter

Shows real-time input (top) and output (bottom) levels from **−60 to 0 dB**. The output band colour shifts toward the accent colour as harmonic content increases — giving a visual read of how hard the saturation is working.

Spark Pill

A harmonic activity indicator in the top-right of the meter section:

Label	Harmonic Amount
CLEAN	0 – 10 % — minimal saturation
LIFT	10 – 45 % — light harmonic enhancement
ALIVE	45 – 75 % — moderate saturation
PUSH	75 – 100 % — heavy drive

Signal Chain (Under the Hood)

```
Input
  → High-pass filter (35 Hz)     removes sub-bass mud before saturation
  → Clean gain stage             scales signal into saturation range
  → Tanh soft-clipping           adds even-order harmonics
  → 2nd-harmonic bias            warms the saturation character
  → Clarity / Mode shelf EQ      shapes tonal character (per MODE)
  → Auto make-up gain            compensates loudness
  → Output trim                  user-controlled OUTPUT knob
  → Dry/Wet blend                MIX knob
Output
```

Typical Use Cases

After a NAM amp sim

Place AtiNAMatiC-Boost on the channel after your Neural Amp Modeler. Use **BALANCED** mode at **40–60 % BOOST**, **MIX 100 %**, and trim OUTPUT to match the unprocessed loudness. This adds the "pushed amp" feel that neural captures sometimes lack.

Parallel saturation bus

Send multiple tracks to an auxiliary. Insert AtiNAMatiC-Boost with **MIX 20–40 %** and **BOOST 70 %** in **THICK** mode. Blend back to taste — adds glue and warmth without thickening transients.

Lead guitar presence boost

Use **BRIGHT** mode with **BOOST 60–80 %** and **MIX 60 %**. Keeps the dry attack while adding harmonic cut-through. Reduce OUTPUT by 2–4 dB to compensate loudness before automation.

Drum bus punch

BALANCED mode, **BOOST 30 %**, **MIX 30–50 %**. Adds body and snap without obvious saturation. Especially effective on room mics or overheads.

Tips

- The **35 Hz high-pass filter** is always active — this is intentional. Sub-bass energy in the saturation stage creates intermodulation distortion; removing it keeps the low end clean.
- Use **BOOST + low MIX** rather than **low BOOST + full MIX** when you want subtle enhancement — pushing the saturation stage harder and blending less gives richer harmonics at equal perceived loudness.

- For A/B comparison, set **MIX to 0 %** and trim **OUTPUT** until loudness matches, then gradually raise MIX.

About

AtiNAMatiC-Boost v1.0.0 Atij 666 Studio Designed & developed by Atij


Built with: - JUCE Framework — Raw Material Software Ltd. - VST3 SDK — Steinberg Media Technologies GmbH - CLAP SDK — Free Audio / clap-juce-extensions - Neural Amp Modeler (NAM) — Steven Atkinson & contributors - The open-source audio & guitar-plugin community

Thank you to everyone who makes open-source audio tools possible.

© 2026 Atij 666 Studio. All rights reserved.

AtiNAMatiC-Cab — User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

1. What it is

Many NAM captures are "amp only" (direct out, no cabinet): played straight they sound fizzy and harsh. Normally you'd load an impulse response. AtiNAMatiC-Cab is the one-knob alternative: a speaker cabinet voiced with filters, where the one knob moves the microphone across the speaker.

- Resonant low cut (the "thump" of a closed box), low-mid body, a slight mid scoop, two cone-breakup presence peaks (~2.5 kHz and ~4.5 kHz) and a steep speaker roll-off.
- **MIC** moves the mic from the dust cap (bright, forward) to the cone edge (darker, warmer). Measured on a cab-less amp: the fizz above 7 kHz is cut by about 11 dB at the cap and 29 dB at the edge.
- Loudness is matched automatically from the filter response (within about ±1.5 dB across the knob and cabinets).
- Zero latency, minimum phase, very light on CPU.

It is not an impulse-response loader and does not try to copy a specific cabinet; it is a fast, musical "cab" that is always in tune with the knob.

2. Signal chain placement

```
Guitar -> ... -> Amp sim (no cab) -> [AtiNAMatiC-Cab] -> Cohere / Air / Room
```

Use it **after** an amp capture that has no cabinet. Do not stack it after a cab/IR (you'd filter twice).

3. Controls

MIC POSITION (big knob, 0–100 %, default 35 %)

Position	Sound
0 % (CAP)	brightest, most forward, most presence
50 % (CONE)	balanced
100 % (EDGE)	darker, warmer, rounder low-mids

CABINET (mode switch)

Cabinet	Low cut / thump	Body	Character
1x12	105 Hz, soft	200 Hz	open-back combo: lighter, looser low end
2x12	85 Hz	160 Hz	balanced
4x12 (default)	75 Hz, resonant	140 Hz	closed-back stack: tight, deep thump

MIX (0–100 %) and OUTPUT (-24 to +12 dB)

Blend with the raw amp (for a little extra edge) and final trim.

4. Meters

- **INPUT / OUTPUT** — peak level.
- **BRIGHT** — where the mic is (100 % = on the cap).
- Status: **ON THE CAP**, **MID CONE**, **CONE EDGE**.

5. Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Cab-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Cab.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Cab.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Cab.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Cab-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Cab.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Cab.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Cab.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Cab.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Cab.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Cab-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.


6. Tips

- High gain: 4x12, MIC 30–50 %. Then **Cohere** if anything still bites.
- Clean / edge of breakup: 1x12, MIC 20–40 %.
- Double-click any knob to reset it; hold Shift while dragging for fine control.

AtiNAMatiC-Cab v1.0.0 · Atij 666 Studio

AtiNAMatiC-Choke — User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

1. What it is

Tight riffs live and die by how notes **stop**. A gate only removes the noise between notes; it can't make a ringing chord stop sooner. AtiNAMatiC-Choke works inside the note's own decay: once a note has fallen a little below its peak, Choke makes the rest of the decay fall faster. Stops get tighter, the riff gets more staccato, and the pick attack is never touched.

- Choke follows each note's own peak, so it works the same on quiet and loud passages (it is relative, not a fixed threshold).
- Every new pick attack restores full level instantly.
- The level detector holds for a full cycle of a low E, so it never rides the waveform: no distortion on low notes.
- Zero latency.

Measured on held notes (100 %): Tight cuts the late tail by about 17 dB, Staccato by about 37 dB, Djent chokes notes within ~0.3 s. Attacks: unchanged.

2. Signal chain placement

```
Guitar -> Gate -> [AtiNAMatiC-Choke] -> ... -> Amp sim          (tighter playing into the amp)
Amp sim -> Cab / IR -> [AtiNAMatiC-Choke]                        (shorter amp ring-out)
```

Both work. Before the amp it shapes how you play into it; after the amp it also shortens the amp's own sustain.

3. Controls

CHOKE (big knob, 0–100 %, default 40 %)

How fast the decay is pulled down once it starts. 0 % (RING) is a clean pass-through.

STYLE (mode switch)

Style	Starts cutting	Max ratio (100 %)	For
Tight	9 dB below the note peak	3.5 : 1	rhythm that should just sound "tight"
Staccato	6 dB below	5 : 1	short, stabbing riffs
Djent	3 dB below	8 : 1	machine-gun stops, chugs, metal breaks

MIX (0–100 %) and OUTPUT (-24 to +12 dB)

Blend with the dry signal (a little ring back in) and final trim.

4. Meters

- **INPUT / OUTPUT** — peak level.
- **CHOKE** — how much the decay is currently being cut, in dB.
- Status: **RINGING**, **TIGHTENING**, **CHOKED**.

5. Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Choke-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Choke.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Choke.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Choke.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Choke-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Choke.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Choke.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Choke.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Choke.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Choke.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Choke-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.

6. Tips

- Use **Gate** for the noise, Choke for the ring: Gate → Choke → amp is a very tight front end.
- On chord stabs, Staccato at 40–60 % plus Mix 80 % keeps a little natural ring.
- Double-click any knob to reset it; hold Shift while dragging for fine control.

AtiNAMatiC-Choke v1.0.0 · Atij 666 Studio

AtiNAMatiC-Cohere — User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

1. What it is

Amp sims, NAM captures especially, often carry a harsh **bite** around 3–4 kHz and a **fizz** around 6–9 kHz that jump out on some notes and chords and not others. A static EQ cut dulls every note to fix the few.

AtiNAMatiC-Cohere cuts those two bands **only while they stick out** compared with the guitar's own normal balance, then glues the result with a gentle compressor and a touch of tape-style saturation. The tone you dialled in stays; the moments that hurt get caught.

- Bite and fizz are detected in narrow bands and cut with smooth, wider filters: up to 9 dB (bite) and 12 dB (fizz) on the worst moments, almost nothing on normal playing.
- Measured on a test signal with fizz spikes: spikes cut by about 5 dB, the rest of the playing by under 1 dB.
- Glue compression and make-up are calibrated so the level stays put (within about ±0.7 dB).
- Zero latency.

2. Signal chain placement

```
Guitar -> ... -> Amp sim -> Cab / IR -> [AtiNAMatiC-Cohere] -> Air / Double / Squash / Level
```

Place Cohere **after** the amp and cab. It works on single tracks and on a guitar bus.

3. Controls

COHERE (big knob, 0–100 %, default 40 %)

One knob for all three stages. At 0 % (RAW) the signal is untouched. Turning it up lowers the margin a band must stick out by before it is cut (6 dB → 1 dB), deepens the glue compression and blends in the saturation.

CHARACTER (mode switch)

Character	Taming	Glue	Saturation	Top end
Smooth	strongest	light	very light	flat
Glue (default)	balanced	balanced	light	flat
Tape	lighter	strongest	most	-1.5 dB shelf above 9 kHz

MIX (0–100 %) and OUTPUT (-24 to +12 dB)

Parallel blend (phase-exact, no combing) and final trim.

4. Meters

- **OUTPUT** — peak level.

- **TAME** — how much bite/fizz is being cut right now (the larger of the two), in dB.
- **GLUE** — compressor gain reduction, in dB.
- Status: **SMOOTH** (nothing to tame), **TAMING**, **TAMING HARD**.

5. Signal chain (inside)

```
Input -> linked detectors: broadband, bite (3.5 kHz, Q 2.5), fizz (7.5 kHz, Q 3)
      -> each band's share vs its own 1.5 s average -> dynamic cuts (Q 1.4 / Q 1.2)
      -> glue: soft-knee RMS compressor (20 ms / 250 ms)
      -> tape-style saturation (blended) -> Tape shelf -> make-up -> MIX -> OUTPUT
```

6. Latency and CPU

Zero latency. Light on CPU.

7. Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Cohere-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Cohere.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Cohere.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Cohere.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Cohere-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Cohere.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Cohere.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Cohere.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Cohere.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Cohere.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Cohere-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.


8. Tips

- On a fizzy high-gain capture, start in Smooth at 40–60 %.
- On a guitar bus, Glue at 30–50 % before **Squash** or **Level** gives a more finished sound.
- Double-click any knob to reset it; hold Shift while dragging for fine control.

AtiNAMatiC-Cohere v1.0.0 · Atij 666 Studio

AtiNAMatiC-Dirt -- User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

What's new in v0.2.0

- **Steady loudness, clean at 0 %.** The drive is now -4 to +24 dB into a unity-slope shaper with curve-derived (static, pedal-style) loudness compensation. The old version jumped +5.7 dB at 0 % in CRUNCH and fell by up to 5 dB at 100 %.
- **4× oversampling** — aliasing at high DIRT was as loud as -12 dB below the note; it is now far lower. Adds **38 samples** of latency (≈0.8 ms at 48 kHz), reported to the host; MIX's dry path is delay-matched.
- Switching TYPE now crossfades the shapers (no click); DIRT, MIX and OUTPUT are all smoothed.
- **New interface** — machined knob with a printed 0–10 scale, hardware-style mode switches that follow automation and preset recall, consistent value text ("72 %", "+1.5 dB"), resizable window (75–150 %, remembered per session). Double-click any knob to reset it; hold **Shift** while dragging for fine adjustment.

---

1. What it is

AtiNAMatiC-Dirt is a pre-amp **character drive** stage designed to sit **before** your Neural Amp Modeler (NAM) amp model in the signal chain. It adds grit, edge, and harmonic texture without crossing into full distortion territory. Think of it as giving the amp model a "dirtier guitar" to work with -- attitude without destruction.

It is intentionally subtle by design. The wave-shaper is auto-normalised so loudness barely changes as DIRT increases, making it safe to dial in and out without level jumps.

Three flavours of breakup let you match the character to the style:

Type	Character
EDGE	Smooth tanh saturation -- warm, even-harmonic sheen
BITE	tanh + soft hard-clip ceiling -- sharper transient attack
CRUNCH	Double-tanh compression -- more squashed, fizzy upper grit

---

2. Signal chain placement

```
Guitar -> [AtiNAMatiC-Dirt] -> NAM Amp Model -> Cab / IR -> AtiNAMatiC-Air -> Master
```

Always place AtiNAMatiC-Dirt before the amp model / NAM. It voices itself for clean-to-crunch source material. Placing it after a fully-distorted amp sim will compound artefacts rather than enhance character.

---

3. The Controls

DIRT (large knob, centre)

The master drive macro. Sweeps from 0% (clean pass-through) to 100% (full harmonic grit). Internally this maps to -4 to +24 dB of drive into a 4× oversampled wave-shaper, with curve-derived loudness compensation so the output level stays steady across the entire sweep.

Most players live between **20% and 55%**. Above 70% the grit becomes deliberate and pronounced -- useful for high-gain styles feeding a clean NAM model.

TYPE (EDGE / BITE / CRUNCH)

Selects the saturation character (see table above). Each type also shifts the pre-emphasis frequency slightly to focus the grit where guitars project:

- **EDGE** focuses around 1.5 kHz -- the classic "woman tone" nasal body.
- **BITE** focuses a little higher -- attack and pick clarity.
- **CRUNCH** focuses upper-mids -- rasp and compression.

MIX (Wet/Dry)

0% = bypass, 100% = fully processed. Default 100%. Blend back the dry signal to add just a hint of grit without committing fully -- useful for studio tracking when the engineer wants flexibility.

OUTPUT (-24 to +12 dB)

Final trim after all processing. Even with auto make-up, different guitar pickups and amp models may need slight level matching here. Use it to match the bypassed level before committing to a setting.

Activity Meter

Real-time dual-bar meter showing input and output levels (-60 to 0 dBFS). As DIRT increases, the output bar transitions from blue-grey to the rust/ember accent colour, giving a visual reference for how much harmonic content is being added.

Grit Pill (top-right of meter area)

A LED-style indicator that names the current saturation character:

Label	Meaning
CLEAN	Negligible drive -- near-transparent output
GRIT	Subtle edge -- just kissing the shaper
BITE	Noticeable character -- harmonic texture
FANG	Heavy grit -- amp model will respond hard

4. System Requirements

	Minimum
OS	Windows 10 64-bit (or later)
CPU	Any x64 processor (SSE2)
RAM	32 MB
Formats	VST3, CLAP, LV2
DAW	Any VST3 or CLAP host (Reaper, Ableton, FL Studio, Bitwig, etc.)

Linux builds (VST3 + CLAP) available via `build-linux.sh`.

---

5. Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Dirt-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Dirt.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Dirt.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Dirt.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Dirt-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Dirt.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Dirt.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Dirt.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Dirt.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Dirt.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Dirt-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.

6. Controls Reference (Quick Summary)

Control	Range	Default	Description
DIRT	0 -- 100%	30%	Drive macro (pre-shaper gain)
TYPE	EDGE/BITE/CRUNCH	EDGE	Saturation character
MIX	0 -- 100%	100%	Dry/wet blend
OUTPUT	-24 to +12 dB	0 dB	Final output trim

7. Signal Chain (Internal)

```
Input
  --> HPF 40 Hz (sub tighten)
  --> Pre-emphasis peak (type-dependent, ~1.5 kHz)
  --> Drive gain (0 to +22 dB, driven by DIRT)
  --> Wave-shaper (EDGE / BITE / CRUNCH)
  --> De-emphasis (mirror of pre-emphasis)
  --> Post-tone tilt (gentle darkening as DIRT rises, prevents harshness)
  --> Auto make-up + OUTPUT trim
  --> Dry/wet MIX
Output
```

8. Typical Use Cases

Clean-ish NAM model, wants more life

- TYPE: EDGE, DIRT: 25-40%, MIX: 100%
- Adds warmth and even harmonics without obvious distortion.

High-gain rhythm -- wants attack and clarity

- TYPE: BITE, DIRT: 35-55%, MIX: 80-100%

- Sharpens pick attack, focuses the midrange before the amp model compresses it.

Lead tone -- compressed, singing grit

- TYPE: CRUNCH, DIRT: 45-65%, MIX: 70-100%
- Double-tanh compression smooths peaks and adds fizzy sustain harmonic content.

Subtle parallel blend

- Any type, DIRT: 50-80%, MIX: 20-40%
- Blends harmonic texture behind the dry signal -- adds "hair" without obvious effect.

---

9. Tips

- **Less is more.** At 30% DIRT even CRUNCH mode is subtle. Increase gradually and listen.
- **Stack with NAM.** AtiNAMatiC-Dirt is designed to excite the NAM model's input stage. Set NAM input gain lower when using high DIRT settings.
- **Use OUTPUT to null-test.** Set MIX to 0% and match levels with OUTPUT. Then raise MIX to hear exactly what Dirt is adding.
- **EDGE for chords, BITE for solos.** Type switching mid-song is valid -- automate it in your DAW.

---

10. About


AtiNAMatiC-Dirt is part of the **AtiNAMatiC Series** -- a suite of focused utility plug-ins built around the Neural Amp Modeler workflow.

- Designed & developed by **Atij** (Atij 666 Studio)
- Built with JUCE Framework (Raw Material Software Ltd.)
- VST3 SDK (Steinberg Media Technologies GmbH)
- Neural Amp Modeler -- Steven Atkinson & contributors
- CMake, MSVC, clap-juce-extensions, and the open-source audio community

Click the **AtiNAMatiC-Dirt** title badge in the plugin UI to open the About panel.

AtiNAMatiC-Double -- User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

What's new in v0.2.0

- **0 % is now true mono.** The doubled voices fade out below 15 %, so the MONO end no longer adds a centred, comb-filtered copy.
- Width changes are smoothed per sample (no zipper noise), the voices no longer glide in pitch for a few seconds after loading, and each voice has a slightly different tone so they read as two takes rather than two copies.
- **New interface** — machined knob with a printed 0–10 scale, hardware-style mode switches that follow automation and preset recall, consistent value text ("72 %", "+1.5 dB"), resizable window (75–150 %, remembered per session). Double-click any knob to reset it; hold **Shift** while dragging for fine adjustment.

---

1. What it is

AtiNAMatiC-Double is a **studio double-tracking simulator** designed to sit after your amp/cab simulator in the signal chain. It produces two virtual "performance" voices from a single take, panned to opposite sides, with independent slow random-walk pitch and timing drift -- giving the perceptual impression of two separate performances without any audible chorus artefacts or comb filtering.

Key design goals:

- **Never sounds like a chorus.** The modulation is a band-limited random walk updating roughly every 0.5--1.5 seconds per voice, not a sine LFO.
- **Mono-safe.** The dry signal is always blended back through the centre so a sum to mono cannot phase-cancel to silence.
- **Always outputs stereo** -- works from a mono or stereo input.
- **One macro.** The WIDTH knob controls delay spread, drift magnitude and pan amount simultaneously through a smooth S-curve so the "natural double" zone sits in the comfortable 30--60% range.

---

2. Signal chain placement

```
Guitar -> Amp Sim (NAM / Helix / etc.) -> Cab / IR -> [Reverb/Delay] -> * AtiNAMatiC-Double * -> Master
```

Place Double **after** cab/IR and any mono reverb/delay. It should be one of the last inserts before the master bus so the stereo image it creates is the final spatial statement of the track.

For parallel double-tracking (blend the "doubled" image under a dry lead):

```
Lead guitar (dry) ------->|
                          +-> Mix -> Master
Doubled send (AtiNAMatiC-Double, MIX 100%) -->|
```

---

3. Controls

WIDTH (large centre knob)

The master macro. Simultaneously scales: - **Base delay spread** -- 8/11/14 ms (voice A) and 14/19/26 ms (voice B) depending on Mode, all scaled further by WIDTH. - **Drift magnitude** -- how far each voice's pitch and timing wanders around its base delay. - **L/R pan amount** -- voice A pans left, voice B pans right; at WIDTH 100% voice A is hard left, voice B is hard right.

A live readout (e.g. "45 %") is displayed at the knob centre.

Tick labels below the knob:

Label	Range	Character
MONO	0--15%	Almost no separation; use as a subtle thickener
DOUBLE	15--70%	Natural double-tracking sweet spot
WIDE	70--100%	Deliberately wide, more dramatic stereo image

MODE (Tight / Loose / Wide)

Shapes the base delay times and maximum drift swing. Does **not** change the rate of the random walk -- all modes stay slow.

Mode	Voice A base	Voice B base	Drift swing	Max pan
Tight	8 ms	14 ms	1.2 ms	85%
Loose	11 ms	19 ms	2.0 ms	90%
Wide	14 ms	26 ms	2.8 ms	100%

- **Tight** -- studio close-mic double, very coherent, suits rhythm guitars and bass.
- **Loose** -- classic "two takes, different day" spread; the default for most uses.
- **Wide** -- maximum spread, almost M/S-like; good for leads and ambient textures.

MIX (0--100%)

Wet/dry balance. At 100% you hear the full doubled image with the dry centre blend baked in. Lower it to taste to keep a leaner dry sound under the image.

OUTPUT (-24 to +12 dB)

Final trim after all processing. The doubling can add perceived loudness; use this to level-match against your bypass.

4. Stereo Image panel

Located below the mode picker, the STEREO IMAGE panel gives real-time visual feedback:

Level bars (L / R) -- RMS dB bars from -60 dBFS to 0 dBFS with colour coding: - Cyan: normal signal - Amber: approaching 0 dB - Red: at or above 0 dB

Voice dot field -- a horizontal strip showing voice A (cyan dot, left-biased) and voice B (violet dot, right-biased). Both dots drift around their pan centres as the random walk updates, giving a live picture of the current stereo spread.

---

5. System requirements

Item	Minimum
OS	Windows 10 64-bit (or later)
CPU	Any modern x64 processor
RAM	64 MB per instance
Plugin formats	VST3, CLAP, LV2, AU on macOS (DAW)
Sample rates	44.1 / 48 / 88.2 / 96 / 176.4 / 192 kHz
Latency	Zero samples (no lookahead)
DAW	Any VST3- or CLAP-compatible host

---

6. Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Double-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Double.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Double.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Double.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.

- **Just this plug-in:** unzip `AtiNAMatiC-Double-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Double.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Double.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Double.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Double.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Double.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Double-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.

7. Controls reference

Control	Range	Default	Unit
WIDTH	0 -- 100	45	%
MODE	Tight/Loose/Wide	Tight	--
MIX	0 -- 100	100	%
OUTPUT	-24 -- +12	0	dB

8. Internal signal chain

```
 Input (mono or stereo)
   |
   v
[Mono sum (L+R)*0.5]
   |
   +-----> [Voice A delay line]  <-- slow random-walk drift (rate ~0.7-1.6 s)
   |            |  fractional-sample read tap
   |            v
   |       [Pan A: left-biased]
   |
   +-----> [Voice B delay line]  <-- independent random-walk drift (rate ~0.9-1.8 s)
   |            |  fractional-sample read tap
   |            v
   |       [Pan B: right-biased]
   |
   +-----> [Dry centre blend]  (always present, scales with WIDTH for mono safety)
   |
   v
[MIX crossfade with dry input]
   |
   v
[OUTPUT gain trim]
   |
   v
Stereo output
```

All delay taps use linear interpolation and a slewed read position (the slew itself creates the micro-pitch variation). There is no nonlinear processing and therefore no oversampling requirement.

---

9. Typical use cases

Rhythm guitars (hard double)

- WIDTH: 70%, MODE: Tight, MIX: 100%
  Tight base delays with hard pan give a classic "guitars left and right" image from one track.

Natural double (two-take feel)

- WIDTH: 45%, MODE: Loose, MIX: 100%
  The sweet spot -- sounds like two separate performances.

Subtle thickener (mono mix)

- WIDTH: 15%, MODE: Tight, MIX: 100%
  Very little separation; mainly adds density without obviously stereo-ising the track.

Wide lead guitar

- WIDTH: 60%, MODE: Wide, MIX: 80%
  Spread lead over the stereo field; back off MIX slightly to keep a centred anchor.

Parallel double-tracking

- Send a copy of the track to AtiNAMatiC-Double, WIDTH: 80%, MIX: 100%.
  Blend the return under the dry lead at -6 to -12 dB.

---

10. Tips

- **Start with MODE: Loose at WIDTH 40--50%** -- this is the most natural starting point for most tracks.
- **Watch the stereo image panel** -- if the voice dots drift too wide apart the image may collapse oddly on mono playback; bring WIDTH down until they sit within the centre 60% of the strip.
- **Automate WIDTH** for a build-up: start a verse at 30%, push to 60% in the chorus for a dramatic stereo expansion.
- **Do not use after reverb.** Applying double-tracking to a reverb tail causes audible smearing. Put reverb after Double, not before.
- **MIX at less than 100%** is useful when blending with a dry lead; this lets you keep a tight centre while still getting separation on the sides.
- **Output trim**: doubling two voices at 0.55 gain each adds roughly +1.5 dB perceived loudness at WIDTH 50%. Use OUTPUT -1.5 dB to level-match for A/B comparison.

---

11. About

AtiNAMatiC-Double is part of the **AtiNAMatiC Series** -- a family of focused, hardware-flavoured guitar tools for the modern post-amp signal chain.


- Design & development: **ATIJ** (Atij 666 Studio)
- Built with **JUCE 8** (juce.com)
- CLAP support via **clap-juce-extensions** (free-audio)
- Built with MSVC / CMake
- Thanks to the open-source community

Personal and commercial use permitted on machines you own. Bug reports and feature requests: click the **AtiNAMatiC-Double** title badge in the plug-in window to open the About screen.

AtiNAMatiC-Double -- Instant double tracking. No chorus. No comb.

AtiNAMatiC-Feel -- User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

What's new in v0.2.0

- **Actually tames pick spikes now.** The compressor uses a peak-hold detector with near-instant attack, so spikes come out smaller instead of larger (the old 3.5–18 ms attacks let the first half-millisecond of every attack through at full make-up gain). Still zero latency.
- **No more low-note distortion.** Both detectors used to ripple with the waveform on low notes (up to -22 dB THD on a low E); distortion is now below -60 dB.
- Make-up gain is now calibrated on DI guitar so the level stays within about ±1 dB across the ASSIST sweep; detection is stereo-linked (loudest channel).
- **New interface** — machined knob with a printed 0–10 scale, hardware-style mode switches that follow automation and preset recall, consistent value text ("72 %", "+1.5 dB"), resizable window (75–150 %, remembered per session). Double-click any knob to reset it; hold **Shift** while dragging for fine adjustment.

---

1. What it is

AtiNAMatiC-Feel is a **feel enhancer** designed to be placed *before* your amp sim. One large knob shapes how your raw pick attack and dynamics are transformed -- from completely transparent to deeply smoothed -- so you can stay focused on playing while the plug-in quietly makes everything respond better.

Under the hood it is a three-stage processing chain:

- **DC blocker (HPF @ 25 Hz)** -- removes subsonic rumble and DC offset so the compressor envelope is never confused by non-audio content.
- **Transient softener** -- a dual-envelope (1.5 ms fast / 20 ms slow attack, shared release) detector finds the exact spike of each pick attack and applies up to 5 dB of gentle duck, only during the initial milliseconds. Long sustain passes completely unaffected.
- **Feedforward soft-knee compressor (log-domain)** -- a single-sidechain stereo-coherent compressor with an auto-threshold that descends as ASSIST rises. Ratio and knee widen simultaneously, giving a smooth, consistent squeeze rather than sudden gain clamps. Stereo image is preserved because both channels share the same gain envelope from the left/right detection chain.
- **Auto make-up gain** -- static, calibrated on DI guitar (gain reduction at a -4.5 dBFS peak reference), so the output stays within about ±1 dB across the full ASSIST sweep.

Zero latency. No lookahead. No oversampling. Behaves identically to an analogue insert in front of your amp sim.

---

2. Signal chain placement

```
Guitar  -->  *** AtiNAMatiC-Feel ***  -->  Amp Sim (NAM / Helix / ML / etc.)  -->  Cab / IR
                                                                                    -->
AtiNAMatiC-Air / Reverb / Master
```

Place Feel **directly before your amp sim**, as the first insert in the chain. This is where it has the most impact -- it shapes the raw pick dynamics before the amp's own non-linearity acts on them.

Not recommended after the cab/IR or in a parallel reverb return -- the transient softener and compressor are tuned for unprocessed guitar signal.

---

3. Controls

ASSIST (large centre knob, 0 -- 100%)

The single master macro. Everything is driven by this one control:

ASSIST value	Threshold	Ratio	Knee	Transient softening	Resulting character
0% (RAW)	off	1:1	--	none	fully transparent
35% (default)	~-22 dB	~1.7:1	6 dB	moderate	comfortable, slightly rounded
65% (FEEL)	~-29 dB	~2.3:1	6 dB	substantial	noticeably smoother, forgiving
100% (PILLOW)	~-34 dB	3:1	6 dB	maximum	very compressed, very smooth

The ASSIST pill (bottom-right of the meter panel) shows a label describing the current character: **RAW**, **EASE**, **FEEL**, **SMOOTH**, or **PILLOW**. A teal LED glows brighter as active softening increases.

Tick marks below the knob label the three anchor points: **RAW** (0%), **FEEL** (50%), and **SMOOTH** (100%).

MODE (three-position selector)

Shapes the character of both the transient softener and compressor:

Mode	Comp attack	Comp release	Max ratio	Transient cut	Best for
Tight	near-instant	90 ms	2.5:1	minimal (×0.25)	Articulate playing where you want punch preserved. Palm mutes stay tight and percussive.
Even (default)	near-instant	130 ms	3:1	moderate (×0.6)	Balanced response that works for most styles -- rhythm and lead alike.
Smooth	~0.1 ms	220 ms	4:1	maximum (×1.0)	Heavy softening for laid-back playing, heavily distorted tones, or when you want everything to feel effortless.

OUTPUT (-24 to +12 dB, default 0 dB)

Master output level after all processing. Use it to match the level of the next plug-in in the chain or compensate for any perceived loudness change. The value is displayed inside the knob's text box.

---

4. Activity meter and pill

Meter panel (ACTIVITY section)

Three horizontal bars show real-time processing status:

Bar	What it shows
INPUT	Peak level entering the plug-in (post DC blocker)
GR (narrow strip)	Gain reduction in dB, filling right-to-left (up to 12 dB range). Teal colour.
OUTPUT	Peak level after all processing. Colour shifts from grey toward teal as the transient softener becomes active.

The dB scale below the meter runs from -60 dB to 0 dB.

FeelPill (bottom-right of the meter row)

A small LED indicator that shows the current processing character and activity:

Label	ASSIST range	Meaning
RAW	0 -- 5%	No processing
EASE	5 -- 30%	Light touch
FEEL	30 -- 65%	Comfortable zone
SMOOTH	65 -- 90%	Strong smoothing
PILLOW	90 -- 100%	Maximum softening

The teal LED brightens proportionally to how much transient softening is currently active. A fast pick on a bright-sounding string will flash the LED; long sustain will keep it dim even at high ASSIST.

---

5. Quick-start settings

Everyday rhythm (feels like a great pick)

- MODE: Even -- ASSIST: 35% -- OUTPUT: 0 dB

Heavy rhythm, lots of palm mutes (tight but forgiving)

- MODE: Tight -- ASSIST: 50% -- OUTPUT: 0 dB

Single-note leads (fluid, consistent sustain)

- MODE: Smooth -- ASSIST: 45% -- OUTPUT: 0 dB

Very aggressive high-gain (tame the harshest attack without killing punch)

- MODE: Tight -- ASSIST: 30% -- OUTPUT: 0 dB

Effortless practice (maximum comfort, nothing hurts)

- MODE: Smooth -- ASSIST: 75% -- OUTPUT: 0 dB

---

6. Latency

AtiNAMatiC-Feel introduces **zero latency** at any sample rate.

No lookahead buffer, no oversampling delay, no latency compensation needed. The plug-in reports 0 samples of latency to the host. Your signal is processed in real time, sample by sample.

---

7. System requirements

	Windows	macOS	Linux
OS	Windows 10 / 11 (64-bit)	macOS 10.15 Catalina or later	Ubuntu 20.04+ / equivalent
Formats	VST3, CLAP, LV2	VST3, AU, CLAP, LV2	VST3, CLAP, LV2
CPU	x86-64	Apple Silicon (arm64) or Intel x86-64	x86-64
RAM	4 GB minimum	4 GB minimum	4 GB minimum
Sample rates	44.1 -- 192 kHz	44.1 -- 192 kHz	44.1 -- 192 kHz

---

8. Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Feel-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Feel.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Feel.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Feel.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Feel-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Feel.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Feel.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Feel.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Feel.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Feel.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Feel-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.

9. Controls reference

Control	Range	Default	Description
ASSIST	0 -- 100%	35%	Master macro. Controls compression threshold, ratio, knee, and transient softening simultaneously.
MODE	Tight / Even / Smooth	Even	Selects attack/release time constants and transient-cut intensity.
OUTPUT	-24 to +12 dB	0 dB	Master output level after all processing.

10. Internal signal chain

Each audio channel passes through the following stages, in order, every sample:

```
Input
  └─ DC blocker (SVF high-pass, 25 Hz, Q = 0.5)
       └─ Transient softener
            • Fast envelope follower  (τ ≈ 1.5 ms)
            • Slow envelope follower  (τ ≈ 30 ms)
            • Overshoot ratio  =  (fast − slow) / slow   [clamped 0..1]
            • Transient duck   =  −overshoot × ASSIST × mode_scale × 4 dB  [applied as linear gain]
                 └─ Feedforward soft-knee compressor (log domain, per channel,
                    sidechain from Ch0 for stereo coherence)
                         • Threshold = map(ASSIST, 0→1, −10 dB → mode_floor_dB)
                         • Ratio     = 1 + ASSIST × (mode_ratioMax − 1)
                         • Knee      = mode_kneeDb  (soft, applied at ±knee/2 around threshold)
                         • Envelope  = attack when GR increases, release when GR decreases
                              └─ Auto make-up gain  (static GR at −4.5 dBFS peak reference)
                                   └─ OUTPUT trim
Output
```

The compressor's gain envelope is **shared across all channels** (computed from Ch0, applied everywhere), preserving the stereo image. The DC blocker processes each channel independently.

---

11. Typical use cases

Before a NAM amp model

Place Feel as the very first insert before NAM. Set MODE to Even and ASSIST to 30--50%. NAM responds to the dynamics you feed it -- softening the pick transient slightly lets NAM breathe more consistently and removes the harshness that aggressive picking sometimes adds at the amp input stage.

Before a high-gain amp sim (Helix, Neural DSP, etc.)

High-gain amps amplify both your playing and your inconsistencies. Feel at 40--55% ASSIST (Even or Tight mode) smooths out the pick strength variance so the amp responds like you're always in the sweet spot.

Comfort playing / practice

When you want everything to feel effortless -- long sessions, sight-reading, or getting ideas down fast -- set MODE to Smooth and ASSIST to 60--80%. The softener takes the edge off harsh attacks and the compressor keeps dynamics forgiving, so you can focus entirely on the music.

Tracking a lead tone

Leads need consistent sustain without choking the note. Even mode at 45% ASSIST keeps the attack articulate (not squashed) while gently lifting the sustain tail and rounding any sharp pick click.

---

12. Tips

- **Start at the default**: MODE Even, ASSIST 35%. This is the calibrated "comfortable" position -- subtle enough that you might not notice it's there, but remove it and you'll miss it.
- **Tight mode for palm mutes**: Tight's short release (80 ms) lets each muted chunk pop distinctly, while still taking the edge off the attack. Great for metal rhythm.
- **Smooth mode for cleans**: On a clean amp, Smooth at 50% ASSIST creates a compressor-pedal-like bloom that suits fingerpicking or chord comping.
- **OUTPUT for gain staging**: If your amp sim or next plug-in is sensitive to input level, use OUTPUT to match unity. Feel's auto make-up covers most of the static GR but you may want a nudge up or down.
- **FeelPill flashing on every pick**: Normal -- it is showing the transient softener firing. If the LED stays bright continuously even between notes, you may have a very hot input signal; lower OUTPUT or the gain into the plug-in.
- **Zero latency means zero offset**: Feel introduces no delay, so no PDC adjustment or manual sample offset is ever needed.

---

13. About

AtiNAMatiC-Feel is part of the AtiNAMatiC series by **Atij 666 Studio** -- a collection of guitar-focused plug-ins built around a single principle: one knob that does the right thing.

Built with: - JUCE -- Raw Material Software Ltd. - VST3 SDK -- Steinberg Media Technologies GmbH - clap-juce-extensions -- Free Audio - Neural Amp Modeler (NAM) -- Steven Atkinson & contributors

Thank you to everyone who makes open-source audio tools possible.

AtiNAMatiC-Feel v1.0.0 · Atij 666 Studio · 2026

AtiNAMatiC-Gate -- User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

What's new in v0.2.0

- **ADAPTIVE now adapts in every case.** The noise-floor tracker could only learn while the gate was closed — so if the noise itself held the gate open from the start, Adaptive never raised the threshold. It now also learns from anything quieter than -50 dBFS.
- **New interface** — machined knob with a printed 0–10 scale, hardware-style mode switches that follow automation and preset recall, consistent value text ("72 %", "+1.5 dB"), resizable window (75–150 %, remembered per session). Double-click any knob to reset it; hold **Shift** while dragging for fine adjustment.

---

1. What it is

AtiNAMatiC-Gate is a **professional noise gate** built specifically for high-gain guitar. One large knob controls everything -- from threshold and hysteresis to hold time and aggressiveness -- so you stay focused on playing instead of tweaking.

Under the hood it is a full pro-grade gate engine:

- **Sidechain HPF at 90 Hz** -- low-end rumble and hum cannot false-trigger the gate.
- **Dual-time-constant detector** -- a fast peak follower catches transients; a slow RMS follower tracks sustain. Both feed the same decision circuit.
- **Hysteresis (open/close gap)** -- the close threshold is always lower than the open threshold, so the gate never chatters at the boundary.
- **Adaptive noise-floor tracking** -- in Adaptive mode the open threshold automatically lifts 10 dB above the measured noise floor, so a warming amp stays gated even as it heats up.
- **Hold time** -- after the signal falls below the close threshold the gate stays fully open for a short hold period, eliminating end-of-note chatter on palm mutes.
- **Asymmetric attack/release with cubic easing** -- smooth, click-free transitions that do not add audible artifacts.
- **3 ms audio lookahead** -- the gate opens *before* the transient arrives, so it never chops a pick attack even at the Tightest setting.
- **Soft attenuation floor (-65 dB)** -- the gate attenuates instead of hard-muting, so bleed and amp hiss fade out rather than snapping off.

---

2. Signal chain placement

```
Guitar  -->  Amp Sim (NAM / Helix / ML Sound Lab / etc.)  -->  Cab / IR
         -->  *** AtiNAMatiC-Gate ***  -->  AtiNAMatiC-Air / Reverb / Master
```

Place the gate **directly after your amp sim / cab IR**, before any time-based effects. Gating after reverb or delay cuts the tail; gating before the amp sim may change the amp's natural compression and feel.

For a parallel rig (wet/dry/wet), insert the gate on each dry cab channel individually.

3. Controls

GATE (large centre knob, 0 -- 100%)

The single master macro. As you turn it clockwise:

GATE value	Open threshold	Hysteresis gap	Hold time	Aggressiveness
0% (OPEN)	-78 dB	4 dB	longest	gentlest
50%	-50 dB	6 dB	medium	moderate
100% (TIGHT)	-22 dB	8 dB	shortest	tightest

Start at 35--50% for most high-gain situations. Increase until the noise between notes disappears. Decrease if the gate is chopping pick attacks or cutting note tails.

The current value is shown as a percentage in the label directly below the knob. Tick marks label the three key positions: **OPEN**, **TRACKING**, and **TIGHT**.

MODE (three-position selector)

Chooses the time constants used by the gate engine:

Mode	Attack	Release	Hold base	Best for
Adaptive (default)	1.5 ms	90 ms	60 ms	Most situations. Threshold follows the noise floor automatically.
Fast	0.4 ms	25 ms	20 ms	Tight metal / djent riffs where you need near-instant gating between fast palm-mute chops.
Natural	2.5 ms	260 ms	120 ms	Clean or lightly driven tones, leads, and any source where you want the gate to breathe.

Hold time scales down with the GATE knob in all modes: the tighter the gate, the shorter the hold.

MIX (0 -- 100%, default 100%)

Dry/wet blend. At 100% only the gated signal is heard. Lower MIX blends in the original dry signal in parallel, useful if you want just a hint of noise reduction without touching the note tails. Default 100%.

OUTPUT (-24 to +12 dB, default 0 dB)

Master output level after gating. Use it to compensate for level differences between gate-open and gate-closed moments in a mix, or simply to match the level of an adjacent track. The value is displayed inside the knob's text box.

ACTIVITY meter (centre panel)

Two horizontal bars showing real-time signal status:

Bar	What it shows
INPUT	Peak level of the signal entering the gate (after the lookahead buffer)
THRESHOLD	The current open threshold -- moves in Adaptive mode as the noise floor is tracked

The dB scale below the meter runs from -60 dB to 0 dB.

State pill (bottom centre, below the meter)

A three-state indicator showing the gate's current condition:

Pill label	Meaning
CLOSED	Gate is attenuating (-65 dB floor applied)
OPEN	Gate is fully open, passing signal at unity
(transitioning)	Gate is in attack or release phase (pill fades between states)

---

4. Quick-start settings

General high-gain rhythm

- MODE: Adaptive -- GATE: 45% -- MIX: 100% -- OUTPUT: 0 dB

Tight djent / metal (fast riffs)

- MODE: Fast -- GATE: 65% -- MIX: 100% -- OUTPUT: 0 dB

Noisy vintage amp (hum reduction)

- MODE: Adaptive -- GATE: 30% -- MIX: 100% -- OUTPUT: 0 dB *(Low GATE keeps threshold below the amp's harmonic floor so sustain is not affected.)*

Lead / single-note lines

- MODE: Natural -- GATE: 35% -- MIX: 100% -- OUTPUT: 0 dB

Parallel blend (keep natural tails)

- MODE: Adaptive -- GATE: 60% -- MIX: 60% -- OUTPUT: 0 dB *(Gated signal blended with 40% dry preserves the natural decay while cutting most noise.)*

---

5. Latency

AtiNAMatiC-Gate introduces exactly **3 ms of lookahead latency** at any sample rate.

This latency is **reported to your DAW** via the standard plug-in latency API, so PDC (Plugin Delay Compensation) is applied automatically -- your gated channel stays phase-aligned with every other track with no manual offset required.

At 44.1 kHz the lookahead is 132 samples. At 48 kHz it is 144 samples. At 96 kHz it is 288 samples.

---

6. System requirements

	Windows	macOS	Linux
OS	Windows 10 / 11 (64-bit)	macOS 10.15 Catalina or later	Ubuntu 20.04+ / equivalent
Formats	VST3, CLAP, LV2	VST3, AU, CLAP, LV2	VST3, CLAP, LV2
CPU	x86-64	Apple Silicon (arm64) or Intel x86-64	x86-64
RAM	4 GB minimum	4 GB minimum	4 GB minimum
Sample rates	44.1 -- 192 kHz	44.1 -- 192 kHz	44.1 -- 192 kHz

---

7. Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Gate-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Gate.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Gate.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Gate.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Gate-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Gate.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Gate.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Gate.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Gate.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Gate.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Gate-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.

8. Controls reference

Control	Range	Default	Description
GATE	0 -- 100%	35%	Master macro. Controls threshold (-78 to -22 dB), hysteresis (4--8 dB), hold time, and aggressiveness.
MODE	Adaptive / Fast / Natural	Adaptive	Selects the time constants for attack, release, and hold.
MIX	0 -- 100%	100%	Dry/wet parallel blend.
OUTPUT	-24 to +12 dB	0 dB	Master output level after gating.

---

9. Internal signal chain

```
Input
  |
  +-- [Sidechain copy] --> HPF @ 90 Hz --> Peak follower + RMS detector
  |                                                  |
  |                                Adaptive noise floor tracker
  |                                                  |
  |                                Gate decision (open / hold / close)
  |                                                  |
  |                                Attack / release with cubic easing
  |                                                  |
  +-- [3 ms lookahead delay] ----------> Gain apply (floor: -65 dB)
                                                     |
                                           MIX (parallel blend with dry)
                                                     |
                                           OUTPUT gain
                                                     |
                                             Output
```

The sidechain path is always mono (left channel only for stereo signals) so the gate decision is consistent regardless of stereo phase differences. The gain is applied identically to all output channels.

---

10. Typical use cases

Rhythm guitar (high gain) Insert after your amp sim / cab IR. Set MODE: Adaptive, GATE: 45%. The gate silences hum and hiss between riffs while the 3 ms lookahead ensures no pick attack is ever lost. Hold time keeps notes from choking on faster riffs.

Lead guitar Set MODE: Natural, GATE: 30--40%. The longer release (260 ms) preserves sustain and lets vibrato notes decay naturally. MIX at 100%. Lower GATE if the gate is audibly squeezing the end of long bends.

Drop-tuned / djent (very fast riffs) Set MODE: Fast, GATE: 60--75%. The 0.4 ms attack is near-instant. If the gate is still letting a tiny burst of pre-note hiss through, increase GATE by 5--10%.

Vintage amp hum Set MODE: Adaptive, GATE: 25--35%. Adaptive mode tracks the hum floor and parks the threshold just above it, so the gate closes as tightly as needed without needing manual threshold adjustment when the amp warms up.

Parallel noise reduction Set MIX: 40--70%. This blends gated and dry signals together. The noise is reduced without completely removing the natural tail of each note. Works well on clean or lightly crunch tones where hard gating sounds unnatural.

---

11. Tips

- **If pick attacks are still being clipped:** lower GATE toward 30%. The threshold may be too high, closing the gate before the pick fully arrives in the lookahead window. Alternatively, check that the gate is after the amp sim (not before) -- amp sims compress the transient which can confuse the detector.
- **If hiss bleeds through between notes:** raise GATE toward 60%. Also check MODE is not set to Natural (long release lets more noise through at the tail of each note).
- **Use GATE + MIX together for parallel gating:** GATE at 70%, MIX at 50% is a common starting point. The gated copy removes most noise while the 50% dry blend preserves natural feel.
- **Adaptive mode with a cold amp:** if your amp sim's noise floor changes as the session warms up, Adaptive tracks it automatically. You rarely need to touch the GATE knob between takes.
- **Automation:** all four parameters (GATE, MODE, MIX, OUTPUT) are fully automatable in any DAW. MODE changes are per-block, so automate it only at section boundaries to avoid audible clicks.
- **3 ms latency:** at 44.1 kHz this is 132 samples -- easily absorbed by any modern DAW with PDC enabled. If you are routing to external hardware, offset your hardware outputs by the same amount.

---

12. About

- Design & development: **Atij** (Atij 666 Studio)
- Built with **JUCE 8** (juce.com)
- DSP inspired by the professional gate designs found in classic hardware units
- Neural Amp Modeler (NAM) by **Steven Atkinson** (the amp sims this gate was built to complement)
- Thank you to the open-source audio and guitar-plugin community

---


13. License & support

Personal and commercial use permitted on machines you own. Bug reports and feature requests: click the **AtiNAMatiC-Gate** title badge in the plug-in window to open the About dialog.

AtiNAMatiC-Gate is part of the AtiNAMatiC Series -- a family of focused, hardware-flavoured guitar tools for the modern post-amp signal chain.

AtiNAMatiC-HitZone — User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

What's new in v0.2.0

- **Auto gain fixed.** The auto loop compared the *input* level with the target and kept adding the same error every block, so it ran to the ±24 dB limit instead of settling. It now regulates the level *after* its gain, settles on the -16 dBFS RMS target, and holds its gain through silence instead of winding up between phrases.
- **Peak protection.** A loud hit after a quiet passage is caught instantly (block-peak ceiling + near-instant gain drop), with a smooth safety knee above -3 dBFS in Auto mode.
- The status label and meter now show the level *going into your amp* (after HitZone's gain), which is what "in the zone" means. The SWEET SPOT tone shelves now reach their setting immediately (they used to take tens of seconds).
- **New interface** — machined knob with a printed 0–10 scale, hardware-style mode switches that follow automation and preset recall, consistent value text ("72 %", "+1.5 dB"), resizable window (75–150 %, remembered per session). Double-click any knob to reset it; hold **Shift** while dragging for fine adjustment.

---

1. What it is

AtiNAMatiC-HitZone is an intelligent input-level conditioner designed to sit **before** Neural Amp Modeler (NAM) plugins in your signal chain. Its job is simple and critical: make sure the signal hitting your NAM model is always at the exact level those models were trained at.

NAM models are typically captured with peaks around –18 dBFS and an RMS around **–16 dBFS**. Feed them too quietly and the amp sim sounds dull, thin, and lifeless. Feed them too loud and they compress, clip, or distort in unpleasant, unintended ways. HitZone watches your input level in real time, adjusts gain automatically, and tells you in plain language: **Too Cold**, **Perfect**, or **Too Hot**.

Beyond gain management, the **Sweet Spot** macro tunes the tonal character of the conditioned signal — from bright and tight (COLD side) to warm and driven (HOT side) — using gentle EQ shelves and a touch of asymmetric tube-style saturation.

In short: AtiNAMatiC-HitZone takes the guesswork out of driving NAM correctly.

---

2. Signal chain placement

```
Guitar → ★ AtiNAMatiC-HitZone ★ → NAM Plugin → Cab / IR → Post-FX → Master
```

Always place HitZone directly before your NAM model, never after it. The level meter and auto-gain are calibrated to NAM's training level. Placing it after NAM has no benefit and may introduce unwanted colouration.

If you use a noise gate, place it **before** HitZone so the gate's closed state does not confuse the auto-gain with near-silence readings.

---

3. The Controls

SWEET SPOT (large central knob)

The master macro knob. Turning it from COLD to HOT simultaneously adjusts:

- **Tonal EQ** — COLD side lifts 4.5 kHz (+2 dB high shelf) and slightly cuts 180 Hz (–2 dB low shelf) for a bright, present character. HOT side does the opposite: +3 dB warmth at 180 Hz and –2.5 dB at 4.5 kHz for a thick, vintage feel.
- **Saturation** — below centre the signal is clean; above centre a gentle asymmetric tube-style soft-clip (2nd-harmonic bias) blends in progressively, reaching full drive at the HOT extreme.

Most players find their sweet spot somewhere between 35 % and 65 %. Highly distorted amp models benefit from the COLD side (keeps things tight); cleaner and crunch models often respond well to the HOT side.

Default: 50 % (centre — flat EQ, no saturation)
Double-click to reset to default.

AUTO (toggle, centre)

Enables real-time automatic gain adjustment.

State	Behaviour
ON (default)	HitZone continuously monitors RMS level and applies up to ±24 dB of gain to keep your signal in the sweet zone (–20 to –12 dBFS, ideal –16 dBFS).
OFF	Auto-gain is disabled. The **GAIN** knob (replaces RESPONSE in the bottom row) lets you dial in a fixed input gain manually.

Auto mode uses an **asymmetric tracking algorithm**: it pulls gain down quickly when the signal is too hot (to protect the NAM model from clipping), but brings gain up slowly when too cold (to avoid level-pumping on transients and note attacks).

RESPONSE (bottom row, centre — when AUTO is ON)

Controls how fast the automatic gain tracks changes in input level.

Position	Up speed	Down speed
0 % (Slow)	~1.5 dB/sec	~6 dB/sec
50 % (default)	~6 dB/sec	~16 dB/sec
100 % (Fast)	~18 dB/sec	~60 dB/sec

Slow response is natural and transparent — good for playing through full songs. Fast response is useful when switching between quiet clean passages and high-gain riffs in the same session.

A **safety stomp** is always active regardless of Response: if the peak level approaches –3 dBFS (dangerously close to clipping the NAM model), the gain is pulled down at the fastest available rate immediately.

Default: 35 %
Double-click to reset to default.

GAIN (bottom row, centre — when AUTO is OFF)

Fixed input gain trim. Range: –24 dB to +24 dB, default 0 dB.

Use this when you want total manual control — for example when recording automation, when your DAW chain already includes level management, or when tracking the gain for a specific guitar/pickup combination.

The **Gain Readout** (small number to the right of the status label) shows the currently applied gain in dB — in Auto mode this reflects the live auto-gain value; in Manual mode it reflects the GAIN knob.

Double-click to reset to 0 dB.

MIX (bottom row, left)

Wet/Dry blend. 0 % = fully dry (bypassed), 100 % = fully processed.

At values below 100 % the processed and original signals are summed. This is useful for parallel-processing workflows: run HitZone at 100 % for the NAM chain and blend in a small amount of unprocessed signal for transient clarity.

Default: 100 %
Double-click to reset to 100 %.

OUTPUT (bottom row, right)

Final output level trim, applied after all processing. Range: –24 dB to +24 dB, default 0 dB.

Use this to compensate for any net level change introduced by the EQ shelves or saturation, or to match levels between HitZone on/off.

Double-click to reset to 0 dB.

---

4. Status indicators

Status label (centre of UI)

Displays the current input-level state in real time, updated at 20 Hz:

Label	Meaning	What to do
Too Cold (blue)	RMS below –21 dBFS — signal is too quiet for NAM	Increase gain at source, or turn up GAIN knob (manual mode)
Perfect (green)	RMS between –21 and –11 dBFS — NAM sweet zone	Nothing — you're in the zone
Too Hot (orange/red)	RMS above –11 dBFS — signal risks clipping the NAM model	Reduce gain at source, or use AUTO

Status uses hysteresis to prevent rapid flickering at zone boundaries: the indicator does not switch back to Perfect until the signal has moved 0.5–1 dB clear of the threshold.

In **AUTO** mode, HitZone drives itself to maintain "Perfect" status. The label may briefly show Too Cold or Too Hot during fast transient changes.

Gain Readout (small number, right of status)

Shows the currently applied input gain in dB (up to one decimal place). In AUTO mode this is the live auto-gain value; in MANUAL mode it mirrors the GAIN knob. Useful for setting a fixed trim: switch AUTO off, watch the readout until it stabilises in manual mode, then use that value as your GAIN knob reference.

Level Meter

A horizontal RMS level meter spanning the COLD–HOT range, positioned between the Sweet Spot knob and the status row.

Element	Meaning
Shaded band	Sweet zone (–20 to –12 dBFS) — target region
Filled bar	Live RMS level
Peak indicator	Short-term peak envelope
Peak-hold dot	Holds the highest peak seen, decays slowly (1.5 s)

The COLD and HOT labels at the left and right of the knob area indicate the tonal character of the Sweet Spot position, **not** the current level status. Level status is indicated by the status label.

---

5. System requirements

	Minimum
OS	Windows 10 (64-bit) or later
CPU	Any modern x86-64 processor
RAM	4 MB per instance
DAW	Any VST3-compatible host (64-bit), or CLAP-compatible host
Sample rates	44.1, 48, 88.2, 96, 176.4, 192 kHz
Buffer sizes	Any (zero-latency processing)

6. Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-HitZone-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-HitZone.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-HitZone.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-HitZone.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-HitZone-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-HitZone.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-HitZone.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-HitZone.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-HitZone.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-HitZone.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-HitZone-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.

7. Controls reference

Control	Range	Default	Description
Sweet Spot	0–100 %	50 %	Tonal character + saturation macro (COLD = bright/clean, HOT = warm/driven)
AUTO	On/Off	On	Enables RMS-based automatic input gain
Response	0–100 %	35 %	Auto-gain tracking speed (visible when AUTO is ON)
Gain	–24 to +24 dB	0 dB	Fixed manual input gain (visible when AUTO is OFF)
Mix	0–100 %	100 %	Wet/Dry blend
Output	–24 to +24 dB	0 dB	Final output level trim

All knobs support **double-click to reset to default**.

8. Internal signal chain

```
 Input
   │
   ├──► [Dry copy for parallel Mix]
   │
   ▼
[Pre-detector HPF @ 35 Hz]  ← prevents subsonic bias in RMS reading
   │
   ▼
[RMS detector]  (60 ms attack / 250 ms release)
[Peak detector] (instant attack / 600 ms release)
[Peak-hold]     (holds, then 1.5 s decay)
   │
   ▼
[Auto-gain / Manual-gain decision]
   → status → UI: Too Cold / Perfect / Too Hot
   │
   ▼
[Input gain (smoothed 30 ms)]
   │
   ▼
[Tilt EQ]
   ├─ Low shelf @ 180 Hz: −2 to +3 dB (Sweet Spot left → right)
   └─ High shelf @ 4.5 kHz: +2 to −2.5 dB (Sweet Spot left → right)
   │
   ▼
[Asymmetric soft saturation]  ← only above 50 % Sweet Spot
   (2nd-harmonic bias, tube-style, blends in progressively)
   │
   ▼
[Output gain (smoothed 20 ms)]
   │
   ▼
[Parallel Mix with dry copy]  (smoothed 20 ms)
   │
   ▼
Output  →  NAM Plugin
```

9. Typical use cases

Standard NAM rig (recommended starting point)

- AUTO: **On** · Sweet Spot: **50 %** · Response: **35 %** · Mix: **100 %** · Output: **0 dB**

Set it and forget it. HitZone centres your signal in NAM's sweet zone and Status will read "Perfect" within a few seconds of playing.

High-gain / tight riff work

- AUTO: **On** · Sweet Spot: **25 %** (COLD side) · Response: **70 %** · Mix: **100 %** · Output: **0 dB**

The COLD tonal character (slight high-shelf lift) keeps chug tight and articulate. Fast Response prevents any level softening between palm mutes.

Clean / crunch with vintage warmth

- AUTO: **On** · Sweet Spot: **70 %** (HOT side) · Response: **30 %** · Mix: **100 %** · Output: **–1 dB**

The HOT tonal character adds low-mid weight and a hint of tube saturation that sits well under cleaner NAM models. Slow Response avoids pumping on sustained notes.

Fixed gain (recording / automation)

- AUTO: **Off** · Gain: set by ear until Status reads "Perfect" · Mix: **100 %** · Output: **0 dB**

Useful when you need a locked gain value — for instance, when recording automation lanes or when your interface's preamp level is already dialled for NAM.

Parallel blend

- AUTO: **On** · Mix: **40–60 %** · Output: **0 dB**

Blends HitZone's conditioned signal with the raw dry signal. Adds level intelligence and tonal shaping while preserving pick attack from the unprocessed chain.

---

10. Tips

- **Start with AUTO ON at 50 % Sweet Spot.** HitZone will normalise most guitars to Perfect within 2–3 seconds of playing. Adjust Sweet Spot from there to taste.
- **Watch the Gain Readout.** If AUTO consistently applies more than ±10 dB, your source level is significantly off NAM's ideal. Consider adjusting at the source (DI level, track fader) so HitZone has less work to do.

- **The safety stomp is always on.** Even in Manual mode, the auto system's peak-danger check does not apply — but the status indicator still tells you when you're Too Hot. Trust it.
- **Use COLD for metal, HOT for blues.** The tonal presets are subtle but stack up across a full mix. High-gain drop-tuned riffs sound tighter on the COLD side; single-coil and P-90 players often prefer the HOT side's extra body.
- **Response at 100 % can pump.** Very fast tracking on signals with wide dynamic range (fingerpicking, clean arpeggios) can audibly breathe. Keep Response below 60 % for expressive playing.
- **Zero latency.** HitZone adds no latency — suitable for monitoring through your DAW without buffer compensation.

---

11. About

AtiNAMatiC-HitZone — Always Hit the Perfect Level

Designed and developed by **Atij** · Atij 666 Studio


Built with: - JUCE 8 — Raw Material Software Ltd. - VST3 SDK — Steinberg Media Technologies GmbH - Neural Amp Modeler (NAM) — Steven Atkinson & contributors - The open-source audio & guitar-plugin community

Personal and commercial use permitted on machines you own.
Bug reports and feature requests: click the **AtiNAMatiC** title badge in the plug-in window to open the About panel.

AtiNAMatiC-HitZone is part of the AtiNAMatiC Series — a family of focused, hardware-flavoured guitar tools for the modern post-amp signal chain.

AtiNAMatiC-Hum — User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

1. What it is

Single-coil pickups, ground loops and nearby power supplies put a steady **hum** (50 or 60 Hz) and a harsher **buzz** (its upper harmonics) into your DI. An amp sim with lots of gain makes it much louder. A gate only hides it between notes; AtiNAMatiC-Hum removes it while you play.

- A cascade of true notches, each only about 2.5 Hz wide, at the mains frequency and its harmonics. Narrow enough that your notes pass.
- **Auto** works out whether your hum is 50 Hz or 60 Hz by itself.
- Measured: hum removed by about 15 dB (30 %), 22 dB (60 %) and 31–38 dB (100 %); a clean guitar with no hum loses only 0.2–0.3 dB.
- Zero latency.

2. Signal chain placement

```
Guitar -> [AtiNAMatiC-Hum] -> Gate -> ... -> Amp sim
```

Put Hum **first**, before the gate and before anything that adds gain.

3. Controls

HUM REMOVAL (big knob, 0–100 %, default 50 %)

Sets both how deep the notches cut (0 → -40 dB) and how many harmonics are treated (2 → 12). The low end of the knob (HUM) takes out the 50/60 Hz hum; higher settings (BUZZ) also remove the upper harmonics that make single-coil buzz.

MAINS (mode switch)

Mains	Use
Auto (default)	detects 50 Hz or 60 Hz from your signal (needs a second or two of hum to decide)
50 Hz	Europe, Asia, Africa, Australia, most of South America
60 Hz	North America, parts of South America, Japan (west), Korea, Taiwan, Philippines

OUTPUT (-24 to +12 dB)

Final trim.

4. Meters

- **INPUT** — peak level.
- **HUM** — energy of the hum series in your input.
- **REMOVED** — how much of it is being taken out, in dB.

- Status: **CLEAN**, **50 HZ HUM** / **60 HZ HUM**, or **... REMOVED**.

5. Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Hum-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Hum.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Hum.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Hum.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Hum-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Hum.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Hum.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Hum.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Hum.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Hum.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Hum-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.


6. Tips

- Start at 40–60 %; go higher only if you still hear buzz after the amp.
- If Auto picks the wrong mains on a near-silent signal, set 50 Hz or 60 Hz manually.
- Double-click any knob to reset it; hold Shift while dragging for fine control.

AtiNAMatiC-Hum v1.0.0 · Atij 666 Studio

AtiNAMatiC-Level — User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

What's new in v0.2.0

- **No more lurching or pumping.** Moving the LEVEL knob used to wipe the loudness detector, briefly releasing the gain; and the 1 dB deadband snapped the target back to 0 dB, so levels hovering near ±1 dB toggled (the "wavy" sound). The detector is now continuous and the deadband holds its value instead of snapping.
- Gaps and silence no longer get boosted (the gain holds when the signal falls 30 dB below target). The output safety stage is now a smooth knee from -2 dBFS instead of a near-hard clip at -0.1 dBFS.
- **New interface** — machined knob with a printed 0–10 scale, hardware-style mode switches that follow automation and preset recall, consistent value text ("72 %", "+1.5 dB"), resizable window (75–150 %, remembered per session). Double-click any knob to reset it; hold **Shift** while dragging for fine adjustment.

What It Is

AtiNAMatiC-Level is an **auto output leveler** designed to live at the very end of your guitar signal chain — after your NAM model, cab sim, EQ, and any other processors.

It continuously measures short-term RMS loudness and applies a smooth correction gain to keep your perceived output level consistent, regardless of what happens upstream: palm mutes, big chords, lead boosts, or riff changes. The result is a more controlled, mix-ready signal with less work from the engineer.

When AUTO is off, the correction is bypassed and the gain stage becomes a simple trim — the meters still run so you can A/B the leveling effect at any time.

Signal Chain Placement

```
Guitar → NAM Model → Cab Sim → EQ / FX → [AtiNAMatiC-Level] → DAW track / bus
```

Place Level **last** in the chain. It should see the fully processed signal so it can react to the actual output loudness, not an intermediate stage.

Controls

Control	Range	Default	Description
LEVEL	Soft → Locked	50%	The main macro. Controls how aggressively the leveler works.
AUTO	ON / OFF	ON	Enables or bypasses the auto-gain correction. Meters always active.
TRIM	−12 dB … +12 dB	0 dB	Output offset applied *after* the leveling stage.

LEVEL macro in detail

The LEVEL knob simultaneously scales three internal parameters:

Parameter	Soft (0%)	Locked (100%)
Detector time	600 ms	250 ms
Attack time	250 ms	20 ms
Release time	1500 ms	400 ms
Max correction	±4 dB	±18 dB

- **Soft** — slow, gentle leveling. Preserves pick dynamics and natural swells. Good for clean tones and recordings where you want to feel the playing.
- **Locked** — fast, tight leveling. Keeps the fader rock-steady. Good for heavy rhythm tracks that need to sit consistently in the mix.
- **Mid (50%)** — a balanced starting point suitable for most uses.

AUTO toggle

- **ON** — correction gain is computed and applied.
- **OFF** — correction is bypassed; only the TRIM offset is applied. The signal passes through untouched (apart from TRIM). Meters still display input/output levels for A/B comparison.

TRIM

Shifts the final output level without changing the leveling action. Use it to match the plugin's output to the rest of your mix, or to compensate for level differences between different NAM models.

Meters & Indicators

Dual-band meter (INPUT / OUTPUT)

- **INPUT** — pre-leveling signal level.
- **OUTPUT** — post-leveling signal level.
- The amber marker at **−18 dBFS** shows the internal RMS target. In Locked mode with a consistent signal, the output should stabilise near this marker.
- The OUTPUT bar colour shifts toward amber as the correction amount increases.

Level Pill (top-right of meter section)

Shows the current correction state:

Display	Meaning
LOCKED	Correction < 0.5 dB — the signal is already at target.
+X dB	Leveler is boosting (signal was too quiet).
−X dB	Leveler is cutting (signal was too loud).
BYPASS	AUTO is off.

The LED dot glows brighter as correction increases.

System Requirements

	Minimum
OS	Windows 10 (64-bit) / macOS 10.15+ / Linux (Ubuntu 20.04+)
CPU	Any modern x64 processor
RAM	4 GB
DAW	Any VST3 or CLAP host
Formats	VST3, CLAP, LV2 (Windows/Linux); + AU (macOS)

Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Level-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Level.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Level.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Level.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Level-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Level.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Level.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Level.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Level.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Level.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Level-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.

Controls Reference

Control	Parameter ID	Type	Range	Default
LEVEL	`level`	Float	0.0 – 1.0	0.5
AUTO	`autoOn`	Bool	ON / OFF	ON
TRIM	`trim`	Float (dB)	−12 – +12	0.0

Internal Signal Chain



Typical Use Cases

Consistent rhythm tracks — Set LEVEL to 70–80%. Palm mutes and full chords will land in the mix at the same perceived level without riding the fader.

Lead guitar — Set LEVEL to 40–60% with a slightly slower feel. The leveler smooths out pick-attack variation without killing the expressiveness of the performance.

Session reamp — Put Level at the end of the reamp chain. Different takes and NAM models can have wildly different output levels; Level normalises them to a common target before committing to the DAW track.

A/B leveling — Toggle AUTO OFF to hear the raw (trim-only) signal. Toggle back ON to hear the leveled version. The meters stay live in both states.

Tips

- **Start at 50% LEVEL.** Adjust up if the output still varies too much between playing styles; adjust down if the leveling feels unnatural.
- **Use TRIM to match other tracks**, not to compensate for gain staging. Keep your input signal healthy (peaking around −12 to −6 dBFS) and let Level do the consistency work.
- **Soft mode respects dynamics.** If you want your clean strums to breathe, stay below 30% LEVEL.

- **Locked mode is a leveling compressor.** At 100%, it behaves almost like a brickwall loudness normaliser — useful for DI tracks going into a heavily distorted amp sim where dynamics don't survive anyway.
- **The −18 dBFS target** is intentionally conservative. It gives headroom for the rest of your mix bus processing.

About

AtiNAMatiC-Level is part of the **AtiNAMatiC Series** — a collection of purpose-built guitar tools by Atij 666 Studio.


Built with: - JUCE Framework — Raw Material Software Ltd. - VST3 SDK — Steinberg Media Technologies GmbH - Neural Amp Modeler (NAM) — Steven Atkinson & contributors - The open-source audio & guitar-plugin community

Thank you to everyone who makes open-source audio tools possible.

Designed & developed by Atij

AtiNAMatiC-Mono — User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

1. What it is

Stereo amp sims, doublers and wideners are great until the low end gets wide and woolly, or the mix is played on a phone or a club PA in mono. AtiNAMatiC-Mono puts stereo where it helps and mono where it matters, with one knob.

- **Bass:** the low end becomes mono below a crossover you set; the rest of the image is untouched.
- **Full:** narrows the whole image from full stereo to mono.
- **Safe:** like Full, but the lows are always mono and the loudness is held as the image narrows.
- Watches left/right correlation and shows **PHASE ISSUE** when the input would partly cancel in mono.
- Zero latency.

2. Signal chain placement

Anywhere after something that makes stereo:

```
Amp sim -> Cab -> Double / Reach / Air -> [AtiNAMatiC-Mono] -> Squash / Level
```

3. Controls

MONO (big knob, 0–100 %, default 50 %)

- **Bass:** the crossover frequency, 40 Hz (0 %) to 400 Hz (100 %), on a log scale. 50 % ≈ 126 Hz.
- **Full / Safe:** how narrow the image is; 0 % = untouched stereo, 100 % = mono.

MODE (switch)

Mode	What MONO does	Loudness
Bass	side removed below the crossover (LR4 high-pass on the side only)	unchanged
Full	whole image narrowed	drops a little as wide content is removed
Safe	lows below 120 Hz always mono + whole image narrowed	held (compensated)

OUTPUT (-24 to +12 dB)

Final trim.

4. Meters

- **LEFT / RIGHT** — peak level of each side.
- **WIDTH** — side-to-mid energy of the output (0 % = mono).
- Status: **STEREO**, **NARROW**, **MONO**, or **PHASE ISSUE** (input correlation below -0.1).

Measured on a wide doubled guitar: Bass at 50 % removes the side below ~60 Hz by 13 dB and at 100 % below ~200 Hz by 25 dB, leaving the upper image and the centre untouched; Full and Safe reach true mono at 100 %, Safe within 0.1 dB of the original loudness.

5. Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Mono-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Mono.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Mono.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Mono.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Mono-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Mono.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Mono.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Mono.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Mono.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Mono.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Mono-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.


6. Tips

- After **Double** or **Reach**, Bass at 30–50 % keeps palm mutes centred and tight.
- Use Full at 100 % as a quick mono check of your whole guitar sound.
- Double-click any knob to reset it; hold Shift while dragging for fine control.

AtiNAMatiC-Mono v1.0.0 · Atij 666 Studio

AtiNAMatiC-Pick — User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

What's new in v0.2.0

- **No fuzz on low notes.** The two envelope followers now share one release, so on sustained notes they move together and only real pick attacks are shaped (they used to ripple at the note frequency and modulate the gain).
- Make-up gain is calibrated so the level stays within ±0.2 dB across the whole SOFT–SHARP range (SOFT used to drop ~3 dB). MIX and OUTPUT are smoothed; detection is stereo-linked.
- **New interface** — machined knob with a printed 0–10 scale, hardware-style mode switches that follow automation and preset recall, consistent value text ("72 %", "+1.5 dB"), resizable window (75–150 %, remembered per session). Double-click any knob to reset it; hold **Shift** while dragging for fine adjustment.

---

1. What it is

AtiNAMatiC-Pick is a **pick attack designer** — a transient shaper that reshapes the leading edge of every note in real time. One large bipolar knob lets you make playing feel **softer and more legato** (turn left toward SOFT) or **sharper, snappier, and more percussive** (turn right toward SHARP), all without touching an EQ or compressor.

Under the hood it is a four-stage chain:

- **Dual envelope follower** — a fast peak follower (1.5 ms attack / 25 ms release) and a slow follower (40 ms / 220 ms) run in parallel. The ratio `(fast − slow) / slow` produces a level-invariant transient strength `T` that peaks near 1.0 on a typical guitar attack and falls back to 0 during sustain.
- **Per-sample gain modulation** — the transient strength drives gain by `g = 1 + A · 0.7 · T` where `A` is the knob mapped to ±1. Sharp settings amplify transient peaks; Soft settings attenuate them. Sustained material is untouched.
- **Tilt EQ** — a subtle ±2 dB tilt scales with the knob. Sharp adds a high-shelf lift @ 4 kHz; Soft adds a gentle low-shelf lift @ 160 Hz. Filter coefficients are re-tuned per block with a small change threshold so the audio never zippers.
- **Auto make-up** — calibrated on DI guitar so the level stays within ±0.2 dB across the full SOFT–SHARP sweep.

Zero latency. No lookahead. No oversampling. Mono or stereo input, always stereo gain shared from the left channel so the stereo image stays glued.

---

2. Signal chain placement

```
Guitar (DI)
   -->  Noise Gate (optional)
   -->  *** AtiNAMatiC-Pick ***
   -->  Amp Sim (NAM / Helix / ML Sound Lab / etc.)
   -->  Cab / IR
   -->  AtiNAMatiC-Air / Reverb / Master bus
```

Before the amp sim is the primary placement — it shapes the raw pick dynamics before the amp's non-linearity acts on them, so the amp responds to the new attack character.

After the amp sim also works for a more "mix-bus" use. In that position you are sharpening or softening the already-distorted tone, so use smaller knob deflections (±20–40%).

Place after a noise gate so the gate's closed state does not confuse the envelope follower with near-silence.

---

3. The Controls

ATTACK (large centre knob, bipolar 0 — 100%, neutral at 50%)

The single master macro. The knob is **bipolar**: 50% is neutral (the plugin is essentially transparent), turning left sweeps toward SOFT, turning right sweeps toward SHARP.

Knob position	Label	Character
0% (full left)	Soft −100%	Maximum transient attenuation. Pillow-soft, very legato.
25%	Soft −50%	Noticeably rounded pick attack. Smoother runs.
50% (centre)	Neutral	Bypass-flat. Knob defaults here. Double-click to return.
75%	Sharp +50%	Brighter, more pronounced pick definition.
100% (full right)	Sharp +100%	Razor-sharp percussive snap. Aggressive note articulation.

The value below the knob updates live: **Neutral**, **Soft −N%**, or **Sharp +N%**.

Tick labels under the knob colour-code the direction:

- **SOFT** (indigo, left)
- **NEUTRAL** (centre)
- **SHARP** (amber, right)

Most players live in the inner ±50% range. Beyond that the effect becomes deliberate.

MIX (0 — 100%)

Dry / wet blend. 0% = bypass, 100% = fully processed (default).

Use a partial blend for parallel transient shaping — for example, dial Sharp +80% and set MIX to 35% to glue a hint of pick clarity onto the original signal without changing its overall character.

OUTPUT (-24 to +12 dB)

Final trim after all processing. Even with auto make-up, different guitars and amp models may need small level matching here. Use it to match the bypassed level before committing to a setting.

Transient activity pill (top-right of meter area)

A small LED-style indicator that responds to the live transient strength `T`. It glows brighter on each pick attack and inherits the active accent colour:

- **Indigo** when the knob is on the SOFT side.
- **Emerald** when at NEUTRAL.
- **Amber** when on the SHARP side.

Use it as a visual reference for how strong each pick attack is being detected.

Input / Output meters

Dual horizontal meters at the bottom of the panel (−60 to 0 dBFS) show the input and output peak levels with a 20 ms ballistic decay. Use them to confirm OUTPUT trim is keeping the bypassed level matched.

---

4. System Requirements

	Minimum
OS	Windows 10 (64-bit) · macOS 10.15+ · Linux (Ubuntu 20.04+)
CPU	Any modern 64-bit processor (zero-latency, very light DSP)
RAM	256 MB
Formats	VST3 · CLAP · LV2 · AU (macOS)
DAW	Any VST3 or CLAP host

---

5. Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Pick-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Pick.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Pick.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Pick.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Pick-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Pick.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Pick.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Pick.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Pick.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Pick.vst3`.

Linux (x86_64 and ARM64)


- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Pick-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.

6. Controls Reference

Control	Range	Default	Behaviour
ATTACK	0 – 100% (bipolar)	50% (Neutral)	Master macro. <50% softens transients; >50% sharpens them. Double-click to return to neutral.
MIX	0 – 100%	100%	Dry / wet blend.
OUTPUT	-24 – +12 dB	0 dB	Final trim after processing.

7. Internal Signal Chain



8. Typical Use Cases

- **Soft +25% on clean guitar** — tames over-eager picking on fingerstyle or jazz parts. Notes flow rather than slap.
- **Soft +50% on hard-strummed acoustic DI** — controls the pick scrape without dulling the body.
- **Sharp +30% on a smooth NAM amp** — restores percussive attack lost in heavy compression / smoothing.
- **Sharp +60% on direct bass** — adds modern slap definition without an EQ boost.
- **Sharp +80%, MIX 35% on a metal rhythm** — parallel transient layer gives the riff bite without changing the rhythm tone itself.
- **Soft +100%, MIX 25% on a lead line** — subtly rounds the attack of every note for a "vocal" lead.

9. Tips

- The knob is **bipolar** — double-click to snap back to Neutral (50%).
- The activity pill colour tells you which side of neutral you are on at a glance.
- When stacking with **AtiNAMatiC-Tight** or **AtiNAMatiC-Feel**, put Pick **before** Feel/Tight — they expect a stable transient envelope.
- For a single-track double, duplicate the channel and set one instance Soft +30% / one Sharp +30% panned wide.
- If you hear pumping on long sustained notes, you have probably set MIX too high in combination with a large Sharp deflection. Drop MIX to 50–70%.
- The plugin is zero-latency. Safe to use on tracking buses and live monitor paths.

10. About


AtiNAMatiC-Pick is part of the **AtiNAMatiC One-Knob** series by **Atij 666 Studio** — a family of simple-by-design guitar utility plugins, each focused on doing one job extremely well with a single macro knob.

Click the **AtiNAMatiC-Pick** badge in the top-left of the plugin window for the About overlay.

© 2026 Atij 666 Studio. All rights reserved.

AtiNAMatiC-Pitch — User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

1. What it is

AtiNAMatiC-Pitch is a one-knob pitch tool with three jobs:

- **Drop** — play drop-tuned parts without retuning: 0 to -7 semitones, always in whole semitones so it is always in tune.
- **Detune** — stereo "micro-shift" thickening: a voice a few cents up on the left, one a few cents down on the right, under your dry signal.
- **Octave** — an octave-below voice, filtered smooth, added under your playing.

It uses a pitch-synchronous granular shifter: a light pitch tracker finds the period of what you are playing and lines the grains up with the waveform, so single notes stay clean. Measured on steady notes: the shifted note is dominant, with by-products 35–41 dB down.

Honest limits: like any real-time shifter, full chords at large shifts (Drop -5 to -7, Octave) warble a little, because a chord has no single period to line up with. Single notes, riffs and small shifts are the cleanest. Drop and Octave also have a short inherent delay (the grain window, roughly 20–30 ms); Detune's delays are part of the effect.

2. Signal chain placement

```
Guitar -> [AtiNAMatiC-Pitch] -> ... -> Amp sim          (Drop, Octave: before the amp)
Amp sim -> Cab / IR -> [AtiNAMatiC-Pitch]               (Detune: after the amp, stereo)
```

Drop and Octave track best on a clean DI, so place them first. Detune works best after the amp. Mono in / stereo out is supported.

3. Controls

PITCH (big knob)

Its meaning depends on the mode; the readout under the knob shows the actual value.

Mode	Knob range	Readout
Drop	0 → -7 semitones (whole steps)	`-3 st`
Detune	0 → 25 cents each way	`12 cents`
Octave	octave-down level 0 → 100 %	`-1 oct 60 %`

MODE (switch)

Drop / Detune / Octave.

MIX (0–100 %)

Drop: wet/dry (100 % = only the shifted signal). Detune and Octave: how much of the added voice(s) you hear on top of the dry signal.

OUTPUT (-24 to +12 dB)

Final trim.

4. Meters

- **INPUT / OUTPUT** — peak level.
- Status: **IN TUNE**, **DROP -n ST**, **DETUNE +/-n CENTS**, **OCTAVE DOWN**.

5. Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Pitch-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Pitch.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Pitch.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Pitch.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Pitch-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Pitch.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Pitch.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Pitch.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Pitch.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Pitch.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.

- **Just this plug-in:** unzip `AtiNAMatiC-Pitch-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.


6. Tips

- Drop -2 st turns standard tuning into "D standard" for a song; -5 st into "B standard" for single-note riffs.
- Detune 8–15 cents after the amp is a classic stereo thickener on clean parts and leads.
- Octave at 30–50 % under a fuzzy lead gives a huge, organ-like low end.
- Double-click any knob to reset it; hold Shift while dragging for fine control.

AtiNAMatiC-Pitch v1.0.0 · Atij 666 Studio

AtiNAMatiC-Reach — User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

1. What it is

AtiNAMatiC-Reach makes a guitar **step forward and spread out** in a mix without getting louder, muddier, or falling apart in mono.

- **Projection (centre):** a presence lift around 2.2 kHz (up to +3.5 dB) and a dip around 300 Hz (up to -2 dB). The guitar reads clearly without turning the fader up.
- **Solid low end:** stereo content below about 150 Hz is folded to the centre, so palm mutes stay tight on any system.
- **Spread (sides):** existing stereo content above 1 kHz is widened, and a spread is generated from the guitar's upper range (above 700 Hz, about 1 ms offset), so a **mono amp sim** gets width too.
- **Mono-safe:** the generated spread goes into left and right with opposite signs, so it cancels exactly when the mix is summed to mono. Only the centre's projection EQ remains.
- Accepts a mono input and outputs stereo. Zero latency.

2. Signal chain placement

```
Guitar -> ... -> Amp sim -> Cab / IR -> [AtiNAMatiC-Reach] -> Squash / Level
```

Place Reach **after** the amp and cab, on a stereo track (or a mono track whose insert outputs stereo).

3. Controls

REACH (big knob, 0–100 %, default 40 %)

NEAR (0 %) is untouched. Turning it up raises projection and spread together. Level is matched within about ±0.2 dB.

SHAPE (mode switch)

Shape	Presence	Widening	Generated spread	Offset
Focus	+3.5 dB	light	light	0.8 ms
Wide (default)	+3 dB	medium	medium	1.0 ms
Huge	+2.5 dB	strong	strong	1.4 ms

(Values at 100 %.)

MIX (0–100 %) and OUTPUT (-24 to +12 dB)

Blend with the dry signal and final trim.

4. Meters

- **LEFT / RIGHT** — peak level of each side.
- **WIDTH** — side-to-mid energy of the output (0 % = mono). Low notes stay centred by design, so width rises on brighter playing.
- Status: **MONO**, **FOCUSED**, **WIDE**, **HUGE**.

5. Signal chain (inside)

```
 L/R -> mid / side
mid  -> presence peak 2.2 kHz -> mud dip 300 Hz                    (projection)
side -> minus low-passed side (<150 Hz) + widened side (>1 kHz)
     +  generated spread: mid -> HP 700 Hz -> LP 9 kHz -> ~1 ms delay
-> L = mid + side, R = mid - side -> MIX -> OUTPUT
```

6. Latency and CPU

Zero latency. Very light on CPU.

7. Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Reach-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Reach.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Reach.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Reach.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Reach-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Reach.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Reach.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Reach.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Reach.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Reach.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Reach-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.


8. Tips

- Reach and **Air** combine well: Air adds room depth, Reach adds projection and spread.
- For double-tracked guitars already hard-panned, use Focus: projection without extra width.
- Double-click any knob to reset it; hold Shift while dragging for fine control.

AtiNAMatiC-Reach v1.0.0 · Atij 666 Studio

AtiNAMatiC-Room — User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

1. What it is

AtiNAMatiC-Room puts a guitar in a real space without blurring it. It is a short, dense room reverb with **ducking**: the reverb dips while you play and blooms back in the gaps, so riffs stay tight and the ambience fills the spaces between them. Built for dense amp-sim mixes, where a normal reverb turns into mud.

- 8-line feedback-delay-network reverb with input diffusion, damping and slow modulation (no metallic ringing).
- The reverb's low end is filtered out (high-pass 180 Hz), so palm mutes stay dry and tight.
- Left and right reverb outputs are decorrelated for a natural stereo room, even from a mono guitar.
- The dry signal is never delayed or changed: zero latency, and ROOM at 0 % is exactly dry.

Measured decay times: Booth ~0.3 s, Studio ~0.6 s, Hall ~1.5 s (at 60 %).

2. Signal chain placement

```
Guitar -> ... -> Amp sim -> Cab / IR -> [AtiNAMatiC-Room] -> Level
```

Place Room **after** the amp and cab, as an insert (it keeps the dry signal at unity and adds the room on top). It accepts a mono input and outputs stereo.

3. Controls

ROOM (big knob, 0–100 %, default 30 %)

How much room you hear. The first half of the knob is subtle ambience; the top half is a clearly audible space. ROOM also nudges the size and decay up slightly as it rises.

SPACE (mode switch)

Space	Decay	Pre-delay	Character
Booth	~0.35 s	4 ms	tight, close, almost "just air"
Studio (default)	~0.7 s	12 ms	a live room around the cab
Hall	~1.6 s	24 ms	big and open, for leads and ambient parts

DUCK (0–100 %, default 50 %)

How far the reverb dips while you play: up to 10 dB at 100 %. Part of that is given back overall, so the gaps bloom at full size while the notes stay clear.

OUTPUT (-24 to +12 dB)

Final trim.

4. Meters

- **INPUT** — peak level of the dry signal.
- **ROOM** — level of the reverb you hear.
- **DUCK** — how far the reverb is currently ducked, in dB.
- Status: **DRY**, **DUCKING** (while you play), **BLOOMING** (in the gaps).

5. Signal chain (inside)

```
dry L/R ──────────────────────────────────────────────┐
mono feed -> pre-delay -> 4 all-pass diffusers        |
          -> 8-line FDN (Hadamard, damping, modulation)  |
          -> 2 decorrelated outputs -> HP 180 Hz / LP 8 kHz
          -> x ROOM level x ducking (from dry envelope) -+-> sum -> OUTPUT
```

6. Latency, tail and CPU

Zero latency. Reports a 3 s tail so hosts let the reverb ring out. Moderate CPU (still very light).

7. Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Room-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Room.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Room.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Room.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Room-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Room.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Room.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Room.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Room.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Room.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Room-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.


8. Tips

- For high-gain rhythm: Booth or Studio, ROOM 20–35 %, DUCK 70–100 %.
- For leads: Hall, ROOM 40–60 %, DUCK 30–50 % so the tail sings between phrases.
- Room and **Air** combine well: Air adds the close "amp in the room" depth, Room the space around it.
- Double-click any knob to reset it; hold Shift while dragging for fine control.

AtiNAMatiC-Room v1.0.0 · Atij 666 Studio

AtiNAMatiC-Sag — User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

1. What it is

A real tube amp with a tube rectifier can't hold its supply voltage when you dig in. The voltage droops, the amp loses a little gain and headroom, then recovers over a few hundred milliseconds. Players call it **sag**: hard notes squash slightly, then **bloom** back. It is a big part of why an old amp feels "spongy" and forgiving.

Amp captures are usually taken with steady test signals, so much of that touch response is missing. AtiNAMatiC-Sag puts the droop-and-recover in front of your amp model.

- Below about -36 dBFS nothing happens; the droop grows with how hard you play.
- The supply can't collapse instantly, so your pick attack passes first and the note sags just after, then swells back.
- As the supply droops the headroom drops too: a gentle, slightly asymmetric soft-clip that only appears while the "supply" is loaded.
- Zero latency.

2. Signal chain placement

```
Guitar -> Gate -> [AtiNAMatiC-Sag] -> Boost / Dirt -> Amp sim -> Cab / IR
```

Place Sag **before** the amp sim. It works on clean, crunch and high-gain models; the effect is most obvious on edge-of-breakup tones.

3. Controls

SAG (big knob, 0–100 %, default 40 %)

How far the supply droops when you dig in.

Position	Feel
0 % (STIFF)	Clean pass-through. Nothing changes.
30–50 % (WARM)	Notes give a little under hard picking; chords feel rounder.
70–100 % (SPONGY)	Obvious squash and bloom; soft playing stays open, hard playing compresses.

Level is calibrated so turning SAG does not make the signal louder or quieter (within about ±1 dB on typical guitar).

SUPPLY (mode switch)

Mode	Droop / recovery	Max droop	Character
Rectifier	20 ms / 180 ms	9 dB	Classic tube-rectifier sag.
Variac	40 ms / 320 ms	6 dB	"Running at low voltage": softer, earlier clipping, slower.
Bloom	6 ms / 450 ms	12 dB	Fast dip, long recovery: notes dip then swell back up.

MIX (0–100 %)

Blend with the dry signal for a subtler effect.

OUTPUT (-24 to +12 dB)

Final level trim.

4. Meters

- **INPUT / OUTPUT** — peak level.
- **DROOP** — how far the supply is currently sagging, in dB.
- Status: **STIFF** (no droop), **BREATHING** (light), **SAGGING** (more than 3 dB).

5. Signal chain (inside)

```
Input -> supply envelope (linked L/R) -> gain droop (smoothed 5 ms)
      -> headroom stage: soft clip whose drive and asymmetry follow the droop
      -> DC blocker -> static make-up -> MIX -> OUTPUT
```

6. Latency and CPU

Zero latency. Very light on CPU.

7. Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Sag-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Sag.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Sag.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Sag.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Sag-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Sag.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Sag.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Sag.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Sag.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Sag.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Sag-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.


8. Tips

- Pair with **Feel** for a very forgiving practice tone: Feel evens out the picking, Sag adds the bloom.
- Bloom mode at 40–60 % on a clean amp gives a nice "swell" on sustained chords.
- Double-click any knob to reset it; hold Shift while dragging for fine control.

AtiNAMatiC-Sag v1.0.0 · Atij 666 Studio

AtiNAMatiC-Slow — User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

1. What it is

Violin-style volume swells without touching a volume knob or pedal. AtiNAMatiC-Slow hides the pick attack of every note and fades the note in, like a classic "slow gear" pedal.

- Every new pick is detected automatically, including picks over strings that are still ringing: besides the overall level, the detector watches the pick click above 4 kHz. It re-arms only once the previous attack has settled, so a note never triggers twice.
- At each new attack the level dips to silence in 4 ms (the last note's tail fades instead of clicking), then the new note swells in over the swell time.
- Noise below about -50 dBFS never triggers a swell.
- 6 ms latency, reported to your DAW (which compensates). Slow uses it to look ahead: the volume is already closed when the pick arrives, so none of the pick click gets through. The delay is inaudible because the attack is hidden anyway.

Measured on picked notes at the default 263 ms swell: 13 % level at 60 ms, 60 % at 150 ms, full level by 270 ms, the same on every note.

2. Signal chain placement

```
Guitar -> [AtiNAMatiC-Slow] -> Amp sim -> Cab / IR -> Room / delay / reverb
```

Before the amp for the classic swell into distortion; after the amp for smoother, more "pad"-like swells. A reverb or delay after it makes the effect bloom.

3. Controls

SWELL TIME (big knob, 50 ms → 2 s)

How long each note takes to fade in. The readout shows the time. Short settings soften the attack; long settings give ambient pads.

CURVE (mode switch)

Curve	Shape	Feel
Swell (default)	smooth S-curve	the classic slow-gear swell
Pad	slow rise in dB, softest start	string-pad, the attack completely hidden
Reverse	holds back, then rushes in at the end	"reversed note" feel

MIX (0–100 %)

100 % = full swell; lower settings let some of the pick attack through.

OUTPUT (-24 to +12 dB)

Final trim.

4. Meters

- **INPUT / OUTPUT** — peak level.
- **SWELL** — the current swell level (0 % at a new attack, 100 % once open).
- Status: **WAITING**, **SWELLING**, **OPEN**.

5. Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Slow-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Slow.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Slow.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Slow.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Slow-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Slow.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Slow.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Slow.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Slow.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Slow.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Slow-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.


6. Tips

- Swell at 300–600 ms with **Room** (Hall) after the amp is an instant ambient guitar.
- Play legato for continuous pads; a new pick restarts the swell.
- For faster playing, shorten the swell time. A note picked again before its swell finishes is faded out while it is still rising.
- Double-click any knob to reset it; hold Shift while dragging for fine control.

AtiNAMatiC-Slow v1.0.0 · Atij 666 Studio

AtiNAMatiC-Squash — User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

What's new in v0.2.0

- **Compression at real-world levels.** The old thresholds assumed a very hot signal: on a typical guitar bus Gentle and Standard barely compressed at all, while the auto make-up added up to +9 dB. Thresholds are re-mapped (tables below) and make-up is calibrated so loudness stays within about ±1 dB across the knob.
- Faster 5 ms RMS detector, stereo-linked gain, smoothed MIX/OUTPUT, and new input/output meters.
- **New interface** — machined knob with a printed 0–10 scale, hardware-style mode switches that follow automation and preset recall, consistent value text ("72 %", "+1.5 dB"), resizable window (75–150 %, remembered per session). Double-click any knob to reset it; hold **Shift** while dragging for fine adjustment.

What It Is

AtiNAMatiC-Squash is a **one-knob feedforward RMS compressor** designed for guitar and bass processing — from subtle bus glue to aggressive, punchy squash. A single **SQUASH** macro knob sets the compression intensity, while three **MODE** characters shape how the compression behaves. A **MIX** control lets you blend the compressed signal in parallel for New York-style compression without touching a ratio or threshold.

Squash is intended to sit after your NAM model and cab sim, adding the final punch and glue that makes a tracked guitar feel controlled and present in the mix without audible pumping.

Signal Chain Placement

```
Guitar -> NAM Model -> Cab Sim -> EQ / FX -> [AtiNAMatiC-Squash] -> DAW track / bus
```

Place Squash **after** your amp sim and cab. It should see the fully processed, speaker-coloured signal. Placing it before the cab will compress the sharp transients before cabinet filtering, which can sound unnatural.

For parallel bus processing, insert Squash on an aux channel and blend using MIX or the host send level.

Controls

Control	Range	Default	Description
SQUASH	Light to Heavy	50%	Main compression intensity macro. Controls threshold, ratio, attack, release, and knee simultaneously.
MODE	Gentle / Standard / Smash	Standard	Selects the compression character.
MIX	0 to 100%	100%	Parallel wet/dry blend. 100% = fully compressed.
OUTPUT	-24 to +24 dB	0 dB	Output trim applied after the compressor and mix blend.

The SQUASH Knob

The SQUASH knob is a smooth macro that scales all five compressor parameters simultaneously. A **smoothstep curve** is applied so the lower half of the travel is more subtle — useful for transparent glue — while the upper half becomes progressively more aggressive.

At **Light (0%)** the plugin is essentially transparent: threshold is high, ratio is minimal, attack is slow, and the soft knee is at its widest.

At **Heavy (100%)** the threshold drops to its lowest point, ratio climbs to the mode maximum, attack tightens to its fastest, and (in Standard and Smash modes) the knee hardens.

Auto makeup gain is static and calibrated for a typical guitar-bus level (around -18 dBFS RMS), so loudness stays within about ±1 dB as you turn the knob. It is applied *after* the time-constant smoother so mode switches never cause gain pumping.

Modes

GENTLE

Slow, transparent bus glue with a wide soft knee. Preserves pick dynamics and natural playing feel. Good for clean tones, acoustic processing, and final bus glue.

Parameter	Light (0%)	Heavy (100%)
Threshold	-12 dB	-30 dB
Ratio	1.5 : 1	3 : 1
Attack	50 ms	12 ms
Release	300 ms	80 ms
Knee	8 dB	4 dB

STANDARD

All-purpose character: snappy but musical. Covers the widest range of applications. Good starting point for any source.

Parameter	Light (0%)	Heavy (100%)
Threshold	-14 dB	-34 dB
Ratio	2 : 1	8 : 1
Attack	25 ms	3 ms
Release	200 ms	40 ms
Knee	6 dB	1.5 dB

SMASH

Aggressive, fast, and tight. Very low thresholds, high ratios, near-zero attack. Adds punch and density. Best used with MIX below 100% to keep transient feel (New York parallel style).

Parameter	Light (0%)	Heavy (100%)
Threshold	-16 dB	-40 dB
Ratio	4 : 1	20 : 1
Attack	8 ms	0.5 ms
Release	100 ms	15 ms
Knee	4 dB	0 dB (hard)

GR Meter

The horizontal segmented bar at the bottom of the plugin displays **Gain Reduction** in real time.

- **Range:** 0 to 18 dB GR
- **Colour zones:**
- Green: 0 to 9 dB GR (normal compression range)
- Amber: 9 to 13.5 dB GR (medium compression)
- Red: 13.5 to 18 dB GR (heavy compression)
- **Peak hold** — a bright marker holds at the highest GR reached for ~2 seconds, then decays slowly.
- **Tick marks** at -6 dB, -12 dB, and -18 dB GR.

The meter has **instant attack** and **100 ms visual release**, giving a fast, responsive readout that mirrors what you hear.

System Requirements

	Minimum
OS	Windows 10 (64-bit) / macOS 10.15+ / Linux (Ubuntu 20.04+)
CPU	Any modern x64 processor
RAM	4 GB
DAW	Any VST3 or CLAP host
Formats	VST3, CLAP, LV2 (Windows/Linux); + AU (macOS)

Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Squash-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Squash.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Squash.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Squash.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Squash-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Squash.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Squash.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Squash.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Squash.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Squash.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Squash-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.

Controls Reference

Control	Parameter ID	Type	Range	Default
SQUASH	`squash`	Float	0.0 to 1.0	0.5
MODE	`mode`	Choice	Gentle / Standard / Smash	Standard (1)
MIX	`mix`	Float	0.0 to 1.0	1.0
OUTPUT	`output`	Float (dB)	-24 to +24	0.0

All parameters are fully automatable and support DAW recall and preset saving.

Internal Signal Chain

```
Input (stereo)
  |
  +-> RMS Envelope Detector (5 ms, stereo-linked: max of L+R)
  |         |
  |         v
  |   Input level in dBFS
  |         |
  |         v
  |   Gain Computer (threshold + soft-knee + ratio set by SQUASH + MODE)
  |         |
  |         v
  |   Per-sample Attack / Release smoother
  |   (both channels track the stereo-linked detector, stereo image preserved)
  |         |
  |         v
  +-> Apply compression gain
  |         |
  |         v
  |   Auto makeup gain (calibrated static, applied after smoother)
  |
  +-> Parallel MIX blend (dry x (1 - MIX) + wet x MIX)
  |
  +-> OUTPUT trim
  |
Output (stereo)
```

The compressor uses **stereo linking**: the RMS detector takes the maximum across both channels so both L and R always receive the same gain reduction, preserving the stereo image under heavy compression.

Typical Use Cases

Rhythm guitar glue (GENTLE, 50-70%) — Tightens palm mutes and power chords without audibly clamping the attack. The wide knee and slow attack let the pick transient through before clamping down.

Lead guitar sustain (STANDARD, 60-80%) — Longer notes and bends sustain more evenly. The shorter release at heavier settings keeps the compressor active between phrases, reducing the perception of the signal pumping up between notes.

Parallel drum-room crush (SMASH, 80-100%, MIX 40-60%) — Full SMASH at high SQUASH destroys dynamics and adds density. Blend back with MIX to taste — the dry transients from the parallel path restore punch while the crushed signal adds body and sustain.

DI bass (STANDARD or SMASH, 50-70%) — Controls the dynamic range of bass lines so low notes and high frets sit at the same level in the mix.

Bus finaliser (GENTLE, 30-50%) — Last insert on a guitar bus. Subtle glue that makes multiple guitar tracks feel like they were played in the same room.

Tips

- **Start in STANDARD at 50%.** Adjust SQUASH until the GR meter shows 3-6 dB on peaks, then stop.
- **Use MIX for parallel compression.** SMASH mode at 90% with MIX at 50% is a classic New York compression sound — dense, punchy, still has transient feel.
- **Watch the amber zone (9-13 dB).** For most guitar work, staying in the green is correct; amber and red zones are for intentional effect.
- **GENTLE at 20-30% is nearly invisible** but makes a mix bus sit more consistently. This is the set-it-and-forget-it zone.
- **The peak hold marker** is useful during tracking. Set a phrase, watch where the peak hold lands, then adjust SQUASH so it lands in the 3-6 dB green zone for the loudest moments.
- **OUTPUT after MIX** — OUTPUT is applied after the parallel blend, so adjusting it does not change the compression behaviour, only the final level.


About

AtiNAMatiC-Squash is part of the **One-Knob Series** by Atij 666 Studio — a collection of purpose-built, single-focus audio tools designed for fast, confident sound shaping.

Built with: - JUCE Framework - Raw Material Software Ltd. - VST3 SDK - Steinberg Media Technologies GmbH - CLAP - Free Audio / Alexandre Bique and contributors

AtiNAMatiC-Strum — User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

1. What it is

A strum is six strings hit at once. A normal full-band transient shaper treats it as one event: lift the attack and the low "thump" of the pick across the strings comes up along with the sparkle, so chords get boomy before they get clear.

AtiNAMatiC-Strum splits the signal into three bands and shapes each one differently:

Band	Range	What STRUM does
Low	below 250 Hz	pulls the attack **down**: tames boom and thump
Mid	250 Hz – 2.5 kHz	a little attack and a little extra ring
High	above 2.5 kHz	pushes the attack **up**: string definition and sparkle

The result is strummed chords that sound articulate and "produced" without getting louder or boomier.

- Each band has its own transient detector, linked across left and right so the stereo image stays still.
- The detectors share one release, so sustained notes are left alone; only real strikes are shaped.
- The three bands add back to exactly the input: at 0 % the signal passes untouched.
- Zero latency.

2. Signal chain placement

```
Guitar -> [AtiNAMatiC-Strum] -> Amp sim -> Cab / IR              (electric)
Acoustic / clean DI -> [AtiNAMatiC-Strum] -> EQ / Reverb         (acoustic)
```

Before the amp sim for electric guitar; anywhere on a clean or acoustic track.

3. Controls

STRUM (big knob, 0–100 %, default 50 %)

How strongly the three bands are shaped. RAW (0 %) is a clean pass-through; POLISHED (100 %) is the full effect. Level is matched across the knob (within about ±0.2 dB).

VOICING (mode switch)

Voicing	Low attack	Mid attack / ring	High attack	For
Clean	-5 dB	+1.5 / +1 dB	+5 dB	clean electric strumming
Crunch	-6 dB	+2 / 0 dB	+3.5 dB	driven rhythm, keeps the amp from flubbing
Acoustic	-5 dB	+1 / +2 dB	+6 dB	acoustic and piezo: sparkle and body ring

(Values at 100 %; they scale with the knob.)

MIX (0–100 %) and OUTPUT (-24 to +12 dB)

Blend with the dry signal (never combs, the bands are phase-exact) and final trim.

4. Meters

- **INPUT** — peak level.
- **STRIKE** — how much high-band attack is being lifted right now.
- **THUMP** — how much low-band attack is being pulled down, in dB.
- Status: **RINGING** (sustain), **PICKING**, **STRUMMING**.

5. Signal chain (inside)

```
Input -> low = LR4 low-pass 250 Hz, rest = input - low
      -> mid = LR4 low-pass 2.5 kHz (of rest), high = rest - mid
      -> per-band linked transient shaper (1 ms / 25 ms attack, shared 100 ms release)
      -> sum -> make-up -> MIX -> OUTPUT
```

6. Latency and CPU

Zero latency. Light on CPU.

7. Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Strum-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Strum.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Strum.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Strum.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Strum-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Strum.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Strum.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Strum.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Strum.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Strum.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Strum-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.


8. Tips

- For palm-muted metal rhythm use **Tight** instead; Strum is voiced for open chords.
- Acoustic voicing at 40–60 % is a quick "mix-ready" acoustic strum.
- Double-click any knob to reset it; hold Shift while dragging for fine control.

AtiNAMatiC-Strum v1.0.0 · Atij 666 Studio

AtiNAMatiC-Tight -- User Manual

Version 1.0.0 · ATIJ STUDIO · Windows · macOS · Linux · VST3 · CLAP · LV2 · AU (macOS) · Free and open source (GPL v3)



What's new in v1.0.0

- First public release, now **free and open source** (GPL v3).
- New look, shared across the whole ONE KNOB Series.
- **Every plug-in format:** VST3, CLAP and LV2 on Windows, macOS and Linux, plus AU on macOS. (The standalone app has been retired: these work best inside your DAW.)
- New **ONE KNOB Series installers** for Windows and macOS: tick the plug-ins and formats you want, skip the rest. Linux gets an install script that asks the same questions.

What's new in v0.2.0

- **Transient shaper rebuilt.** It now uses one stereo-linked detector with a shared release (no more gain ripple / fuzz on low notes) and tops out at about +6 dB on attacks instead of +9 dB, which produced +11–14 dB spikes into the amp.
- Removed a memory allocation that happened on the audio thread every block (a potential source of dropouts); MIX and OUTPUT are smoothed; new input/output meters.
- **New interface** — machined knob with a printed 0–10 scale, hardware-style mode switches that follow automation and preset recall, consistent value text ("72 %", "+1.5 dB"), resizable window (75–150 %, remembered per session). Double-click any knob to reset it; hold **Shift** while dragging for fine adjustment.

---

1. What it is

AtiNAMatiC-Tight is a **guitar tightener and transient enhancer**. One large knob shapes everything from low-end tightness and body clarity to pick attack definition -- so you can dial in exactly the weight and snap you need without touching an EQ or transient shaper separately.

Under the hood it is a four-stage DSP chain, all pure signal processing with zero machine-learning models:

- **High-pass filter (4th-order Butterworth, dual cascaded biquads)** -- removes sub-bass mud and low-end bleed so every note starts clean. Cut frequency rises with the TIGHT knob so harder settings trim progressively more low-end.
- **Low-mid dip (peaking EQ, 280 Hz)** -- surgically reduces the boxy "cardboard" resonance common on both high-gain guitar and direct bass. Deeper at higher TIGHT values.
- **Presence shelf (2.5 kHz)** -- adds upper-mid detail and cut that brings the attack of pick strikes forward in a mix without harshness.
- **Transient shaper** -- a parallel dynamic processor that boosts the first few milliseconds of each note relative to the sustain tail. Stronger in Extreme mode, gentlest in Classic. Zero look-ahead latency.
- **Block-rate parameter smoother** -- all three filter targets use a 40 ms one-pole smoother so sweeping the TIGHT knob in real-time produces no zipper noise or clicks.

---

2. Signal chain placement

```
Guitar (DI or amp mic)
  -->  Noise Gate (e.g. AtiNAMatiC-Gate)
  -->  *** AtiNAMatiC-Tight ***
  -->  Amp Sim (NAM / Helix / ML Sound Lab / etc.)
  -->  Cab / IR
  -->  AtiNAMatiC-Air / Reverb / Master bus
```

Before the amp sim is the primary placement. Tightening the source signal before saturation prevents the amp from compressing and fattening up low-end mud -- it gives the amp sim a clean, focused note to work with.

After the amp sim also works and is useful when the amp's own compression has already softened pick attack too much. In that case raise TIGHT more conservatively (30--50%) to avoid over-thinning a post-distortion sound.

For a parallel DI/recorded rig, insert on each dry channel individually before the amp.

---

3. Controls

TIGHT (large centre knob, 0 -- 100%)

The single master macro. As you turn it clockwise all four DSP stages intensify simultaneously, scaled by the current MODE:

TIGHT value	Effect
0% (LOOSE)	HPF near the lowest setting for the mode, minimal dip, minimal presence boost, no transient shaping -- the signal is essentially flat through the plug-in.
50%	Moderate HPF trim, audible low-mid clean-up, slight presence lift, subtle pick definition. Good starting point for most clean or lightly driven tones.
100% (TIGHT)	Full HPF for the mode, maximum low-mid dip, full presence shelf, strongest transient shaping. Aggressive -- designed for down-tuned or 7/8-string high-gain.

Suggested starting points:

- Single-coil / Strat clean: 25--45%
- Humbucker crunch: 40--60%
- High-gain drop-tuned: 55--80%
- Bass guitar direct: 30--55%

The current value is displayed as a percentage in the label below the knob. Tick marks at the left and right ends label **LOOSE** and **TIGHT**.

MODE (three-position selector)

Sets the overall aggressiveness of the processing at any given TIGHT value.

Mode	HPF range	Low-mid dip (max)	Presence (max)	Transient peak (max)	Best for
Classic	45--110 Hz	-3 dB	+1.5 dB	~+2.7 dB	Clean tones, vintage amp sims, jazz, country -- you want tightness without losing warmth.
Modern	55--150 Hz	-5.5 dB	+3 dB	~+5 dB	The default. Modern high-gain, rock, metal -- balanced tightness and presence.
Extreme	70--220 Hz	-8 dB	+4.5 dB	~+6.6 dB	Djent, drop-tuned 7/8 string, heavily saturated amp sims -- you need maximum clarity under extreme gain.

Switching MODE at any TIGHT setting produces an immediate change in character. If you find that TIGHT above 60% becomes too thin in a particular mode, drop to the mode below rather than reducing TIGHT.

MIX (0 -- 100%, default 100%)

Dry/wet blend. At 100% only the processed signal is heard. Reducing MIX blends in the original unprocessed signal in parallel, which is useful if the full effect is too drastic but you still want some tightening. For most guitar work keep at 100%.

OUTPUT (-24 to +24 dB, default 0 dB)

Master output level after all processing. The HPF and low-mid dip together remove energy, so higher TIGHT values may reduce perceived loudness slightly. Use OUTPUT to compensate and level-match against a bypass.

---

4. Meter

LOW END (left panel)

A single vertical bar meter showing the real-time energy of the ~80 Hz band of the **input** signal. This lets you see how much sub-bass content the HPF is working against, even before it is removed.

- **No bar / very dim**: signal is already clean at the low end. HPF may have little to remove.
- **Moderate bar**: typical for a direct guitar with some pickup resonance or single-coil hum. Nominal operating range.
- **Full bar**: significant low-end content -- often a bass guitar, sub-bass synth, or a guitar with pickup placed very close to the bridge. Increase TIGHT to address it.

The dB scale runs from -60 dB to 0 dB in 10 dB steps.

---

5. System Requirements

Item	Minimum
OS	Windows 10 64-bit or later
CPU	Any modern 64-bit x86 processor
RAM	16 MB (plug-in itself; host requirements vary)
Plugin format	VST3 or CLAP, LV2 (DAW)
Latency	0 samples (no look-ahead)

6. Installation

Windows (64-bit)

- **Easiest:** run `ONE-KNOB-Series-v1.0.0-Windows-x64-Setup.exe`, tick the plug-ins and formats you want and untick the rest.
- **Just this plug-in:** unzip `AtiNAMatiC-Tight-v1.0.0-Windows-x64.zip` and copy:

File	Copy to
`AtiNAMatiC-Tight.vst3`	`C:\Program Files\Common Files\VST3\`
`AtiNAMatiC-Tight.clap`	`C:\Program Files\Common Files\CLAP\`
`AtiNAMatiC-Tight.lv2`	`C:\Program Files\Common Files\LV2\`

macOS 10.15 or later (Apple Silicon and Intel)

- **Easiest:** open `ONE-KNOB-Series-v1.0.0-macOS-Installer.pkg`, click **Customize** and tick the plug-ins and formats you want.
- **Just this plug-in:** unzip `AtiNAMatiC-Tight-v1.0.0-macOS.zip` and copy:

File	Copy to
`AtiNAMatiC-Tight.vst3`	`/Library/Audio/Plug-Ins/VST3/`
`AtiNAMatiC-Tight.component` (AU)	`/Library/Audio/Plug-Ins/Components/`
`AtiNAMatiC-Tight.clap`	`/Library/Audio/Plug-Ins/CLAP/`
`AtiNAMatiC-Tight.lv2`	`/Library/Audio/Plug-Ins/LV2/`

The plug-ins aren't signed by Apple. If macOS blocks the installer, right-click it and choose **Open**. If you copied files from the zip, clear the quarantine flag in Terminal, e.g. `xattr -cr /Library/Audio/Plug-Ins/VST3/AtiNAMatiC-Tight.vst3`.

Linux (x86_64 and ARM64)

- **Easiest:** extract `ONE-KNOB-Series-v1.0.0-Linux-x86_64.tar.gz` (or `-Linux-ARM64`) and run `./install.sh`. It asks which plug-ins and formats to install. Use `./install.sh --system` to install for all users.
- **Just this plug-in:** unzip `AtiNAMatiC-Tight-v1.0.0-Linux-x86_64.zip` (or `-Linux-ARM64`) and copy the `.vst3` folder to `~/.vst3/`, the `.clap` file to `~/.clap/` and the `.lv2` folder to `~/.lv2/`.

Then rescan plug-ins in your DAW.

7. Controls Reference

Control	Range	Default	Unit
TIGHT	0 -- 100	50	%
MODE	Classic / Modern / Extreme	Modern	--
MIX	0 -- 100	100	%
OUTPUT	-24 -- +24	0	dB

8. Internal Signal Chain

```
Input
  |
  +-- [DC Blocker]
  |
  +-- [HPF x2, 4th-order Butterworth]
  |      Cutoff: MODE-dependent linear scale × TIGHT
  |      Classic: 45–110 Hz  |  Modern: 55–150 Hz  |  Extreme: 70–220 Hz
  |
  +-- [Low-mid peaking EQ, 280 Hz]
  |      Gain: 0 to −3 / −5.5 / −8 dB (Classic / Modern / Extreme) × TIGHT
  |      Q: 0.8
  |
  +-- [Presence shelf, 2.5 kHz]
  |      Gain: 0 to +1.5 / +3.0 / +4.5 dB (Classic / Modern / Extreme) × TIGHT
  |
  +-- [Transient shaper]
         Fast envelope (1 ms attack) vs. slow envelope (30 ms attack), shared 120 ms release,
stereo-linked
         Differential gain scales with MODE aggressiveness × TIGHT
  |
  +-- [MIX: parallel blend with dry input]
  |
  +-- [OUTPUT gain]
  |
Output
```

All filter target parameters are smoothed at block rate (40 ms one-pole) to prevent parameter-sweep artifacts.

---

9. Typical Use Cases

Drop-tuned electric guitar (high-gain metal)

Set MODE to **Extreme**, start TIGHT at 65%. The HPF cuts the sub-90 Hz content that would otherwise build up into mud under heavy distortion. The low-mid dip reduces the "boxy" 280 Hz resonance that makes down-tuned guitars sound congested. The presence boost restores pick definition lost under the gain stage.

Bright clean electric / Strat

Set MODE to **Classic**, TIGHT at 30--40%. You want tightness without losing the warmth of the single-coil pickup. Classic mode keeps the HPF at a modest frequency and the dip very subtle.

Direct-in bass guitar

Set MODE to **Modern**, TIGHT at 40--55%. The low-mid dip at 280 Hz removes the nasal resonance common to direct bass. Keep the HPF moderate to preserve fundamental weight. Watch the LOW END meter -- if it is consistently at the top, reduce TIGHT to retain low-end energy.

Acoustic guitar body resonance

Set MODE to **Classic**, TIGHT at 20--40%, MIX at 60--80%. Light parallel tightening removes room boom and body resonance without dulling the top end.

Before amp simulation (best)

Insert AtiNAMatiC-Tight before the amp sim so it feeds a clean, focused source into the distortion stage. The amp's gain will then emphasise the tightened note instead of compressing and fattening the low-end mud.

---

10. Tips

- **Compare LOOSE vs TIGHT at 100% MIX** to hear the maximum range of the plug-in, then dial back to the appropriate level for your source.
- **Use the MIX knob for parallel tightening** when the full effect thins out the tone too much -- 60--80% blend often gives the best of both worlds.
- **Automation**: TIGHT is designed to be automated safely -- the 40 ms parameter smoother prevents clicks even when values jump between notes.
- **Stack with AtiNAMatiC-Gate**: Gate first (pre-amp) to silence the noise floor, then Tight to shape the tone of the notes that pass through.
- **Stack with AtiNAMatiC-Air**: Place Air after the cab IR to add high-frequency shimmer back on top of Tight's controlled low-mid response.
- **Output level**: If you use Tight before an amp sim, check that the output level into the amp is similar to bypass. The dip and HPF remove energy so you may need to add +1--3 dB on the OUTPUT knob.

---

11. About

AtiNAMatiC-Tight is part of the **AtiNAMatiC Series** by **Atij 666 Studio** -- a collection of focused, single-purpose tools built for guitar production.

Built with JUCE 8. No machine-learning models, no online activation.

© 2024 Atij 666 Studio. All rights reserved.