Tbl — A Program to Format Tables[†]

L. L. Cherry M. E. Lesk

Bell Laboratories Murray Hill, New Jersey 07974

ABSTRACT

Tbl is a document formatting preprocessor for *troff* or *nroff* which makes even fairly complex tables easy to specify and enter. Tables are made up of columns which may be independently centered, right-adjusted, left-adjusted, or aligned by decimal points. Headings may be placed over single columns or groups of columns. A table entry may contain equations, or may consist of several rows of text. Horizontal or vertical lines may be drawn as desired in the table, and any table or element may be enclosed in a box. For example:

U. S. Energy Production/Consumption					
	(in quadrillion Btu)				
Year	Voca Production Consumption		Net		
1 cai	all sources		Net		
1953	36.77	36.27	+0.51		
1958	38.81	40.35	-1.54		
1963	45.85	48.32	-2.47		
1968	56.81	61.00	-4.19		
1973	62.06	74.28	-12.22		
1978	61.01	78.09	-17.08		
1983	61.19	70.05	-8.86		
1987	64.55	76.01	-11.46		

1. Introduction.

Tbl turns a simple description of a table into a troff or troffnroff reference(latest program (list of commands) that prints the table. It attempts to isolate a portion of a job that it can successfully handle and leave the remainder for other programs. Thus tbl may be used with the equation formatting program eqn)eqn reference(latest or various layout macro packages reference(latest msmacros) reference(lesk kernighan typesetting) reference(mashey smith documentation), but does not duplicate their functions.

This memorandum is divided into two parts. First we give the rules for preparing *tbl* input; then some examples are shown. The description of rules is

precise but technical, and the beginning user may prefer to read the examples first, as they show some common table arrangements. A section explaining how to invoke *tbl* precedes the examples. To avoid repetition, henceforth read *troff* as "troff or nroff."

The input to *tbl* is text for a document, with tables preceded by a ".TS" (table start) command and followed by a ".TE" (table end) command. *Tbl* processes the tables, generating *troff* formatting commands, and leaves the remainder of the text unchanged. The .TS and .TE lines are copied, too, so that *troff* page layout macros (such as the memo formatting macros reference(latest msmacros)) can use these lines to delimit and place tables as they see fit. In particular, any arguments on the .TS or .TE lines are copied but otherwise ignored, and may be used by document layout macro commands.

[†]This is a version of |reference(v7tbl)| revised by Lorinda Cherry.

The format of the input is as follows:

text .TS table .TE text .TS table .TE

where the format of each table is as follows:

.TS
options;
format.
data
.TE

Each table is independent, and must contain formatting information followed by the data to be entered in the table. The formatting information, which describes the individual columns and rows of the table, may be preceded by a few options that affect the entire table. A detailed description of tables is given in the next section.

2. Input commands.

As indicated above, a table contains, first, global options, then a format section describing the layout of the table entries, and then the data to be printed. The format and data are always required, but not the options. The various parts of the table are entered as follows:

2.1. Options

There may be a single line of options affecting the whole table. If present, this line must follow the .TS line immediately and must contain a list of option names separated by spaces, tabs, or commas, and must be terminated by a semicolon. The allowable options are:

center the table (default is leftcenter adjust); expand make the table as wide as the current line length; box enclose the table in a box: allbox enclose each item in the table in a box: enclose the table in two boxes; doublebox use x instead of tab to separate data tab(x)items.

delim(xy) recognize x and y as the eqn delimiters.

Tbl tries to keep boxed tables on one page by issuing appropriate troff "need" (.ne) commands. These requests are calculated from the number of lines in the tables, and if there are spacing commands embedded in the input, these requests may be inaccurate; use normal troff procedures, such as keep-release macros, in that case. The user who must have a multi-page boxed table should use macros designed for this purpose, as explained below under 'Usage.'

2.2. Format

The format section of the table specifies the layout of the columns. Each line in this section corresponds to one line of the table (except that the last line corresponds to all following lines up to the next .T&, if any — see below), and each line contains a keyletter for each column of the table. It is good practice to separate the key letters for each column by spaces or tabs. Each key-letter is one of the following:

L or 1 to indicate a left-adjusted column entry;

R or r to indicate a right-adjusted column entry;

C or c to indicate a centered column entry;

N or n to indicate a numerical column entry, to be aligned with other numerical entries so that the units digits of numbers line up;

A or a to indicate an alphabetic subcolumn; all corresponding entries are aligned on the left, and positioned so that the widest is centered within the column (see example on page 12);

S or s to indicate a spanned heading, i.e. to indicate that the entry from the previous column continues across this column (not allowed for the first column, obviously); or

to indicate a vertically spanned heading, i.e. to indicate that the entry from the previous row continues down through this row. (Not allowed for the first row of the table, obviously).

When numerical alignment is specified, a location for the decimal point is sought. The rightmost dot(.) adjacent to a digit is used as a decimal point; if there is no dot adjoining a digit, the rightmost digit is used as a units digit; if no alignment is indicated, the item is centered in the column. However, the special non-printing character string \& may be used to

override unconditionally dots and digits, or to align alphabetic data; this string lines up where a dot normally would, and then disappears from the final output. In the example below, the items shown at the left will be aligned (in a numerical column) as shown on the right:

13	13
4.2	4.2
26.4.12	26.4.12
abc	abc
abc\&	abc
43\&3.22	433.22
749.12	749.12

Note: If numerical data are used in the same column with wider L or r type table entries, the widest *number* is centered relative to the wider L or r items (L is used instead of l for readability; they have the same meaning as key-letters). Alignment within the numerical items is preserved. This is similar to the behavior of a type data, as explained above. However, alphabetic subcolumns (requested by the a key-letter) are always slightly indented relative to L items; if necessary, the column width is increased to force this. This is not true for n type entries.

Warning: the n and a items should not be used in the same column.

For readability, the key-letters describing each column should be separated by spaces. The end of the format section is indicated by a period. The layout of the key-letters in the format section resembles the layout of the actual data in the table. Thus a simple format might appear as:

which specifies a table of three columns. The first line of the table contains a heading centered across all three columns; each remaining line contains a left-adjusted item in the first column followed by two columns of numerical data. A sample table in this format might be:

Ove	rall title	
Item-a	34.22	9.1
Item-b	12.65	.02
Items: c,d,e	23	5.8
Total	69.87	14.92

There are some additional features of the key-letter system:

Horizontal lines — A key-letter may be replaced by

_ (underscore) to indicate a horizontal line in place of the corresponding column entry, or by = to indicate a double horizontal line. If an adjacent column contains a horizontal line, or if there are vertical lines adjoining this column, this horizontal line is extended to meet the nearby lines. If any data entry is provided for this column, it is ignored and a warning message is printed.

Vertical lines — A vertical bar may be placed between column key-letters. This will cause a vertical line between the corresponding columns of the table. A vertical bar to the left of the first key-letter or to the right of the last one produces a line at the edge of the table. If two vertical bars appear between key-letters, a double vertical line is drawn.

Space between columns — A number may follow the key-letter. This indicates the amount of separation between this column and the next column. The number normally specifies the separation in ens*. If the "expand" option is used, then these numbers are multiplied by a constant such that the table is as wide as the current line length. The default column separation number is 3. If the separation is changed the worst case (largest space requested) governs.

Vertical spanning — Normally, vertically spanned items extending over several rows of the table are centered in their vertical range. If a keyletter is followed by t or T, any corresponding vertically spanned item will begin at the top line of its range.

Font changes — A key-letter may be followed by a string containing a font name or number preceded by the letter f or F. This indicates that the corresponding column should be in a different font from the default font (usually Roman). All font names are one or two letters; a one-letter font name should be separated from whatever follows by a space or tab. The single letters B, b, I, and i are shorter synonyms for fB and fI and refer to the bold and italic fonts in the current font family. Font change commands given with the table entries override these specifications.

Point size changes — A key-letter may be followed by the letter p or P and a number to indicate the point size of the corresponding table entries.

^{*} One en is about the width of the letter 'n', or more precisely, half the current type size measured in points (1 point = 1/72 inch).

The number may be a signed digit, in which case it is taken as an increment or decrement from the current point size. If both a point size and a column separation value are given, one or more blanks must separate them.

Vertical spacing changes — A key-letter may be followed by the letter v or V and a number to indicate the vertical line spacing to be used within a multi-line corresponding table entry. The number may be a signed digit, in which case it is taken as an increment or decrement from the current vertical spacing. A column separation value must be separated by blanks or some other specification from a vertical spacing request. This request has no effect unless the corresponding table entry is a text block (see below).

Column width indication — A key-letter may be followed by the letter w or W and a width value in parentheses. This width is used as a minimum column width. If the largest element in the column is not as wide as the width value given after the w, the largest element is assumed to be that wide. If the largest element in the column is wider than the specified value, its width is used. The width is also used as a default line length for included text blocks. Normal troff units can be used to scale the width value; if none are used, the default is ens. If the width specification is a unitless integer the parentheses may be omitted. If the width value is changed in a column, the last one given controls.

Equal width columns — A key-letter may be followed by the letter e or E to indicate equal width columns. All columns whose key-letters are followed by e or E are made the same width. This permits the user to get a group of regularly spaced columns.

Staggered columns — A key-letter may be followed by the letter u or U to indicate that the corresponding entry is to be moved up one half line. This makes it easy, for example, to have a column of differences between numbers in an adjoining column. The allbox option does not work with staggered columns.

Zero-width item — A key-letter may be followed by the letter z or Z to indicate that the corresponding data item is to be ignored in calculating column widths. This may be useful, for example, in allowing headings to run across adjacent columns where spanned headings would be inappropriate.

Note: The order of the above features is immaterial; they need not be separated by spaces, except as indicated above to avoid ambiguities involving point size and font changes. Thus a numerical column entry in italic font and 12 point type with a minimum width of 2.5 inches and separated by 6 ens from the next column could be specified as

np12w(2.5i)fI 6

Alternative notation — Instead of listing the format of successive lines of a table on consecutive lines of the format section, successive line formats may be given on the same line, separated by commas, so that the format for the example above might have been written:

css, lnn.

Default — Column descriptors missing from the end of a format line are assumed to be L. The longest line in the format section, however, defines the number of columns in the table; extra columns in the data are ignored silently.

2.3. Data

The data for the table are typed after the format. Normally, each table line is typed as one line of data. Very long input lines can be broken: any line whose last character is \ is combined with the following line (and the \ vanishes). The data for different columns (the table entries) are separated by tabs, or by whatever character has been specified with the option tabs. There are a few special cases:

Troff commands within tables — An input line beginning with a . followed by anything but a number is assumed to be a command to troff and is passed through unchanged, retaining its position in the table. So, for example, vertical space within a table may be produced by .sp commands in the data.

Full width horizontal lines — An input line containing only _ (underscore) or = (equal sign) is taken to be a single or double line, respectively, extending the full width of the table.

Single column horizontal lines — An input table entry containing only the character _ or = is taken to be a single or double line extending the full width of the column. Such lines are extended to meet horizontal or vertical lines adjoining this column. To obtain these characters explicitly in a column, either precede them by \& or follow them by a space before the usual tab or newline.

Short horizontal lines — An input table entry containing only the string _ is taken to be a single line as wide as the contents of the column. It is not extended to meet adjoining lines.

Repeated characters — An input table entry containing only a string of the form \Rx where x is any character is replaced by repetitions of the character x as wide as the data in the column. The sequence of x's is not extended to meet adjoining columns.

Vertically spanned items — An input table entry containing only the character string \^ indicates that the table entry immediately above spans downward over this row. It is equivalent to a table format key-letter of ^.

Text blocks — In order to include a block of text as a table entry, precede it by T{ and follow it by T}. Thus the sequence

```
... T{
block of
text
T}...
```

is the way to enter, as a single entry in the table, something that cannot conveniently be typed as a simple string between tabs. Note that the T} end delimiter must begin a line; additional columns of data may follow after a tab on the same line. See the example on page 44 for an illustration of included text blocks in a table. If more than fifty or so text blocks are used in a table, various limits in the *troff* program are likely to be exceeded, producing diagnostics such as 'too many string/macro names' or 'too many number registers.'

Text blocks are pulled out from the table, processed separately by troff, and replaced in the table as a solid block. If no line length is specified in the block of text tself, or in the table format, the default is to use $L \times C/(N+1)$ where L is the current line length, C is the number of table columns spanned by the text, and N is the total number of columns in the table. The other parameters (point size, font, etc.) used in setting the block of text are those in effect at the beginning of the table (including the effect of the . TS macro) and any table format specifications of size, spacing and font, using the p, v and f modifiers to the column key-letters. Commands within the text block itself are also recognized, of course. However, troff commands within the table data but not within the text block do not affect that block.

Warnings: Although any number of lines may be

present in a table, only the first 200 lines are used in calculating the widths of the various columns. A multi-page table, of course, may be arranged as several single-page tables if this proves to be a problem. Other difficulties with formatting may arise because, in the calculation of column widths all table entries are assumed to be in the font and size being used when the . TS command was encountered, except for font and size changes indicated (a) in the table format section and (b) within the table data (as in the entry $s+3\left(\frac{p}{s0}\right)$. Therefore, although arbitrary troff requests may be sprinkled in a table, care must be taken to avoid confusing the width calculations; use requests such as .ps with care.

2.4. Additional Command Lines

If the format of a table must be changed after many similar lines, as with sub-headings or summarizations, the .T& (table continue) command can be used to change column parameters. The outline of such a table input is:

```
.TS options; format. data
...
.T& format. data
.T& format. data
.T& format.
```

as in the examples on pages 43 and 46. Using this procedure, each table line can be close to its corresponding format line.

Warning: It is not possible to change the number of columns, the space between columns, the global options such as *box*, or the selection of columns to be made equal width. Nor is .T& recognized after the first 200 lines of a table.

3. Usage.

On UNIX® systems, tbl can be run on a simple table with the command

```
tbl input-file | troff
```

but for more complicated use, where there are several input files, and they contain equations and -ms layout commands as well as tables, the normal command

would be

and, of course, the usual options may be used on the *troff* and *eqn* commands. If any of the file names are – the standard input is read at that point.

For the convenience of users employing line printers without adequate driving tables or post-filters, there is a special -TX command line option to *tbl* which produces output that does not have fractional line motions in it.

Note that when eqn and tbl are used together on the same file, tbl should be used first. If there are no equations within tables, either order works, but it is usually faster to run tbl first, since eqn normally produces a larger expansion of the input than tbl. However, if there are equations within tables (using the delim mechanism in eqn), tbl must be first or the output will be scrambled. Users must also beware of using equations in n-style columns; this is nearly always wrong, since tbl attempts to split numerical format items into two parts and this is not possible with equations. The user can defend against this by giving the delim(xx) table option; this prevents splitting of numerical columns within the delimiters. For example, if the eqn delimiters are \$\$, giving delim(\$\$) a numerical column such as 1245\$+- 16\$ will be divided after 1245, not after 16.

Tbl accepts up to about 35 columns, the exact number depending on the availability of number registers. The user must avoid number register names used by *tbl*, which include two-digit numbers from 31 to 97, and strings of the form 4x, 5x, #x, x+, $x \mid$, x , and x-, where x is any lower case letter. The names ##, #-, and $\#^$ are also used in certain circumstances. To conserve number register names, the n and a formats share a register; hence the restriction above that they may not be used in the same column.

For aid in writing layout macros, *tbl* defines a number register TW which is the table width; it is defined by the time that the .TE macro is invoked and may be used in the expansion of that macro. More importantly, to assist in laying out multi-page boxed tables the macro T# is defined to produce the bottom lines and side lines of a boxed table, and then invoked at its end. By use of this macro in the page footer a multi-page table can be boxed. In particular, the -ms macros can be used to print a multi-page boxed table with a repeated heading by giving the argument H to the .TS macro. If the table start macro is written

• TH

must be given in the table after any table heading (or at the start if none). Material up to the .TH is placed at the top of each page of table; the remaining lines in the table are placed on several pages as required. Note that this is *not* a feature of *tbl*, but of the -ms layout macros.

4. Examples.

Here are some examples illustrating features of tbl. The symbol \oplus in the input represents a tab character.

Input:

.TS box; c c c11r. Fact © Location © Statistic

Largest state

Alaska

591,004 sq. mi. Smallest state © Rhode Island © 1,212 sq. mi.

Longest river © Mississippi-Missouri © 3,710 mi.

Highest mountain ⊕ Mount McKinley, AK ⊕ 20,320 ft.

Lowest point © Death Valley, CA © -282 ft.

.TE

Input:

```
.TS
allbox;
c s s
ссс
nnn.
AT&T Common Stock
Year © Price © Dividend
1984 © 15-20 © $1.20
5 \( \Dag{19-25} \( \Dag{1.20} \)
6 \oplus 21\text{-}28 \oplus 1.20
7 © 20-36 © 1.20
8 \oplus 24\text{-}30 \oplus 1.20
9 \oplus 29\text{-}37 \oplus .30*
.TE
```

* (first quarter only)

Input:

.TS
box;
css
c c c
1 1 n.
Major New York Bridges
=
Bridge Designer Length
Brooklyn © J. A. Roebling © 1595 Manhattan © G. Lindenthal © 1470 Williamsburg © L. L. Buck © 1600
_ ⊕ ⊕ 1380 Triborough ⊕ O. H. Ammann ⊕_

Output:

Fact	Location	Statistic
Largest state	Alaska	591,004 sq. mi.
Smallest state	Rhode Island	1,212 sq. mi.
Longest river	Mississippi-Missouri	3,710 mi.
Highest mountain	Mount McKinley, AK	20,320 ft.
Lowest point	Death Valley, CA	-282 ft.

Output:

AT&T Common Stock			
Year	ar Price Divider		
1984	15-20	\$1.20	
5	19-25	1.20	
6	21-28	1.20	
7	20-36	1.20	
8	24-30	1.20	
9	29-37	.30*	

^{* (}first quarter only)

Bronx Whitestone © O. H. Ammann © 2300 Throgs Neck © O. H. Ammann © 1800

George Washington © O. H. Ammann © 3500 .TE

Output:

Major New York Bridges			
Bridge	Length		
Brooklyn	J. A. Roebling	1595	
Manhattan	G. Lindenthal	1470	
Williamsburg	L. L. Buck	1600	
Queensborough	Palmer &	1182	
	Hornbostel		
		1380	
Triborough	O. H. Ammann		
		383	
Bronx Whitestone	O. H. Ammann	2300	
Throgs Neck	O. H. Ammann	1800	
George Washington	O. H. Ammann	3500	

Input:

Output:

Input:

Output:

march
Months
december

Input:

.FP helvetica

.TS

box; cf(CW s s s. Composition of Foods

Input:

.TS allbox; cfI s s c cw(1i) cw(1i) lp9 lp9 lp9. New York Area Rocks Era © Formation © Age (years) Precambrian ⊕ Reading Prong ⊕>1 billion Paleozoic

Manhattan Prong

400 million Mesozoic ⊕ T{ .na Newark Basin, incl. Stockton, Lockatong, and Brunswick formations; also Watchungs and Palisades. T) \oplus 200 million Cenozoic

Coastal Plain

T{ On Long Island 30,000 years; Cretaceous sediments redeposited by recent glaciation. .ad **T**} .TE

Output:

Composition of Foods			
	Percent by Weight		
Food	Protein	Fat	Carbo-
			hydrate
Apples	.4	.5	13.0
Halibut	18.4	5.2	
Lima beans	7.5	.8	22.0
Milk	3.3	4.0	5.0
Mushrooms	3.5	.4	6.0
Rye bread	9.0	.6	52.7

Output:

New York Area Rocks				
Era	Formation	Age (years)		
Precambrian	Reading Prong	>1 billion		
Paleozoic	Manhattan Prong	400 million		
Mesozoic	Newark Basin, incl. Stockton, Lockatong, and Brunswick formations; also Watchungs and Palisades.	200 million		
Cenozoic	Coastal Plain	On Long Island 30,000 years; Cretaceous sediments redeposited by recent glaciation.		

Input:

.EQ
delim \$\$
.EN

...
.TS
doublebox;
c c
11.
Name © Definition
.sp
.vs +2p

Gamma \oplus \$GAMMA (z) = int sub 0 sup inf t sup {z-1} e sup -t dt\$

Zeta \oplus \$ zeta (s) = sum from k=1 to inf k sup -s \sim (Re \sim s > 1)\$

Error \circ \$ roman erf (z) = 2 over sqrt pi int sub 0 sup z e sup {-t sup 2} dt\$ Bessel \circ \$ J sub 0 (z) = 1 over pi int sub 0 sup pi cos (z sin theta) d theta \$

Sine \oplus \$sin (x) = 1 over 2i (e sup ix - e sup -ix)\$

Output:

Name	Definition
	a [∞]
Gamma	$\Gamma(z) = \int_0^\infty t^{z-1} e^{-t} dt$ $\sin(x) = \frac{1}{2i} (e^{ix} - e^{-ix})$
	1
Sine	$\sin(x) = \frac{1}{2!} (e^{ix} - e^{-ix})$
Error	$\operatorname{erf}(z) = \frac{2}{1-z^2} \int_0^z e^{-t^2} dt$
	$\operatorname{erf}(z) = \frac{2}{\sqrt{\pi}} \int_0^z e^{-t^2} dt$
	$J_0(z) = \frac{1}{\pi} \int_0^{\pi} \cos(z \sin \theta) d\theta$
Bessel	$J_0(z) = \frac{1}{\pi} \int_0^{\pi} \cos(z \sin \theta) d\theta$
	∞
Zeta	$\zeta(s) = \sum k^{-s} (\text{Re } s > 1)$
	k=1

Input:

.TS

.vs -2p .TE

box, tab(:); cb s s s s cp-2 s s s s c | c | c | c | c c | | c | c | c | c r2 | n2 n2 n2 n. Readability of Text Line Width and Leading for 10-Point Type Line: Set: 1-Point: 2-Point: 4-Point Width: Solid: Leading: Leading: Leading 9 Pica:\-9.3:\-6.0:\-5.3:\-7.1 14 Pica:\-4.5:\-0.6:\-0.3:\-1.7 19 Pica:\-5.0:\-5.1: 0.0:\-2.0 31 Pica:\-3.7:\-3.8:\-2.4:\-3.6 43 Pica:\-9.1:\-9.0:\-5.9:\-8.8 .TE

Output:

Readability of Text				
ne Width a	and Leading f	or 10-Point T	`ype	
Line Set 1-Point 2-Point 4-Point				
Solid	Leading	Leading	Leading	
-9.3	-6.0	-5.3	-7.1	
-4.5	-0.6	-0.3	-1.7	
-5.0	-5.1	0.0	-2.0	
-3.7	-3.8	-2.4	-3.6	
-9.1	-9.0	-5.9	-8.8	
	Set Solid -9.3 -4.5 -5.0 -3.7	Set New Width and Leading for Set I-Point Solid Leading Leading -9.3 -6.0 -4.5 -0.6 -5.0 -5.1 -3.7 -3.8	Re Width and Leading for 10-Point T Set 1-Point 2-Point Solid Leading Leading -9.3 -6.0 -5.3 -4.5 -0.6 -0.3 -5.0 -5.1 0.0 -3.7 -3.8 -2.4	

Input:

.TS
c s
cip-2 s
l n
a n.
Some London Transport Statistics
(Year 1964)
Railway route miles © 244
Tube © 66

Sub-surface ⊕ 22	Output:	
Surface © 156	Some London Transpor	rt Statistics
.sp .5	(Year 1964)	
.T&	Railway route miles	244
lr	Tube	66
ar.	Sub-surface	22
Passenger traffic \- railway	Surface	156
Journeys © 674 million Average length © 4.55 miles	Passenger traffic – railway	
Passenger miles © 3,066 million	Journeys	674 million
.T&	Average length	4.55 miles
lr	Passenger miles	3,066 million
ar.	Passenger traffic – road	3,000 illillion
Passenger traffic \- road	Journeys	2,252 million
Journeys © 2,252 million	Average length	2.26 miles
Average length © 2.26 miles	Passenger miles	5,094 million
Passenger miles © 5,094 million	_	
.T&	Vehicles	12,521
1 n	Railway motor cars	2,905
an.	Railway trailer cars	1,269
.sp .5	Total railway Omnibuses	4,174
Vehicles © 12,521	Offinibuses	8,347
Railway motor cars © 2,905	Staff	73,739
Railway trailer cars © 1,269	Administrative, etc.	5,582
Total railway ⊕ 4,174	Civil engineering	5,134
Omnibuses © 8,347	Electrical eng.	1,714
.T&	Mech. eng. – railway	4,310
l n	Mech. eng. – road	9,152
an.	Railway operations	8,930
.sp .5	Road operations	35,946
Staff © 73,739	Other	2,971
Administrative, etc. © 5,582		
Civil engineering © 5,134		
Electrical eng. © 1,714 Mech. eng. \- railway © 4,310		
Mech. eng. $\$ rankway $0.4,510$ Mech. eng. $\$ road $0.9,152$		
Railway operations © 8,930		
Road operations © 35,946		
Other © 2,971		
.TE		
Input:		
.TS		
center box;		
cBp+2 s s		
cB s s		
li l lb. Crisis and Emergency Numbers		
•sp		
24-Hour Hotlines		
Abuse © Child Abuse Reports © 1-800-792-8610		
.sp .5 Alcohol ⊕ Ala-Call ⊕ 1-800-322-5525		
Alcohol © Overdose © 1-800-962-1253		
.sp .5		
Drug ① Drug Hotline ① 1-800-225-0196		
Drug © Overdose © 1-800-962-1253		

```
Drug D Narcotics Anonymous D 1-800-992-0401
.sp .5
Poison © Poison Hotline © 1-800-962-1253
.sp .5
Runaways @ Hotline @ 1-800-231-6946
Runaways © Covenant House © 1-800-999-9999
.T&
cB s s
li l lb.
Other Hotlines
AIDS ® National AIDS Hotline ® 1-800-342-AIDS
AIDS ® NJ AIDS Hotline ® 1-800-624-2377
Drug © Cocaine © 1-800-COCAINE
Eating © Eating Disorders Hotline © 1-800-624-2268
Support <sup>⊕</sup> Support Group Information <sup>⊕</sup> 1-800-367-6274
VD © VD Information © 1-800-227-8922
.TE
```

Output:

Crisis and Emergency Numbers			
24-Hour Hotlines			
Abuse	Child Abuse Reports	1-800-792-8610	
Alcohol	Ala-Call	1-800-322-5525	
Alcohol	Overdose	1-800-962-1253	
Drug	Drug Hotline	1-800-225-0196	
Drug	Overdose	1-800-962-1253	
Drug	Narcotics Anonymous	1-800-992-0401	
Poison	Poison Hotline	1-800-962-1253	
Runaways	Hotline	1-800-231-6946	
Runaways	Covenant House	1-800-999-9999	
	Other Hotlines		
AIDS	National AIDS Hotline	1-800-342-AIDS	
AIDS	NJ AIDS Hotline	1-800-624-2377	
Drug	Cocaine	1-800-COCAINE	
Eating	Eating Disorders Hotline	1-800-624-2268	
Support	Support Group Information	1-800-367-6274	
VD	VD Information	1-800-227-8922	

This is a paragraph of normal text placed here only to indicate where the left and right margins are. In this way the reader can judge the appearance of centered tables or expanded tables, and observe how such tables are formatted.

Input:

.TS
expand;
cssss
cccc
llnn.

New Jersey Bell Labs Locations
Name © Address © Area Code © Phone
Chester © Chester, NJ 07930 © 201 © 879-3400
Corporate Park III © Somerset, NJ 08873 © 201 © 271-2300
Crawford Hill © Holmdel, NJ 07733 © 201 © 888-7000
ERC © Hopewell Township, NJ 08525 © 609 © 639-1234
Freehold © Freehold, NJ 07728 © 201 © 577-5000
Headquarters Plaza © Morristown, NJ 07960 © 201 © 898-6000
Holmdel © Holmdel, NJ 07733 © 201 © 834-1000

Knightsbridge © Piscataway, NJ 08854 © 201 © 457-2000 Liberty Corner © Warren, NJ 07060 © 201 © 580-4000 Lincroft © Lincroft, NJ 07738 © 201 © 576-4000 Middletown © Middletown, NJ 07748 © 201 © 957-2000 Morris O Morristown, NJ 07960 O 201 O 898-1000 Murray Hill ⊕ Murray Hill, NJ 07974 ⊕ 201 ⊕ 582-3000 Parsippany © Parsippany, NJ 07054 © 201 © 299-3000 Patriots Plaza © Morristown, NJ 07960 © 201 © 829-7200 Red Hill [©] Middletown, NJ 07748 [©] 201 [©] 949-3000 Short Hills ⊕ Short Hills, NJ 07078 ⊕ 201 ⊕ 564-2000 Somerset © Somerset, NJ 08873 © 201 © 560-1300 Summit [⊕] Summit, NJ 07901 [⊕] 201 [⊕] 522-6555 Warren Service Center © Warren, NJ 07060 © 201 © 756-1527 West Long Branch ${\mathbb O}$ West Long Branch, NJ 07764 ${\mathbb O}$ 201 ${\mathbb O}$ 870-7000 Woodhollow Darsippany, NJ 07054 D 201 D 581-3000 .TE

Output:

New Jersey Bell Labs Locations

Name	Address	Area Code	Phone
Chester	Chester, NJ 07930	201	879-3400
Corporate Park III	Somerset, NJ 08873	201	271-2300
Crawford Hill	Holmdel, NJ 07733	201	888-7000
ERC	Hopewell Township, NJ 08525	609	639-1234
Freehold	Freehold, NJ 07728	201	577-5000
Headquarters Plaza	Morristown, NJ 07960	201	898-6000
Holmdel	Holmdel, NJ 07733	201	834-1000
Knightsbridge	Piscataway, NJ 08854	201	457-2000
Liberty Corner	Warren, NJ 07060	201	580-4000
Lincroft	Lincroft, NJ 07738	201	576-4000
MDC	Hopewell Township, NJ 08525	609	639-6100
Middletown	Middletown, NJ 07748	201	957-2000
Morris	Morristown, NJ 07960	201	898-1000
Murray Hill	Murray Hill, NJ 07974	201	582-3000
Parsippany	Parsippany, NJ 07054	201	299-3000
Patriots Plaza	Morristown, NJ 07960	201	829-7200
Red Hill	Middletown, NJ 07748	201	949-3000
Short Hills	Short Hills, NJ 07078	201	564-2000
Somerset	Somerset, NJ 08873	201	560-1300
Summit	Summit, NJ 07901	201	522-6555
Warren Service Center	Warren, NJ 07060	201	756-1527
West Long Branch	West Long Branch, NJ 07764	201	870-7000
Whippany	Whippany, NJ 07981	201	386-3000
Woodhollow	Parsippany, NJ 07054	201	581-3000

```
Input:
   .TS
   box:
   cb s s s
   c \mid c \mid c \mid s
   ltiw(1i) | ltw(2i) | lp8 | lw(1.6i)p8.
   Some Interesting Places
   Name Description Description
   American Museum of Natural History
   The collections fill 11.5 acres (Michelin) or 25 acres (MTA)
   of exhibition halls on four floors. There is a full-sized replica
   of a blue whale and the world's largest star sapphire (stolen in 1964).
   T} O Hours O 10-5:45 S M Tu Th, 10-9 W Sat. Sun.
   \hat{\mathbb{T}} \^ \O \can \D Location \O T{
   Central Park West & 79th St.
   T}
   ^{\oplus} \^{\oplus} Admission ^{\oplus} Donation: $1.00 asked
   \^ O \^ O Subway O AA to 81st St.
   \^ ① \^ ① Telephone ① 212-769-5100
   Bronx Zoo T T
   About a mile long and .6 mile wide, this is the largest zoo in America.
   A lion eats 18 pounds
   of meat a day while a sea lion eats 15 pounds of fish.
   T \ \O Hours \O T \{
   10-5 M-Sat, to 5:30 Sun
   \^ ① \^ ① Location ① T{
   185th St. & Southern Blvd, the Bronx.
   \^ ① \^ ① Admission ① $3.75/1.50 adult/children; Tu,We,Th donation
   \^ O \^ O Subway O 2, 5 to East Tremont Ave.
   Brooklyn Museum O T{
   Five floors of galleries contain American and ancient art.
   There are American period rooms and architectural ornaments saved
   from wreckers, such as a classical figure from Pennsylvania Station.
   T} ① Hours ① 10-5, closed Tues
   \^ ① \^ ① Location ① T{
   Eastern Parkway & Washington Ave., Brooklyn.
   \^ \O \^ \O Subway \O 2,3 to Eastern Parkway.
   \^ \O \^ \O Telephone \O 212-367-1010
   New-York Historical Society
   T D T (
   All the original paintings for Audubon's
   Birds of America
   are here, as are exhibits of American decorative arts, New York history,
   Hudson River school paintings, carriages, and glass paperweights.
   T\} \mathbin{\hbox{$\,@$}} Hours \mathbin{\hbox{$\,@$}} T\{
   Tues-Sun, 10-5
   T}
   ^{\mathbb{T}} \^ \O \cap \ Location \O T{
   Central Park West & 77th St.
   T}
   \^ ① \^ ① Admission ① Free
```

.TE

Output:

Some Interesting Places			
Name	Description	Practical Information	
American	The collections fill 11.5 acres	Hours	10-5:45 S M Tu Th, 10-9 W Sat. Sun.
Museum of Natu-	(Michelin) or 25 acres (MTA) of	Location	Central Park West & 79th St.
ral History	exhibition halls on four floors.	Admission	Donation: \$1.00 asked
	There is a full-sized replica of a	Subway	AA to 81st St.
	blue whale and the world's largest	Telephone	212-769-5100
	star sapphire (stolen in 1964).		
Bronx Zoo	About a mile long and .6 mile	Hours	10-5 M-Sat, to 5:30 Sun
	wide, this is the largest zoo in	Location	185th St. & Southern Blvd, the Bronx.
	America. A lion eats 18 pounds of	Admission	\$3.75/1.50 adult/children; Tu,We,Th donation
	meat a day while a sea lion eats 15	Subway	2, 5 to East Tremont Ave.
	pounds of fish.	Telephone	212-367-1010
Brooklyn Museum	Five floors of galleries contain	Hours	10-5, closed Tues
	American and ancient art. There	Location	Eastern Parkway & Washington Ave.,
	are American period rooms and		Brooklyn.
	architectural ornaments saved from	Admission	Free
	wreckers, such as a classical figure	Subway	2,3 to Eastern Parkway.
	from Pennsylvania Station.	Telephone	718-638-5000
New-York Histor-	All the original paintings for	Hours	Tues-Sun, 10-5
ical Society	Audubon's Birds of America are	Location	Central Park West & 77th St.
	here, as are exhibits of American	Admission	Free
	decorative arts, New York history,	Subway	AA to 81st St.
	Hudson River school paintings,	Telephone	212-873-3400
	carriages, and glass paperweights.		

5. Acknowledgments.

Many thanks are due to J. C. Blinn, who has done a large amount of testing and assisted with the design of the program. He has also written many of the more intelligible sentences in this document and helped edit all of it. All phototypesetting programs on UNIX are dependent on the work of the late J. F. Ossanna, whose assistance with this program in particular had been most helpful. This program is patterned on a table formatter originally written by J. F. Gimpel. The assistance of T. A. Dolotta, B. W. Kernighan, and J. N. Sturman is gratefully acknowledged.

6. References.

reference placement

7. List of Tbl Command Characters and Words

Command	Meaning	Section
a A	Alphabetic subcolumn	2.2
allbox	Draw box around all items	2.1
b B	Boldface item	2.2
box	Draw box around table	2.1
c C	Centered column	2.2
center	Center table in page	2.1
delim(xy)	Set eqn delimiters	2.1
doublebox	Doubled box around table	2.1
e E	Equal width columns	2.2
expand	Make table full line width	2.1
f F	Font change	2.2
i I	Italic item	2.2
1 L	Left adjusted column	2.2
linesize(n)	Set point size for drawing lines	2.1

n N	Numerical column	2.2
nnn	Column separation	2.2
pР	Point size change	2.2
r R	Right adjusted column	2.2
s S	Spanned item	2.2
t T	Vertical spanning at top	2.2
tab(x)	Change data separator character	2.1
$T\{T\}$	Text block	2.3
u U	Staggered columns	2.2
v V	Vertical spacing change	2.2
w W	Minimum width value	2.2
z Z	Ignore width of data in this column	2.2
. xx	Included troff command	2.3
	Vertical line	2.2
	Double vertical line	2.2
^	Vertical span	2.2
\^	Vertical span	2.3
=	Double horizontal line	2.3
_	Horizontal line	2.3
_	Short horizontal line	2.3
\Rx	Repeat character	2.3