Project Smart Layer by Azam Puri

What the mill needs to provide to install the app (read-only on your ERP)

In one line

The app sits on top of your ERP, **only reads** it (never changes anything), and shows you clean reports and alerts on a web page. It is installed on **one computer that stays on**; everyone else just opens a web page in their browser.

Collect these before we start (tick each box)

- ■ **A computer that stays on** - a Windows PC (Windows 10 or 11, 64-bit) that is never switched off, sitting near your ERP server, on the **same network/LAN** as it. 8 GB RAM and 20 GB free space is plenty. (Do not use a personal laptop that sleeps.)
- ■ **The ERP database login (view-only)** - three things written on a paper: (1) the database **address** as `host:port/service` (e.g. `192.168.18.199:1521/orcl`), (2) a **username**, (3) its **password**. Ask your ERP/IT person for a **read-only** login - one that can look but not change.
- ■ **(Oracle 11g only) the Oracle Instant Client** - a free small download from Oracle ("Instant Client Basic Light, Windows 64-bit"). Unzip it to a simple folder like `C:\oracle\instantclient_23` and remember that folder. If your ERP is Oracle 12c or newer, you may not need this.
- ■ **(If you have a loom scoreboard) its database file** - the loom monitor (e.g. OLMS) keeps an Access file like `OLMSDB.mdb`. Make a copy of it to a fixed folder, e.g. `E:\scoreboard_copy\OLMSDB_copy.mdb`, and remember that path. (The app reads the copy so it never disturbs the live scoreboard.) Skip this if you have no scoreboard.
- ■ **The mill's name** - exactly how you want it shown on the dashboard.
- ■ **Internet on this PC for one minute** - only to send us the machine ID and get your licence.

How to install - click by click

- 1. Copy `SmartLayer-Setup.exe` onto the always-on PC and **double-click** it.
- 2. If a blue box says *"Windows protected your PC"*, click **More info**, then **Run anyway** (this is normal for new apps).
- 3. Click **Next** / **Install**, wait for the bar to fill, then **Finish**.
- 4. A **setup window** opens and asks questions one at a time. Type the answers you collected above (mill name, then the database address, username, password; the Oracle folder if asked; the scoreboard copy path if you have one; and a **dashboard password** you choose). Press Enter after each.
- 5. It then **reads your ERP once** to recognise it, and does the **first sync** (pulling the data). This can take a few minutes - let it finish and leave the window open until it says it is done.

Get your licence - one time

- Open the black command window (Start menu → type `cmd`), then type `SmartLayer.exe machine-id` and press Enter. It prints a long ID.
- Send us that ID. We send back a licence code tied to this one PC.
- Open the dashboard, go to the **Licence** screen, and paste the code. Done.

Check the numbers are right

- Type `SmartLayer.exe check --deep` and press Enter. It checks the pulled data and **flags anything that looks wrong** (so you know before trusting a report).

Open the dashboard

- On this PC: open a browser and go to `http://localhost:8080`.
- On a phone or another PC on the mill network: `http://<this-PC-address>:8080` (ask IT for this PC's address, e.g. `192.168.18.50`).
- The data refreshes by itself on a schedule. To pull fresh data by hand any time: `SmartLayer.exe sync`.

If your ERP is a new one we have not seen

The app reads your ERP once at setup and recognises it automatically. If it is a brand-new ERP we have not profiled, it drafts the connection and flags the few things it is unsure about for a one-time confirm - then it works the same as any other mill.

The app NEVER	
Writes to the ERP	every connection is read-only (SET TRANSACTION READ ONLY)
Sends mill data out	all data stays on the mill's own PC
Needs admin DB rights	a plain read-only login is enough