

AZWAW AIMENE

Procédure Installation et configuration [UniFi OS Server](#)



Introduction-----	3
Environnement: -----	3
Configuration de l'IP statique -----	3
Installation de Podman-----	5
Téléchargement de l'installateur UniFi OS Server -----	5
Lancement de l'installation -----	6
Vérification du service -----	6
Configuration initiale de UniFi OS Server -----	8
Choix du type de compte -----	9
Création du réseau Wi-Fi-----	12
Test de connexion -----	13

Introduction

Cette procédure décrit le processus d'installation et de configuration d'un serveur UniFi sur Debian 12 à l'aide de Podman, afin de gérer de manière centralisée les équipements réseau Ubiquiti dans un environnement conteneurisé.

Environnement:

- Mini PC Skareudi
- IP 192.168.1.10
- Debian 12 Server
- AP Ubiquiti U7 Outdoor.
- Pfsense
- TPLink switch

Configuration de l'IP statique

Vérification de l'interface réseau et configuration d'une IP fixe dans `/etc/network/interfaces` en passant en root avec `su -`

```
unifi@unifi:~$ ip a
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN group default qlen 1000
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
    inet 127.0.0.1/8 scope host lo
        valid_lft forever preferred_lft forever
    inet6 ::1/128 scope host noprefixroute
        valid_lft forever preferred_lft forever
2: enp1s0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc mq state UP group default qlen 1000
    link/ether 00:e2:69:a4:22:13 brd ff:ff:ff:ff:ff:ff
    inet 192.168.1.102/24 brd 192.168.1.255 scope global dynamic enp1s0
        valid_lft 6746sec preferred_lft 6746sec
    inet6 fe80::2e2:69ff:fea4:2213/64 scope link
        valid_lft forever preferred_lft forever
3: enp2s0: <BROADCAST,MULTICAST> mtu 1500 qdisc noop state DOWN group default qlen 1000
    link/ether 00:e2:69:a4:22:14 brd ff:ff:ff:ff:ff:ff
4: enp3s0: <BROADCAST,MULTICAST> mtu 1500 qdisc noop state DOWN group default qlen 1000
    link/ether 00:e2:69:a4:22:15 brd ff:ff:ff:ff:ff:ff
5: enp4s0: <BROADCAST,MULTICAST> mtu 1500 qdisc noop state DOWN group default qlen 1000
    link/ether 00:e2:69:a4:22:16 brd ff:ff:ff:ff:ff:ff
unifi@unifi:~$
```

En tape `nano /etc/networking/interfaces`

```

GNU nano 7.2 /etc/network/interfaces
# This file describes the network interfaces available on your system
# and how to activate them. For more information, see interfaces(5).

source /etc/network/interfaces.d/*

# The loopback network interface
auto lo
iface lo inet loopback

# The primary network interface
auto enp1s0
iface enp1s0 inet static
    address 192.168.1.10
    netmask 255.255.255.0
    gateway 192.168.1.1
    dns-nameservers 8.8.8.8

```

- La configuration :
 - Adresse : IP 192.168.1.10,
 - Masque 255.255.255.0,
 - Passerelle 192.168.1.1,
 - DNS 8.8.8.8.
 - Le service réseau est redémarré en tape **systemctl restart networking** pour appliquer les changements.

Installation de Podman

Installation des paquets nécessaires en root : en passe en mode root en tape **su -**

En tape **apt install -y podman uidmap slirp4netns iptables curl wget ca-certificates**

```

root@unifi:~# apt install -y podman uidmap slirp4netns iptables curl wget ca-certificates
Lecture des listes de paquets... Fait
Construction de l'arbre des dépendances... Fait
Lecture des informations d'état... Fait
wget est déjà la version la plus récente (1.21.3-1+deb12u1).
ca-certificates est déjà la version la plus récente (20230311+deb12u1).
Les paquets supplémentaires suivants seront installés :
  aardvark-dns buildah catatonit common containernetworking-plugins crun dirmngr fuse-overlayfs
  gnupg gnupg-l10n gnupg-utils golang-github-containers-common golang-github-containers-image g

```

- Vérification de la version installée : **podman --version**

```

root@unifi:~# podman --version
podman version 4.3.1

```

Téléchargement de l'installateur UniFi OS Server

- Création des répertoires nécessaires avec la commande **mkdir**

```
root@unifi:~# mkdir -p /usr/local/src/unifi-os-server
root@unifi:~#
```

- Accès au répertoire d'installation avec la commande **cd**

```
root@unifi:~# cd /usr/local/src/unifi-os-server
root@unifi:/usr/local/src/unifi-os-server#
```

- Téléchargement du serveur UniFi OS on utilise la commande **curl -LO** + le lien [https://fw-download.ubnt.com/data/unifi-os-server/\[...\].23-x64](https://fw-download.ubnt.com/data/unifi-os-server/[...].23-x64)

```
root@unifi:~# cd /usr/local/src/unifi-os-server
root@unifi:/usr/local/src/unifi-os-server# curl -LO https://fw-download.ubnt.com/data/unifi-os-server/8b93-linux-x64-4.2.23-158fa00b-6b2c-4cd8-94ea-e92bc4a81369.23-x64
% Total    % Received % Xferd  Average Speed   Time    Time     Time  Current
           Dload  Upload   Total   Spent    Left   Speed
0  626M    0  137k    0     0  12867      0  14:11:09  0:00:10  14:10:59 28627-  0:00:07 --:--:--    0
```

- Attribution des droits d'exécution en tape la commande **chmod +x ./8b93-linux-x64-4.2.23-158fa00b-6b2c-4cd8-94ea-e92bc4a81369.23-x64**

-

```
root@unifi:/usr/local/src/unifi-os-server# chmod +x ./8b93-linux-x64-4.2.23-158fa00b-6b2c-4cd8-94ea-e92bc4a81369.23-x64
root@unifi:/usr/local/src/unifi-os-server#
```

Lancement de l'installation

Exécution de l'installateur. Tape **./[...].23-x64** Répondre **y** pour confirmer. Tape **./[...].23-x64**

```
root@unifi:/usr/local/src/unifi-os-server# chmod +x ./8b93-linux-x64-4.2.23-158fa00b-6b2c-4cd8-94ea-e92bc4a81369.23-x64
root@unifi:/usr/local/src/unifi-os-server# ./8b93-linux-x64-4.2.23-158fa00b-6b2c-4cd8-94ea-e92bc4a81369.23-x64
Checking compatible podman runtime available...
Checking slirp4netns available...
You are about to install UOS Server version 4.2.23. Proceed? (y/N):
```

Vérification du service

Vérification que le service UniFi OS est actif : tape **uosservice status**

```
root@unifi:~# uosservice status
CONTAINER ID   NAMES      CREATED                                RUNNING FOR   STATUS
6bd34223a6d1   uosservice 2026-05-24 20:21:53.660175751 +0200 CEST  57 minutes ago Up 56 minutes ago

Host service:

• uosservice.service - Unifi OS Service
  Loaded: loaded (/etc/systemd/system/uosservice.service; enabled; preset: enabled)
  Active: active (running) since Sun 2026-05-24 20:22:11 CEST; 56min ago
  Main PID: 16306 (uosservice)
  Tasks: 12 (limit: 9296)
  Memory: 16.2M
  CPU: 10.274s
  CGroup: /system.slice/uosservice.service
          └─16306 /usr/local/bin/uosservice service
             └─16312 /var/lib/uosservice/discovery

mai 24 20:22:11 unifi uosservice[16306]: 2026-05-24T18:22:11.506395Z INFO 60: UOS Server starting up
```

Accès à interface web

Ouvrir un navigateur et saisir l'URL suivante: **<https://192.168.1.10:11443>**

- Accepter l'avertissement SSL



Votre connexion n'est pas privée

Des pirates informatiques tentent peut-être de voler vos informations sur **192.168.1.10** (mots de passe, messages ou cartes de crédit, par exemple). [En savoir plus sur cet avertissement](#)

NET::ERR_CERT_AUTHORITY_INVALID

Masquer les paramètres avancés

Revenir en lieu sûr


Impossible de vérifier sur le serveur qu'il s'agit bien du domaine **192.168.1.10**, car son certificat de sécurité n'est pas considéré comme fiable par le système d'exploitation de votre ordinateur. Cela peut être dû à une mauvaise configuration ou bien à l'interception de votre connexion par un pirate informatique.

[Continuer vers le site 192.168.1.10 \(dangereux\)](#)

Revenir Windows

Configuration initiale de UniFi OS Server


L'assistant de configuration s'affiche. Saisir le nom



The image shows the UniFi OS Server Setup screen. On the left, there is a graphic of three server racks. On the right, the title "UniFi OS Server Setup" is displayed. Below the title, the text "Name Your UniFi OS Server" is shown. A text input field contains the text "UOS Server".

Choix du type de compte

Choisir Proceed **Without a UI Account** pour rester en mode local sans compte cloud Ubiquiti.



The image shows the "Create a UI Account" screen. On the left, there is a graphic of three server racks. On the right, the title "Create a UI Account" is displayed. Below the title, the text "Already have an account? [Sign In](#)" is shown. There are three input fields: "Email" (with a red border and the text "Please enter a valid email address"), "Username", and "Password" (with a password strength indicator). Below the input fields, there are three checkboxes: "This software is licensed for personal or organizational use only." (checked), "Resale, redistribution, or commercial exploitation is strictly prohibited." (checked), and "Receive periodic newsletters and updates on our products and services." (checked). At the bottom, there is a link "Proceed Without a UI Account" with a red arrow pointing to it. In the bottom right corner, there is a "Activate Windows" watermark.

Définir un mot de passe d'au moins 12 caractères et accepter les conditions d'utilisation



Set Console password

Please set up your password for your console. It helps to prevent unauthorized access.

Password

••••••••



Password must have at least 12 characters.

Repeat Password

••••••••



☒ This software is licensed for personal or organizational use only.

☒ Resale, redistribution, or commercial exploitation is strictly prohibited.

☐ I understand and agree to [Terms of Service](#) and [Privacy Policy](#)

Fin du setup



Setup Complete!

Activer Windows [Go to Dashboard](#)
Accédez aux paramètres de votre système.



Tableau de bord UniFi Network

UniFi-Controller

Network

UniFi

Search

All (1)Switches (0)APs (1)

Type	Name	Application	Status	IP Address	Uplink	Parent Device	Ch. 2.4 G...	Ch. 5 GHz	Ch. 6 GHz	Connect...	Experie...	24HR Usa...
	U7 Outdoor	Network		192.168.1.103	-	-	-	-	-	0	No Clients	-

Activer Windows
Accédez aux paramètres pour activer Windows.

UniFi-Controller

Network

UniFi

Search

All (1)Switches (0)APs (1)

Type	Name	Application	Status	IP Address	Uplink	Parent Device	Ch. 2.4 G...	Ch. 5 GHz	Ch. 6 GHz	Connect...	Experie...	24HR Usa...
	U7 Outdoor	Network	Up to date	192.168.1.103	GbE	-	-	-	-	0	No Clients	-

Activer Windows
Accédez aux paramètres pour activer Windows.

Création du réseau Wi-Fi

Aller dans Settings --> WiFi --> Create New. Saisir le nom du SSID, le mot de passe, activer les bandes 2.4 GHz et 5 GHz.

UniFi-Controller

Network

Search Settings

Overview

WiFi

Networks

Internet

VPN

Policy Engine

CyberSecure

Profiles

System

UniFi OS Server

Control Plane

Identity

Network 9.3.43

UniFi

WiFi

NetworksDHCP Manager

Name	Router	Subnet	DHCP	IP Leases	Pool Size	Available
Default	Third-party Gateway	192.168.1.0/24	Server	-	249	249

NameNetworkBroadcasting APsWiFi BandClientsSecurity

Create New

Channel Plan

Click on a channel to exclude it from use

2.4 GHz2412-2484 MHz

5 GHz5180-5885 MHz

Channels	1	2	3	4	5	6	7	8	9	10	11	12	13	14
20 MHz														
40 MHz														

Channels	36	40	44	48	52	56	60	64	100	104	108	112	116	120	124	128	132	136	140	144	149	153	157	161	165
20 MHz																									
40 MHz																									
80 MHz																									
160 MHz																									
240 MHz																									

In Use

Enabled

DFS

Not available

Restore to Defaults

Default WiFi Speeds

Maximum Speed

Conservative

Custom

Apply to All APs

UniFi-Controller

Network

UniFi

Search Settings

Overview

WiFi

Networks

Internet

VPN

Policy Engine

CyberSecure

Profiles

System

UniFi OS Server

Control Plane

Identity

Network 9.3.43

Submit Support Ticket

Name

U7

Password

.....

Must have at least 8 characters.

Broadcasting APs

All

Specific

Groups

Advanced

Auto

Manual

Private Pre-Shared Keys

Hotspot

Off

Captive Portal

Passpoint

Enhanced IoT Connectivity

WiFi Band

2.4 GHz

5 GHz

6 GHz

MLO

Band Steering

Hide WiFi Name

Client Device Isolation

Proxy ARP

BSS Transition

Submit

Add WiFi Network

Cancel

Test de connexion

Connecter un client au réseau Wi-Fi. Le dashboard affiche 1 client connecté en 5 GHz, canal 149, signal -50 dBm.

Unifi-Controller

0 1 1

Server IP192.168.1.10

System Uptime2h 50m 31s

Network 9.3.43

Azwaw-s-S24-Ultra b4:3b

Azwaw-s-S24-Ultr... 22:e5:bd:18:b4:3b

-50 dBm Ch. 149 (5 GHz, 40 MHz)