

Photon Fusion

2.0.0

1 Photon Fusion API Documentation	1
1.1 Main Fusion API	1
2 Photon Fusion Overview	3
2.1 Choosing the Right Mode	4
2.2 Topology Differences	5
2.2.1 Server Mode	5
2.2.1.1 Client Side Prediction	5
2.2.2 Host Mode	6
2.2.3 Shared Mode	6
2.2.4 Cost	6
3 Hierarchical Index	7
3.1 Class Hierarchy	7
4 Class Index	15
4.1 Class List	15
5 Namespace Documentation	29
5.1 Fusion Namespace Reference	29
5.1.1 Enumeration Type Documentation	40
5.1.1.1 CompareOperator	41
5.1.1.2 ConnectionType	41
5.1.1.3 GameMode	41
5.1.1.4 HitboxTypes	42
5.1.1.5 HitOptions	42
5.1.1.6 NetworkObjectAcquireResult	42
5.1.1.7 NetworkObjectFlags	43
5.1.1.8 NetworkObjectHeaderFlags	43
5.1.1.9 NetworkPrefabTableGetPrefabResult	44
5.1.1.10 NetworkSceneInfoChangeSource	44
5.1.1.11 NetworkSceneInfoDefaultFlags	44
5.1.1.12 NetworkSpawnFlags	44
5.1.1.13 NetworkSpawnStatus	45
5.1.1.14 NetworkTypeIdKind	45
5.1.1.15 PageSizes	45
5.1.1.16 PriorityLevel	46
5.1.1.17 RenderSource	46
5.1.1.18 RenderTimeframe	46
5.1.1.19 RpcChannel	47
5.1.1.20 RpcHostMode	47
5.1.1.21 RpcLocalInvokeResult	47
5.1.1.22 RpcSendCullResult	48
5.1.1.23 RpcSendMessageResult	48

5.1.1.24 RpcSources	49
5.1.1.25 RpcTargets	49
5.1.1.26 RpcTargetStatus	49
5.1.1.27 ScriptHeaderBackColor	49
5.1.1.28 ScriptHeaderIcon	50
5.1.1.29 SessionLobby	50
5.1.1.30 ShutdownReason	50
5.1.1.31 SimulationModes	51
5.1.1.32 SimulationStages	51
5.1.1.33 Topologies	52
5.1.1.34 Units	52
5.1.1.35 UnityPlayerLoopSystemAddMode	52
5.1.2 Function Documentation	54
5.1.2.1 NetworkObjectSpawnDelegate()	54
5.1.2.2 RpcInvokeDelegate()	54
5.1.2.3 RpcStaticInvokeDelegate()	54
5.2 Fusion.Analyzer Namespace Reference	55
5.3 Fusion.Async Namespace Reference	55
5.4 Fusion.Internal Namespace Reference	55
5.5 Fusion.LagCompensation Namespace Reference	56
5.5.1 Enumeration Type Documentation	57
5.5.1.1 HitType	57
5.5.2 Function Documentation	57
5.5.2.1 PreProcessingDelegate()	57
5.6 Fusion.Protocol Namespace Reference	58
5.7 Fusion.Runtime Namespace Reference	58
5.8 Fusion.Runtime.Unity Namespace Reference	58
5.9 Fusion.Sockets Namespace Reference	58
5.9.1 Enumeration Type Documentation	59
5.9.1.1 NetCommands	59
5.9.1.2 NetConnectFailedReason	59
5.9.1.3 NetDisconnectReason	59
5.9.1.4 NetPacketType	59
5.10 Fusion.Sockets.Stun Namespace Reference	59
5.10.1 Enumeration Type Documentation	60
5.10.1.1 NATType	60
5.11 UnityEngine Namespace Reference	60
5.12 UnityEngine.SceneManagement Namespace Reference	60
5.13 UnityEngine.Scripting Namespace Reference	60
5.14 UnityEngine.Serialization Namespace Reference	60

6 Class Documentation

61

6.1 _128 Struct Reference	61
6.1.1 Detailed Description	61
6.1.2 Member Data Documentation	61
6.1.2.1 Data	61
6.1.2.2 SIZE	62
6.2 _16 Struct Reference	62
6.2.1 Detailed Description	62
6.2.2 Member Data Documentation	62
6.2.2.1 Data	62
6.2.2.2 SIZE	62
6.3 _2 Struct Reference	63
6.3.1 Detailed Description	63
6.3.2 Member Data Documentation	63
6.3.2.1 Data	63
6.3.2.2 SIZE	63
6.4 _256 Struct Reference	63
6.4.1 Detailed Description	64
6.4.2 Member Data Documentation	64
6.4.2.1 Data	64
6.4.2.2 SIZE	64
6.5 _32 Struct Reference	64
6.5.1 Detailed Description	65
6.5.2 Member Data Documentation	65
6.5.2.1 Data	65
6.5.2.2 SIZE	65
6.6 _4 Struct Reference	65
6.6.1 Detailed Description	66
6.6.2 Member Data Documentation	66
6.6.2.1 Data	66
6.6.2.2 SIZE	66
6.7 _512 Struct Reference	66
6.7.1 Detailed Description	66
6.7.2 Member Data Documentation	67
6.7.2.1 Data	67
6.7.2.2 SIZE	67
6.8 _64 Struct Reference	67
6.8.1 Detailed Description	67
6.8.2 Member Data Documentation	67
6.8.2.1 Data	68
6.8.2.2 SIZE	68
6.9 _8 Struct Reference	68
6.9.1 Detailed Description	68

6.9.2 Member Data Documentation	68
6.9.2.1 Data	68
6.9.2.2 SIZE	69
6.10 Allocator Struct Reference	69
6.10.1 Detailed Description	70
6.10.2 Member Data Documentation	70
6.10.2.1 BUCKET_COUNT	70
6.10.2.2 BUCKET_INVALID	70
6.10.2.3 HEAP_ALIGNMENT	70
6.10.2.4 REPLICATE_WORD_ALIGN	71
6.10.2.5 REPLICATE_WORD_SHIFT	71
6.10.2.6 REPLICATE_WORD_SIZE	71
6.11 Allocator.Config Struct Reference	71
6.11.1 Detailed Description	72
6.11.2 Constructor & Destructor Documentation	72
6.11.2.1 Config()	72
6.11.3 Member Function Documentation	72
6.11.3.1 Equals() [1/2]	73
6.11.3.2 Equals() [2/2]	73
6.11.3.3 GetHashCode()	73
6.11.3.4 ToString()	74
6.11.4 Member Data Documentation	74
6.11.4.1 BlockCount	74
6.11.4.2 BlockShift	74
6.11.4.3 DEFAULT_BLOCK_COUNT	74
6.11.4.4 DEFAULT_BLOCK_SHIFT	74
6.11.4.5 GlobalsSize	74
6.11.4.6 SIZE	75
6.11.5 Property Documentation	75
6.11.5.1 BlockByteSize	75
6.11.5.2 BlockWordCount	75
6.11.5.3 HeapSizeAllocated	75
6.11.5.4 HeapSizeUsable	75
6.12 Angle Struct Reference	75
6.12.1 Detailed Description	77
6.12.2 Member Function Documentation	77
6.12.2.1 Clamp() [1/2]	77
6.12.2.2 Clamp() [2/2]	77
6.12.2.3 Equals() [1/2]	77
6.12.2.4 Equals() [2/2]	78
6.12.2.5 GetHashCode()	78
6.12.2.6 Lerp()	78

6.12.2.7 Max()	79
6.12.2.8 Min()	79
6.12.2.9 operator Angle() [1/3]	79
6.12.2.10 operator Angle() [2/3]	79
6.12.2.11 operator Angle() [3/3]	80
6.12.2.12 operator double()	80
6.12.2.13 operator float()	80
6.12.2.14 operator"!=()	81
6.12.2.15 operator+()	81
6.12.2.16 operator-()	82
6.12.2.17 operator<()	82
6.12.2.18 operator<=()	82
6.12.2.19 operator==()	83
6.12.2.20 operator>()	83
6.12.2.21 operator>=()	84
6.12.2.22 ToString()	84
6.12.3 Member Data Documentation	84
6.12.3.1 SIZE	84
6.13 AssetObject Class Reference	84
6.13.1 Detailed Description	85
6.14 TaskManager Class Reference	85
6.14.1 Detailed Description	85
6.14.2 Member Function Documentation	85
6.14.2.1 ContinueWhenAll()	85
6.14.2.2 Run()	86
6.14.2.3 Service()	86
6.14.2.4 Setup()	87
6.15 AuthorityMasks Class Reference	87
6.15.1 Detailed Description	87
6.15.2 Member Data Documentation	87
6.15.2.1 ALL	87
6.15.2.2 INPUT	87
6.15.2.3 NONE	88
6.15.2.4 PROXY	88
6.15.2.5 STATE	88
6.16 Behaviour Class Reference	88
6.16.1 Detailed Description	89
6.16.2 Member Function Documentation	89
6.16.2.1 AddBehaviour< T >()	89
6.16.2.2 DestroyBehaviour()	89
6.16.2.3 GetBehaviour< T >()	89
6.16.2.4 TryGetBehaviour< T >()	90

6.17 BehaviourStats Struct Reference	90
6.17.1 Detailed Description	90
6.17.2 Member Data Documentation	90
6.17.2.1 FixedUpdateExecutionTime	90
6.17.2.2 FixedUpdateInvocations	91
6.17.2.3 RenderExecutionTime	91
6.17.2.4 RenderInvocations	91
6.18 CapacityAttribute Class Reference	91
6.18.1 Detailed Description	91
6.18.2 Constructor & Destructor Documentation	91
6.18.2.1 CapacityAttribute()	91
6.18.3 Property Documentation	92
6.18.3.1 Length	92
6.19 DefaultForPropertyAttribute Class Reference	92
6.19.1 Detailed Description	92
6.19.2 Constructor & Destructor Documentation	92
6.19.2.1 DefaultForPropertyAttribute()	92
6.19.3 Property Documentation	93
6.19.3.1 PropertyName	93
6.19.3.2 WordCount	93
6.19.3.3 WordOffset	93
6.20 DisplayAsEnumAttribute Class Reference	93
6.20.1 Detailed Description	94
6.21 DolfAttributeBase Class Reference	94
6.21.1 Detailed Description	94
6.22 DrawIfAttribute Class Reference	94
6.22.1 Detailed Description	95
6.22.2 Constructor & Destructor Documentation	95
6.22.2.1 DrawIfAttribute() [1/2]	95
6.22.2.2 DrawIfAttribute() [2/2]	96
6.22.3 Member Data Documentation	96
6.22.3.1 Mode	96
6.23 DynamicHeap Struct Reference	96
6.23.1 Detailed Description	98
6.23.2 Member Function Documentation	98
6.23.2.1 CollectGarbage()	98
6.23.2.2 CollectGarbageDelegate()	99
6.23.2.3 Free()	99
6.23.2.4 SetForcedAlive< T >()	99
6.23.3 Member Data Documentation	100
6.23.3.1 _debruijnTable	100
6.24 DynamicHeap.Ignore Class Reference	100

6.24.1 Detailed Description	100
6.25 DynamicHeapInstance Class Reference	100
6.25.1 Detailed Description	101
6.25.2 Constructor & Destructor Documentation	101
6.25.2.1 DynamicHeapInstance()	101
6.25.3 Member Function Documentation	101
6.25.3.1 Allocate()	101
6.25.3.2 AllocateArray< T >()	101
6.25.3.3 AllocateArrayPointers< T >()	102
6.25.3.4 AllocateTracked< T >()	102
6.25.3.5 AllocateTrackedArray< T >()	103
6.25.3.6 AllocateTrackedArrayPointers< T >()	104
6.25.3.7 Free()	105
6.26 FieldsMask< T > Class Template Reference	105
6.26.1 Detailed Description	106
6.26.2 Constructor & Destructor Documentation	106
6.26.2.1 FieldsMask() [1/5]	106
6.26.2.2 FieldsMask() [2/5]	106
6.26.2.3 FieldsMask() [3/5]	107
6.26.2.4 FieldsMask() [4/5]	107
6.26.2.5 FieldsMask() [5/5]	107
6.26.3 Member Function Documentation	107
6.26.3.1 operator Mask256()	107
6.27 FixedArray< T > Class Template Reference	107
6.27.1 Detailed Description	109
6.27.2 Constructor & Destructor Documentation	109
6.27.2.1 FixedArray()	109
6.27.3 Member Function Documentation	109
6.27.3.1 Clear()	109
6.27.3.2 CopyFrom() [1/2]	109
6.27.3.3 CopyFrom() [2/2]	110
6.27.3.4 CopyTo() [1/2]	110
6.27.3.5 CopyTo() [2/2]	111
6.27.3.6 Create< T >()	111
6.27.3.7 Create< TActual, TAdapted >()	111
6.27.3.8 CreateFromFieldSequence< T >()	112
6.27.3.9 GetEnumerator()	112
6.27.3.10 IndexOf< T >()	112
6.27.3.11 ToArray()	113
6.27.3.12 ToListString()	113
6.27.3.13 ToString()	113
6.27.4 Property Documentation	113

6.27.4.1 Length	114
6.27.4.2 this[int index]	114
6.28 FixedArray< T >.Enumerator Struct Reference	114
6.28.1 Detailed Description	114
6.28.2 Constructor & Destructor Documentation	114
6.28.2.1 Enumerator()	114
6.28.3 Member Function Documentation	115
6.28.3.1 Dispose()	115
6.28.3.2 MoveNext()	115
6.28.3.3 Reset()	115
6.28.4 Property Documentation	115
6.28.4.1 Current	115
6.29 FixedBufferPropertyAttribute Class Reference	116
6.29.1 Detailed Description	116
6.29.2 Constructor & Destructor Documentation	116
6.29.2.1 FixedBufferPropertyAttribute()	116
6.29.3 Property Documentation	117
6.29.3.1 Capacity	117
6.29.3.2 SurrogateType	117
6.29.3.3 Type	117
6.30 FixedStorage Class Reference	117
6.30.1 Detailed Description	117
6.30.2 Member Function Documentation	117
6.30.2.1 GetWordCount< T >()	117
6.31 FloatCompressed Struct Reference	118
6.31.1 Detailed Description	118
6.31.2 Member Function Documentation	119
6.31.2.1 Equals() [1/2]	119
6.31.2.2 Equals() [2/2]	119
6.31.2.3 GetHashCode()	119
6.31.2.4 operator float()	120
6.31.2.5 operator FloatCompressed()	120
6.31.2.6 operator"!=()	120
6.31.2.7 operator==()	121
6.31.3 Member Data Documentation	121
6.31.3.1 valueEncoded	121
6.32 FloatUtils Class Reference	121
6.32.1 Detailed Description	122
6.32.2 Member Function Documentation	122
6.32.2.1 Compress()	122
6.32.2.2 Decompress()	122
6.32.3 Member Data Documentation	123

6.32.3.1 DEFAULT_ACCURACY	123
6.33 HeapConfiguration Class Reference	123
6.33.1 Detailed Description	123
6.33.2 Member Function Documentation	123
6.33.2.1 Init()	124
6.33.2.2 ToString()	124
6.33.3 Member Data Documentation	124
6.33.3.1 GlobalsSize	124
6.33.3.2 PageCount	124
6.33.3.3 PageShift	124
6.34 Hitbox Class Reference	124
6.34.1 Detailed Description	125
6.34.2 Member Function Documentation	126
6.34.2.1 DrawGizmos()	126
6.34.2.2 OnDrawGizmos()	126
6.34.3 Member Data Documentation	126
6.34.3.1 BoxExtents	126
6.34.3.2 CapsuleHeight	126
6.34.3.3 CapsuleRadius	126
6.34.3.4 GizmosColor	127
6.34.3.5 Offset	127
6.34.3.6 Root	127
6.34.3.7 SphereRadius	127
6.34.3.8 Type	127
6.34.4 Property Documentation	127
6.34.4.1 ColliderIndex	127
6.34.4.2 HitboxActive	128
6.34.4.3 HitboxIndex	128
6.34.4.4 Position	128
6.35 HitboxManager Class Reference	128
6.35.1 Detailed Description	130
6.35.2 Member Function Documentation	130
6.35.2.1 AfterTick()	130
6.35.2.2 AfterUpdate()	131
6.35.2.3 BeforeAllTicks()	131
6.35.2.4 OverlapBox() [1/3]	131
6.35.2.5 OverlapBox() [2/3]	131
6.35.2.6 OverlapBox() [3/3]	132
6.35.2.7 OverlapSphere() [1/3]	133
6.35.2.8 OverlapSphere() [2/3]	134
6.35.2.9 OverlapSphere() [3/3]	135
6.35.2.10 PositionRotation() [1/2]	136

6.35.2.11 PositionRotation() [2/2]	136
6.35.2.12 Raycast() [1/3]	137
6.35.2.13 Raycast() [2/3]	137
6.35.2.14 Raycast() [3/3]	138
6.35.2.15 RaycastAll() [1/3]	139
6.35.2.16 RaycastAll() [2/3]	140
6.35.2.17 RaycastAll() [3/3]	141
6.35.2.18 WriteBenchmarkResults()	141
6.35.3 Member Data Documentation	142
6.35.3.1 BVHDepth	142
6.35.3.2 BVHNodes	142
6.35.3.3 DrawInfo	142
6.35.3.4 TotalHitboxes	142
6.36 HitboxRoot Class Reference	142
6.36.1 Detailed Description	144
6.36.2 Member Enumeration Documentation	144
6.36.2.1 ConfigFlags	144
6.36.3 Member Function Documentation	144
6.36.3.1 DrawGizmos()	144
6.36.3.2 InitHitboxes()	145
6.36.3.3 IsHitboxActive()	145
6.36.3.4 OnDrawGizmos()	145
6.36.3.5 SetHitboxActive()	145
6.36.3.6 SetMinBoundingRadius()	146
6.36.4 Member Data Documentation	146
6.36.4.1 BroadRadius	146
6.36.4.2 Config	146
6.36.4.3 GizmosColor	147
6.36.4.4 Hitboxes	147
6.36.4.5 MAX_HITBOXES	147
6.36.4.6 Offset	147
6.36.5 Property Documentation	147
6.36.5.1 HitboxRootActive	147
6.36.5.2 InInterest	148
6.36.5.3 Manager	148
6.37 HostMigrationConfig Class Reference	148
6.37.1 Detailed Description	148
6.37.2 Member Data Documentation	148
6.37.2.1 EnableAutoUpdate	148
6.37.2.2 UpdateDelay	148
6.38 HostMigrationToken Class Reference	149
6.38.1 Detailed Description	149

6.38.2 Property Documentation	149
6.38.2.1 GameMode	149
6.39 IAfterAllTicks Interface Reference	149
6.39.1 Detailed Description	149
6.39.2 Member Function Documentation	149
6.39.2.1 AfterAllTicks()	149
6.40 IAfterClientPredictionReset Interface Reference	150
6.40.1 Detailed Description	150
6.40.2 Member Function Documentation	150
6.40.2.1 AfterClientPredictionReset()	150
6.41 IAfterHostMigration Interface Reference	150
6.41.1 Detailed Description	151
6.41.2 Member Function Documentation	151
6.41.2.1 AfterHostMigration()	151
6.42 IAfterRender Interface Reference	151
6.42.1 Detailed Description	151
6.42.2 Member Function Documentation	151
6.42.2.1 AfterRender()	151
6.43 IAfterSpawned Interface Reference	151
6.43.1 Detailed Description	152
6.43.2 Member Function Documentation	152
6.43.2.1 AfterSpawned()	152
6.44 IAfterTick Interface Reference	152
6.44.1 Detailed Description	152
6.44.2 Member Function Documentation	152
6.44.2.1 AfterTick()	153
6.45 IAfterUpdate Interface Reference	153
6.45.1 Detailed Description	153
6.45.2 Member Function Documentation	153
6.45.2.1 AfterUpdate()	153
6.46 IAsyncOperation Interface Reference	153
6.46.1 Detailed Description	154
6.46.2 Property Documentation	154
6.46.2.1 Error	154
6.46.2.2 IsDone	154
6.46.3 Event Documentation	154
6.46.3.1 Completed	154
6.47 IBeforeAllTicks Interface Reference	155
6.47.1 Detailed Description	155
6.47.2 Member Function Documentation	155
6.47.2.1 BeforeAllTicks()	155
6.48 IBeforeClientPredictionReset Interface Reference	155

6.48.1 Detailed Description	156
6.48.2 Member Function Documentation	156
6.48.2.1 BeforeClientPredictionReset()	156
6.49 IBeforeCopyPreviousState Interface Reference	156
6.49.1 Detailed Description	156
6.49.2 Member Function Documentation	156
6.49.2.1 BeforeCopyPreviousState()	157
6.50 IBeforeHitboxRegistration Interface Reference	157
6.50.1 Detailed Description	157
6.50.2 Member Function Documentation	157
6.50.2.1 BeforeHitboxRegistration()	157
6.51 IBeforeTick Interface Reference	157
6.51.1 Detailed Description	158
6.51.2 Member Function Documentation	158
6.51.2.1 BeforeTick()	158
6.52 IBeforeUpdate Interface Reference	158
6.52.1 Detailed Description	158
6.52.2 Member Function Documentation	158
6.52.2.1 BeforeUpdate()	158
6.53 ICoroutine Interface Reference	159
6.53.1 Detailed Description	159
6.54 IDespawned Interface Reference	159
6.54.1 Detailed Description	159
6.54.2 Member Function Documentation	159
6.54.2.1 Despawned()	159
6.55 IElementReaderWriter< T > Interface Template Reference	160
6.55.1 Detailed Description	160
6.55.2 Member Function Documentation	160
6.55.2.1 GetElementWordCount()	160
6.55.2.2 Read()	160
6.55.2.3 ReadRef()	161
6.55.2.4 Write()	161
6.56 IFixedStorage Interface Reference	162
6.56.1 Detailed Description	162
6.57 IInputAuthorityGained Interface Reference	162
6.57.1 Detailed Description	162
6.57.2 Member Function Documentation	162
6.57.2.1 InputAuthorityGained()	162
6.58 IInputAuthorityLost Interface Reference	162
6.58.1 Detailed Description	163
6.58.2 Member Function Documentation	163
6.58.2.1 InputAuthorityLost()	163

6.59 IInterestEnter Interface Reference	163
6.59.1 Detailed Description	163
6.59.2 Member Function Documentation	163
6.59.2.1 InterestEnter()	163
6.60 IInterestExit Interface Reference	164
6.60.1 Detailed Description	164
6.60.2 Member Function Documentation	164
6.60.2.1 InterestExit()	164
6.61 ILocalPrefabCreated Interface Reference	164
6.61.1 Detailed Description	164
6.61.2 Member Function Documentation	165
6.61.2.1 LocalPrefabCreated()	165
6.62 INetworkArray Interface Reference	165
6.62.1 Detailed Description	165
6.62.2 Property Documentation	165
6.62.2.1 this[int index]	165
6.63 INetworkAssetSource< T > Interface Template Reference	166
6.63.1 Detailed Description	166
6.63.2 Member Function Documentation	166
6.63.2.1 Acquire()	166
6.63.2.2 Release()	167
6.63.2.3 WaitForResult()	167
6.63.3 Property Documentation	167
6.63.3.1 Description	167
6.63.3.2 IsCompleted	167
6.64 INetworkDictionary Interface Reference	167
6.64.1 Detailed Description	168
6.64.2 Member Function Documentation	168
6.64.2.1 Add()	168
6.65 INetworkInput Interface Reference	168
6.65.1 Detailed Description	168
6.66 INetworkLinkedList Interface Reference	168
6.66.1 Detailed Description	169
6.66.2 Member Function Documentation	169
6.66.2.1 Add()	169
6.67 INetworkObjectInitializer Interface Reference	169
6.67.1 Detailed Description	169
6.67.2 Member Function Documentation	169
6.67.2.1 InitializeNetworkState()	169
6.68 INetworkObjectProvider Interface Reference	170
6.68.1 Detailed Description	170
6.68.2 Member Function Documentation	170

6.68.2.1 AcquirePrefabInstance()	170
6.68.2.2 ReleaseInstance()	171
6.69 INetworkPrefabSource Interface Reference	171
6.69.1 Detailed Description	171
6.69.2 Property Documentation	171
6.69.2.1 AssetGuid	172
6.70 INetworkRunnerCallbacks Interface Reference	172
6.70.1 Detailed Description	173
6.70.2 Member Function Documentation	173
6.70.2.1 OnConnectedToServer()	173
6.70.2.2 OnConnectFailed()	173
6.70.2.3 OnConnectRequest()	173
6.70.2.4 OnCustomAuthenticationResponse()	174
6.70.2.5 OnDisconnectedFromServer()	174
6.70.2.6 OnHostMigration()	174
6.70.2.7 OnInput()	175
6.70.2.8 OnInputMissing()	175
6.70.2.9 OnObjectEnterAOI()	175
6.70.2.10 OnObjectExitAOI()	175
6.70.2.11 OnPlayerJoined()	176
6.70.2.12 OnPlayerLeft()	176
6.70.2.13 OnReliableDataProgress()	176
6.70.2.14 OnReliableDataReceived()	177
6.70.2.15 OnSceneLoadDone()	177
6.70.2.16 OnSceneLoadStart()	177
6.70.2.17 OnSessionListUpdated()	178
6.70.2.18 OnShutdown()	178
6.70.2.19 OnUserSimulationMessage()	178
6.71 INetworkRunnerUpdater Interface Reference	178
6.71.1 Detailed Description	179
6.71.2 Member Function Documentation	179
6.71.2.1 Initialize()	179
6.71.2.2 Shutdown()	179
6.72 INetworkSceneManager Interface Reference	180
6.72.1 Detailed Description	180
6.72.2 Member Function Documentation	180
6.72.2.1 GetSceneRef() [1/2]	181
6.72.2.2 GetSceneRef() [2/2]	181
6.72.2.3 Initialize()	181
6.72.2.4 IsRunnerScene()	181
6.72.2.5 LoadScene()	181
6.72.2.6 MakeDontDestroyOnLoad()	182

6.72.2.7 MoveGameObjectToScene()	182
6.72.2.8 OnSceneInfoChanged()	182
6.72.2.9 Shutdown()	182
6.72.2.10 TryGetPhysicsScene2D()	183
6.72.2.11 TryGetPhysicsScene3D()	183
6.72.2.12 UnloadScene()	183
6.72.3 Property Documentation	183
6.72.3.1 IsBusy	183
6.72.3.2 MainRunnerScene	184
6.73 INetworkStruct Interface Reference	184
6.73.1 Detailed Description	184
6.74 INetworkTRSPTeleport Interface Reference	184
6.74.1 Detailed Description	184
6.74.2 Member Function Documentation	184
6.74.2.1 Teleport()	185
6.75 IUnitySurrogate Interface Reference	185
6.75.1 Detailed Description	185
6.75.2 Member Function Documentation	185
6.75.2.1 Read()	185
6.75.2.2 Write()	186
6.76 IUnityValueSurrogate< T > Interface Template Reference	186
6.76.1 Detailed Description	186
6.76.2 Property Documentation	187
6.76.2.1 DataProperty	187
6.77 UnityArraySurrogate< T, ReaderWriter > Class Template Reference	187
6.77.1 Detailed Description	187
6.77.2 Member Function Documentation	188
6.77.2.1 Init()	188
6.77.2.2 Read()	188
6.77.2.3 Write()	188
6.77.3 Property Documentation	189
6.77.3.1 DataProperty	189
6.78 UnityDictionarySurrogate< KeyType, KeyReaderWriter, ValueType, ValueReaderWriter > Class Template Reference	189
6.78.1 Detailed Description	189
6.78.2 Member Function Documentation	190
6.78.2.1 Init()	190
6.78.2.2 Read()	190
6.78.2.3 Write()	191
6.78.3 Property Documentation	191
6.78.3.1 DataProperty	191
6.79 UnityLinkedListSurrogate< T, ReaderWriter > Class Template Reference	191

6.79.1 Detailed Description	191
6.79.2 Member Function Documentation	192
6.79.2.1 Init()	192
6.79.2.2 Read()	192
6.79.2.3 Write()	193
6.79.3 Property Documentation	193
6.79.3.1 DataProperty	193
6.80 UnitySurrogateBase Class Reference	193
6.80.1 Detailed Description	194
6.80.2 Member Function Documentation	194
6.80.2.1 Init()	194
6.80.2.2 Read()	194
6.80.2.3 Write()	194
6.81 UnityValueSurrogate< T, TReaderWriter > Class Template Reference	195
6.81.1 Detailed Description	195
6.81.2 Member Function Documentation	196
6.81.2.1 Init()	196
6.81.2.2 Read()	196
6.81.2.3 Write()	196
6.81.3 Property Documentation	197
6.81.3.1 DataProperty	197
6.82 InterpolatedErrorCorrectionSettings Class Reference	197
6.82.1 Detailed Description	197
6.82.2 Member Data Documentation	197
6.82.2.1 MaxRate	198
6.82.2.2 MinRate	198
6.82.2.3 PosBlendEnd	198
6.82.2.4 PosBlendStart	198
6.82.2.5 PosMinCorrection	199
6.82.2.6 PosTeleportDistance	199
6.82.2.7 RotBlendEnd	199
6.82.2.8 RotBlendStart	199
6.82.2.9 RotTeleportRadians	200
6.83 IPlayerJoined Interface Reference	200
6.83.1 Detailed Description	200
6.83.2 Member Function Documentation	200
6.83.2.1 PlayerJoined()	200
6.84 IPlayerLeft Interface Reference	200
6.84.1 Detailed Description	201
6.84.2 Member Function Documentation	201
6.84.2.1 PlayerLeft()	201
6.85 IRemotePrefabCreated Interface Reference	201

6.85.1 Detailed Description	201
6.85.2 Member Function Documentation	201
6.85.2.1 RemotePrefabCreated()	202
6.86 ISceneLoadDone Interface Reference	202
6.86.1 Detailed Description	202
6.86.2 Member Function Documentation	202
6.86.2.1 SceneLoadDone()	202
6.87 ISceneLoadStart Interface Reference	202
6.87.1 Detailed Description	203
6.87.2 Member Function Documentation	203
6.87.2.1 SceneLoadStart()	203
6.88 ISimulationEnter Interface Reference	203
6.88.1 Detailed Description	203
6.88.2 Member Function Documentation	203
6.88.2.1 SimulationEnter()	203
6.89 ISimulationExit Interface Reference	204
6.89.1 Detailed Description	204
6.89.2 Member Function Documentation	204
6.89.2.1 SimulationExit()	204
6.90 ISpawned Interface Reference	204
6.90.1 Detailed Description	204
6.90.2 Member Function Documentation	205
6.90.2.1 Spawned()	205
6.91 IStateAuthorityChanged Interface Reference	205
6.91.1 Detailed Description	205
6.91.2 Member Function Documentation	205
6.91.2.1 StateAuthorityChanged()	205
6.92 LagCompensatedHit Struct Reference	205
6.92.1 Detailed Description	206
6.92.2 Member Function Documentation	206
6.92.2.1 operator LagCompensatedHit() [1/2]	206
6.92.2.2 operator LagCompensatedHit() [2/2]	207
6.92.3 Member Data Documentation	207
6.92.3.1 Collider	207
6.92.3.2 Collider2D	207
6.92.3.3 Distance	207
6.92.3.4 GameObject	208
6.92.3.5 Hitbox	208
6.92.3.6 Normal	208
6.92.3.7 Point	208
6.92.3.8 Type	208
6.93 AABB Struct Reference	208

6.93.1 Detailed Description	209
6.93.2 Constructor & Destructor Documentation	209
6.93.2.1 AABB() [1/2]	209
6.93.2.2 AABB() [2/2]	209
6.93.3 Member Data Documentation	210
6.93.3.1 Center	210
6.93.3.2 Extents	210
6.93.3.3 Max	210
6.93.3.4 Min	210
6.94 BoxOverlapQuery Class Reference	210
6.94.1 Detailed Description	211
6.94.2 Constructor & Destructor Documentation	211
6.94.2.1 BoxOverlapQuery() [1/2]	211
6.94.2.2 BoxOverlapQuery() [2/2]	211
6.94.3 Member Function Documentation	212
6.94.3.1 Check()	212
6.94.4 Member Data Documentation	212
6.94.4.1 Center	212
6.94.4.2 Extents	212
6.94.4.3 Rotation	213
6.95 BoxOverlapQueryParams Struct Reference	213
6.95.1 Detailed Description	213
6.95.2 Constructor & Destructor Documentation	213
6.95.2.1 BoxOverlapQueryParams()	213
6.95.3 Member Data Documentation	214
6.95.3.1 Center	214
6.95.3.2 Extents	214
6.95.3.3 QueryParams	214
6.95.3.4 Rotation	214
6.95.3.5 StaticHitsCapacity	215
6.96 BVHDraw Class Reference	215
6.96.1 Detailed Description	215
6.96.2 Member Function Documentation	215
6.96.2.1 GetEnumerator()	215
6.97 BVHNodeDrawInfo Class Reference	215
6.97.1 Detailed Description	216
6.97.2 Property Documentation	216
6.97.2.1 Bounds	216
6.97.2.2 Depth	216
6.97.2.3 MaxDepth	216
6.98 ColliderDrawInfo Class Reference	216
6.98.1 Detailed Description	217

6.98.2 Property Documentation	217
6.98.2.1 BoxExtents	217
6.98.2.2 CapsuleHeight	217
6.98.2.3 LocalToWorldMatrix	217
6.98.2.4 Offset	217
6.98.2.5 Radius	218
6.98.2.6 Type	218
6.99 HitboxColliderContainerDraw Class Reference	218
6.99.1 Detailed Description	218
6.99.2 Member Function Documentation	218
6.99.2.1 GetEnumerator()	218
6.100 LagCompensatedExt Class Reference	218
6.100.1 Detailed Description	219
6.100.2 Member Function Documentation	219
6.100.2.1 SortDistance()	219
6.100.2.2 SortReference()	219
6.101 LagCompensationDraw Class Reference	220
6.101.1 Detailed Description	220
6.101.2 Member Function Documentation	220
6.101.2.1 GizmosDrawWireCapsule()	220
6.101.3 Member Data Documentation	221
6.101.3.1 BVHDraw	221
6.101.3.2 SnapshotHistoryDraw	221
6.102 LagCompensationUtils.ContactData Struct Reference	221
6.102.1 Detailed Description	221
6.102.2 Member Data Documentation	221
6.102.2.1 Normal	221
6.102.2.2 Penetration	222
6.102.2.3 Point	222
6.103 PositionRotationQueryParams Struct Reference	222
6.103.1 Detailed Description	222
6.103.2 Constructor & Destructor Documentation	222
6.103.2.1 PositionRotationQueryParams()	222
6.103.3 Member Data Documentation	223
6.103.3.1 Hitbox	223
6.103.3.2 QueryParams	223
6.104 Query Class Reference	223
6.104.1 Detailed Description	224
6.104.2 Constructor & Destructor Documentation	224
6.104.2.1 Query()	224
6.104.3 Member Function Documentation	224
6.104.3.1 Check()	224

6.104.4 Member Data Documentation	225
6.104.4.1 Alpha	225
6.104.4.2 LayerMask	225
6.104.4.3 Options	225
6.104.4.4 Player	225
6.104.4.5 PreProcessingDelegate	225
6.104.4.6 Tick	226
6.104.4.7 TickTo	226
6.104.4.8 TriggerInteraction	226
6.104.4.9 UserArgs	226
6.105 QueryParams Struct Reference	226
6.105.1 Detailed Description	227
6.105.2 Member Data Documentation	227
6.105.2.1 Alpha	227
6.105.2.2 LayerMask	227
6.105.2.3 Options	227
6.105.2.4 Player	227
6.105.2.5 PreProcessingDelegate	227
6.105.2.6 Tick	228
6.105.2.7 TickTo	228
6.105.2.8 TriggerInteraction	228
6.105.2.9 UserArgs	228
6.106 RaycastAllQuery Class Reference	228
6.106.1 Detailed Description	229
6.106.2 Constructor & Destructor Documentation	229
6.106.2.1 RaycastAllQuery() [1/2]	229
6.106.2.2 RaycastAllQuery() [2/2]	229
6.107 RaycastQuery Class Reference	229
6.107.1 Detailed Description	230
6.107.2 Constructor & Destructor Documentation	230
6.107.2.1 RaycastQuery()	230
6.107.3 Member Function Documentation	230
6.107.3.1 Check()	231
6.107.4 Member Data Documentation	231
6.107.4.1 Direction	231
6.107.4.2 Length	231
6.107.4.3 Origin	231
6.108 RaycastQueryParams Struct Reference	231
6.108.1 Detailed Description	232
6.108.2 Constructor & Destructor Documentation	232
6.108.2.1 RaycastQueryParams()	232
6.108.3 Member Data Documentation	233

6.108.3.1 Direction	233
6.108.3.2 Length	233
6.108.3.3 Origin	233
6.108.3.4 QueryParams	233
6.108.3.5 StaticHitsCapacity	233
6.109 SnapshotHistoryDraw Class Reference	233
6.109.1 Detailed Description	234
6.109.2 Member Function Documentation	234
6.109.2.1 GetEnumerator()	234
6.110 SphereOverlapQuery Class Reference	234
6.110.1 Detailed Description	235
6.110.2 Constructor & Destructor Documentation	235
6.110.2.1 SphereOverlapQuery() [1/2]	235
6.110.2.2 SphereOverlapQuery() [2/2]	235
6.110.3 Member Function Documentation	235
6.110.3.1 Check()	235
6.110.4 Member Data Documentation	236
6.110.4.1 Center	236
6.110.4.2 Radius	236
6.111 SphereOverlapQueryParams Struct Reference	236
6.111.1 Detailed Description	237
6.111.2 Constructor & Destructor Documentation	237
6.111.2.1 SphereOverlapQueryParams()	237
6.111.3 Member Data Documentation	237
6.111.3.1 Center	237
6.111.3.2 QueryParams	237
6.111.3.3 Radius	238
6.111.3.4 StaticHitsCapacity	238
6.112 LagCompensationSettings Class Reference	238
6.112.1 Detailed Description	238
6.112.2 Member Data Documentation	238
6.112.2.1 CachedStaticCollidersSize	239
6.112.2.2 Enabled	239
6.112.2.3 HitboxBufferLengthInMs	239
6.112.2.4 HitboxDefaultCapacity	239
6.112.3 Property Documentation	239
6.112.3.1 ExpansionFactor	239
6.112.3.2 Optimize	239
6.113 LobbyInfo Class Reference	240
6.113.1 Detailed Description	240
6.113.2 Property Documentation	240
6.113.2.1 IsValid	240

6.113.2.2 Name	240
6.113.2.3 Region	240
6.114 LogSimpleUnity Class Reference	241
6.114.1 Detailed Description	241
6.115 NestedComponentUtilities Class Reference	241
6.115.1 Detailed Description	242
6.115.2 Member Function Documentation	242
6.115.2.1 EnsureRootComponentExists< T, TStopOn >()	242
6.115.2.2 FindObjectsOfTypeInOrder< T >() [1/2]	243
6.115.2.3 FindObjectsOfTypeInOrder< T >() [2/2]	243
6.115.2.4 FindObjectsOfTypeInOrder< T, TCast >() [1/2]	244
6.115.2.5 FindObjectsOfTypeInOrder< T, TCast >() [2/2]	244
6.115.2.6 GetNestedComponentInChildren< T, TStopOn >()	245
6.115.2.7 GetNestedComponentInParent< T, TStopOn >()	245
6.115.2.8 GetNestedComponentInParents< T, TStopOn >()	246
6.115.2.9 GetNestedComponentsInChildren< T >()	246
6.115.2.10 GetNestedComponentsInChildren< T, TSearch, TStop >()	246
6.115.2.11 GetNestedComponentsInChildren< T, TStopOn >()	247
6.115.2.12 GetNestedComponentsInParents< T >()	247
6.115.2.13 GetNestedComponentsInParents< T, TStop >()	248
6.115.2.14 GetParentComponent< T >()	248
6.116 NetworkArray< T > Struct Template Reference	248
6.116.1 Detailed Description	250
6.116.2 Constructor & Destructor Documentation	250
6.116.2.1 NetworkArray()	250
6.116.3 Member Function Documentation	250
6.116.3.1 Clear()	251
6.116.3.2 CopyFrom() [1/2]	251
6.116.3.3 CopyFrom() [2/2]	251
6.116.3.4 CopyTo() [1/3]	252
6.116.3.5 CopyTo() [2/3]	252
6.116.3.6 CopyTo() [3/3]	252
6.116.3.7 Get()	253
6.116.3.8 GetEnumerator()	253
6.116.3.9 operator NetworkArrayReadOnly< T >()	253
6.116.3.10 Set()	253
6.116.3.11 ToArray()	254
6.116.3.12 ToListString()	254
6.116.3.13 ToReadOnly()	254
6.116.3.14 ToString()	254
6.116.4 Property Documentation	254
6.116.4.1 Length	254

6.116.4.2 this[int index]	254
6.117 NetworkArray< T >.Enumerator Struct Reference	255
6.117.1 Detailed Description	255
6.117.2 Constructor & Destructor Documentation	255
6.117.2.1 Enumerator()	255
6.117.3 Member Function Documentation	256
6.117.3.1 Dispose()	256
6.117.3.2 MoveNext()	256
6.117.3.3 Reset()	256
6.117.4 Property Documentation	256
6.117.4.1 Current [1/2]	256
6.117.4.2 Current [2/2]	257
6.118 NetworkArrayExtensions Class Reference	257
6.118.1 Detailed Description	257
6.118.2 Member Function Documentation	257
6.118.2.1 GetRef< T >()	257
6.118.2.2 IndexOf< T >()	258
6.119 NetworkArrayReadOnly< T > Struct Template Reference	258
6.119.1 Detailed Description	258
6.119.2 Property Documentation	259
6.119.2.1 Length	259
6.119.2.2 this[int index]	259
6.120 NetworkAssemblyIgnoreAttribute Class Reference	259
6.120.1 Detailed Description	259
6.121 NetworkAssemblyWeavedAttribute Class Reference	259
6.121.1 Detailed Description	259
6.122 NetworkBehaviour Class Reference	259
6.122.1 Detailed Description	262
6.122.2 Member Function Documentation	262
6.122.2.1 CopyBackingFieldsToState()	262
6.122.2.2 CopyStateFrom()	263
6.122.2.3 CopyStateToBackingFields()	263
6.122.2.4 Despawned()	263
6.122.2.5 FixedUpdateNetwork()	264
6.122.2.6 GetArrayReader< T >() [1/2]	264
6.122.2.7 GetArrayReader< T >() [2/2]	264
6.122.2.8 GetBehaviourReader< T >() [1/2]	265
6.122.2.9 GetBehaviourReader< T >() [2/2]	265
6.122.2.10 GetBehaviourReader< TBehaviour, TProperty >()	266
6.122.2.11 GetChangeDetector()	266
6.122.2.12 GetDictionaryReader< K, V >() [1/2]	267
6.122.2.13 GetDictionaryReader< K, V >() [2/2]	267

6.122.2.14	GetInput< T >() [1/2]	268
6.122.2.15	GetInput< T >() [2/2]	268
6.122.2.16	GetLinkListReader< T >() [1/2]	268
6.122.2.17	GetLinkListReader< T >() [2/2]	269
6.122.2.18	GetLocalAuthorityMask()	269
6.122.2.19	GetPropertyReader< T >() [1/2]	269
6.122.2.20	GetPropertyReader< T >() [2/2]	270
6.122.2.21	GetPropertyReader< TBehaviour, TProperty >()	270
6.122.2.22	MakeInitializer< K, V >()	271
6.122.2.23	MakeInitializer< T >()	271
6.122.2.24	MakePtr< T >() [1/2]	271
6.122.2.25	MakePtr< T >() [2/2]	272
6.122.2.26	MakeRef< T >() [1/2]	273
6.122.2.27	MakeRef< T >() [2/2]	273
6.122.2.28	NetworkDeserialize()	274
6.122.2.29	NetworkSerialize()	274
6.122.2.30	NetworkUnwrap()	275
6.122.2.31	NetworkWrap()	275
6.122.2.32	operator NetworkBehaviourId()	275
6.122.2.33	ReinterpretState< T >()	277
6.122.2.34	ReplicateTo()	277
6.122.2.35	ResetState()	278
6.122.2.36	Spawned()	278
6.122.2.37	TryGetSnapshotsBuffers()	278
6.122.3	Member Data Documentation	278
6.122.3.1	offset	279
6.122.4	Property Documentation	279
6.122.4.1	ChangedTick	279
6.122.4.2	DynamicWordCount	279
6.122.4.3	HasInputAuthority	279
6.122.4.4	HasStateAuthority	279
6.122.4.5	Id	280
6.122.4.6	IsProxy	280
6.122.4.7	StateBuffer	280
6.122.4.8	StateBufferIsValid	280
6.123	NetworkBehaviour.ArrayReader< T > Struct Template Reference	280
6.123.1	Detailed Description	280
6.123.2	Member Function Documentation	281
6.123.2.1	Read()	281
6.124	NetworkBehaviour.BehaviourReader< T > Struct Template Reference	281
6.124.1	Detailed Description	281
6.124.2	Member Function Documentation	282

6.124.2.1 Read()	282
6.124.3 Member Data Documentation	282
6.124.3.1 T	282
6.125 NetworkBehaviour.ChangeDetector Class Reference	283
6.125.1 Detailed Description	283
6.125.2 Member Enumeration Documentation	283
6.125.2.1 Source	283
6.125.3 Member Function Documentation	284
6.125.3.1 DetectChanges() [1/2]	284
6.125.3.2 DetectChanges() [2/2]	284
6.125.3.3 Init()	285
6.126 NetworkBehaviour.ChangeDetector.Enumerable Struct Reference	285
6.126.1 Detailed Description	285
6.126.2 Member Function Documentation	285
6.126.2.1 Changed()	285
6.126.2.2 GetEnumerator()	286
6.127 NetworkBehaviour.ChangeDetector.Enumerator Struct Reference	286
6.127.1 Detailed Description	286
6.127.2 Member Function Documentation	286
6.127.2.1 MoveNext()	287
6.127.2.2 Reset()	287
6.127.3 Property Documentation	287
6.127.3.1 Current	287
6.128 NetworkBehaviour.DictionaryReader< K, V > Struct Template Reference	287
6.128.1 Detailed Description	287
6.128.2 Member Function Documentation	288
6.128.2.1 Read()	288
6.129 NetworkBehaviour.LinkListReader< T > Struct Template Reference	288
6.129.1 Detailed Description	288
6.129.2 Member Function Documentation	289
6.129.2.1 Read()	289
6.130 NetworkBehaviour.PropertyReader< T > Struct Template Reference	289
6.130.1 Detailed Description	289
6.130.2 Constructor & Destructor Documentation	290
6.130.2.1 PropertyReader()	290
6.130.3 Member Function Documentation	290
6.130.3.1 Read()	290
6.130.4 Member Data Documentation	290
6.130.4.1 T	290
6.131 NetworkBehaviour.Buffer Struct Reference	291
6.131.1 Detailed Description	292
6.131.2 Member Function Documentation	292

6.131.2.1 operator bool()	292
6.131.2.2 Read() [1/5]	292
6.131.2.3 Read() [2/5]	292
6.131.2.4 Read() [3/5]	293
6.131.2.5 Read() [4/5]	293
6.131.2.6 Read() [5/5]	293
6.131.2.7 Read< T >() [1/2]	295
6.131.2.8 Read< T >() [2/2]	295
6.131.2.9 ReinterpretState< T >()	296
6.131.3 Property Documentation	296
6.131.3.1 Length	296
6.131.3.2 this[int index]	297
6.131.3.3 Tick	297
6.131.3.4 Valid	297
6.132 NetworkBehaviourBufferInterpolator Struct Reference	297
6.132.1 Detailed Description	299
6.132.2 Constructor & Destructor Documentation	299
6.132.2.1 NetworkBehaviourBufferInterpolator()	299
6.132.3 Member Function Documentation	299
6.132.3.1 Angle() [1/2]	299
6.132.3.2 Angle() [2/2]	300
6.132.3.3 Bool() [1/2]	300
6.132.3.4 Bool() [2/2]	300
6.132.3.5 Float() [1/2]	302
6.132.3.6 Float() [2/2]	302
6.132.3.7 Int() [1/2]	302
6.132.3.8 Int() [2/2]	304
6.132.3.9 operator bool()	304
6.132.3.10 Quaternion() [1/2]	304
6.132.3.11 Quaternion() [2/2]	305
6.132.3.12 Select< T >() [1/2]	305
6.132.3.13 Select< T >() [2/2]	306
6.132.3.14 Vector2() [1/2]	306
6.132.3.15 Vector2() [2/2]	307
6.132.3.16 Vector3() [1/2]	307
6.132.3.17 Vector3() [2/2]	307
6.132.3.18 Vector4() [1/2]	308
6.132.3.19 Vector4() [2/2]	308
6.132.4 Member Data Documentation	308
6.132.4.1 Alpha	308
6.132.4.2 Behaviour	309
6.132.4.3 From	309

6.132.4.4 To	309
6.132.4.5 Valid	309
6.133 NetworkBehaviourId Struct Reference	309
6.133.1 Detailed Description	310
6.133.2 Member Function Documentation	310
6.133.2.1 Equals() [1/2]	310
6.133.2.2 Equals() [2/2]	311
6.133.2.3 GetHashCode()	311
6.133.2.4 operator"!="()	311
6.133.2.5 operator=="()	312
6.133.2.6 ToString()	312
6.133.3 Member Data Documentation	312
6.133.3.1 Behaviour	313
6.133.3.2 Object	313
6.133.3.3 SIZE	313
6.133.4 Property Documentation	313
6.133.4.1 IsValid	313
6.133.4.2 None	313
6.134 NetworkBehaviourUtils Class Reference	313
6.134.1 Detailed Description	315
6.134.2 Member Function Documentation	315
6.134.2.1 CloneArray< T >()	315
6.134.2.2 CopyFromNetworkArray< T >()	316
6.134.2.3 CopyFromNetworkDictionary< D, K, V >()	316
6.134.2.4 CopyFromNetworkList< T >()	317
6.134.2.5 GetMetaData()	317
6.134.2.6 GetRpcStaticIndexOrThrow()	318
6.134.2.7 GetStaticWordCount()	318
6.134.2.8 GetWordCount()	319
6.134.2.9 HasStaticWordCount()	319
6.134.2.10 InitializeNetworkArray< T >()	320
6.134.2.11 InitializeNetworkDictionary< D, K, V >()	320
6.134.2.12 InitializeNetworkList< T >()	321
6.134.2.13 InternalOnDestroy()	322
6.134.2.14 InternalOnDisable()	322
6.134.2.15 InternalOnEnable()	322
6.134.2.16 MakeSerializableDictionary< K, V >()	322
6.134.2.17 NotifyLocalSimulationNotAllowedToSendRpc()	323
6.134.2.18 NotifyLocalTargetedRpcCulled()	323
6.134.2.19 NotifyNetworkUnwrapFailed< T >()	324
6.134.2.20 NotifyNetworkWrapFailed< T >() [1/2]	324
6.134.2.21 NotifyNetworkWrapFailed< T >() [2/2]	324

6.134.2.22 NotifyRpcTargetUnreachable()	325
6.134.2.23 RegisterMetaData()	325
6.134.2.24 RegisterRpcInvokeDelegates()	325
6.134.2.25 ShouldRegisterRpcInvokeDelegates()	326
6.134.2.26 ThrowIfBehaviourNotInitialized()	326
6.134.2.27 TryGetRpcInvokeDelegateArray()	327
6.134.2.28 TryGetRpcStaticInvokeDelegate()	327
6.134.3 Member Data Documentation	327
6.134.3.1 InvokeRpc	327
6.135 NetworkBehaviourUtils.ArrayInitializer< T > Struct Template Reference	328
6.135.1 Detailed Description	328
6.135.2 Member Function Documentation	328
6.135.2.1 operator NetworkArray< T >()	328
6.135.2.2 operator NetworkLinkedList< T >()	329
6.136 NetworkBehaviourUtils.DictionaryInitializer< K, V > Struct Template Reference	329
6.136.1 Detailed Description	329
6.136.2 Member Function Documentation	330
6.136.2.1 operator NetworkDictionary< K, V >()	330
6.137 NetworkBehaviourUtils.MetaData Struct Reference	330
6.137.1 Detailed Description	330
6.137.2 Member Data Documentation	330
6.137.2.1 HasReplicateToOverride	331
6.138 NetworkBehaviourWeavedAttribute Class Reference	331
6.138.1 Detailed Description	331
6.138.2 Constructor & Destructor Documentation	331
6.138.2.1 NetworkBehaviourWeavedAttribute()	331
6.138.3 Property Documentation	332
6.138.3.1 WordCount	332
6.139 NetworkBool Struct Reference	332
6.139.1 Detailed Description	332
6.139.2 Constructor & Destructor Documentation	332
6.139.2.1 NetworkBool()	332
6.139.3 Member Function Documentation	333
6.139.3.1 Equals() [1/2]	333
6.139.3.2 Equals() [2/2]	333
6.139.3.3 GetHashCode()	333
6.139.3.4 operator bool()	334
6.139.3.5 operator NetworkBool()	334
6.139.3.6 ToString()	334
6.140 NetworkButtons Struct Reference	334
6.140.1 Detailed Description	336
6.140.2 Constructor & Destructor Documentation	336

6.140.2.1 NetworkButtons()	336
6.140.3 Member Function Documentation	336
6.140.3.1 Equals() [1/2]	336
6.140.3.2 Equals() [2/2]	337
6.140.3.3 GetHashCode()	337
6.140.3.4 GetPressed()	337
6.140.3.5 GetReleased()	338
6.140.3.6 IsSet()	338
6.140.3.7 IsSet< T >()	338
6.140.3.8 Set()	339
6.140.3.9 Set< T >()	339
6.140.3.10 SetAllDown()	340
6.140.3.11 SetAllUp()	340
6.140.3.12 SetDown()	340
6.140.3.13 SetDown< T >()	340
6.140.3.14 SetUp()	341
6.140.3.15 SetUp< T >()	341
6.140.3.16 WasPressed()	341
6.140.3.17 WasPressed< T >()	342
6.140.3.18 WasReleased()	342
6.140.3.19 WasReleased< T >()	343
6.140.4 Member Data Documentation	343
6.140.4.1 NetworkButtons	343
6.140.5 Property Documentation	344
6.140.5.1 Bits	344
6.141 NetworkConfiguration Class Reference	344
6.141.1 Detailed Description	345
6.141.2 Member Enumeration Documentation	345
6.141.2.1 ReliableDataTransfers	345
6.141.3 Member Function Documentation	345
6.141.3.1 Init()	345
6.141.4 Member Data Documentation	346
6.141.4.1 ConnectionShutdownTime	346
6.141.4.2 ConnectionTimeout	346
6.141.4.3 ReliableDataTransferModes	346
6.141.5 Property Documentation	346
6.141.5.1 ConnectAttempts	346
6.141.5.2 ConnectInterval	347
6.141.5.3 ConnectionDefaultRtt	347
6.141.5.4 ConnectionPingInterval	347
6.141.5.5 MtuDefault	347
6.141.5.6 SocketRecvBufferSize	347

6.141.5.7 SocketSendBufferSize	347
6.142 NetworkDelegates Class Reference	348
6.142.1 Detailed Description	348
6.143 NetworkDeserializeMethodAttribute Class Reference	348
6.143.1 Detailed Description	348
6.144 NetworkDictionary< K, V > Struct Template Reference	349
6.144.1 Detailed Description	350
6.144.2 Constructor & Destructor Documentation	351
6.144.2.1 NetworkDictionary()	351
6.144.3 Member Function Documentation	351
6.144.3.1 Add() [1/2]	351
6.144.3.2 Add() [2/2]	351
6.144.3.3 Clear()	352
6.144.3.4 ContainsKey()	352
6.144.3.5 ContainsValue()	352
6.144.3.6 Get()	352
6.144.3.7 GetEnumerator()	353
6.144.3.8 operator NetworkDictionaryReadOnly< K, V >()	353
6.144.3.9 Remove() [1/2]	353
6.144.3.10 Remove() [2/2]	353
6.144.3.11 Set()	354
6.144.3.12 ToReadOnly()	354
6.144.3.13 TryGet()	354
6.144.4 Member Data Documentation	355
6.144.4.1 META_WORD_COUNT	355
6.144.5 Property Documentation	355
6.144.5.1 Capacity	355
6.144.5.2 Count	355
6.144.5.3 this[K key]	355
6.145 NetworkDictionary< K, V >.Enumerator Struct Reference	355
6.145.1 Detailed Description	356
6.145.2 Member Function Documentation	356
6.145.2.1 Dispose()	356
6.145.2.2 MoveNext()	356
6.145.2.3 Reset()	357
6.145.3 Property Documentation	357
6.145.3.1 Current	357
6.146 NetworkDictionaryReadOnly< K, V > Struct Template Reference	357
6.146.1 Detailed Description	358
6.146.2 Member Function Documentation	358
6.146.2.1 Get()	358
6.146.2.2 TryGet()	358

6.146.3 Property Documentation	359
6.146.3.1 Capacity	359
6.146.3.2 Count	359
6.147 NetworkedAttribute Class Reference	359
6.147.1 Detailed Description	360
6.147.2 Constructor & Destructor Documentation	360
6.147.2.1 NetworkedAttribute()	360
6.147.3 Property Documentation	360
6.147.3.1 Default	360
6.148 NetworkedWeavedAttribute Class Reference	360
6.148.1 Detailed Description	361
6.148.2 Constructor & Destructor Documentation	361
6.148.2.1 NetworkedWeavedAttribute()	361
6.148.3 Property Documentation	361
6.148.3.1 WordCount	361
6.148.3.2 WordOffset	361
6.149 NetworkEvents Class Reference	362
6.149.1 Detailed Description	363
6.150 NetworkEvents.ConnectFailedEvent Class Reference	363
6.150.1 Detailed Description	363
6.151 NetworkEvents.ConnectRequestEvent Class Reference	363
6.151.1 Detailed Description	364
6.152 NetworkEvents.CustomAuthenticationResponse Class Reference	364
6.152.1 Detailed Description	364
6.153 NetworkEvents.DisconnectFromServerEvent Class Reference	364
6.153.1 Detailed Description	364
6.154 NetworkEvents.HostMigrationEvent Class Reference	364
6.154.1 Detailed Description	364
6.155 NetworkEvents.InputEvent Class Reference	364
6.155.1 Detailed Description	365
6.156 NetworkEvents.InputPlayerEvent Class Reference	365
6.156.1 Detailed Description	365
6.157 NetworkEvents.ObjectEvent Class Reference	365
6.157.1 Detailed Description	365
6.158 NetworkEvents.ObjectPlayerEvent Class Reference	365
6.158.1 Detailed Description	365
6.159 NetworkEvents.PlayerEvent Class Reference	365
6.159.1 Detailed Description	366
6.160 NetworkEvents.ReliableDataEvent Class Reference	366
6.160.1 Detailed Description	366
6.161 NetworkEvents.ReliableProgressEvent Class Reference	366
6.161.1 Detailed Description	366

6.162 NetworkEvents.RunnerEvent Class Reference	366
6.162.1 Detailed Description	366
6.163 NetworkEvents.SessionListUpdateEvent Class Reference	366
6.163.1 Detailed Description	367
6.164 NetworkEvents.ShutdownEvent Class Reference	367
6.164.1 Detailed Description	367
6.165 NetworkEvents.SimulationMessageEvent Class Reference	367
6.165.1 Detailed Description	367
6.166 NetworkId Struct Reference	367
6.166.1 Detailed Description	369
6.166.2 Member Function Documentation	369
6.166.2.1 CompareTo()	369
6.166.2.2 Equals() [1/2]	369
6.166.2.3 Equals() [2/2]	370
6.166.2.4 GetHashCode()	370
6.166.2.5 operator bool()	370
6.166.2.6 operator"!="()	370
6.166.2.7 operator==()	371
6.166.2.8 Read()	371
6.166.2.9 ToNamePrefixString()	371
6.166.2.10 ToString()	371
6.166.2.11 Write() [1/2]	371
6.166.2.12 Write() [2/2]	372
6.166.3 Member Data Documentation	372
6.166.3.1 ALIGNMENT	372
6.166.3.2 BLOCK_SIZE	372
6.166.3.3 Raw	372
6.166.3.4 SIZE	373
6.166.4 Property Documentation	373
6.166.4.1 Comparer	373
6.166.4.2 IsReserved	373
6.166.4.3 IsValid	373
6.167 NetworkId.EqualityComparer Class Reference	373
6.167.1 Detailed Description	374
6.167.2 Member Function Documentation	374
6.167.2.1 Equals()	374
6.167.2.2 GetHashCode()	374
6.168 NetworkInput Struct Reference	374
6.168.1 Detailed Description	375
6.168.2 Member Function Documentation	375
6.168.2.1 Convert< T >()	375
6.168.2.2 Get< T >()	375

6.168.2.3 Is< T >()	376
6.168.2.4 Set< T >()	376
6.168.2.5 TryGet< T >()	376
6.168.2.6 TrySet< T >()	376
6.168.3 Property Documentation	377
6.168.3.1 Data	377
6.168.3.2 IsValid	377
6.168.3.3 Type	377
6.168.3.4 WordCount	377
6.169 NetworkInputUtils Class Reference	377
6.169.1 Detailed Description	378
6.169.2 Member Function Documentation	378
6.169.2.1 GetMaxWordCount()	378
6.169.2.2 GetType()	378
6.169.2.3 GetTypeKey()	378
6.169.2.4 GetWordCount()	379
6.170 NetworkInputWeavedAttribute Class Reference	379
6.170.1 Detailed Description	379
6.170.2 Constructor & Destructor Documentation	379
6.170.2.1 NetworkInputWeavedAttribute()	379
6.170.3 Property Documentation	380
6.170.3.1 WordCount	380
6.171 NetworkLinkedList< T > Struct Template Reference	380
6.171.1 Detailed Description	382
6.171.2 Constructor & Destructor Documentation	382
6.171.2.1 NetworkLinkedList()	382
6.171.3 Member Function Documentation	382
6.171.3.1 Add() [1/2]	382
6.171.3.2 Add() [2/2]	383
6.171.3.3 Clear()	383
6.171.3.4 Contains() [1/2]	383
6.171.3.5 Contains() [2/2]	383
6.171.3.6 Get()	384
6.171.3.7 GetEnumerator()	384
6.171.3.8 IndexOf() [1/2]	384
6.171.3.9 IndexOf() [2/2]	384
6.171.3.10 Remap()	384
6.171.3.11 Remove() [1/2]	385
6.171.3.12 Remove() [2/2]	385
6.171.3.13 Set()	385
6.171.4 Member Data Documentation	385
6.171.4.1 ELEMENT_WORDS	385

6.171.4.2 META_WORDS	386
6.171.5 Property Documentation	386
6.171.5.1 Capacity	386
6.171.5.2 Count	386
6.171.5.3 this[int index]	386
6.172 NetworkLinkedList< T >.Enumerator Struct Reference	386
6.172.1 Detailed Description	387
6.172.2 Member Function Documentation	387
6.172.2.1 Dispose()	387
6.172.2.2 MoveNext()	387
6.172.2.3 Reset()	387
6.172.3 Property Documentation	387
6.172.3.1 Current	387
6.173 NetworkLinkedListReadOnly< T > Struct Template Reference	388
6.173.1 Detailed Description	389
6.173.2 Member Function Documentation	389
6.173.2.1 Contains() [1/2]	389
6.173.2.2 Contains() [2/2]	389
6.173.2.3 Get()	389
6.173.2.4 IndexOf() [1/2]	390
6.173.2.5 IndexOf() [2/2]	390
6.173.3 Member Data Documentation	390
6.173.3.1 ELEMENT_WORDS	390
6.173.3.2 META_WORDS	390
6.173.4 Property Documentation	391
6.173.4.1 Capacity	391
6.173.4.2 Count	391
6.173.4.3 this[int index]	391
6.174 NetworkLoadSceneParameters Struct Reference	391
6.174.1 Detailed Description	392
6.174.2 Member Function Documentation	392
6.174.2.1 Equals() [1/2]	392
6.174.2.2 Equals() [2/2]	393
6.174.2.3 GetHashCode()	393
6.174.2.4 operator!=(())	393
6.174.2.5 operator==(())	394
6.174.2.6 ToString()	394
6.174.3 Member Data Documentation	394
6.174.3.1 LoadId	394
6.174.4 Property Documentation	394
6.174.4.1 IsActiveOnLoad	394
6.174.4.2 IsLocalPhysics2D	395

6.174.4.3 IsLocalPhysics3D	395
6.174.4.4 IsSingleLoad	395
6.174.4.5 LoadSceneMode	395
6.174.4.6 LoadSceneParameters	395
6.174.4.7 LocalPhysicsMode	395
6.175 NetworkMecanimAnimator Class Reference	396
6.175.1 Detailed Description	396
6.175.2 Member Function Documentation	396
6.175.2.1 SetTrigger() [1/2]	397
6.175.2.2 SetTrigger() [2/2]	397
6.175.3 Member Data Documentation	397
6.175.3.1 Animator	397
6.175.3.2 ApplyTiming	398
6.175.4 Property Documentation	398
6.175.4.1 DynamicWordCount	398
6.176 NetworkObject Class Reference	398
6.176.1 Detailed Description	400
6.176.2 Member Function Documentation	400
6.176.2.1 AssignInputAuthority()	401
6.176.2.2 Awake()	401
6.176.2.3 CopyStateFrom() [1/2]	401
6.176.2.4 CopyStateFrom() [2/2]	401
6.176.2.5 GetLocalAuthorityMask()	401
6.176.2.6 GetWordCount()	402
6.176.2.7 NetworkUnwrap()	402
6.176.2.8 NetworkWrap()	402
6.176.2.9 OnDestroy()	403
6.176.2.10 operator NetworkId()	403
6.176.2.11 PriorityLevelDelegate()	403
6.176.2.12 ReleaseStateAuthority()	404
6.176.2.13 RemoveInputAuthority()	404
6.176.2.14 ReplicateToDelegate()	404
6.176.2.15 RequestStateAuthority()	404
6.176.2.16 SetPlayerAlwaysInterested()	405
6.176.3 Member Data Documentation	405
6.176.3.1 Flags	405
6.176.3.2 IsResume	405
6.176.3.3 NestedObjects	405
6.176.3.4 NetworkedBehaviours	405
6.176.3.5 NetworkTypeId	406
6.176.3.6 PriorityCallback	406
6.176.3.7 ReplicateTo	406

6.176.3.8 SortKey	406
6.176.4 Property Documentation	406
6.176.4.1 HasInputAuthority	406
6.176.4.2 HasStateAuthority	407
6.176.4.3 Id	407
6.176.4.4 InputAuthority	407
6.176.4.5 IsInSimulation	407
6.176.4.6 IsProxy	407
6.176.4.7 IsSpawnable	407
6.176.4.8 IsValid	408
6.176.4.9 LastReceiveTick	408
6.176.4.10 Name	408
6.176.4.11 RenderSource	408
6.176.4.12 RenderTime	408
6.176.4.13 RenderTimeframe	408
6.176.4.14 Runner	409
6.176.4.15 StateAuthority	409
6.177 NetworkObjectFlagsExtensions Class Reference	409
6.177.1 Detailed Description	409
6.177.2 Member Function Documentation	409
6.177.2.1 GetVersion()	409
6.177.2.2 IsIgnored()	410
6.177.2.3 IsVersionCurrent()	410
6.177.2.4 SetCurrentVersion()	410
6.177.2.5 SetIgnored()	412
6.178 NetworkObjectGuid Struct Reference	412
6.178.1 Detailed Description	414
6.178.2 Constructor & Destructor Documentation	414
6.178.2.1 NetworkObjectGuid() [1/4]	414
6.178.2.2 NetworkObjectGuid() [2/4]	414
6.178.2.3 NetworkObjectGuid() [3/4]	414
6.178.2.4 NetworkObjectGuid() [4/4]	415
6.178.3 Member Function Documentation	415
6.178.3.1 CompareTo()	415
6.178.3.2 Equals() [1/2]	415
6.178.3.3 Equals() [2/2]	416
6.178.3.4 GetHashCode()	416
6.178.3.5 operator Guid()	416
6.178.3.6 operator NetworkObjectGuid()	417
6.178.3.7 operator NetworkPrefabRef()	417
6.178.3.8 operator "!="()	417
6.178.3.9 operator "=="()	418

6.178.3.10 Parse()	418
6.178.3.11 ToString() [1/2]	418
6.178.3.12 ToString() [2/2]	418
6.178.3.13 ToUnityGuidString()	419
6.178.3.14 TryParse()	419
6.178.4 Member Data Documentation	419
6.178.4.1 ALIGNMENT	419
6.178.4.2 RawGuidValue	419
6.178.4.3 SIZE	420
6.178.5 Property Documentation	420
6.178.5.1 Empty	420
6.178.5.2 IsValid	420
6.179 NetworkObjectGuid.EqualityComparer Class Reference	420
6.179.1 Detailed Description	420
6.179.2 Member Function Documentation	420
6.179.2.1 Equals()	421
6.179.2.2 GetHashCode()	421
6.180 NetworkObjectHeader Struct Reference	421
6.180.1 Detailed Description	422
6.180.2 Member Function Documentation	422
6.180.2.1 Equals() [1/2]	423
6.180.2.2 Equals() [2/2]	423
6.180.2.3 GetBehaviourChangedTickArray()	423
6.180.2.4 GetDataPointer()	423
6.180.2.5 GetDataWordCount()	424
6.180.2.6 GetHashCode()	424
6.180.2.7 GetMainNetworkTRSPData()	424
6.180.2.8 HasMainNetworkTRSP()	425
6.180.2.9 operator"!="()	425
6.180.2.10 operator=="()	425
6.180.2.11 ToString()	425
6.180.3 Member Data Documentation	426
6.180.3.1 _reserved	426
6.180.3.2 BehaviourCount	426
6.180.3.3 Flags	426
6.180.3.4 Id	426
6.180.3.5 InputAuthority	426
6.180.3.6 NestingKey	427
6.180.3.7 NestingRoot	427
6.180.3.8 PLAYER_DATA_WORD	427
6.180.3.9 SIZE	427
6.180.3.10 StateAuthority	427

6.180.3.11 Type	427
6.180.3.12 WordCount	428
6.180.3.13 WORDS	428
6.180.4 Property Documentation	428
6.180.4.1 ByteCount	428
6.181 NetworkObjectHeaderPtr Struct Reference	428
6.181.1 Detailed Description	428
6.181.2 Member Data Documentation	429
6.181.2.1 Ptr	429
6.181.3 Property Documentation	429
6.181.3.1 Id	429
6.181.3.2 Type	429
6.182 NetworkObjectInitializerUnity Class Reference	429
6.182.1 Detailed Description	429
6.182.2 Member Function Documentation	429
6.182.2.1 InitializeNetworkState()	429
6.183 NetworkObjectMeta Class Reference	430
6.183.1 Detailed Description	430
6.183.2 Property Documentation	430
6.183.2.1 Id	430
6.183.2.2 InputAuthority	430
6.183.2.3 StateAuthority	431
6.183.2.4 Type	431
6.184 NetworkObjectNestingKey Struct Reference	431
6.184.1 Detailed Description	432
6.184.2 Constructor & Destructor Documentation	432
6.184.2.1 NetworkObjectNestingKey()	432
6.184.3 Member Function Documentation	432
6.184.3.1 Equals() [1/2]	432
6.184.3.2 Equals() [2/2]	433
6.184.3.3 GetHashCode()	433
6.184.3.4 ToString()	433
6.184.4 Member Data Documentation	434
6.184.4.1 ALIGNMENT	434
6.184.4.2 SIZE	434
6.184.4.3 Value	434
6.184.5 Property Documentation	434
6.184.5.1 IsNone	434
6.184.5.2 IsValid	435
6.185 NetworkObjectNestingKey.EqualityComparer Class Reference	435
6.185.1 Detailed Description	435
6.185.2 Member Function Documentation	435

6.185.2.1 Equals()	435
6.185.2.2 GetHashCode()	435
6.186 NetworkObjectPrefabData Class Reference	436
6.186.1 Detailed Description	436
6.186.2 Member Data Documentation	436
6.186.2.1 Guid	436
6.187 NetworkObjectProviderDummy Class Reference	436
6.187.1 Detailed Description	437
6.188 NetworkObjectReleaseContext Struct Reference	437
6.188.1 Detailed Description	437
6.188.2 Constructor & Destructor Documentation	437
6.188.2.1 NetworkObjectReleaseContext()	437
6.188.3 Member Function Documentation	438
6.188.3.1 ToString()	438
6.188.4 Member Data Documentation	438
6.188.4.1 IsBeingDestroyed	438
6.188.4.2 IsNestedObject	438
6.188.4.3 Object	438
6.188.4.4 Typeld	439
6.189 NetworkObjectSortKeyComparer Class Reference	439
6.189.1 Detailed Description	439
6.189.2 Member Function Documentation	439
6.189.2.1 Compare()	439
6.189.3 Member Data Documentation	440
6.189.3.1 Instance	440
6.190 NetworkObjectSpawnException Class Reference	440
6.190.1 Detailed Description	440
6.190.2 Constructor & Destructor Documentation	440
6.190.2.1 NetworkObjectSpawnException()	440
6.190.3 Property Documentation	441
6.190.3.1 Message	441
6.190.3.2 Status	441
6.190.3.3 Typeld	441
6.191 NetworkObjectStats Class Reference	441
6.191.1 Detailed Description	442
6.191.2 Member Function Documentation	442
6.191.2.1 Reset()	442
6.191.3 Member Data Documentation	442
6.191.3.1 AreaOfInterestPlayerCount	442
6.191.3.2 InBandwidth	442
6.191.3.3 InUpdates	443
6.191.3.4 OutBandwidth	443

6.191.3.5 OutUpdates	443
6.192 NetworkObjectTypeId Struct Reference	443
6.192.1 Detailed Description	445
6.192.2 Member Function Documentation	445
6.192.2.1 Equals() [1/2]	445
6.192.2.2 Equals() [2/2]	445
6.192.2.3 FromCustom()	446
6.192.2.4 FromPrefabId()	446
6.192.2.5 FromSceneRefAndObjectIndex()	446
6.192.2.6 FromStruct()	447
6.192.2.7 GetHashCode()	447
6.192.2.8 operator NetworkObjectTypeId()	447
6.192.2.9 operator"!="()	448
6.192.2.10 operator=="()	448
6.192.2.11 ToString()	448
6.192.3 Member Data Documentation	448
6.192.3.1 _value0	448
6.192.3.2 _value1	449
6.192.3.3 ALIGNMENT	449
6.192.3.4 MAX_SCENE_OBJECT_INDEX	449
6.192.3.5 SIZE	449
6.192.4 Property Documentation	449
6.192.4.1 AsCustom	449
6.192.4.2 AsInternalStructId	450
6.192.4.3 AsPrefabId	450
6.192.4.4 AsSceneObjectId	450
6.192.4.5 Comparer	450
6.192.4.6 IsCustom	451
6.192.4.7 IsNone	451
6.192.4.8 IsPrefab	451
6.192.4.9 IsSceneObject	451
6.192.4.10 IsStruct	451
6.192.4.11 IsValid	451
6.192.4.12 Kind	452
6.192.4.13 PlayerData	452
6.193 NetworkObjectTypeId.EqualityComparer Class Reference	452
6.193.1 Detailed Description	452
6.193.2 Member Function Documentation	452
6.193.2.1 Equals()	452
6.193.2.2 GetHashCode()	452
6.194 NetworkPhysicsInfo Struct Reference	453
6.194.1 Detailed Description	453

6.194.2 Member Data Documentation	453
6.194.2.1 SIZE	453
6.194.2.2 TimeScale	453
6.194.2.3 WORD_COUNT	454
6.195 NetworkPrefabAcquireContext Struct Reference	454
6.195.1 Detailed Description	454
6.195.2 Constructor & Destructor Documentation	454
6.195.2.1 NetworkPrefabAcquireContext()	454
6.195.3 Member Data Documentation	455
6.195.3.1 DontDestroyOnLoad	455
6.195.3.2 IsSynchronous	455
6.195.3.3 Meta	455
6.195.3.4 PrefabId	455
6.195.4 Property Documentation	455
6.195.4.1 Data	455
6.195.4.2 HasHeader	456
6.196 NetworkPrefabAttribute Class Reference	456
6.196.1 Detailed Description	456
6.197 NetworkPrefabId Struct Reference	456
6.197.1 Detailed Description	458
6.197.2 Member Function Documentation	458
6.197.2.1 CompareTo() [1/2]	458
6.197.2.2 CompareTo() [2/2]	458
6.197.2.3 Equals() [1/2]	458
6.197.2.4 Equals() [2/2]	458
6.197.2.5 FromIndex()	459
6.197.2.6 FromRaw()	459
6.197.2.7 GetHashCode()	459
6.197.2.8 operator"!="()	459
6.197.2.9 operator==(())	459
6.197.2.10 ToString() [1/2]	460
6.197.2.11 ToString() [2/2]	460
6.197.3 Member Data Documentation	460
6.197.3.1 ALIGNMENT	460
6.197.3.2 MAX_INDEX	460
6.197.3.3 RawValue	460
6.197.3.4 SIZE	460
6.197.4 Property Documentation	461
6.197.4.1 AsIndex	461
6.197.4.2 IsNone	461
6.197.4.3 IsValid	461
6.198 NetworkPrefabId.EqualityComparer Class Reference	461

6.198.1 Detailed Description	461
6.198.2 Member Function Documentation	462
6.198.2.1 Equals()	462
6.198.2.2 GetHashCode()	462
6.199 NetworkPrefabInfo Struct Reference	462
6.199.1 Detailed Description	462
6.199.2 Member Data Documentation	463
6.199.2.1 Header	463
6.199.2.2 IsSynchronous	463
6.199.2.3 Prefab	463
6.199.3 Property Documentation	463
6.199.3.1 Data	463
6.199.3.2 HasHeader	463
6.200 NetworkPrefabRef Struct Reference	464
6.200.1 Detailed Description	465
6.200.2 Constructor & Destructor Documentation	465
6.200.2.1 NetworkPrefabRef() [1/4]	465
6.200.2.2 NetworkPrefabRef() [2/4]	465
6.200.2.3 NetworkPrefabRef() [3/4]	466
6.200.2.4 NetworkPrefabRef() [4/4]	466
6.200.3 Member Function Documentation	466
6.200.3.1 CompareTo()	466
6.200.3.2 Equals() [1/2]	467
6.200.3.3 Equals() [2/2]	467
6.200.3.4 GetHashCode()	467
6.200.3.5 operator Guid()	468
6.200.3.6 operator NetworkObjectGuid()	468
6.200.3.7 operator NetworkPrefabRef()	468
6.200.3.8 operator "!="()	469
6.200.3.9 operator "=="()	469
6.200.3.10 Parse()	469
6.200.3.11 ToString() [1/2]	470
6.200.3.12 ToString() [2/2]	470
6.200.3.13 ToUnityGuidString()	470
6.200.3.14 TryParse()	470
6.200.4 Member Data Documentation	470
6.200.4.1 ALIGNMENT	471
6.200.4.2 RawGuidValue	471
6.200.4.3 SIZE	471
6.200.5 Property Documentation	471
6.200.5.1 Empty	471
6.200.5.2 IsValid	471

6.201 NetworkPrefabRef.EqualityComparer Class Reference	471
6.201.1 Detailed Description	472
6.201.2 Member Function Documentation	472
6.201.2.1 Equals()	472
6.201.2.2 GetHashCode()	472
6.202 NetworkPrefabTable Class Reference	472
6.202.1 Detailed Description	474
6.202.2 Member Function Documentation	474
6.202.2.1 AddInstance()	474
6.202.2.2 AddSource()	474
6.202.2.3 Clear()	474
6.202.2.4 Contains()	475
6.202.2.5 GetEntries()	475
6.202.2.6 GetGuid()	475
6.202.2.7 GetId()	476
6.202.2.8 GetInstancesCount()	476
6.202.2.9 GetSource() [1/2]	476
6.202.2.10 GetSource() [2/2]	477
6.202.2.11 IsAcquired()	477
6.202.2.12 Load()	477
6.202.2.13 RemoveInstance()	478
6.202.2.14 TryAddSource()	478
6.202.2.15 Unload()	479
6.202.2.16 UnloadAll()	479
6.202.2.17 UnloadUnreferenced()	479
6.202.3 Member Data Documentation	480
6.202.3.1 Options	480
6.202.4 Property Documentation	480
6.202.4.1 Prefabs	480
6.202.4.2 Version	480
6.203 NetworkPrefabTableOptions Struct Reference	480
6.203.1 Detailed Description	481
6.203.2 Member Data Documentation	481
6.203.2.1 Default	481
6.203.2.2 UnloadPrefabOnReleasingLastInstance	481
6.203.2.3 UnloadUnusedPrefabsOnShutdown	481
6.204 NetworkProjectConfig Class Reference	481
6.204.1 Detailed Description	483
6.204.2 Member Enumeration Documentation	483
6.204.2.1 PeerModes	483
6.204.2.2 ReplicationFeatures	484
6.204.3 Member Function Documentation	484

6.204.3.1 Deserialize()	484
6.204.3.2 GetExecutionOrder()	485
6.204.3.3 Serialize()	485
6.204.3.4 ToString()	485
6.204.3.5 UnloadGlobal()	485
6.204.4 Member Data Documentation	486
6.204.4.1 AssembliesToWeave	486
6.204.4.2 BuildTypes	486
6.204.4.3 CheckNetworkedPropertiesBeingEmpty	486
6.204.4.4 CheckRpcAttributeUsage	486
6.204.4.5 CurrentTypeId	486
6.204.4.6 CurrentVersion	487
6.204.4.7 DefaultResourceName	487
6.204.4.8 EnqueueIncompleteSynchronousSpawns	487
6.204.4.9 Heap	487
6.204.4.10 HideNetworkObjectInactivityGuard	487
6.204.4.11 HostMigration	488
6.204.4.12 InvokeRenderInBatchMode	488
6.204.4.13 LagCompensation	488
6.204.4.14 Network	488
6.204.4.15 NetworkConditions	488
6.204.4.16 NetworkIdsObjectName	488
6.204.4.17 NullChecksForNetworkedProperties	489
6.204.4.18 PeerMode	489
6.204.4.19 PrefabTable	489
6.204.4.20 Simulation	489
6.204.4.21 TimeSynchronizationOverride	489
6.204.4.22 TypeId	489
6.204.4.23 UseSerializableDictionary	490
6.204.4.24 Version	490
6.204.5 Property Documentation	490
6.204.5.1 Global	490
6.205 NetworkProjectConfigAsset Class Reference	490
6.205.1 Detailed Description	491
6.205.2 Member Function Documentation	491
6.205.2.1 TryGetGlobal()	491
6.205.2.2 UnloadGlobal()	492
6.205.3 Member Data Documentation	492
6.205.3.1 BehaviourMeta	492
6.205.3.2 Config	492
6.205.3.3 PrefabOptions	492
6.205.3.4 Prefabs	492

6.205.4 Property Documentation	492
6.205.4.1 Global	493
6.205.4.2 IsGlobalLoaded	493
6.206 NetworkProjectConfigAsset.SerializableSimulationBehaviourMeta Struct Reference	493
6.206.1 Detailed Description	493
6.206.2 Member Data Documentation	493
6.206.2.1 ExecutionOrder	493
6.206.2.2 Type	494
6.207 NetworkRNG Struct Reference	494
6.207.1 Detailed Description	495
6.207.2 Constructor & Destructor Documentation	495
6.207.2.1 NetworkRNG()	495
6.207.3 Member Function Documentation	495
6.207.3.1 Next()	495
6.207.3.2 NextExclusive()	496
6.207.3.3 NextInt32()	496
6.207.3.4 NextSingle()	496
6.207.3.5 NextSingleExclusive()	496
6.207.3.6 NextUInt32()	497
6.207.3.7 RangeExclusive() [1/2]	497
6.207.3.8 RangeExclusive() [2/2]	497
6.207.3.9 RangeInclusive() [1/4]	497
6.207.3.10 RangeInclusive() [2/4]	498
6.207.3.11 RangeInclusive() [3/4]	498
6.207.3.12 RangeInclusive() [4/4]	498
6.207.3.13 ToString()	498
6.207.4 Member Data Documentation	498
6.207.4.1 MAX	498
6.207.4.2 SIZE	499
6.207.5 Property Documentation	499
6.207.5.1 Peek	499
6.208 NetworkRpcStaticWeavedInvokerAttribute Class Reference	499
6.208.1 Detailed Description	499
6.208.2 Constructor & Destructor Documentation	499
6.208.2.1 NetworkRpcStaticWeavedInvokerAttribute()	499
6.208.3 Property Documentation	500
6.208.3.1 Key	500
6.209 NetworkRpcWeavedInvokerAttribute Class Reference	500
6.209.1 Detailed Description	500
6.209.2 Constructor & Destructor Documentation	500
6.209.2.1 NetworkRpcWeavedInvokerAttribute()	500
6.209.3 Property Documentation	501

6.209.3.1 Key	501
6.209.3.2 Sources	501
6.209.3.3 Targets	501
6.210 NetworkRunner Class Reference	501
6.210.1 Detailed Description	510
6.210.2 Member Enumeration Documentation	510
6.210.2.1 BuildTypes	510
6.210.2.2 States	510
6.210.3 Member Function Documentation	511
6.210.3.1 AddCallbacks()	511
6.210.3.2 AddGlobal()	511
6.210.3.3 AddPlayerAreaOfInterest()	511
6.210.3.4 Attach() [1/2]	511
6.210.3.5 Attach() [2/2]	512
6.210.3.6 ClearPlayerAreaOfInterest()	512
6.210.3.7 Despawn()	512
6.210.3.8 DestroySingleton< T >()	513
6.210.3.9 Disconnect()	513
6.210.3.10 EnsureRunnerSceneIsActive()	513
6.210.3.11 Exists() [1/2]	514
6.210.3.12 Exists() [2/2]	514
6.210.3.13 FindObject()	514
6.210.3.14 GetAllBehaviours()	515
6.210.3.15 GetAllBehaviours< T >() [1/2]	515
6.210.3.16 GetAllBehaviours< T >() [2/2]	515
6.210.3.17 GetAreaOfInterestGizmoData()	516
6.210.3.18 GetInputForPlayer< T >()	516
6.210.3.19 GetInstancesEnumerator()	516
6.210.3.20 GetInterfaceListHead()	516
6.210.3.21 GetInterfaceListNext()	517
6.210.3.22 GetInterfaceListPrev()	517
6.210.3.23 GetInterfaceListsCount()	518
6.210.3.24 GetPhysicsScene()	518
6.210.3.25 GetPhysicsScene2D()	518
6.210.3.26 GetPlayerActorId()	518
6.210.3.27 GetPlayerConnectionToken()	519
6.210.3.28 GetPlayerConnectionType()	519
6.210.3.29 GetPlayerObject()	519
6.210.3.30 GetPlayerRtt()	520
6.210.3.31 GetPlayerUserId()	520
6.210.3.32 GetRawInputForPlayer()	520
6.210.3.33 GetResumeSnapshotNetworkObjects()	521

6.210.3.34 GetResumeSnapshotNetworkSceneObjects()	521
6.210.3.35 GetRpcTargetStatus()	521
6.210.3.36 GetRunnerForGameObject()	521
6.210.3.37 GetRunnerForScene()	522
6.210.3.38 GetSingleton< T >()	522
6.210.3.39 HasSingleton< T >()	522
6.210.3.40 InstantiateInRunnerScene() [1/2]	523
6.210.3.41 InstantiateInRunnerScene() [2/2]	523
6.210.3.42 InstantiateInRunnerScene< T >() [1/2]	523
6.210.3.43 InstantiateInRunnerScene< T >() [2/2]	523
6.210.3.44 InvokeSceneLoadDone()	524
6.210.3.45 InvokeSceneLoadStart()	524
6.210.3.46 IsInterestedIn()	524
6.210.3.47 IsPlayerValid()	524
6.210.3.48 JoinSessionLobby()	525
6.210.3.49 LoadScene() [1/3]	525
6.210.3.50 LoadScene() [2/3]	526
6.210.3.51 LoadScene() [3/3]	526
6.210.3.52 MakeDontDestroyOnLoad()	527
6.210.3.53 MoveGameObjectToSameScene()	527
6.210.3.54 MoveGameObjectToScene()	527
6.210.3.55 MoveToRunnerScene()	528
6.210.3.56 MoveToRunnerScene< T >()	528
6.210.3.57 ObjectDelegate()	528
6.210.3.58 OnBeforeSpawned()	529
6.210.3.59 PushHostMigrationSnapshot()	529
6.210.3.60 RegisterSceneObjects()	529
6.210.3.61 RemoveCallbacks()	530
6.210.3.62 RemoveGlobal()	530
6.210.3.63 RemoveSimulationBehavior()	530
6.210.3.64 RenderInternal()	530
6.210.3.65 SendReliableDataToPlayer()	530
6.210.3.66 SendReliableDataToServer()	531
6.210.3.67 SendRpc() [1/2]	531
6.210.3.68 SendRpc() [2/2]	531
6.210.3.69 SetAreaOfInterestCellSize()	532
6.210.3.70 SetAreaOfInterestGrid()	532
6.210.3.71 SetIsSimulated()	532
6.210.3.72 SetMasterClient()	533
6.210.3.73 SetPlayerAlwaysInterested()	533
6.210.3.74 SetPlayerObject()	533
6.210.3.75 Shutdown()	534

6.210.3.76 SinglePlayerContinue()	534
6.210.3.77 SinglePlayerPause() [1/2]	534
6.210.3.78 SinglePlayerPause() [2/2]	534
6.210.3.79 Spawn() [1/5]	534
6.210.3.80 Spawn() [2/5]	535
6.210.3.81 Spawn() [3/5]	535
6.210.3.82 Spawn() [4/5]	536
6.210.3.83 Spawn() [5/5]	537
6.210.3.84 Spawn< T >()	537
6.210.3.85 SpawnAsync() [1/5]	538
6.210.3.86 SpawnAsync() [2/5]	539
6.210.3.87 SpawnAsync() [3/5]	539
6.210.3.88 SpawnAsync() [4/5]	540
6.210.3.89 SpawnAsync() [5/5]	540
6.210.3.90 SpawnAsync< T >()	541
6.210.3.91 StartGame()	542
6.210.3.92 TryFindBehaviour()	542
6.210.3.93 TryFindBehaviour< T >()	543
6.210.3.94 TryFindObject()	543
6.210.3.95 TryGetBehaviourStats()	544
6.210.3.96 TryGetInputForPlayer< T >()	544
6.210.3.97 TryGetNetworkedBehaviourFromNetworkedObjectRef< T >()	544
6.210.3.98 TryGetNetworkedBehaviourId()	545
6.210.3.99 TryGetObjectRefFromNetworkedBehaviour()	545
6.210.3.100 TryGetObjectStats()	546
6.210.3.101 TryGetPhysicsInfo()	546
6.210.3.102 TryGetPlayerObject()	546
6.210.3.103 TryGetPlayerStats()	547
6.210.3.104 TryGetSceneInfo()	547
6.210.3.105 TryGetSimulationStats()	547
6.210.3.106 TrySetPhysicsInfo()	548
6.210.3.107 TrySpawn() [1/5]	548
6.210.3.108 TrySpawn() [2/5]	549
6.210.3.109 TrySpawn() [3/5]	549
6.210.3.110 TrySpawn() [4/5]	550
6.210.3.111 TrySpawn() [5/5]	550
6.210.3.112 TrySpawn< T >()	551
6.210.3.113 UnloadScene()	552
6.210.3.114 UpdateInternal()	552
6.210.4 Property Documentation	552
6.210.4.1 ActivePlayers	552
6.210.4.2 AuthenticationValues	552

6.210.4.3 BuildType	553
6.210.4.4 CanSpawn	553
6.210.4.5 Config	553
6.210.4.6 CurrentConnectionType	553
6.210.4.7 DeltaTime	553
6.210.4.8 GameMode	553
6.210.4.9 Instances	554
6.210.4.10 IsClient	554
6.210.4.11 IsCloudReady	554
6.210.4.12 IsConnectedToServer	554
6.210.4.13 IsFirstTick	554
6.210.4.14 IsForward	554
6.210.4.15 IsLastTick	555
6.210.4.16 IsPlayer	555
6.210.4.17 IsResimulation	555
6.210.4.18 IsResume	555
6.210.4.19 IsRunning	555
6.210.4.20 IsSceneAuthority	555
6.210.4.21 IsSceneManagerBusy	556
6.210.4.22 IsServer	556
6.210.4.23 IsSharedModeMasterClient	556
6.210.4.24 IsShutdown	556
6.210.4.25 IsSinglePlayer	556
6.210.4.26 IsStarting	556
6.210.4.27 LagCompensation	557
6.210.4.28 LatestServerTick	557
6.210.4.29 LobbyInfo	557
6.210.4.30 LocalAlpha	557
6.210.4.31 LocalPlayer	557
6.210.4.32 LocalRenderTime	557
6.210.4.33 Mode	558
6.210.4.34 NATType	558
6.210.4.35 ObjectProvider	558
6.210.4.36 Prefabs	558
6.210.4.37 ProvideInput	558
6.210.4.38 RemoteRenderTime	558
6.210.4.39 SceneManager	559
6.210.4.40 SessionInfo	559
6.210.4.41 SimulationTime	559
6.210.4.42 SimulationUnityScene	559
6.210.4.43 Stage	559
6.210.4.44 State	559

6.210.4.45 Tick	560
6.210.4.46 TickRate	560
6.210.4.47 TicksExecuted	560
6.210.4.48 Topology	560
6.210.4.49 UserId	560
6.210.5 Event Documentation	560
6.210.5.1 ObjectAcquired	560
6.211 NetworkRunnerCallbackArgs Class Reference	561
6.211.1 Detailed Description	561
6.212 NetworkRunnerCallbackArgs.ConnectRequest Class Reference	561
6.212.1 Detailed Description	561
6.212.2 Member Function Documentation	561
6.212.2.1 Accept()	562
6.212.2.2 Refuse()	562
6.212.2.3 Waiting()	562
6.212.3 Property Documentation	562
6.212.3.1 RemoteAddress	562
6.213 NetworkRunnerUpdaterDefault Class Reference	562
6.213.1 Detailed Description	563
6.213.2 Member Function Documentation	563
6.213.2.1 RegisterInPlayerLoop()	563
6.213.2.2 UnregisterFromPlayerLoop()	564
6.213.3 Member Data Documentation	564
6.213.3.1 RenderSettings	564
6.213.3.2 UpdateSettings	564
6.214 NetworkRunnerUpdaterDefault.NetworkRunnerRender Struct Reference	564
6.214.1 Detailed Description	564
6.215 NetworkRunnerUpdaterDefault.NetworkRunnerUpdate Struct Reference	565
6.215.1 Detailed Description	565
6.216 NetworkRunnerUpdaterDefault.InvokeSettings Struct Reference	565
6.216.1 Detailed Description	565
6.216.2 Member Function Documentation	566
6.216.2.1 Equals() [1/2]	566
6.216.2.2 Equals() [2/2]	566
6.216.2.3 GetHashCode()	566
6.216.2.4 operator"!=()	567
6.216.2.5 operator==(())	567
6.216.2.6 ToString()	567
6.216.3 Member Data Documentation	568
6.216.3.1 AddMode	568
6.216.3.2 ReferencePlayerLoopSystem	568
6.217 NetworkSceneAsyncOp Struct Reference	568

6.217.1 Detailed Description	569
6.217.2 Member Function Documentation	569
6.217.2.1 AddOnCompleted()	569
6.217.2.2 FromAsyncOperation()	569
6.217.2.3 FromCompleted()	570
6.217.2.4 FromCoroutine()	570
6.217.2.5 FromError()	571
6.217.2.6 FromTask()	571
6.217.2.7 GetAwaiter()	572
6.217.3 Member Data Documentation	572
6.217.3.1 SceneRef	572
6.217.4 Property Documentation	572
6.217.4.1 Error	572
6.217.4.2 IsDone	572
6.217.4.3 IsValid	572
6.218 NetworkSceneAsyncOp.Awaiter Struct Reference	573
6.218.1 Detailed Description	573
6.218.2 Constructor & Destructor Documentation	573
6.218.2.1 Awaiter()	573
6.218.3 Member Function Documentation	574
6.218.3.1 GetResult()	574
6.218.3.2 OnCompleted()	574
6.218.4 Property Documentation	574
6.218.4.1 IsCompleted	574
6.219 NetworkSceneInfo Struct Reference	574
6.219.1 Detailed Description	575
6.219.2 Member Function Documentation	576
6.219.2.1 AddSceneRef()	576
6.219.2.2 Equals() [1/2]	576
6.219.2.3 Equals() [2/2]	576
6.219.2.4 GetHashCode()	577
6.219.2.5 IndexOf()	577
6.219.2.6 operator NetworkSceneInfo()	577
6.219.2.7 RemoveSceneRef()	578
6.219.2.8 ToString()	578
6.219.3 Member Data Documentation	578
6.219.3.1 MaxScenes	578
6.219.3.2 SIZE	579
6.219.3.3 WORD_COUNT	579
6.219.4 Property Documentation	579
6.219.4.1 SceneCount	579
6.219.4.2 SceneParams	579

6.219.4.3 Scenes	579
6.219.4.4 Version	579
6.220 NetworkSceneLoadId Struct Reference	580
6.220.1 Detailed Description	580
6.220.2 Constructor & Destructor Documentation	580
6.220.2.1 NetworkSceneLoadId()	580
6.220.3 Member Function Documentation	580
6.220.3.1 Equals() [1/2]	581
6.220.3.2 Equals() [2/2]	581
6.220.3.3 GetHashCode()	581
6.220.4 Member Data Documentation	581
6.220.4.1 Value	581
6.221 NetworkSceneObjectId Struct Reference	582
6.221.1 Detailed Description	582
6.221.2 Member Function Documentation	582
6.221.2.1 Equals() [1/2]	582
6.221.2.2 Equals() [2/2]	583
6.221.2.3 GetHashCode()	583
6.221.2.4 ToString()	583
6.221.3 Member Data Documentation	583
6.221.3.1 ObjectId	584
6.221.3.2 Scene	584
6.221.3.3 SceneLoadId	584
6.221.4 Property Documentation	584
6.221.4.1 IsValid	584
6.222 NetworkSerializeMethodAttribute Class Reference	584
6.222.1 Detailed Description	585
6.222.2 Property Documentation	585
6.222.2.1 MaxSize	585
6.223 NetworkSimulationConfiguration Class Reference	585
6.223.1 Detailed Description	586
6.223.2 Member Function Documentation	586
6.223.2.1 Clone()	586
6.223.2.2 Create()	586
6.223.3 Member Data Documentation	586
6.223.3.1 AdditionalJitter	587
6.223.3.2 AdditionalLoss	587
6.223.3.3 DelayMax	587
6.223.3.4 DelayMin	587
6.223.3.5 DelayPeriod	587
6.223.3.6 DelayShape	587
6.223.3.7 DelayThreshold	588

6.223.3.8 Enabled	588
6.223.3.9 LossChanceMax	588
6.223.3.10 LossChanceMin	588
6.223.3.11 LossChancePeriod	588
6.223.3.12 LossChanceShape	588
6.223.3.13 LossChanceThreshold	589
6.224 NetworkSpawnOp Struct Reference	589
6.224.1 Detailed Description	589
6.224.2 Member Function Documentation	590
6.224.2.1 GetAwaiter()	590
6.224.3 Member Data Documentation	590
6.224.3.1 Runner	590
6.224.4 Property Documentation	590
6.224.4.1 IsFailed	590
6.224.4.2 IsQueued	590
6.224.4.3 IsSpawned	590
6.224.4.4 Object	591
6.224.4.5 Status	591
6.225 NetworkSpawnOp.Awaiter Struct Reference	591
6.225.1 Detailed Description	591
6.225.2 Constructor & Destructor Documentation	591
6.225.2.1 Awaiter()	591
6.225.3 Member Function Documentation	592
6.225.3.1 GetResult()	592
6.225.3.2 OnCompleted()	592
6.225.4 Property Documentation	592
6.225.4.1 IsCompleted	593
6.226 NetworkString< TSize > Class Template Reference	593
6.226.1 Detailed Description	595
6.226.2 Constructor & Destructor Documentation	596
6.226.2.1 NetworkString()	596
6.226.3 Member Function Documentation	596
6.226.3.1 Assign()	596
6.226.3.2 Compare() [1/3]	596
6.226.3.3 Compare() [2/3]	597
6.226.3.4 Compare() [3/3]	597
6.226.3.5 Compare< TOtherSize >() [1/2]	597
6.226.3.6 Compare< TOtherSize >() [2/2]	598
6.226.3.7 Contains() [1/3]	599
6.226.3.8 Contains() [2/3]	599
6.226.3.9 Contains() [3/3]	599
6.226.3.10 Contains< TOtherSize >() [1/2]	600

6.226.3.11 Contains< TOtherSize >() [2/2]	600
6.226.3.12 EndsWith()	601
6.226.3.13 EndsWith< TOtherSize >()	601
6.226.3.14 Equals() [1/4]	602
6.226.3.15 Equals() [2/4]	602
6.226.3.16 Equals() [3/4]	603
6.226.3.17 Equals() [4/4]	603
6.226.3.18 Equals< TOtherSize >() [1/2]	603
6.226.3.19 Equals< TOtherSize >() [2/2]	604
6.226.3.20 Get()	604
6.226.3.21 GetCapacity< TSize >()	605
6.226.3.22 GetCharCount()	605
6.226.3.23 GetEnumerator()	605
6.226.3.24 GetHashCode()	606
6.226.3.25 IndexOf() [1/6]	606
6.226.3.26 IndexOf() [2/6]	606
6.226.3.27 IndexOf() [3/6]	607
6.226.3.28 IndexOf() [4/6]	607
6.226.3.29 IndexOf() [5/6]	608
6.226.3.30 IndexOf() [6/6]	608
6.226.3.31 IndexOf< TOtherSize >() [1/4]	609
6.226.3.32 IndexOf< TOtherSize >() [2/4]	609
6.226.3.33 IndexOf< TOtherSize >() [3/4]	610
6.226.3.34 IndexOf< TOtherSize >() [4/4]	611
6.226.3.35 operator NetworkString< TSize >()	612
6.226.3.36 operator string()	612
6.226.3.37 operator !=() [1/3]	612
6.226.3.38 operator !=() [2/3]	613
6.226.3.39 operator !=() [3/3]	613
6.226.3.40 operator ==() [1/3]	613
6.226.3.41 operator ==() [2/3]	614
6.226.3.42 operator ==() [3/3]	614
6.226.3.43 Set()	615
6.226.3.44 StartsWith()	615
6.226.3.45 StartsWith< TOtherSize >()	615
6.226.3.46 Substring() [1/2]	616
6.226.3.47 Substring() [2/2]	616
6.226.3.48 ToLower()	617
6.226.3.49 ToString()	617
6.226.3.50 ToUpper()	617
6.226.4 Property Documentation	618
6.226.4.1 Capacity	618

6.226.4.2 Length	618
6.226.4.3 this[int index]	618
6.226.4.4 Value	618
6.227 NetworkStructUtils Class Reference	618
6.227.1 Detailed Description	619
6.227.2 Member Function Documentation	619
6.227.2.1 GetWordCount< T >()	619
6.228 NetworkStructWeavedAttribute Class Reference	619
6.228.1 Detailed Description	620
6.228.2 Constructor & Destructor Documentation	620
6.228.2.1 NetworkStructWeavedAttribute()	620
6.228.3 Property Documentation	620
6.228.3.1 WordCount	620
6.229 NetworkTransform Class Reference	620
6.229.1 Detailed Description	621
6.229.2 Member Function Documentation	621
6.229.2.1 SetAreaOfInterestOverride()	621
6.229.2.2 Teleport()	622
6.229.3 Member Data Documentation	622
6.229.3.1 DisableSharedModelInterpolation	622
6.229.3.2 SyncParent	622
6.229.3.3 SyncScale	622
6.229.4 Property Documentation	623
6.229.4.1 AutoUpdateAreaOfInterestOverride	623
6.230 NetworkTRSP Class Reference	623
6.230.1 Detailed Description	624
6.230.2 Member Function Documentation	624
6.230.2.1 Render()	624
6.230.2.2 ResolveAOIOVERRIDE()	624
6.230.2.3 SetAreaOfInterestOverride()	625
6.230.2.4 SetParentTransform()	625
6.230.2.5 Teleport()	625
6.230.3 Property Documentation	625
6.230.3.1 Data	626
6.230.3.2 IsMainTRSP	626
6.230.3.3 State	626
6.231 NetworkTRSPData Struct Reference	626
6.231.1 Detailed Description	627
6.231.2 Member Data Documentation	627
6.231.2.1 AreaOfInterestOverride	627
6.231.2.2 Parent	627
6.231.2.3 Position	627

6.231.2.4 POSITION_OFFSET	628
6.231.2.5 Rotation	628
6.231.2.6 Scale	628
6.231.2.7 SIZE	628
6.231.2.8 TeleportKey	628
6.231.2.9 WORDS	628
6.231.3 Property Documentation	629
6.231.3.1 NonNetworkedParent	629
6.232 NormalizedRectAttribute Class Reference	629
6.232.1 Detailed Description	629
6.232.2 Constructor & Destructor Documentation	629
6.232.2.1 NormalizedRectAttribute()	629
6.232.3 Member Data Documentation	630
6.232.3.1 AspectRatio	630
6.232.3.2 InvertY	630
6.233 PlayerRef Struct Reference	630
6.233.1 Detailed Description	632
6.233.2 Member Function Documentation	632
6.233.2.1 Equals() [1/2]	632
6.233.2.2 Equals() [2/2]	632
6.233.2.3 FromEncoded()	633
6.233.2.4 FromIndex()	633
6.233.2.5 GetHashCode()	633
6.233.2.6 operator!=(())	633
6.233.2.7 operator==(())	634
6.233.2.8 Read()	634
6.233.2.9 ToString()	635
6.233.2.10 Write()	635
6.233.2.11 Write< T >()	635
6.233.3 Member Data Documentation	635
6.233.3.1 MASTER_CLIENT_RAW	636
6.233.3.2 SIZE	636
6.233.4 Property Documentation	636
6.233.4.1 AsIndex	636
6.233.4.2 Comparer	636
6.233.4.3 IsMasterClient	636
6.233.4.4 IsNone	637
6.233.4.5 IsRealPlayer	637
6.233.4.6 MasterClient	637
6.233.4.7 None	637
6.233.4.8 PlayerId	637
6.233.4.9 RawEncoded	637

6.234 PreserveInPluginAttribute Class Reference	638
6.234.1 Detailed Description	638
6.234.2 Constructor & Destructor Documentation	638
6.234.2.1 PreserveInPluginAttribute()	638
6.235 IMessage Interface Reference	638
6.235.1 Detailed Description	638
6.236 Ptr Struct Reference	638
6.236.1 Detailed Description	639
6.236.2 Member Function Documentation	640
6.236.2.1 Equals() [1/2]	640
6.236.2.2 Equals() [2/2]	640
6.236.2.3 GetHashCode()	640
6.236.2.4 operator bool()	641
6.236.2.5 operator"!="()	641
6.236.2.6 operator+()	641
6.236.2.7 operator-()	642
6.236.2.8 operator==()	642
6.236.2.9 ToString()	642
6.236.3 Member Data Documentation	643
6.236.3.1 Address	643
6.236.3.2 SIZE	643
6.236.4 Property Documentation	643
6.236.4.1 Null	643
6.237 Ptr.EqualityComparer Class Reference	643
6.237.1 Detailed Description	644
6.237.2 Member Function Documentation	644
6.237.2.1 Equals()	644
6.237.2.2 GetHashCode()	644
6.238 QuaternionCompressed Struct Reference	644
6.238.1 Detailed Description	645
6.238.2 Member Function Documentation	646
6.238.2.1 Equals() [1/2]	646
6.238.2.2 Equals() [2/2]	646
6.238.2.3 GetHashCode()	646
6.238.2.4 operator Quaternion()	647
6.238.2.5 operator QuaternionCompressed()	647
6.238.2.6 operator"!="()	647
6.238.2.7 operator==()	648
6.238.3 Member Data Documentation	648
6.238.3.1 wEncoded	648
6.238.3.2 xEncoded	648
6.238.3.3 yEncoded	649

6.238.3.4 zEncoded	649
6.238.4 Property Documentation	649
6.238.4.1 W	649
6.238.4.2 X	649
6.238.4.3 Y	649
6.238.4.4 Z	649
6.239 ReadWriteUtils Class Reference	650
6.239.1 Detailed Description	650
6.239.2 Member Function Documentation	650
6.239.2.1 ReadFloat()	651
6.239.2.2 ReadNetworkBehaviourRef()	652
6.239.2.3 ReadQuaternion()	652
6.239.2.4 ReadVector2()	653
6.239.2.5 ReadVector3()	653
6.239.2.6 ReadVector4()	653
6.239.2.7 WriteEmptyNetworkBehaviourRef()	654
6.239.2.8 WriteFloat()	654
6.239.2.9 WriteNetworkBehaviourRef()	654
6.239.2.10 WriteNullBehaviourRef()	655
6.239.2.11 WriteQuaternion()	655
6.239.2.12 WriteVector2()	655
6.239.2.13 WriteVector3()	655
6.239.2.14 WriteVector4()	657
6.239.3 Member Data Documentation	657
6.239.3.1 ACCURACY	657
6.240 ReadWriteUtilsForWeaver Class Reference	657
6.240.1 Detailed Description	658
6.240.2 Member Function Documentation	658
6.240.2.1 GetByteCountUtf8NoHash()	658
6.240.2.2 GetWordCountString()	658
6.240.2.3 ReadBoolean()	659
6.240.2.4 ReadStringUtf32NoHash()	659
6.240.2.5 ReadStringUtf32WithHash()	660
6.240.2.6 ReadStringUtf8NoHash()	660
6.240.2.7 VerifyRawNetworkUnwrap< T >()	660
6.240.2.8 VerifyRawNetworkWrap< T >()	661
6.240.2.9 WriteBoolean()	661
6.240.2.10 WriteStringUtf32NoHash()	662
6.240.2.11 WriteStringUtf32WithHash()	662
6.240.2.12 WriteStringUtf8NoHash()	663
6.241 ReflectionUtils Class Reference	663
6.241.1 Detailed Description	663

6.241.2 Member Function Documentation	664
6.241.2.1 GetAllNetworkBehaviourTypes()	664
6.241.2.2 GetAllSimulationBehaviourTypes()	664
6.241.2.3 GetAllWeavedAssemblies()	664
6.241.2.4 GetAllWeavedNetworkBehaviourTypes()	664
6.241.2.5 GetAllWeavedSimulationBehaviourTypes()	665
6.241.2.6 GetAllWeaverGeneratedTypes()	665
6.241.2.7 GetCustomAttributeOrThrow< T >()	665
6.241.2.8 GetWeavedAttributeOrThrow()	666
6.242 RenderAttribute Class Reference	666
6.242.1 Detailed Description	667
6.242.2 Constructor & Destructor Documentation	667
6.242.2.1 RenderAttribute() [1/2]	667
6.242.2.2 RenderAttribute() [2/2]	667
6.242.3 Property Documentation	667
6.242.3.1 Method	667
6.242.3.2 Source	667
6.242.3.3 Timeframe	668
6.243 RenderTimeline Struct Reference	668
6.243.1 Detailed Description	668
6.243.2 Member Function Documentation	668
6.243.2.1 GetRenderBuffers()	668
6.244 RenderWeavedAttribute Class Reference	669
6.244.1 Detailed Description	669
6.244.2 Constructor & Destructor Documentation	669
6.244.2.1 RenderWeavedAttribute()	669
6.245 ResolveNetworkPrefabSourceAttribute Class Reference	669
6.245.1 Detailed Description	669
6.246 RpcAttribute Class Reference	669
6.246.1 Detailed Description	670
6.246.2 Constructor & Destructor Documentation	670
6.246.2.1 RpcAttribute() [1/2]	671
6.246.2.2 RpcAttribute() [2/2]	671
6.246.3 Property Documentation	671
6.246.3.1 Channel	671
6.246.3.2 HostMode	671
6.246.3.3 InvokeLocal	671
6.246.3.4 Sources	672
6.246.3.5 Targets	672
6.246.3.6 TickAligned	672
6.247 RpcHeader Struct Reference	672
6.247.1 Detailed Description	673

6.247.2 Member Function Documentation	673
6.247.2.1 Create() [1/2]	673
6.247.2.2 Create() [2/2]	673
6.247.2.3 Read()	674
6.247.2.4 ReadSize()	674
6.247.2.5 ToString()	675
6.247.2.6 Write()	675
6.247.3 Member Data Documentation	675
6.247.3.1 Behaviour	675
6.247.3.2 Method	675
6.247.3.3 Object	676
6.247.3.4 SIZE	676
6.248 RpcInfo Struct Reference	676
6.248.1 Detailed Description	676
6.248.2 Member Function Documentation	677
6.248.2.1 FromLocal()	677
6.248.2.2 FromMessage()	677
6.248.2.3 ToString()	678
6.248.3 Member Data Documentation	678
6.248.3.1 Channel	678
6.248.3.2 IsInvokeLocal	678
6.248.3.3 Source	678
6.248.3.4 Tick	678
6.249 RpcInvokeData Struct Reference	678
6.249.1 Detailed Description	679
6.249.2 Member Function Documentation	679
6.249.2.1 ToString()	679
6.249.3 Member Data Documentation	679
6.249.3.1 Delegate	679
6.249.3.2 Key	680
6.249.3.3 Sources	680
6.249.3.4 Targets	680
6.250 RpcInvokeInfo Struct Reference	680
6.250.1 Detailed Description	681
6.250.2 Member Function Documentation	681
6.250.2.1 ToString()	681
6.250.3 Member Data Documentation	681
6.250.3.1 LocalInvokeResult	681
6.250.3.2 SendCullResult	681
6.250.3.3 SendResult	681
6.251 RpcSendResult Struct Reference	682
6.251.1 Detailed Description	682

6.251.2 Member Function Documentation	682
6.251.2.1 ToString()	682
6.251.3 Member Data Documentation	682
6.251.3.1 MessageSize	682
6.251.3.2 Result	683
6.252 RpcTargetAttribute Class Reference	683
6.252.1 Detailed Description	683
6.252.2 Constructor & Destructor Documentation	683
6.252.2.1 RpcTargetAttribute()	683
6.253 SceneLoadDoneArgs Struct Reference	683
6.253.1 Detailed Description	684
6.253.2 Constructor & Destructor Documentation	684
6.253.2.1 SceneLoadDoneArgs()	684
6.253.3 Member Data Documentation	684
6.253.3.1 RootGameObjects	684
6.253.3.2 Scene	685
6.253.3.3 SceneObjects	685
6.253.3.4 SceneRef	685
6.254 SceneRef Struct Reference	685
6.254.1 Detailed Description	686
6.254.2 Member Function Documentation	686
6.254.2.1 Equals() [1/2]	686
6.254.2.2 Equals() [2/2]	687
6.254.2.3 FromIndex()	687
6.254.2.4 FromPath()	688
6.254.2.5 FromRaw()	688
6.254.2.6 GetHashCode()	688
6.254.2.7 IsPath()	689
6.254.2.8 operator"!="()	690
6.254.2.9 operator==(())	690
6.254.2.10 ToString() [1/2]	691
6.254.2.11 ToString() [2/2]	691
6.254.3 Member Data Documentation	691
6.254.3.1 FLAG_ADDRESSABLE	691
6.254.3.2 RawValue	691
6.254.3.3 SIZE	692
6.254.4 Property Documentation	692
6.254.4.1 AsIndex	692
6.254.4.2 AsPathHash	692
6.254.4.3 IsIndex	692
6.254.4.4 IsValid	692
6.254.4.5 None	693

6.255 SerializableDictionary< TKey, TValue > Class Template Reference	693
6.255.1 Detailed Description	694
6.255.2 Member Function Documentation	694
6.255.2.1 Add()	694
6.255.2.2 Clear()	694
6.255.2.3 ContainsKey()	695
6.255.2.4 Create< TKey, TValue >()	695
6.255.2.5 GetEnumerator()	695
6.255.2.6 Remove()	696
6.255.2.7 Reset()	696
6.255.2.8 Store()	696
6.255.2.9 TryGetValue()	696
6.255.2.10 Wrap()	697
6.255.3 Member Data Documentation	697
6.255.3.1 EntryKeyPropertyPath	697
6.255.3.2 ItemsPropertyPath	697
6.255.4 Property Documentation	697
6.255.4.1 Count	698
6.255.4.2 IsReadOnly	698
6.255.4.3 Keys	698
6.255.4.4 this[TKey key]	698
6.255.4.5 Values	698
6.256 SessionInfo Class Reference	699
6.256.1 Detailed Description	699
6.256.2 Member Function Documentation	699
6.256.2.1 operator bool()	699
6.256.2.2 ToString()	700
6.256.2.3 UpdateCustomProperties()	700
6.256.3 Property Documentation	700
6.256.3.1 IsOpen	700
6.256.3.2 IsValid	700
6.256.3.3 IsVisible	701
6.256.3.4 MaxPlayers	701
6.256.3.5 Name	701
6.256.3.6 PlayerCount	701
6.256.3.7 Properties	701
6.256.3.8 Region	701
6.257 Simulation Class Reference	702
6.257.1 Detailed Description	705
6.257.2 Member Function Documentation	705
6.257.2.1 AfterSimulation()	705
6.257.2.2 AfterUpdate()	705

6.257.2.3 BeforeFirstTick()	705
6.257.2.4 BeforeSimulation()	706
6.257.2.5 BeforeUpdate()	706
6.257.2.6 GetAreaOfInterestGizmoData()	706
6.257.2.7 GetInputAuthority()	706
6.257.2.8 GetInputForPlayer()	707
6.257.2.9 GetObjectsAndPlayersInAreaOfInterestCell()	707
6.257.2.10 GetStateAuthority()	707
6.257.2.11 HasAnyActiveConnections()	708
6.257.2.12 IsInputAuthority()	708
6.257.2.13 IsInterestedIn()	708
6.257.2.14 IsLocalSimulationInputAuthority()	709
6.257.2.15 IsLocalSimulationStateAuthority() [1/2]	709
6.257.2.16 IsLocalSimulationStateAuthority() [2/2]	709
6.257.2.17 IsLocalSimulationStateOrInputSource()	710
6.257.2.18 IsStateAuthority() [1/2]	710
6.257.2.19 IsStateAuthority() [2/2]	710
6.257.2.20 NetworkConnected()	711
6.257.2.21 NetworkDisconnected()	711
6.257.2.22 NetworkReceiveDone()	711
6.257.2.23 NoSimulation()	712
6.257.2.24 TryGetHostPlayer()	712
6.257.2.25 Update()	712
6.257.3 Member Data Documentation	712
6.257.3.1 _stats	712
6.257.4 Property Documentation	713
6.257.4.1 ActivePlayers	713
6.257.4.2 Config	713
6.257.4.3 DeltaTime	713
6.257.4.4 InputCount	713
6.257.4.5 IsClient	713
6.257.4.6 IsFirstTick	714
6.257.4.7 IsForward	714
6.257.4.8 IsLastTick	714
6.257.4.9 IsLocalPlayerFirstExecution	714
6.257.4.10 IsMasterClient	714
6.257.4.11 IsPlayer	715
6.257.4.12 IsResimulation	715
6.257.4.13 IsRunning	715
6.257.4.14 IsServer	715
6.257.4.15 IsShutdown	715
6.257.4.16 IsSinglePlayer	715

6.257.4.17 LatestServerTick	716
6.257.4.18 LocalAddress	716
6.257.4.19 LocalAlpha	716
6.257.4.20 LocalPlayer	716
6.257.4.21 Mode	716
6.257.4.22 NetConfigPointer	716
6.257.4.23 ObjectCount	717
6.257.4.24 Objects	717
6.257.4.25 ProjectConfig	717
6.257.4.26 RemoteAlpha	717
6.257.4.27 RemoteTick	717
6.257.4.28 RemoteTickPrevious	717
6.257.4.29 SendDelta	718
6.257.4.30 SendRate	718
6.257.4.31 Stage	718
6.257.4.32 Tick	718
6.257.4.33 TickDeltaDouble	718
6.257.4.34 TickDeltaFloat	718
6.257.4.35 TickPrevious	719
6.257.4.36 TickRate	719
6.257.4.37 TickStride	719
6.257.4.38 Time	719
6.257.4.39 Topology	719
6.258 Simulation.AreaOfInterest Struct Reference	719
6.258.1 Detailed Description	720
6.258.2 Member Function Documentation	720
6.258.2.1 GetCellSize()	720
6.258.2.2 SphereToCells()	720
6.258.2.3 ToCell() [1/2]	721
6.258.2.4 ToCell() [2/2]	721
6.258.2.5 ToCellCenter()	722
6.258.3 Member Data Documentation	722
6.258.3.1 CELL_SIZE	722
6.258.3.2 x	722
6.259 SimulationBehaviour Class Reference	723
6.259.1 Detailed Description	724
6.259.2 Member Function Documentation	724
6.259.2.1 FixedUpdateNetwork()	724
6.259.2.2 Render()	724
6.259.3 Property Documentation	724
6.259.3.1 CanReceiveRenderCallback	724
6.259.3.2 CanReceiveSimulationCallback	725

6.259.3.3 Object	725
6.259.3.4 Runner	725
6.260 SimulationBehaviourAttribute Class Reference	725
6.260.1 Detailed Description	725
6.260.2 Property Documentation	726
6.260.2.1 Modes	726
6.260.2.2 Stages	726
6.260.2.3 Topologies	726
6.261 SimulationBehaviourListScope Struct Reference	726
6.261.1 Detailed Description	726
6.261.2 Member Function Documentation	727
6.261.2.1 Dispose()	727
6.262 SimulationConfig Class Reference	727
6.262.1 Detailed Description	728
6.262.2 Member Enumeration Documentation	728
6.262.2.1 DataConsistency	728
6.262.2.2 InputTransferModes	728
6.262.3 Member Data Documentation	728
6.262.3.1 HostMigration	728
6.262.3.2 InputDataWordCount	729
6.262.3.3 InputTransferMode	729
6.262.3.4 ObjectDataConsistency	729
6.262.3.5 PlayerCount	729
6.262.3.6 ReplicationFeatures	729
6.262.3.7 TickRateSelection	729
6.262.3.8 Topology	730
6.262.4 Property Documentation	730
6.262.4.1 AreaOfInterestEnabled	730
6.262.4.2 InputTotalWordCount	730
6.262.4.3 SchedulingEnabled	730
6.262.4.4 SchedulingWithoutAOI	730
6.263 SimulationConnectionStats Class Reference	730
6.263.1 Detailed Description	731
6.263.2 Member Data Documentation	731
6.263.2.1 InMessagesBandwidth	731
6.263.2.2 InMessagesPerPacket	731
6.263.2.3 InObjectBandwidth	731
6.263.2.4 InObjectDestroysPerPacket	732
6.263.2.5 InObjectUpdatesPerPacket	732
6.263.2.6 InPacketsBandwidth	732
6.263.2.7 InPacketsRecv	732
6.263.2.8 InputsBandwidth	732

6.263.2.9 InputsMissing	732
6.263.2.10 InputsPerPacket	732
6.263.2.11 InReliableDataBandwidth	732
6.263.2.12 OutMessagesBandwidth	733
6.263.2.13 OutMessagesPerPacket	733
6.263.2.14 OutObjectBandwidth	733
6.263.2.15 OutObjectDestroysPerPacket	733
6.263.2.16 OutObjectUpdatesPerPacket	733
6.263.2.17 OutPacketsBandwidth	733
6.263.2.18 OutPacketsDelivered	733
6.263.2.19 OutPacketsLost	733
6.263.2.20 OutPacketsSent	734
6.263.2.21 OutReliableDataBandwidth	734
6.263.2.22 RoundTripTime	734
6.264 SimulationInput Class Reference	734
6.264.1 Detailed Description	735
6.264.2 Member Function Documentation	735
6.264.2.1 Clear()	735
6.264.2.2 CopyFrom()	735
6.264.3 Property Documentation	735
6.264.3.1 Data	735
6.264.3.2 Header	736
6.264.3.3 Player	736
6.264.3.4 Sent	736
6.265 SimulationInput.Buffer Class Reference	736
6.265.1 Detailed Description	737
6.265.2 Constructor & Destructor Documentation	737
6.265.2.1 Buffer()	737
6.265.3 Member Function Documentation	737
6.265.3.1 Add()	737
6.265.3.2 Clear()	738
6.265.3.3 Contains()	738
6.265.3.4 CopySortedTo()	738
6.265.3.5 Get()	739
6.265.3.6 GetInsertTime()	739
6.265.3.7 Remove()	739
6.265.4 Property Documentation	740
6.265.4.1 Count	740
6.265.4.2 Full	740
6.266 SimulationInputHeader Struct Reference	740
6.266.1 Detailed Description	741
6.266.2 Member Data Documentation	741

6.266.2.1 InterpAlpha	741
6.266.2.2 InterpFrom	741
6.266.2.3 InterpTo	741
6.266.2.4 SIZE	741
6.266.2.5 Tick	741
6.266.2.6 WORD_COUNT	742
6.267 SimulationMessage Struct Reference	742
6.267.1 Detailed Description	744
6.267.2 Member Function Documentation	744
6.267.2.1 Allocate()	744
6.267.2.2 Clone()	745
6.267.2.3 GetData()	745
6.267.2.4 GetFlag()	745
6.267.2.5 IsTargeted()	746
6.267.2.6 ReadInt()	746
6.267.2.7 ReadNetworkedObjectRef()	746
6.267.2.8 ReadVector3()	747
6.267.2.9 ReferenceCountAdd()	747
6.267.2.10 ReferenceCountSub()	747
6.267.2.11 SetDummy()	748
6.267.2.12 SetNotTickAligned()	748
6.267.2.13 SetStatic()	748
6.267.2.14 SetTarget()	748
6.267.2.15 SetUnreliable()	748
6.267.2.16 ToString() [1/2]	749
6.267.2.17 ToString() [2/2]	749
6.267.2.18 WriteInt()	749
6.267.2.19 WriteNetworkedObjectRef()	749
6.267.2.20 WriteVector3()	750
6.267.3 Member Data Documentation	750
6.267.3.1 Capacity	750
6.267.3.2 FLAG_DUMMY	750
6.267.3.3 FLAG_INTERNAL	750
6.267.3.4 FLAG_NOT_TICK_ALIGNED	750
6.267.3.5 FLAG_REMOTE	751
6.267.3.6 FLAG_STATIC	751
6.267.3.7 FLAG_TARGET_PLAYER	751
6.267.3.8 FLAG_TARGET_SERVER	751
6.267.3.9 FLAG_UNRELIABLE	751
6.267.3.10 FLAG_USER_FLAGS_START	751
6.267.3.11 FLAG_USER_MESSAGE	752
6.267.3.12 Flags	752

6.267.3.13 FLAGS_RESERVED	752
6.267.3.14 FLAGS_RESERVED_BITS	752
6.267.3.15 Offset	752
6.267.3.16 References	752
6.267.3.17 SIZE	753
6.267.3.18 Source	753
6.267.3.19 Target	753
6.267.3.20 Tick	753
6.267.4 Property Documentation	753
6.267.4.1 IsUnreliable	753
6.268 SimulationMessagePtr Struct Reference	753
6.268.1 Detailed Description	754
6.268.2 Member Data Documentation	754
6.268.2.1 Message	754
6.269 SimulationRuntimeConfig Struct Reference	754
6.269.1 Detailed Description	754
6.269.2 Member Data Documentation	755
6.269.2.1 HostPlayer	755
6.269.2.2 MasterClient	755
6.269.2.3 PlayerMaxCount	755
6.269.2.4 ServerMode	755
6.269.2.5 TickRate	755
6.269.2.6 Topology	755
6.270 SimulationStats Class Reference	756
6.270.1 Detailed Description	757
6.270.2 Member Data Documentation	757
6.270.2.1 EngineDelta	757
6.270.2.2 ForwardSteps	757
6.270.2.3 InBandwidth	757
6.270.2.4 InPackets	757
6.270.2.5 InputReceiveDelta	758
6.270.2.6 InputReceiveDeltaDeviation	758
6.270.2.7 InterpolationOffset	758
6.270.2.8 InterpolationOffsetDeviation	758
6.270.2.9 InterpolationOffsetTarget	758
6.270.2.10 InterpolationSpeed	758
6.270.2.11 ObjectsCount	759
6.270.2.12 ObjectsGlobalCount	759
6.270.2.13 ObjectsPredictedCount	759
6.270.2.14 OutBandwidth	759
6.270.2.15 OutPackets	759
6.270.2.16 PlayersCount	759

6.270.2.17 Resimulations	760
6.270.2.18 RoundTripTime	760
6.270.2.19 SimulationSpeed	760
6.270.2.20 SimulationTimeOffset	760
6.270.2.21 SimulationTimeOffsetDeviation	760
6.270.2.22 SimulationTimeOffsetTarget	760
6.270.2.23 SpawnQueueSize	761
6.270.2.24 StateReceiveDelta	761
6.270.2.25 StateReceiveDeltaDeviation	761
6.270.2.26 TimeResets	761
6.271 NetAddress Struct Reference	761
6.271.1 Detailed Description	762
6.271.2 Member Function Documentation	762
6.271.2.1 Any()	762
6.271.2.2 AnyIPv6()	763
6.271.2.3 CreateFromIpPort()	763
6.271.2.4 FromActorId()	764
6.271.2.5 LocalhostIPv4()	764
6.271.2.6 LocalhostIPv6()	764
6.271.3 Property Documentation	765
6.271.3.1 ActorId	765
6.271.3.2 IsIPv6	765
6.271.3.3 IsRelayAddr	765
6.271.3.4 IsValid	765
6.272 NetBitBufferList Struct Reference	765
6.272.1 Detailed Description	766
6.272.2 Member Function Documentation	766
6.272.2.1 AddFirst()	766
6.272.2.2 AddLast()	766
6.272.2.3 IsInList()	767
6.272.2.4 Remove()	767
6.272.2.5 RemoveHead()	767
6.273 NetCommandAccepted Struct Reference	768
6.273.1 Detailed Description	768
6.274 NetCommandConnect Struct Reference	768
6.274.1 Detailed Description	769
6.275 NetCommandDisconnect Struct Reference	769
6.275.1 Detailed Description	769
6.276 NetCommandHeader Struct Reference	769
6.276.1 Detailed Description	770
6.276.2 Member Function Documentation	770
6.276.2.1 Create()	770

6.277 NetCommandRefused Struct Reference	770
6.277.1 Detailed Description	771
6.278 NetConfig Struct Reference	771
6.278.1 Detailed Description	772
6.278.2 Member Data Documentation	772
6.278.2.1 Address	772
6.278.2.2 ConnectAttempts	772
6.278.2.3 ConnectInterval	772
6.278.2.4 ConnectionDefaultRtt	772
6.278.2.5 ConnectionGroups	773
6.278.2.6 ConnectionPingInterval	773
6.278.2.7 ConnectionSendBuffers	773
6.278.2.8 ConnectionShutdownTime	773
6.278.2.9 ConnectionTimeout	773
6.278.2.10 DefaultMtu	773
6.278.2.11 MaxConnections	774
6.278.2.12 Notify	774
6.278.2.13 OperationExpireTime	774
6.278.2.14 PacketSize	774
6.278.2.15 Simulation	774
6.278.2.16 SocketRecvBuffer	774
6.278.2.17 SocketSendBuffer	775
6.278.3 Property Documentation	775
6.278.3.1 ConnectionsPerGroup	775
6.278.3.2 Defaults	775
6.278.3.3 PacketSizeInBits	775
6.279 StunClient.TestIPs Class Reference	775
6.279.1 Detailed Description	775
6.280 StartGameArgs Struct Reference	776
6.280.1 Detailed Description	777
6.280.2 Member Function Documentation	777
6.280.2.1 ToString()	777
6.280.3 Member Data Documentation	777
6.280.3.1 Address	778
6.280.3.2 AuthValues	778
6.280.3.3 Config	778
6.280.3.4 ConnectionToken	778
6.280.3.5 CustomCallbackInterfaces	778
6.280.3.6 CustomLobbyName	778
6.280.3.7 CustomPhotonAppSettings	779
6.280.3.8 CustomPublicAddress	779
6.280.3.9 CustomSTUNServer	779

6.280.3.10 DisableNATPunchthrough	779
6.280.3.11 EnableClientSessionCreation	779
6.280.3.12 GameMode	779
6.280.3.13 HostMigrationResume	780
6.280.3.14 HostMigrationToken	780
6.280.3.15 IsOpen	780
6.280.3.16 IsVisible	780
6.280.3.17 MatchmakingMode	780
6.280.3.18 ObjectInitializer	780
6.280.3.19 ObjectProvider	781
6.280.3.20 OnGameStarted	781
6.280.3.21 PlayerCount	781
6.280.3.22 Scene	781
6.280.3.23 SceneManager	781
6.280.3.24 SessionName	781
6.280.3.25 SessionProperties	782
6.280.3.26 StartGameCancellationToken	782
6.280.3.27 Updater	782
6.280.3.28 UseCachedRegions	782
6.280.3.29 UseDefaultPhotonCloudPorts	782
6.281 StartGameResult Class Reference	782
6.281.1 Detailed Description	783
6.281.2 Member Function Documentation	783
6.281.2.1 ToString()	783
6.281.3 Property Documentation	783
6.281.3.1 ErrorMessage	783
6.281.3.2 Ok	784
6.281.3.3 ShutdownReason	784
6.281.3.4 StackTrace	784
6.282 StatsMetaAttribute Class Reference	784
6.282.1 Detailed Description	785
6.283 Tick Struct Reference	785
6.283.1 Detailed Description	786
6.283.2 Member Function Documentation	786
6.283.2.1 CompareTo()	786
6.283.2.2 Equals() [1/2]	786
6.283.2.3 Equals() [2/2]	787
6.283.2.4 GetHashCode()	787
6.283.2.5 Next()	787
6.283.2.6 operator bool()	788
6.283.2.7 operator int()	788
6.283.2.8 operator Tick()	788

6.283.2.9 operator"!=()	790
6.283.2.10 operator<()	790
6.283.2.11 operator<=()	790
6.283.2.12 operator==(())	790
6.283.2.13 operator>()	791
6.283.2.14 operator>=()	791
6.283.2.15 ToString()	791
6.283.3 Member Data Documentation	791
6.283.3.1 ALIGNMENT	791
6.283.3.2 Raw	791
6.283.3.3 SIZE	792
6.284 Tick.EqualityComparer Class Reference	792
6.284.1 Detailed Description	792
6.284.2 Member Function Documentation	792
6.284.2.1 Equals()	792
6.284.2.2 GetHashCode()	793
6.285 Tick.RelationalComparer Class Reference	793
6.285.1 Detailed Description	793
6.285.2 Member Function Documentation	793
6.285.2.1 Compare()	793
6.286 Tick.Accumulator Struct Reference	794
6.286.1 Detailed Description	795
6.286.2 Member Function Documentation	795
6.286.2.1 AddTicks()	795
6.286.2.2 AddTime()	795
6.286.2.3 Alpha()	795
6.286.2.4 ConsumeTick()	796
6.286.2.5 Start()	796
6.286.2.6 StartNew()	796
6.286.2.7 Stop()	797
6.286.3 Property Documentation	797
6.286.3.1 Pending	797
6.286.3.2 Remainder	797
6.286.3.3 Running	797
6.286.3.4 TimeScale	797
6.287 TickRate Struct Reference	798
6.287.1 Detailed Description	799
6.287.2 Member Enumeration Documentation	799
6.287.2.1 ValidateResult	799
6.287.3 Member Function Documentation	800
6.287.3.1 ClampSelection()	800
6.287.3.2 Get()	800

6.287.3.3 GetDivisor()	800
6.287.3.4 GetTickRate()	801
6.287.3.5 Init()	801
6.287.3.6 IsValid() [1/2]	802
6.287.3.7 IsValid() [2/2]	802
6.287.3.8 Resolve()	802
6.287.3.9 ToArray()	803
6.287.3.10 Validate()	803
6.287.3.11 ValidateSelection()	803
6.287.4 Property Documentation	804
6.287.4.1 Available	804
6.287.4.2 Client	804
6.287.4.3 Count	804
6.287.4.4 this[int index]	804
6.288 TickRate.Resolved Struct Reference	805
6.288.1 Detailed Description	806
6.288.2 Member Data Documentation	806
6.288.2.1 Client	806
6.288.2.2 ClientSend	806
6.288.2.3 Server	806
6.288.2.4 ServerSend	806
6.288.2.5 SIZE	806
6.288.2.6 WORDS	807
6.288.3 Property Documentation	807
6.288.3.1 ClientSendDelta	807
6.288.3.2 ClientTickDelta	807
6.288.3.3 ClientTickStride	807
6.288.3.4 ServerSendDelta	807
6.288.3.5 ServerTickDelta	807
6.288.3.6 ServerTickStride	808
6.289 TickRate.Selection Struct Reference	808
6.289.1 Detailed Description	808
6.289.2 Member Data Documentation	808
6.289.2.1 Client	808
6.289.2.2 ClientSendIndex	808
6.289.2.3 ServerIndex	809
6.289.2.4 ServerSendIndex	809
6.290 TickTimer Struct Reference	809
6.290.1 Detailed Description	810
6.290.2 Member Function Documentation	810
6.290.2.1 CreateFromSeconds()	810
6.290.2.2 CreateFromTicks()	810

6.290.2.3 Expired()	811
6.290.2.4 ExpiredOrNotRunning()	811
6.290.2.5 RemainingTicks()	812
6.290.2.6 RemainingTime()	812
6.290.2.7 ToString()	812
6.290.3 Property Documentation	812
6.290.3.1 IsRunning	813
6.290.3.2 None	813
6.290.3.3 TargetTick	813
6.291 TimeSyncConfiguration Class Reference	813
6.291.1 Detailed Description	813
6.291.2 Member Data Documentation	813
6.291.2.1 ExtraInterpolationOffset	814
6.291.2.2 ExtraSimulationOffset	814
6.291.2.3 MaxLateInputs	814
6.291.2.4 MaxLateSnapshots	814
6.292 UnitAttribute Class Reference	814
6.292.1 Detailed Description	815
6.293 UnityContextMenuAttribute Class Reference	815
6.293.1 Detailed Description	815
6.293.2 Constructor & Destructor Documentation	815
6.293.2.1 UnityContextMenuAttribute()	815
6.293.3 Property Documentation	815
6.293.3.1 order	816
6.294 UnityDelayedAttribute Class Reference	816
6.294.1 Detailed Description	816
6.294.2 Property Documentation	816
6.294.2.1 order	816
6.295 UnityFormerlySerializedAsAttribute Class Reference	816
6.295.1 Detailed Description	817
6.295.2 Constructor & Destructor Documentation	817
6.295.2.1 UnityFormerlySerializedAsAttribute()	817
6.296 UnityHeaderAttribute Class Reference	817
6.296.1 Detailed Description	817
6.296.2 Constructor & Destructor Documentation	817
6.296.2.1 UnityHeaderAttribute()	817
6.296.3 Property Documentation	818
6.296.3.1 order	818
6.297 UnityMinAttribute Class Reference	818
6.297.1 Detailed Description	818
6.297.2 Constructor & Destructor Documentation	818
6.297.2.1 UnityMinAttribute()	818

6.297.3 Property Documentation	818
6.297.3.1 order	819
6.298 UnityMultilineAttribute Class Reference	819
6.298.1 Detailed Description	819
6.298.2 Property Documentation	819
6.298.2.1 order	819
6.299 UnityNonReorderableAttribute Class Reference	819
6.299.1 Detailed Description	820
6.299.2 Property Documentation	820
6.299.2.1 order	820
6.300 UnityNonSerializedAttribute Class Reference	820
6.300.1 Detailed Description	820
6.301 UnityRangeAttribute Class Reference	820
6.301.1 Detailed Description	820
6.301.2 Constructor & Destructor Documentation	821
6.301.2.1 UnityRangeAttribute()	821
6.301.3 Property Documentation	821
6.301.3.1 order	821
6.302 UnitySerializeField Class Reference	821
6.302.1 Detailed Description	821
6.303 UnitySerializeReference Class Reference	821
6.303.1 Detailed Description	821
6.304 UnitySpaceAttribute Class Reference	822
6.304.1 Detailed Description	822
6.304.2 Constructor & Destructor Documentation	822
6.304.2.1 UnitySpaceAttribute()	822
6.304.3 Property Documentation	822
6.304.3.1 order	822
6.305 UnityTooltipAttribute Class Reference	823
6.305.1 Detailed Description	823
6.305.2 Constructor & Destructor Documentation	823
6.305.2.1 UnityTooltipAttribute()	823
6.305.3 Property Documentation	823
6.305.3.1 order	823
6.306 Vector2Compressed Struct Reference	824
6.306.1 Detailed Description	824
6.306.2 Member Function Documentation	825
6.306.2.1 Equals() [1/2]	825
6.306.2.2 Equals() [2/2]	825
6.306.2.3 GetHashCode()	825
6.306.2.4 operator Vector2()	826
6.306.2.5 operator Vector2Compressed()	826

6.306.2.6 operator"!=()	826
6.306.2.7 operator==(())	827
6.306.3 Member Data Documentation	827
6.306.3.1 xEncoded	827
6.306.3.2 yEncoded	827
6.306.4 Property Documentation	827
6.306.4.1 X	828
6.306.4.2 Y	828
6.307 Vector3Compressed Struct Reference	828
6.307.1 Detailed Description	829
6.307.2 Member Function Documentation	829
6.307.2.1 Equals() [1/2]	829
6.307.2.2 Equals() [2/2]	830
6.307.2.3 GetHashCode()	830
6.307.2.4 operator Vector2()	830
6.307.2.5 operator Vector3()	831
6.307.2.6 operator Vector3Compressed() [1/2]	831
6.307.2.7 operator Vector3Compressed() [2/2]	831
6.307.2.8 operator"!=()	832
6.307.2.9 operator==(())	832
6.307.3 Member Data Documentation	832
6.307.3.1 xEncoded	832
6.307.3.2 yEncoded	833
6.307.3.3 zEncoded	833
6.307.4 Property Documentation	833
6.307.4.1 X	833
6.307.4.2 Y	833
6.307.4.3 Z	833
6.308 Vector4Compressed Struct Reference	833
6.308.1 Detailed Description	834
6.308.2 Member Function Documentation	835
6.308.2.1 Equals() [1/2]	835
6.308.2.2 Equals() [2/2]	835
6.308.2.3 GetHashCode()	835
6.308.2.4 operator Vector4()	836
6.308.2.5 operator Vector4Compressed()	836
6.308.2.6 operator"!=()	836
6.308.2.7 operator==(())	837
6.308.3 Member Data Documentation	837
6.308.3.1 wEncoded	837
6.308.3.2 xEncoded	837
6.308.3.3 yEncoded	838

6.308.3.4 zEncoded	838
6.308.4 Property Documentation	838
6.308.4.1 W	838
6.308.4.2 X	838
6.308.4.3 Y	838
6.308.4.4 Z	838
6.309 WarnIfAttribute Class Reference	839
6.309.1 Detailed Description	839
6.309.2 Member Data Documentation	839
6.309.2.1 Message	839
6.310 WeaverGeneratedAttribute Class Reference	839
6.310.1 Detailed Description	839
Index	841

Chapter 1

Photon Fusion API Documentation

Welcome to the Photon [Fusion](#) API online documentation.

1.1 Main Fusion API

Class	Description
Fusion.NetworkRunner	Represents a Server or Client Simulation
Fusion.NetworkObject	This stores the object's network identity and manages the object's state and input authority
Fusion.NetworkProjectConfig	The core Fusion config file that is shared with all peers at startup
Fusion.NetworkBehaviour	Base class for Fusion network components, which are associated with a Fusion.NetworkObject
Fusion.NetworkTransform	Replicates a Unity Transform's position and rotation state

Chapter 2

Photon Fusion Overview

Fusion is a new high performance state synchronization networking library for Unity. **Fusion** is built with simplicity in mind to integrate naturally into the common Unity workflow, while also offering advanced features like data compression, client-side prediction and lag compensation out of the box.

Behind the covers, **Fusion** relies on a state-of-the-art compression algorithm to reduce bandwidth requirements with minimal CPU overhead. Data is transferred as partial chunks with eventual consistency. A fully configurable area-of-interest system is supplied to allow support for very high player counts.

The **Fusion** API is designed to be similar to regular Unity MonoBehaviour code. For example, RPCs and network state is defined with attributes on methods and properties of MonoBehaviour with no need for explicit serialization code and network objects can be defined as prefabs using all of Unity's most recent prefab features like nesting and variants.

Inputs, Networked Properties and RPCs provide the foundation for writing gameplay code with **Fusion**.




Figure 2.1 Overview of the Core Fusion APIs

Using a Networked Property in Fusion:

```
[Networked] public byte life { get; set; }
```

Using Network Input for client-side predicted movement:

```
public override void FixedUpdateNetwork
{
    if (GetInput(out NetworkInputData data))
    {
        data.direction.Normalize(); // normalize to prevent cheating with impossible inputs
        _characterController.Move(5 * data.direction * Runner.DeltaTime);
    }
}
```

Declaring a Remote Procedure Call (RPC) in Fusion:

```
[Rpc(RpcSources.InputAuthority, RpcTargets.StateAuthority)]
public void RPC_Configure(string name, Color color)
{
    playerName = name;
    playerColor = color;
}
```

2.1 Choosing the Right Mode

Fusion supports two fundamentally different network topologies with the same API as well as a single player mode with no network connection.

The first step when starting with Fusion is to choose between Server/Host and Shared mode.

The **Quadrant** provides a good starting point for deciding what mode is right for your application.




Figure 2.2 The Quadrant

2.2 Topology Differences




Figure 2.3 Fusion Network Topologies

2.2.1 Server Mode

In Server Mode the server has full and exclusive State Authority over all objects, no exceptions.

Clients can only modify networked objects by sending their input to the server (and have the server react to that input) or by requesting a change using an RPC.

The server application is built from the Unity project and runs a full headless Unity build. This headless build needs to be hosted on a server machine or a cloud hosted server. Photon does not provide servers for hosting a dedicated fusion server application.

2.2.1.1 Client Side Prediction

Client Side Prediction is a popular multiplayer architecture in which clients use their own inputs to predict their movement before receiving confirmation from the server. This allows the gameplay to feel snappy and hides latency.

In **Fusion** Server Mode, any changes a client makes directly to the networked state is only a local prediction, which will be overridden with actual authoritative snapshots from the server when those are received. This is known as reconciliation, as the client is rolled back to the server-provided state and re-simulated forward to the local (predicted) tick.

If previous predictions were accurate, this process is seamless. If not, the state will be updated and because the network state is separate from the rendering state, the rendering may either snap to this new state or use various forms of interpolation, error correction and smoothing to reduce the visual artifacts caused by the correction.

2.2.2 Host Mode

In Host Mode, the host acts as both a server and a client. The host has a local player and polls input for it and interpolates on rendering as expected of a client.

Overall the mode is equivalent to a dedicated server albeit much cheaper to run as no dedicated server hosting costs are incurred. This benefit comes in expense of losing a trustworthy authority; in other words a rogue host can cheat.

When running hosted mode from behind a firewall or a router, the Photon cloud transparently provides UDP punch through or package relay as needed,

Since the session is owned by the host, it will be lost if the host disconnects. [Fusion](#) does provide a host migration mechanism to allow transfer of network authority to a new client in the event that the current host is disconnected. Do note that, unlike Shared Mode, this requires special handling in client code.

2.2.3 Shared Mode

In shared mode, authority over network objects is distributed among all clients. Specifically, each client initially has State Authority over objects they spawn, but are free to release that State Authority to other clients. Optionally, clients may be allowed to take State Authority at will.

In shared mode features such as client side prediction and rollback are not available. Simulation always moves forward at the same tick rate on all clients.

The Shared Mode network session is owned by the Photon cloud and remains alive as long as any client is connected to it. The Photon cloud serves as a package relay and has full access to the network state with no need to run Unity, allowing for lightweight server logic and data validation (e.g. cheat protection) to be implemented without the need to spin up dedicated server hardware.

For those coming from Photon Unity Networking (PUN). Shared mode is in many ways similar to PUN, albeit more feature complete, faster, and with no run-time allocation overhead.

2.2.4 Cost

The same CCU costs apply for all modes. The server and clients all have to be connected to the Photon Cloud at all times for connection management. In Server Mode there are additional costs for hosting the dedicated server on a cloud service or your own hardware.

Chapter 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

Allocator	69
Allocator.Config	71
AssetObject	84
TaskManager	85
AuthorityMasks	87
Behaviour	88
Hitbox	124
NetworkEvents	362
NetworkObject	398
NetworkObjectPrefabData	436
NetworkRunner	501
SimulationBehaviour	723
HitboxManager	128
NetworkBehaviour	259
HitboxRoot	142
NetworkMecanimAnimator	396
NetworkTRSP	623
NetworkTransform	620
BehaviourStats	90
CapacityAttribute	91
DefaultForPropertyAttribute	92
DisplayAsEnumAttribute	93
DofAttributeBase	94
DrawIfAttribute	94
WarnIfAttribute	839
DynamicHeap	96
DynamicHeap.Ignore	100
DynamicHeap.Instance	100
FieldsMask< T >	105
FixedArray< T >	107
FixedArray< T >.Enumerator	114
FixedBufferPropertyAttribute	116
FixedStorage	117
FloatUtils	121

HeapConfiguration	123
HostMigrationConfig	148
HostMigrationToken	149
IAfterAllTicks	149
NetworkMecanimAnimator	396
NetworkTransform	620
IAfterClientPredictionReset	150
IAfterHostMigration	150
IAfterRender	151
IAfterSpawned	151
IAfterTick	152
HitboxManager	128
IAfterUpdate	153
HitboxManager	128
IAsyncOperation	153
ICoroutine	159
IBeforeAllTicks	155
HitboxManager	128
NetworkTransform	620
IBeforeClientPredictionReset	155
IBeforeCopyPreviousState	156
NetworkTransform	620
IBeforeHitboxRegistration	157
IBeforeTick	157
IBeforeUpdate	158
IDespawned	159
NetworkBehaviour	259
IElementReaderWriter< T >	160
IFixedStorage	162
_128	61
_16	62
_2	63
_256	63
_32	64
_4	65
_512	66
_64	67
_8	68
IInputAuthorityGained	162
IInputAuthorityLost	162
IInterestEnter	163
IInterestExit	164
ILocalPrefabCreated	164
INetworkArray	165
NetworkArray< T >	248
INetworkAssetSource< T >	166
INetworkDictionary	167
NetworkDictionary< K, V >	349
INetworkInput	168
INetworkLinkedList	168
NetworkLinkedList< T >	380
INetworkObjectInitializer	169
NetworkObjectInitializerUnity	429
INetworkObjectProvider	170
NetworkObjectProviderDummy	436

INetworkRunnerCallbacks	172
NetworkDelegates	348
NetworkEvents	362
INetworkRunnerUpdater	178
NetworkRunnerUpdaterDefault	562
INetworkSceneManager	180
INetworkStruct	184
Angle	75
FloatCompressed	118
NetworkBehaviourId	309
NetworkBool	332
NetworkButtons	334
NetworkId	367
NetworkObjectGuid	412
NetworkObjectHeader	421
NetworkObjectNestingKey	431
NetworkObjectTypeId	443
NetworkPhysicsInfo	453
NetworkPrefabId	456
NetworkPrefabRef	464
NetworkRNG	494
NetworkSceneInfo	574
NetworkString< TSize >	593
NetworkTRSPData	626
PlayerRef	630
Ptr	638
QuaternionCompressed	644
SceneRef	685
TickTimer	809
Vector2Compressed	824
Vector3Compressed	828
Vector4Compressed	833
_128	61
_16	62
_2	63
_256	63
_32	64
_4	65
_512	66
_64	67
_8	68
INetworkTRSPTeleport	184
NetworkTransform	620
IUnitySurrogate	185
IUnityValueSurrogate< T >	186
UnityValueSurrogate< T, TReaderWriter >	195
UnitySurrogateBase	193
UnityArraySurrogate< T, ReaderWriter >	187
UnityDictionarySurrogate< KeyType, KeyReaderWriter, ValueType, ValueReaderWriter >	189
UnityLinkedListSurrogate< T, ReaderWriter >	191
UnityValueSurrogate< T, TReaderWriter >	195
InterpolatedErrorCorrectionSettings	197
IPlayerJoined	200
IPlayerLeft	200
IRemotePrefabCreated	201
ISceneLoadDone	202
ISceneLoadStart	202

ISimulationEnter	203
ISimulationExit	204
ISpawned	204
NetworkBehaviour	259
IStateAuthorityChanged	205
LagCompensatedHit	205
AABB	208
BoxOverlapQueryParams	213
BVHDraw	215
BVHNodeDrawInfo	215
ColliderDrawInfo	216
HitboxColliderContainerDraw	218
LagCompensatedExt	218
LagCompensationDraw	220
LagCompensationUtils.ContactData	221
PositionRotationQueryParams	222
Query	223
BoxOverlapQuery	210
RaycastQuery	229
RaycastAllQuery	228
SphereOverlapQuery	234
QueryParams	226
RaycastQueryParams	231
SnapshotHistoryDraw	233
SphereOverlapQueryParams	236
LagCompensationSettings	238
LobbyInfo	240
LogSimpleUnity	241
NestedComponentUtilities	241
NetworkArray< T >.Enumerator	255
NetworkArrayExtensions	257
NetworkArrayReadOnly< T >	258
NetworkAssemblyIgnoreAttribute	259
NetworkAssemblyWeavedAttribute	259
NetworkBehaviour.ArrayReader< T >	280
NetworkBehaviour.BehaviourReader< T >	281
NetworkBehaviour.ChangeDetector	283
NetworkBehaviour.ChangeDetector.Enumerable	285
NetworkBehaviour.ChangeDetector.Enumerator	286
NetworkBehaviour.DictionaryReader< K, V >	287
NetworkBehaviour.LinkListReader< T >	288
NetworkBehaviour.PropertyReader< T >	289
NetworkBehaviourBuffer	291
NetworkBehaviourBufferInterpolator	297
NetworkBehaviourUtils	313
NetworkBehaviourUtils.ArrayInitializer< T >	328
NetworkBehaviourUtils.DictionaryInitializer< K, V >	329
NetworkBehaviourUtils.MetaData	330
NetworkBehaviourWeavedAttribute	331
NetworkConfiguration	344
NetworkDeserializeMethodAttribute	348
NetworkDictionary< K, V >.Enumerator	355
NetworkDictionaryReadOnly< K, V >	357
NetworkedAttribute	359
NetworkedWeavedAttribute	360
NetworkEvents.ConnectFailedEvent	363
NetworkEvents.ConnectRequestEvent	363
NetworkEvents.CustomAuthenticationResponse	364

NetworkEvents.DisconnectFromServerEvent	364
NetworkEvents.HostMigrationEvent	364
NetworkEvents.InputEvent	364
NetworkEvents.InputPlayerEvent	365
NetworkEvents.ObjectEvent	365
NetworkEvents.ObjectPlayerEvent	365
NetworkEvents.PlayerEvent	365
NetworkEvents.ReliableDataEvent	366
NetworkEvents.ReliableProgressEvent	366
NetworkEvents.RunnerEvent	366
NetworkEvents.SessionListUpdateEvent	366
NetworkEvents.ShutdownEvent	367
NetworkEvents.SimulationMessageEvent	367
NetworkId.EqualityComparer	373
NetworkInput	374
NetworkInputUtils	377
NetworkInputWeavedAttribute	379
NetworkLinkedList< T >.Enumerator	386
NetworkLinkedListReadOnly< T >	388
NetworkLoadSceneParameters	391
NetworkObjectFlagsExtensions	409
NetworkObjectGuid.EqualityComparer	420
NetworkObjectHeaderPtr	428
NetworkObjectMeta	430
NetworkObjectNestingKey.EqualityComparer	435
NetworkObjectReleaseContext	437
NetworkObjectSortKeyComparer	439
NetworkObjectSpawnException	440
NetworkObjectStats	441
NetworkObjectTypeId.EqualityComparer	452
NetworkPrefabAcquireContext	454
NetworkPrefabAttribute	456
NetworkPrefabId.EqualityComparer	461
NetworkPrefabInfo	462
NetworkPrefabRef.EqualityComparer	471
NetworkPrefabTable	472
NetworkPrefabTableOptions	480
NetworkProjectConfig	481
NetworkProjectConfigAsset	490
NetworkProjectConfigAsset.SerializableSimulationBehaviourMeta	493
NetworkRpcStaticWeavedInvokerAttribute	499
NetworkRpcWeavedInvokerAttribute	500
NetworkRunnerCallbackArgs	561
NetworkRunnerCallbackArgs.ConnectRequest	561
NetworkRunnerUpdaterDefault.NetworkRunnerRender	564
NetworkRunnerUpdaterDefault.NetworkRunnerUpdate	565
NetworkRunnerUpdaterDefault.InvokeSettings	565
NetworkSceneAsyncOp	568
NetworkSceneAsyncOp.Awaiter	573
NetworkSceneLoadId	580
NetworkSceneObjectId	582
NetworkSerializeMethodAttribute	584
NetworkSimulationConfiguration	585
NetworkSpawnOp	589
NetworkSpawnOp.Awaiter	591
NetworkStructUtils	618
NetworkStructWeavedAttribute	619
NormalizedRectAttribute	629

PreserveInPluginAttribute	638
IMessage	638
Ptr.EqualityComparer	643
ReadWriteUtils	650
ReadWriteUtilsForWeaver	657
ReflectionUtils	663
RenderAttribute	666
RenderTimeline	668
RenderWeavedAttribute	669
ResolveNetworkPrefabSourceAttribute	669
RpcAttribute	669
RpcHeader	672
RpcInfo	676
RpcInvokeData	678
RpcInvokeInfo	680
RpcSendResult	682
RpcTargetAttribute	683
SceneLoadDoneArgs	683
SerializableDictionary< TKey, TValue >	693
SessionInfo	699
Simulation	702
Simulation.AreaOfInterest	719
SimulationBehaviourAttribute	725
SimulationBehaviourListScope	726
SimulationConfig	727
SimulationConnectionStats	730
SimulationInput	734
SimulationInput.Buffer	736
SimulationInputHeader	740
SimulationMessage	742
SimulationMessagePtr	753
SimulationRuntimeConfig	754
SimulationStats	756
NetAddress	761
NetBitBufferList	765
NetCommandAccepted	768
NetCommandConnect	768
NetCommandDisconnect	769
NetCommandHeader	769
NetCommandRefused	770
NetConfig	771
StunClient.TestIPs	775
StartGameArgs	776
StartGameResult	782
StatsMetaAttribute	784
Tick	785
Tick.EqualityComparer	792
Tick.RelationalComparer	793
TickAccumulator	794
TickRate	798
TickRate.Resolved	805
TickRate.Selection	808
TimeSyncConfiguration	813
UnitAttribute	814
UnityContextMenuMenuItemAttribute	815
UnityDelayedAttribute	816
UnityFormerlySerializedAsAttribute	816
UnityHeaderAttribute	817

UnityMinAttribute	818
UnityMultilineAttribute	819
UnityNonReorderableAttribute	819
UnityNonSerializedAttribute	820
UnityRangeAttribute	820
UnitySerializeField	821
UnitySerializeReference	821
UnitySpaceAttribute	822
UnityTooltipAttribute	823
WeaverGeneratedAttribute	839
IElementReaderWriter< K >	160
IElementReaderWriter< V >	160
INetworkAssetSource< NetworkObject >	166
INetworkPrefabSource	171
NetworkBehaviour.PropertyReader< Fusion.NetworkBehaviourId >	289

Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

_128	A FixedStorage that can hold up to 128 words	61
_16	A FixedStorage that can hold up to 16 words	62
_2	A FixedStorage that can hold up to 2 words	63
_256	A FixedStorage that can hold up to 256 words	63
_32	A FixedStorage that can hold up to 32 words	64
_4	A FixedStorage that can hold up to 4 words	65
_512	A FixedStorage that can hold up to 512 words	66
_64	A FixedStorage that can hold up to 64 words	67
_8	A FixedStorage that can hold up to 8 words	68
Allocator	Memory Allocator	69
Allocator.Config	Memory Allocator Configuration	71
Angle	A Networked fusion type for degrees. This can be used with the NetworkedAttribute , in RPCs, or in NetworkInput structs	75
AssetObject	Base class for all Fusion assets	84
TaskManager	Task Factory is used to create new Tasks and Schedule long running Tasks	85
AuthorityMasks	Provides constants and methods for managing authority masks	87
Behaviour	Alternative base class to Unity's MonoBehaviour. This allows for components that work both in Unity, as well as the Photon relays	88
BehaviourStats	Represents statistics related to the execution of a SimulationBehaviour	90

CapacityAttribute	
Capacity Attribute	91
DefaultForPropertyAttribute	
Default For Property Attribute	92
DisplayAsEnumAttribute	
Casts an enum or int value in the inspector to specific enum type for rendering of its popup list. Supplying a method name rather than a type allows a property with the type Type to be used to dynamically get the enum type	93
DolfAttributeBase	
Editor attribute for selective editor rendering. Condition member can be a property, field or method (with a return value)	94
DrawIfAttribute	
Editor attribute for selectively drawing/hiding fields. Condition member can be a property, field or method (with a return value)	94
DynamicHeap	
A dynamic heap for allocating and tracking unmanaged objects	96
DynamicHeap.Ignore	
Ignore this field when scanning for pointers	100
DynamicHeapInstance	
Dynamic heap instance	100
FieldsMask< T >	
Base class for FieldsMask<T>	105
FixedArray< T >	
A fixed size array that can be used in structs	107
FixedArray< T >.Enumerator	
Enumerator for the FixedArray struct	114
FixedBufferPropertyAttribute	
Fixed Buffer Property Attribute	116
FixedStorage	
Provides utility methods for fixed storage types	117
FloatCompressed	
Represents a compressed float value for network transmission	118
FloatUtils	
Provides utility methods for compressing and decompressing float values	121
HeapConfiguration	
Memory Heap Settings	123
Hitbox	
Represents a single lag-compensated collider. Multiple component instances can be added anywhere in the hierarchy of a NetworkObject which includes a HitboxRoot	124
HitboxManager	
Entry point for lag compensated Hitbox queries, which maintains a history buffer, and provides lag compensated raycast and overlap methods. Singleton instance is accessible through the property Runner.LagCompensation	128
HitboxRoot	
Root Hitbox group container. Manages registering/unregistering hitboxes with the group, and defines the broadphase geometry for the group	142
HostMigrationConfig	
Project configuration settings specific to how the Host Migration behaves	148
HostMigrationToken	
Transitory Holder with all necessary information to restart the Fusion Runner after the Host Migration has completed	149
IAfterAllTicks	
Interface for AfterAllTicks callback. Called after the re-simulation loop (when applicable), and also after the forward simulation loop. Implement this interface on SimulationBehaviour and NetworkBehaviour classes	149

IAfterClientPredictionReset	Callback interface for AfterClientPredictionReset . Called at the very start of the resimulation loop (on clients with prediction enabled), immediately after state is set to the latest server snapshot. Implement this interface on SimulationBehaviour and NetworkBehaviour classes	150
IAfterHostMigration	Used to mark NetworkBehaviors that need to be react after a Host Migration process	150
IAfterRender	Interface for AfterRender callback. Called after the render loop	151
IAfterSpawned	Interface for AfterSpawned callback. Called after the object is spawned	151
IAfterTick	Interface for AfterTick callback. Called after each tick simulation completes. Implement this interface on SimulationBehaviour and NetworkBehaviour classes	152
IAfterUpdate	Interface for the AfterUpdate callback, which is called at the end of each Fusion Update segment. Implement this interface on SimulationBehaviour and NetworkBehaviour classes	153
IAsyncOperation	Defines an asynchronous operation	153
IBeforeAllTicks	Interface for BeforeAllTicks callback. Called before the re-simulation loop (when applicable), and also before the forward simulation loop. Implement this interface on SimulationBehaviour and NetworkBehaviour classes	155
IBeforeClientPredictionReset	Callback interface for BeforeClientPredictionReset . Called at the very start of the re-simulation loop (on clients with prediction enabled), before state is set to the latest server snapshot. Implement this interface on SimulationBehaviour and NetworkBehaviour classes	155
IBeforeCopyPreviousState	Interface for BeforeCopyPreviousState callback. Called before the copy of the previous state	156
IBeforeHitboxRegistration	Interface for BeforeHitboxRegistration callback. Implement this interface on SimulationBehaviour and NetworkBehaviour classes	157
IBeforeTick	Interface for BeforeTick callback. Called before each tick is simulated. Implement this interface on SimulationBehaviour and NetworkBehaviour classes	157
IBeforeUpdate	Interface for the BeforeUpdate callback, which is called at the beginning of each Fusion Update segment. Implement this interface on SimulationBehaviour and NetworkBehaviour classes	158
ICoroutine	Defines a coroutine	159
IDespawned	Interface for Despawned callback. Called when a NetworkBehaviour is despawned	159
IElementReaderWriter< T >	Defines the interface for reading and writing elements in a byte array	160
IFixedStorage	Interface for fixed storage types	162
IInputAuthorityGained	Interface for handling the event when the input authority is gained	162
IInputAuthorityLost	Interface for handling the event when the input authority is lost	162
IInterestEnter	Interface for handling the event when a player enters the area of interest	163
IInterestExit	Interface for handling the event when a player exits the area of interest	164
ILocalPrefabCreated	Interface for handling the event when a local prefab is created	164
INetworkArray	Defines the interface for a networked array	165

INetworkAssetSource< T >	
Interface for a network asset source	166
INetworkDictionary	
Defines the interface for a networked dictionary	167
INetworkInput	
Flag interface for custom NetworkInput structs	168
INetworkLinkedList	
Defines the interface for a networked linked list	168
INetworkObjectInitializer	
Interface for initializing network objects	169
INetworkObjectProvider	
Interface which defines the handlers for NetworkRunner Spawn() and Despawn() actions. Passing an instance of this interface to NetworkRunner.StartGame(StartGameArgs) as the StartGameArgs.ObjectProvider argument value will assign that instance as the handler for runner Spawn() and Despawn() actions. By default (if StartGameArgs.ObjectProvider == null) actions will use Instantiate() , and Despawn() actions will use Destroy()	170
INetworkPrefabSource	
Interface for a network prefab source	171
INetworkRunnerCallbacks	
Interface for NetworkRunner callbacks. Register a class/struct instance which implements this interface with NetworkRunner.AddCallbacks(INetworkRunnerCallbacks[])	172
INetworkRunnerUpdater	
Interface which defines the handlers for NetworkRunner Updates. An implementation is responsible for calling NetworkRunner.UpdateInternal(double) and NetworkRunner.RenderInternal periodically	178
INetworkSceneManager	
Interface for a NetworkRunner scene manager. A scene manager is responsible for loading and unloading scenes	180
INetworkStruct	
Base interface for all Fusion Network Structs	184
INetworkTRSPTeleport	
Implement this interface on a NetworkTRSP implementation to indicate it can be teleported	184
IUnitySurrogate	
Represents an interface for Unity surrogates. This interface provides methods for reading and writing data	185
IUnityValueSurrogate< T >	
Represents an interface for Unity value surrogates. This interface provides a property for accessing and modifying the data	186
UnityArraySurrogate< T, ReaderWriter >	
A base class for Unity array surrogates	187
UnityDictionarySurrogate< KeyType, KeyReaderWriter, ValueType, ValueReaderWriter >	
A surrogate for serializing a dictionary	189
UnityLinkedListSurrogate< T, ReaderWriter >	
A surrogate for serializing a linked list	191
UnitySurrogateBase	
Represents a base class for Unity surrogates. This class is serializable and provides abstract methods for reading, writing, and initializing data	193
UnityValueSurrogate< T, TReaderWriter >	
Represents a base class for Unity value surrogates. This class is serializable and provides methods for reading, writing, and initializing data	195
InterpolatedErrorCorrectionSettings	
A set of parameters that tune the interpolated correction of prediction error on transform data	197
IPlayerJoined	
Interface for handling the event when a player joins the game	200
IPlayerLeft	
Interface for handling the event when a player leaves the game	200
IRemotePrefabCreated	
Interface for handling the event when a remote prefab is created	201

ISceneLoadDone	Interface for handling the event when a scene load operation is completed	202
ISceneLoadStart	Interface for handling the event when a scene load operation is started	202
ISimulationEnter	Interface for SimulationEnter callback. Called when the NetworkObject joins AreaOfInterest. Implement this interface on SimulationBehaviour and NetworkBehaviour classes	203
ISimulationExit	Interface for the SimulationExit callback. Called when the NetworkObject leaves AreaOfInterest. Implement this interface on SimulationBehaviour and NetworkBehaviour classes	204
ISpawned	Interface for handling the event when an object is spawned	204
IStateAuthorityChanged	Interface for handling the event when the state authority changes	205
LagCompensatedHit	Defines a lag compensated query hit result	205
AABB	Represents an Axis-Aligned Bounding Box (AABB)	208
BoxOverlapQuery	Class that represents a box overlap query. Used to query against the NetworkRunner.LagCompensation API	210
BoxOverlapQueryParams	Base parameters needed to execute a box overlap query	213
BVHDraw	Provide a way to iterate over BVH and return a BVHNodeDrawInfo for each node	215
BVHNodeDrawInfo	Container class to provide the necessary info to draw nodes from the BVH	215
ColliderDrawInfo	Container class to provide the necessary information to draw a hitbox collider	216
HitboxColliderContainerDraw	Provide a way to iterate over the HitboxBuffer.HitboxSnapshot and return the ColliderDrawInfo for each collider on the snapshot	218
LagCompensatedExt	LagCompensated Extension methods	218
LagCompensationDraw	Provide access to iterate over the lag compensation system components and give the necessary information to draw them	220
LagCompensationUtils.ContactData	Details regarding a shape intersection. It does not carry information about the intersection happening or not	221
PositionRotationQueryParams	Query parameters for position rotation query	222
Query	Base class for all Lag Compensation queries	223
QueryParams	Base parameters needed to execute a query	226
RaycastAllQuery	Class that represents a raycast all query. Used to query against the NetworkRunner.LagCompensation API	228
RaycastQuery	Class that represents a raycast query. Used to query against the NetworkRunner.LagCompensation API	229
RaycastQueryParams	Base parameters needed to execute a raycast query	231
SnapshotHistoryDraw	Provide a way to iterate over the HitboxBuffer and return the HitboxColliderContainerDraw container for each snapshot on the buffer	233

SphereOverlapQuery	
Class that represents a sphere overlap query. Used to query against the NetworkRunner.LagCompensation API	234
SphereOverlapQueryParams	
Base parameters needed to execute a sphere overlap query	236
LagCompensationSettings	
Settings for lag compensation history	238
LobbyInfo	
Holds information about a Lobby	240
LogSimpleUnity	
Log Simple Unity	241
NestedComponentUtilities	
Tools to replace GetComponent variants that respects nested objects. These are used to find components of a NetworkedObjects without also finding components that belong to parent or child NetworkedObjects	241
NetworkArray< T >	
Fusion type for networking arrays. Maximum capacity is fixed, and is set with the CapacityAttribute	248
NetworkArray< T >.Enumerator	
Enumerator for NetworkArray	255
NetworkArrayExtensions	
Provides extension methods for the NetworkArray class	257
NetworkArrayReadOnly< T >	
Provides a read-only view of a network array	258
NetworkAssemblyIgnoreAttribute	
Network Assembly Ignore Attribute	259
NetworkAssemblyWeavedAttribute	
Network Assembly Weaved Attribute	259
NetworkBehaviour	
Base class for Fusion network components, which are associated with a NetworkObject	259
NetworkBehaviour.ArrayReader< T >	
Provides a reader for network arrays of type T	280
NetworkBehaviour.BehaviourReader< T >	
Provides a reader for network behaviours of type T	281
NetworkBehaviour.ChangeDetector	
Change detector for a NetworkBehaviour	283
NetworkBehaviour.ChangeDetector.Enumerable	
Struct representing a collection of changes detected in a NetworkBehaviour	285
NetworkBehaviour.ChangeDetector.Enumerator	
Enumerator for the collection of changes detected in a NetworkBehaviour	286
NetworkBehaviour.DictionaryReader< K, V >	
Provides a reader for network dictionaries with keys of type K and values of type V	287
NetworkBehaviour.LinkListReader< T >	
Provides a reader for network linked lists of type T	288
NetworkBehaviour.PropertyReader< T >	
Provides a reader for properties of type T in a network behaviour	289
NetworkBehaviourBuffer	
Provides low level accesss to data buffers that can be read using a NetworkBehaviour.Reader	291
NetworkBehaviourBufferInterpolator	
The NetworkBehaviourBufferInterpolator struct is used to interpolate between two NetworkBehaviourBuffer instances. This is a read-only, ref struct, meaning it cannot be boxed and it can only be used on the stack	297
NetworkBehaviourId	
Represents the unique identifier for a NetworkBehaviour instance	309
NetworkBehaviourUtils	
This static class provides utility methods for working with NetworkBehaviour objects	313

NetworkBehaviourUtils.ArrayInitializer< T >	
A utility structure for initializing NetworkArray and NetworkLinkedList with inline initialization	328
NetworkBehaviourUtils.DictionaryInitializer< K, V >	
A utility structure for initializing NetworkDictionary with inline initialization	329
NetworkBehaviourUtils.Metadata	
This structure holds metadata for a NetworkBehaviour object	330
NetworkBehaviourWeavedAttribute	
Network Behaviour Weaved Attribute	331
NetworkBool	
Represents a boolean value that can be networked	332
NetworkButtons	
Represents a set of buttons that can be networked	334
NetworkConfiguration	
Main network configuration class	344
NetworkDelegates	
Network Runner Callbacks Delegates	348
NetworkDeserializeMethodAttribute	
Network Deserialize Method Attribute	348
NetworkDictionary< K, V >	
Fusion type for networking Dictionaries. Maximum capacity is fixed, and is set with the CapacityAttribute .	
349	
NetworkDictionary< K, V >.Enumerator	
Enumerator for NetworkDictionary	355
NetworkDictionaryReadOnly< K, V >	
A read-only version of NetworkDictionary<TKey,TValue>	357
NetworkedAttribute	
359	
NetworkedWeavedAttribute	
Networked Weaved Attribute	360
NetworkEvents	
Companion component for NetworkRunner . Exposes INetworkRunnerCallbacks as UnityEvents, which can be wired up to other components in the inspector	362
NetworkEvents.ConnectFailedEvent	
UnityEvent for ConnectFailed	363
NetworkEvents.ConnectRequestEvent	
UnityEvent for ConnectRequest	363
NetworkEvents.CustomAuthenticationResponse	
UnityEvent for Custom Authentication	364
NetworkEvents.DisconnectFromServerEvent	
UnityEvent for DisconnectFromServer	364
NetworkEvents.HostMigrationEvent	
UnityEvent for HostMigration	364
NetworkEvents.InputEvent	
UnityEvent for NetworkInput	364
NetworkEvents.InputPlayerEvent	
UnityEvent for NetworkInput with PlayerRef	365
NetworkEvents.ObjectEvent	
UnityEvent for NetworkObject	365
NetworkEvents.ObjectPlayerEvent	
UnityEvent for NetworkObject with PlayerRef	365
NetworkEvents.PlayerEvent	
UnityEvent for PlayerRef	365
NetworkEvents.ReliableDataEvent	
UnityEvent for Reliable Data	366
NetworkEvents.ReliableProgressEvent	
UnityEvent for Reliable Data Progress	366

NetworkEvents.RunnerEvent	
UnityEvent for NetworkRunner	366
NetworkEvents.SessionListUpdateEvent	
UnityEvent for SessionInfo List	366
NetworkEvents.ShutdownEvent	
UnityEvent for Shutdown	367
NetworkEvents.SimulationMessageEvent	
UnityEvent for SimulationMessage	367
NetworkId	
The unique identifier for a network entity	367
NetworkId.EqualityComparer	
IEqualityComparer interface for NetworkId objects	373
NetworkInput	
NetworkInput Struct	374
NetworkInputUtils	
Utility methods for NetworkInput	377
NetworkInputWeavedAttribute	
Network Input Weaved Attribute	379
NetworkLinkedList< T >	
Fusion type for networking LinkedLists. Maximum capacity is fixed, and is set with the CapacityAttribute .	
Typical Usage:	380
NetworkLinkedList< T >.Enumerator	
Enumerator for NetworkLinkedList<T>	386
NetworkLinkedListReadOnly< T >	
Read-only version of NetworkLinkedList<T>	388
NetworkLoadSceneParameters	
Parameters for loading a scene	391
NetworkMecanimAnimator	
A component for synchronizing the Animator controller state from the State Authority to network proxies. Requires a Unity Animator component, and a NetworkObject component. NOTE↔ : Animator Root Motion is not compatible with re-simulation and prediction	396
NetworkObject	
The primary Fusion component for networked GameObject entities. This stores the object's network identity and manages the object's state and input authority	398
NetworkObjectFlagsExtensions	
Extension methods for the NetworkObjectFlags enum	409
NetworkObjectGuid	
NetworkObjectGuid	412
NetworkObjectGuid.EqualityComparer	
EqualityComparer for NetworkObjectGuid	420
NetworkObjectHeader	
Network object header information for a NetworkObject	421
NetworkObjectHeaderPtr	
Represents a pointer to a NetworkObjectHeader . This struct is unsafe because it uses pointers	428
NetworkObjectInitializerUnity	
Initializes network objects for Unity	429
NetworkObjectMeta	
Meta information about a network object	430
NetworkObjectNestingKey	
A key used to identify a network object nesting	431
NetworkObjectNestingKey.EqualityComparer	
Implements the IEqualityComparer interface	435
NetworkObjectPrefabData	
This class represents the data for a network object prefab	436

NetworkObjectProviderDummy	
A dummy implementation of the INetworkObjectProvider interface. This class is used for testing purposes and throws a NotImplementedException for all its methods	436
NetworkObjectReleaseContext	
Represents the context for releasing a network object. This struct is unsafe because it uses pointers	437
NetworkObjectSortKeyComparer	
This class is used to compare two NetworkObject instances based on their SortKey. It implements the IComparer interface	439
NetworkObjectSpawnException	
Network Object Spawn Exception	440
NetworkObjectStats	
The NetworkObjectStats class provides statistics related to a network object. It includes bandwidth, updates, and player count within the area of interest	441
NetworkObjectTypeId	
ID for a NetworkObject Prefab which has been cataloged in a NetworkProjectConfig.PrefabTable	443
NetworkObjectTypeId.EqualityComparer	
NetworkObjectTypeId Comparer	452
NetworkPhysicsInfo	
Network Physics INetworkStruct	453
NetworkPrefabAcquireContext	
Represents the context for acquiring a prefab instance for a network object. This struct is unsafe because it uses pointers	454
NetworkPrefabAttribute	
Network Prefab Attribute	456
NetworkPrefabId	
ID for a NetworkObject Prefab which has been cataloged in a NetworkProjectConfig.PrefabTable	456
NetworkPrefabId.EqualityComparer	
Equality comparer for NetworkPrefabId	461
NetworkPrefabInfo	
Meta data for a NetworkObject prefab which has been cataloged in a NetworkProjectConfig.PrefabTable	462
NetworkPrefabRef	
NetworkPrefabRef	464
NetworkPrefabRef.EqualityComparer	
EqualityComparer for NetworkPrefabRef	471
NetworkPrefabTable	
Class representing a table of network prefabs	472
NetworkPrefabTableOptions	
Options for the NetworkPrefabTable	480
NetworkProjectConfig	
The core Fusion config file that is shared with all peers at startup	481
NetworkProjectConfigAsset	
Manages and references the current instance of NetworkProjectConfig	490
NetworkProjectConfigAsset.SerializableSimulationBehaviourMeta	
An auto-generated list containing meta information about all the SimulationBehaviours in the project, e.g. execution order	493
NetworkRNG	
PCG32 random generator, 16 bytes in size. http://www.pcg-random.org	494
NetworkRpcStaticWeavedInvokerAttribute	
Network Rpc Static Weaved Invoker Attribute Contains info about a static weaved RPC Method	499
NetworkRpcWeavedInvokerAttribute	
Network Rpc Weaved Invoker Attribute Contains info about a weaved RPC Method	500
NetworkRunner	
Host Migration related code in order to get a copy of the Simulation State	501
NetworkRunnerCallbackArgs	
Stores data types used on the INetworkRunnerCallbacks interface	561

NetworkRunnerCallbackArgs.ConnectRequest	
Data holder of a Connection Request from a remote client	561
NetworkRunnerUpdaterDefault	
Default implementation of INetworkRunnerUpdater that uses the Unity PlayerLoop	562
NetworkRunnerUpdaterDefault.NetworkRunnerRender	
Used to invoke NetworkRunner.RenderInternal in the PlayerLoop	564
NetworkRunnerUpdaterDefault.NetworkRunnerUpdate	
Used to invoke NetworkRunner.UpdateInternal(double) in the PlayerLoop	565
NetworkRunnerUpdaterDefault.InvokeSettings	
Settings for the NetworkRunnerUpdaterDefault	565
NetworkSceneAsyncOp	
A wrapper for async scene operations	568
NetworkSceneAsyncOp.Awaiter	
Awaiter for NetworkSceneAsyncOp	573
NetworkSceneInfo	
Can store up to 8 active scenes and allows for duplicates. Each write increases Version which can be used to generate unique scene objects ids for when a scene is supposed to be reloaded	574
NetworkSceneLoadId	
A unique identifier for a scene load operation	580
NetworkSceneObjectId	
A unique identifier for a scene object	582
NetworkSerializeMethodAttribute	
Network Serialize Method Attribute	584
NetworkSimulationConfiguration	
Configuration for network conditions simulation (induced latency and loss)	585
NetworkSpawnOp	
Spawn Operation	589
NetworkSpawnOp.Awaiter	
Awaiter for NetworkSpawnOp	591
NetworkString< TSize >	
Fixed-size UTF32 string. All operations are alloc-free, except for converting to System.String	593
NetworkStructUtils	
Utility methods for INetworkStruct	618
NetworkStructWeavedAttribute	
Describes the total number of WORDs a INetworkStruct uses	619
NetworkTransform	
Add to any NetworkObject Transform, or its associated child Transforms to automatically synchronize TRSP (Position/Rotation/Scale/Parent)	620
NetworkTRSP	
Base class for spatial (Position/Rotation/Scale/Parent) synchronization component, such as NetworkTransform . Provides the base logic for render interpolation, parenting synchronization, and teleport, that can be used in components derived from this class	623
NetworkTRSPData	
Data structure storing spatial (Position/Rotation/Scale/Parent) synchronization data for spatial synchronization components, NetworkTRSP and its subclass NetworkTransform	626
NormalizedRectAttribute	
Enables a special inspector drawer for Unity Rect type, specially designed for editing Rect↔ Transforms using normalized values	629
PlayerRef	
Represents a Fusion player	630
PreserveInPluginAttribute	
Preserve In Plugin Attribute	638
IMessage	
Represents a Protocol Message	638
Ptr	
Ptr	638
Ptr.EqualityComparer	
Ptr Equality Comparer	643

QuaternionCompressed	Represents a compressed Quaternion value for network transmission	644
ReadWriteUtils	Provides utility methods for reading and writing data	650
ReadWriteUtilsForWeaver	Provides utility methods for reading and writing data	657
ReflectionUtils	Provides utility methods for reflection	663
RenderAttribute	Override default render settings for [Networked] properties	666
RenderTimeline	Can be used to acquire interpolated data for different points in time	668
RenderWeavedAttribute	Render Weaved Attribute	669
ResolveNetworkPrefabSourceAttribute	Resolve Network Prefab Source Attribute	669
RpcAttribute	Flags a method as being a networked Remote Procedure Call. Only usable in a NetworkBehaviour . Calls to this method (from the indicated allowed RpcSources) will generate a network message, which will execute the method remotely on the indicated RpcTargets . The RPC method can include an empty RpcInfo argument, that will include meta information about the RPC on the receiving peer	669
RpcHeader	Header for RPC messages	672
RpcInfo	RpcInfo is a struct that contains information about the RPC message	676
RpcInvokeData	Represents the data required to invoke an RPC message	678
RpcInvokeInfo	May be used as an optional RpcAttribute return value. Contains meta data about the RPC send, such as failure to send reasons, culling, message size, etc	680
RpcSendResult	RPC send operation result information	682
RpcTargetAttribute	RPC attribute used to indicate a specific target player for an RPC when sending from one player to another. RPC is sent to the server, and then is forwarded to the specified player. Usage: . . .	683
SceneLoadDoneArgs	Struct that contains information about a scene after it has been loaded	683
SceneRef	Scene reference struct. Can be used to reference a scene by index or by path	685
SerializableDictionary< TKey, TValue >	A serializable dictionary	693
SessionInfo	Holds information about the Game Session	699
Simulation	Main simulation class	702
Simulation.AreaOfInterest	Area of Interest Definition	719
SimulationBehaviour	Base class for a Fusion aware Behaviour (derived from UnityEngine.MonoBehaviour). Objects derived from this object can be associated with a NetworkRunner and Simulation . If a parent NetworkObject is found, this component will also be associated with that network entity	723
SimulationBehaviourAttribute	Attribute for specifying which SimulationStages and SimulationModes this SimulationBehaviour will execute in. Can be used to limit execution to only Host, Server or Client peers, or to only execute on Resimulation or Forward ticks. Usage:	725

SimulationBehaviourListScope	Provides a scope for a SimulationBehaviourUpdater.BehaviourList , incrementing its lock count on creation and decrementing it on disposal. If the lock count reaches zero on disposal, all pending removals in the list are performed	726
SimulationConfig	Project configuration settings specific to how the Simulation class behaves	727
SimulationConnectionStats	Simulation Connection Statistics	730
SimulationInput	Simulation Input	734
SimulationInput.Buffer	Buffer for SimulationInputs	736
SimulationInputHeader	Simulation Input Header	740
SimulationMessage	Simulation Message	742
SimulationMessagePtr	Simulation Message Pointer	753
SimulationRuntimeConfig	Stores the runtime configuration of the simulation	754
SimulationStats	Simulation Stats	756
NetAddress	Represents a Network Address, which includes a IP and Port This can contains either a IPv4 or a IPv6 address	761
NetBitBufferList	Represents a linked list of Fusion.Sockets.NetBitBuffer	765
NetCommandAccepted	Accepted Command, sent by the server when a remote client connection is accepted	768
NetCommandConnect	Connect Command used to signal a remote server that a client is trying to connect to it	768
NetCommandDisconnect	Disconnect Command, it can be used by either side of the connection	769
NetCommandHeader	Network Command Header Describe its type and usual settings for all commands	769
NetCommandRefused	Refuse Command, sent by the server when the connection was refused. This happens when the server has reached its max connection capacity	770
NetConfig	General configuration used to drive the behavior of the Socket library	771
StunClient.TestIPs	List of public DNS Servers	775
StartGameArgs	Fusion Start Arguments, used to configure the simulation mode and other settings	776
StartGameResult	Represents the result of starting the Fusion Simulation	782
StatsMetaAttribute	This stat goes on field elements of classes/structs and is used by FieldsMask	784
Tick	A tick is a 32-bit integer that represents a frame number	785
Tick.EqualityComparer	Provides a mechanism for comparing two Tick objects for equality	792
Tick.RelationalComparer	Provides a mechanism for comparing two Tick objects	793
TickAccumulator	A tick accumulator	794
TickRate	A tick rate is a collection of tick rates	798

TickRate.Resolved	
Represents a resolved tick rate	805
TickRate.Selection	
Represents a selection of tick rates for client and server	808
TickTimer	
A timer that is based on ticks instead of seconds	809
TimeSyncConfiguration	
Time Synchronization Configuration	813
UnitAttribute	
Unit Attribute class. Used to mark a field with the respective Units	814
UnityContextMenuAttribute	
Unity ContextMenuAttribute	815
UnityDelayedAttribute	
Unity DelayedAttribute	816
UnityFormerlySerializedAsAttribute	
Unity FormerlySerializedAsAttribute	816
UnityHeaderAttribute	
Unity HeaderAttribute	817
UnityMinAttribute	
Unity MinAttribute	818
UnityMultilineAttribute	
Unity MultilineAttribute	819
UnityNonReorderableAttribute	
Unity NonReorderableAttribute	819
UnityNonSerializedAttribute	
Unity NonSerializedAttribute	820
UnityRangeAttribute	
Unity RangeAttribute	820
UnitySerializeField	
Unity SerializeField	821
UnitySerializeReference	
Unity SerializeReference	821
UnitySpaceAttribute	
Unity SpaceAttribute	822
UnityTooltipAttribute	
Unity TooltipAttribute	823
Vector2Compressed	
Represents a compressed Vector2 value for network transmission	824
Vector3Compressed	
Represents a compressed Vector3 value for network transmission	828
Vector4Compressed	
Represents a compressed Vector4 value for network transmission	833
WarnIfAttribute	
Editor attribute for adding notices to fields if the condition member evaluates as true. Condition member can be a property, field or method (with a return value)	839
WeaverGeneratedAttribute	
Weaver Generated Attribute	839

Chapter 5

Namespace Documentation

5.1 Fusion Namespace Reference

Classes

- struct [_128](#)
A [FixedStorage](#) that can hold up to 128 words.
- struct [_16](#)
A [FixedStorage](#) that can hold up to 16 words.
- struct [_2](#)
A [FixedStorage](#) that can hold up to 2 words.
- struct [_256](#)
A [FixedStorage](#) that can hold up to 256 words.
- struct [_32](#)
A [FixedStorage](#) that can hold up to 32 words.
- struct [_4](#)
A [FixedStorage](#) that can hold up to 4 words.
- struct [_512](#)
A [FixedStorage](#) that can hold up to 512 words.
- struct [_64](#)
A [FixedStorage](#) that can hold up to 64 words.
- struct [_8](#)
A [FixedStorage](#) that can hold up to 8 words.
- struct [Allocator](#)
Memory [Allocator](#)
- struct [Angle](#)
A [Networked](#) fusion type for degrees. This can be used with the [NetworkedAttribute](#), in [RPCs](#), or in [NetworkInput](#) structs.
- class [AssetObject](#)
Base class for all [Fusion](#) assets.
- class [AuthorityMasks](#)
Provides constants and methods for managing authority masks.
- class [Behaviour](#)
Alternative base class to Unity's [MonoBehaviour](#). This allows for components that work both in Unity, as well as the [Photon](#) relays.
- struct [BehaviourStats](#)

- Represents statistics related to the execution of a [SimulationBehaviour](#).*

 - class [CapacityAttribute](#)

Capacity Attribute
 - class [DefaultForPropertyAttribute](#)

Default For Property Attribute
 - class [DisplayAsEnumAttribute](#)

Casts an enum or int value in the inspector to specific enum type for rendering of its popup list. Supplying a method name rather than a type allows a property with the type `Type` to be used to dynamically get the enum type.
 - class [DolfAttributeBase](#)

Editor attribute for selective editor rendering. Condition member can be a property, field or method (with a return value).
 - class [DrawIfAttribute](#)

Editor attribute for selectively drawing/hiding fields. Condition member can be a property, field or method (with a return value).
 - struct [DynamicHeap](#)

A dynamic heap for allocating and tracking unmanaged objects.
 - class [DynamicHeapInstance](#)

Dynamic heap instance.
 - class [FieldsMask](#)

Base class for [FieldsMask<T>](#).
 - class [FixedArray](#)

A fixed size array that can be used in structs.
 - class [FixedBufferPropertyAttribute](#)

Fixed Buffer Property Attribute
 - class [FixedStorage](#)

Provides utility methods for fixed storage types.
 - struct [FloatCompressed](#)

Represents a compressed float value for network transmission.
 - class [FloatUtils](#)

Provides utility methods for compressing and decompressing float values.
 - class [HeapConfiguration](#)

Memory Heap Settings
 - class [Hitbox](#)

Represents a single lag-compensated collider. Multiple component instances can be added anywhere in the hierarchy of a [NetworkObject](#) which includes a [HitboxRoot](#).
 - class [HitboxManager](#)

Entry point for lag compensated [Hitbox](#) queries, which maintains a history buffer, and provides lag compensated raycast and overlap methods. Singleton instance is accessible through the property `Runner.LagCompensation`.
 - class [HitboxRoot](#)

Root [Hitbox](#) group container. Manages registering/unregistering hitboxes with the group, and defines the broadphase geometry for the group.
 - class [HostMigrationConfig](#)

Project configuration settings specific to how the Host Migration behaves.
 - class [HostMigrationToken](#)

Transitory Holder with all necessary information to restart the [Fusion](#) Runner after the Host Migration has completed
 - interface [IAfterAllTicks](#)

Interface for [AfterAllTicks](#) callback. Called after the re-simulation loop (when applicable), and also after the forward simulation loop. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.
 - interface [IAfterClientPredictionReset](#)

Callback interface for [AfterClientPredictionReset](#). Called at the very start of the resimulation loop (on clients with prediction enabled), immediately after state is set to the latest server snapshot. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.
 - interface [IAfterHostMigration](#)

- Used to mark NetworkBehaviours that need to be react after a Host Migration process*
- interface [IAfterRender](#)
Interface for [AfterRender](#) callback. Called after the render loop.
 - interface [IAfterSpawned](#)
Interface for [AfterSpawned](#) callback. Called after the object is spawned.
 - interface [IAfterTick](#)
Interface for [AfterTick](#) callback. Called after each tick simulation completes. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.
 - interface [IAfterUpdate](#)
Interface for the [AfterUpdate](#) callback, which is called at the end of each [Fusion](#) Update segment. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.
 - interface [IAsyncOperation](#)
Defines an asynchronous operation.
 - interface [IBeforeAllTicks](#)
Interface for [BeforeAllTicks](#) callback. Called before the re-simulation loop (when applicable), and also before the forward simulation loop. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.
 - interface [IBeforeClientPredictionReset](#)
Callback interface for [BeforeClientPredictionReset](#). Called at the very start of the re-simulation loop (on clients with prediction enabled), before state is set to the latest server snapshot. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.
 - interface [IBeforeCopyPreviousState](#)
Interface for [BeforeCopyPreviousState](#) callback. Called before the copy of the previous state.
 - interface [IBeforeHitboxRegistration](#)
Interface for [BeforeHitboxRegistration](#) callback. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.
 - interface [IBeforeTick](#)
Interface for [BeforeTick](#) callback. Called before each tick is simulated. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.
 - interface [IBeforeUpdate](#)
Interface for the [BeforeUpdate](#) callback, which is called at the beginning of each [Fusion](#) Update segment. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.
 - interface [ICoroutine](#)
Defines a coroutine.
 - interface [IDespawned](#)
Interface for [Despawned](#) callback. Called when a [NetworkBehaviour](#) is despawned.
 - interface [IElementReaderWriter](#)
Defines the interface for reading and writing elements in a byte array.
 - interface [IFixedStorage](#)
Interface for fixed storage types.
 - interface [IInputAuthorityGained](#)
Interface for handling the event when the input authority is gained.
 - interface [IInputAuthorityLost](#)
Interface for handling the event when the input authority is lost.
 - interface [IInterestEnter](#)
Interface for handling the event when a player enters the area of interest.
 - interface [IInterestExit](#)
Interface for handling the event when a player exits the area of interest.
 - interface [ILocalPrefabCreated](#)
Interface for handling the event when a local prefab is created.
 - interface [INetworkArray](#)
Defines the interface for a networked array.
 - interface [INetworkAssetSource](#)

- Interface for a network asset source.*

 - interface [INetworkDictionary](#)

Defines the interface for a networked dictionary.
 - interface [INetworkInput](#)

Flag interface for custom [NetworkInput](#) structs.
 - interface [INetworkLinkedList](#)

Defines the interface for a networked linked list.
 - interface [INetworkObjectInitializer](#)

Interface for initializing network objects.
 - interface [INetworkObjectProvider](#)

Interface which defines the handlers for [NetworkRunner](#) [Spawn\(\)](#) and [Despawn\(\)](#) actions. Passing an instance of this interface to [NetworkRunner.StartGame\(StartGameArgs\)](#) as the [StartGameArgs.ObjectProvider](#) argument value will assign that instance as the handler for runner [Spawn\(\)](#) and [Despawn\(\)](#) actions. By default (if [StartGameArgs.ObjectProvider](#) == null) actions will use [Instantiate\(\)](#), and [Despawn\(\)](#) actions will use [Destroy\(\)](#).
 - interface [INetworkPrefabSource](#)

Interface for a network prefab source.
 - interface [INetworkRunnerCallbacks](#)

Interface for [NetworkRunner](#) callbacks. Register a class/struct instance which implements this interface with [NetworkRunner.AddCallbacks\(INetworkRunnerCallbacks\[\]\)](#).
 - interface [INetworkRunnerUpdater](#)

Interface which defines the handlers for [NetworkRunner](#) Updates. An implementation is responsible for calling [NetworkRunner.UpdateInternal\(double\)](#) and [NetworkRunner.RenderInternal](#) periodically.
 - interface [INetworkSceneManager](#)

Interface for a [NetworkRunner](#) scene manager. A scene manager is responsible for loading and unloading scenes
 - interface [INetworkStruct](#)

Base interface for all [Fusion](#) Network Structs
 - interface [INetworkTRSPTeleport](#)

Implement this interface on a [NetworkTRSP](#) implementation to indicate it can be teleported.
 - class [InterpolatedErrorCorrectionSettings](#)

A set of parameters that tune the interpolated correction of prediction error on transform data.
 - interface [IPlayerJoined](#)

Interface for handling the event when a player joins the game.
 - interface [IPlayerLeft](#)

Interface for handling the event when a player leaves the game.
 - interface [IRemotePrefabCreated](#)

Interface for handling the event when a remote prefab is created.
 - interface [ISceneLoadDone](#)

Interface for handling the event when a scene load operation is completed.
 - interface [ISceneLoadStart](#)

Interface for handling the event when a scene load operation is started.
 - interface [ISimulationEnter](#)

Interface for [SimulationEnter](#) callback. Called when the [NetworkObject](#) joins AreaOfInterest. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.
 - interface [ISimulationExit](#)

Interface for the [SimulationExit](#) callback. Called when the [NetworkObject](#) leaves AreaOfInterest. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.
 - interface [ISpawned](#)

Interface for handling the event when an object is spawned.
 - interface [IStateAuthorityChanged](#)

Interface for handling the event when the state authority changes.
 - struct [LagCompensatedHit](#)

Defines a lag compensated query hit result.

- class [LagCompensationSettings](#)
Settings for lag compensation history.
- class [LobbyInfo](#)
Holds information about a Lobby
- class [LogSimpleUnity](#)
Log Simple Unity
- class [NestedComponentUtilities](#)
Tools to replace GetComponent variants that respects nested objects. These are used to find components of a NetworkedObjects without also finding components that belong to parent or child NetworkedObjects.
- struct [NetworkArray](#)
Fusion type for networking arrays. Maximum capacity is fixed, and is set with the [CapacityAttribute](#).

- class [NetworkArrayExtensions](#)
Provides extension methods for the [NetworkArray](#) class.
- struct [NetworkArrayReadOnly](#)
Provides a read-only view of a network array.
- class [NetworkAssemblyIgnoreAttribute](#)
Network Assembly Ignore Attribute
- class [NetworkAssemblyWeavedAttribute](#)
Network Assembly Weaved Attribute
- class [NetworkBehaviour](#)
Base class for [Fusion](#) network components, which are associated with a [NetworkObject](#).
- struct [NetworkBehaviourBuffer](#)
Provides low level accesss to data buffers that can be read using a [NetworkBehaviourReader](#).
- struct [NetworkBehaviourBufferInterpolator](#)
The [NetworkBehaviourBufferInterpolator](#) struct is used to interpolate between two [NetworkBehaviourBuffer](#) instances. This is a read-only, ref struct, meaning it cannot be boxed and it can only be used on the stack.
- struct [NetworkBehaviourId](#)
Represents the unique identifier for a [NetworkBehaviour](#) instance.
- class [NetworkBehaviourUtils](#)
This static class provides utility methods for working with [NetworkBehaviour](#) objects.
- class [NetworkBehaviourWeavedAttribute](#)
Network [Behaviour](#) Weaved Attribute
- struct [NetworkBool](#)
Represents a boolean value that can be networked.
- struct [NetworkButtons](#)
Represents a set of buttons that can be networked.
- class [NetworkConfiguration](#)
Main network configuration class.
- class [NetworkDelegates](#)
Network Runner Callbacks Delegates
- class [NetworkDeserializeMethodAttribute](#)
Network Deserialize Method Attribute
- struct [NetworkDictionary](#)
Fusion type for networking Dictionaries. Maximum capacity is fixed, and is set with the [CapacityAttribute](#).

- struct [NetworkDictionaryReadOnly](#)
A read-only version of [NetworkDictionary](#)<TKey,TValue>.
- class [NetworkedAttribute](#)
- class [NetworkedWeavedAttribute](#)

Networked Weaved Attribute

- class [NetworkEvents](#)

Companion component for [NetworkRunner](#). Exposes [INetworkRunnerCallbacks](#) as UnityEvents, which can be wired up to other components in the inspector.

- struct [NetworkId](#)

The unique identifier for a network entity.

- struct [NetworkInput](#)

[NetworkInput](#) Struct

- class [NetworkInputUtils](#)

Utility methods for [NetworkInput](#)

- class [NetworkInputWeavedAttribute](#)

Network Input Weaved Attribute

- struct [NetworkLinkedList](#)

[Fusion](#) type for networking [LinkedLists](#). Maximum capacity is fixed, and is set with the [CapacityAttribute](#).

Typical Usage:

- struct [NetworkLinkedListReadOnly](#)

Read-only version of [NetworkLinkedList](#)<T>.

- struct [NetworkLoadSceneParameters](#)

Parameters for loading a scene

- class [NetworkMecanimAnimator](#)

A component for synchronizing the Animator controller state from the State Authority to network proxies. Requires a Unity Animator component, and a [NetworkObject](#) component. NOTE: Animator Root Motion is not compatible with re-simulation and prediction.

- class [NetworkObject](#)

The primary [Fusion](#) component for networked GameObject entities. This stores the object's network identity and manages the object's state and input authority.

- class [NetworkObjectFlagsExtensions](#)

Extension methods for the [NetworkObjectFlags](#) enum.

- struct [NetworkObjectGuid](#)

[NetworkObjectGuid](#)

- struct [NetworkObjectHeader](#)

Network object header information for a [NetworkObject](#).

- struct [NetworkObjectHeaderPtr](#)

Represents a pointer to a [NetworkObjectHeader](#). This struct is unsafe because it uses pointers.

- class [NetworkObjectInitializerUnity](#)

Initializes network objects for Unity.

- class [NetworkObjectMeta](#)

Meta information about a network object.

- struct [NetworkObjectNestingKey](#)

A key used to identify a network object nesting.

- class [NetworkObjectPrefabData](#)

This class represents the data for a network object prefab.

- class [NetworkObjectProviderDummy](#)

A dummy implementation of the [INetworkObjectProvider](#) interface. This class is used for testing purposes and throws a [NotImplementedException](#) for all its methods.

- struct [NetworkObjectReleaseContext](#)

Represents the context for releasing a network object. This struct is unsafe because it uses pointers.

- class [NetworkObjectSortKeyComparer](#)

This class is used to compare two [NetworkObject](#) instances based on their SortKey. It implements the [IComparer](#) interface.

- class [NetworkObjectSpawnException](#)

- Network Object Spawn Exception*
- class [NetworkObjectStats](#)
 - The [NetworkObjectStats](#) class provides statistics related to a network object. It includes bandwidth, updates, and player count within the area of interest.*
- struct [NetworkObjectTypeId](#)
 - ID for a [NetworkObject](#) Prefab which has been cataloged in a [NetworkProjectConfig.PrefabTable](#).*
- struct [NetworkPhysicsInfo](#)
 - Network Physics [INetworkStruct](#)*
- struct [NetworkPrefabAcquireContext](#)
 - Represents the context for acquiring a prefab instance for a network object. This struct is unsafe because it uses pointers.*
- class [NetworkPrefabAttribute](#)
 - Network Prefab Attribute*
- struct [NetworkPrefabId](#)
 - ID for a [NetworkObject](#) Prefab which has been cataloged in a [NetworkProjectConfig.PrefabTable](#).*
- struct [NetworkPrefabInfo](#)
 - Meta data for a [NetworkObject](#) prefab which has been cataloged in a [NetworkProjectConfig.PrefabTable](#).*
- struct [NetworkPrefabRef](#)
 - [NetworkPrefabRef](#)*
- class [NetworkPrefabTable](#)
 - Class representing a table of network prefabs.*
- struct [NetworkPrefabTableOptions](#)
 - Options for the [NetworkPrefabTable](#).*
- class [NetworkProjectConfig](#)
 - The core [Fusion](#) config file that is shared with all peers at startup.*
- class [NetworkProjectConfigAsset](#)
 - Manages and references the current instance of [NetworkProjectConfig](#)*
- struct [NetworkRNG](#)
 - PCG32 random generator, 16 bytes in size. <http://www.pcg-random.org>*
- class [NetworkRpcStaticWeavedInvokerAttribute](#)
 - Network Rpc Static Weaved Invoker Attribute Contains info about a static weaved RPC Method*
- class [NetworkRpcWeavedInvokerAttribute](#)
 - Network Rpc Weaved Invoker Attribute Contains info about a weaved RPC Method*
- class [NetworkRunner](#)
 - Host Migration related code in order to get a copy of the [Simulation](#) State*
- class [NetworkRunnerCallbackArgs](#)
 - Stores data types used on the [INetworkRunnerCallbacks](#) interface*
- class [NetworkRunnerUpdaterDefault](#)
 - Default implementation of [INetworkRunnerUpdater](#) that uses the Unity PlayerLoop.*
- struct [NetworkRunnerUpdaterDefaultInvokeSettings](#)
 - Settings for the [NetworkRunnerUpdaterDefault](#).*
- struct [NetworkSceneAsyncOp](#)
 - A wrapper for async scene operations.*
- struct [NetworkSceneInfo](#)
 - Can store up to 8 active scenes and allows for duplicates. Each write increases [Version](#) which can be used to generate unique scene objects ids for when a scene is supposed to be reloaded.*
- struct [NetworkSceneLoadId](#)
 - A unique identifier for a scene load operation.*
- struct [NetworkSceneObjectId](#)
 - A unique identifier for a scene object.*
- class [NetworkSerializeMethodAttribute](#)

- Network Serialize Method Attribute*
- class [NetworkSimulationConfiguration](#)
 - Configuration for network conditions simulation (induced latency and loss).*
- struct [NetworkSpawnOp](#)
 - Spawn Operation*
- class [NetworkString](#)
 - Fixed-size UTF32 string. All operations are alloc-free, except for converting to System.String.*
- class [NetworkStructUtils](#)
 - Utility methods for [INetworkStruct](#)*
- class [NetworkStructWeavedAttribute](#)
 - Describes the total number of WORDs a [INetworkStruct](#) uses.*
- class [NetworkTransform](#)
 - Add to any [NetworkObject](#) Transform, or its associated child Transforms to automatically synchronize TRSP (Position/Rotation/Scale/Parent).*
- class [NetworkTRSP](#)
 - Base class for spatial (Position/Rotation/Scale/Parent) synchronization component, such as [NetworkTransform](#). Provides the base logic for render interpolation, parenting synchronization, and teleport, that can be used in components derived from this class.*
- struct [NetworkTRSPData](#)
 - Data structure storing spatial (Position/Rotation/Scale/Parent) synchronization data for spatial synchronization components, [NetworkTRSP](#) and its subclass [NetworkTransform](#).*
- class [NormalizedRectAttribute](#)
 - Enables a special inspector drawer for Unity Rect type, specially designed for editing RectTransforms using normalized values.*
- struct [PlayerRef](#)
 - Represents a [Fusion](#) player.*
- class [PreserveInPluginAttribute](#)
 - Preserve In Plugin Attribute*
- struct [Ptr](#)
 - [Ptr](#)*
- struct [QuaternionCompressed](#)
 - Represents a compressed Quaternion value for network transmission.*
- class [ReadWriteUtils](#)
 - Provides utility methods for reading and writing data.*
- class [ReadWriteUtilsForWeaver](#)
 - Provides utility methods for reading and writing data.*
- class [ReflectionUtils](#)
 - Provides utility methods for reflection.*
- class [RenderAttribute](#)
 - Override default render settings for [\[Networked\]](#) properties.*
- struct [RenderTimeline](#)
 - Can be used to acquire interpolated data for different points in time.*
- class [RenderWeavedAttribute](#)
 - Render Weaved Attribute*
- class [ResolveNetworkPrefabSourceAttribute](#)
 - Resolve Network Prefab Source Attribute*
- class [RpcAttribute](#)
 - Flags a method as being a networked Remote Procedure Call. Only usable in a [NetworkBehaviour](#). Calls to this method (from the indicated allowed [RpcSources](#)) will generate a network message, which will execute the method remotely on the indicated [RpcTargets](#). The RPC method can include an empty [RpcInfo](#) argument, that will include meta information about the RPC on the receiving peer.*
- struct [RpcHeader](#)

- Header for RPC messages.*

 - struct [RpcInfo](#)

[RpcInfo](#) is a struct that contains information about the RPC message.
 - struct [RpcInvokeData](#)

Represents the data required to invoke an RPC message.
 - struct [RpcInvokeInfo](#)

May be used as an optional [RpcAttribute](#) return value. Contains meta data about the RPC send, such as failure to send reasons, culling, message size, etc.
 - struct [RpcSendResult](#)

RPC send operation result information.
 - class [RpcTargetAttribute](#)

RPC attribute used to indicate a specific target player for an RPC when sending from one player to another. RPC is sent to the server, and then is forwarded to the specified player. Usage:
 - struct [SceneLoadDoneArgs](#)

Struct that contains information about a scene after it has been loaded.
 - struct [SceneRef](#)

Scene reference struct. Can be used to reference a scene by index or by path.
 - class [SerializableDictionary](#)

A serializable dictionary.
 - class [SessionInfo](#)

Holds information about the Game Session
 - class [Simulation](#)

Main simulation class
 - class [SimulationBehaviour](#)

Base class for a [Fusion](#) aware [Behaviour](#) (derived from `UnityEngine.MonoBehaviour`). Objects derived from this object can be associated with a [NetworkRunner](#) and [Simulation](#). If a parent [NetworkObject](#) is found, this component will also be associated with that network entity.
 - class [SimulationBehaviourAttribute](#)

Attribute for specifying which [SimulationStages](#) and [SimulationModes](#) this [SimulationBehaviour](#) will execute in. Can be used to limit execution to only Host, Server or Client peers, or to only execute on Resimulation or Forward ticks. Usage:
 - struct [SimulationBehaviourListScope](#)

Provides a scope for a `SimulationBehaviourUpdater.BehaviourList`, incrementing its lock count on creation and decrementing it on disposal. If the lock count reaches zero on disposal, all pending removals in the list are performed.
 - class [SimulationConfig](#)

Project configuration settings specific to how the [Simulation](#) class behaves.
 - class [SimulationConnectionStats](#)

[Simulation](#) Connection Statistics
 - class [SimulationInput](#)

[Simulation](#) Input
 - struct [SimulationInputHeader](#)

[Simulation](#) Input Header
 - struct [SimulationMessage](#)

[Simulation](#) Message
 - struct [SimulationMessagePtr](#)

[Simulation](#) Message Pointer
 - struct [SimulationRuntimeConfig](#)

Stores the runtime configuration of the simulation
 - class [SimulationStats](#)

[Simulation](#) Stats
 - struct [StartGameArgs](#)

[Fusion](#) Start Arguments, used to configure the simulation mode and other settings

- class [StartGameResult](#)
Represents the result of starting the [Fusion Simulation](#)
- class [StatsMetaAttribute](#)
This stat goes on field elements of classes/structs and is used by [FieldsMask](#).
- struct [Tick](#)
A tick is a 32-bit integer that represents a frame number.
- struct [TickAccumulator](#)
A tick accumulator.
- struct [TickRate](#)
A tick rate is a collection of tick rates.
- struct [TickTimer](#)
A timer that is based on ticks instead of seconds.
- class [TimeSyncConfiguration](#)
Time Synchronization Configuration
- class [UnitAttribute](#)
Unit Attribute class. Used to mark a field with the respective [Units](#)
- class [UnityContextMenuMenuItemAttribute](#)
Unity ContextMenuItemAttribute
- class [UnityDelayedAttribute](#)
Unity DelayedAttribute
- class [UnityFormerlySerializedAsAttribute](#)
Unity FormerlySerializedAsAttribute
- class [UnityHeaderAttribute](#)
Unity HeaderAttribute
- class [UnityMinAttribute](#)
Unity MinAttribute
- class [UnityMultilineAttribute](#)
Unity MultilineAttribute
- class [UnityNonReorderableAttribute](#)
Unity NonReorderableAttribute
- class [UnityNonSerializedAttribute](#)
Unity NonSerializedAttribute
- class [UnityRangeAttribute](#)
Unity RangeAttribute
- class [UnitySerializeField](#)
Unity SerializeField
- class [UnitySerializeReference](#)
Unity SerializeReference
- class [UnitySpaceAttribute](#)
Unity SpaceAttribute
- class [UnityTooltipAttribute](#)
Unity TooltipAttribute
- struct [Vector2Compressed](#)
Represents a compressed Vector2 value for network transmission.
- struct [Vector3Compressed](#)
Represents a compressed Vector3 value for network transmission.
- struct [Vector4Compressed](#)
Represents a compressed Vector4 value for network transmission.
- class [WarnIfAttribute](#)
Editor attribute for adding notices to fields if the condition member evaluates as true. Condition member can be a property, field or method (with a return value).
- class [WeaverGeneratedAttribute](#)
Weaver Generated Attribute

Enumerations

- enum class **AnimatorSyncSettings**
- enum class [CompareOperator](#)
Comparison method for evaluating condition member value against compareToValues.
- enum class [ConnectionType](#)
Defines the type of the current connection with the Remote Peer, either the Server or a Client
- enum class **DrawIfMode**
- enum class **EditorButtonVisibility**
- enum class [GameMode](#)
Fusion Game Mode.
- enum class [HitboxTypes](#)
Defines the collision geometry type of a Hitbox.
- enum class [HitOptions](#)
- enum class [NetworkObjectAcquireResult](#)
Enum representing the possible results of acquiring a prefab instance for a network object.
- enum class **NetworkObjectConnectionDataStatus**
- enum class **NetworkObjectDestroyFlags**
- enum class [NetworkObjectFlags](#) : int
Enum representing the flags for network objects in the Fusion system. This enum is marked with the Flags attribute, allowing it to be treated as a bit field.
- enum class [NetworkObjectHeaderFlags](#) : int
Enum representing various flags for a network object header. Each flag represents a different state or property of a network object.
- enum class **NetworkObjectHeaderPlayerDataFlags** : int
- enum class **NetworkObjectPacketFlags**
- enum class **NetworkObjectRuntimeFlags** : int
- enum class [NetworkPrefabTableGetPrefabResult](#)
Enum representing the possible results of attempting to get a prefab from the NetworkPrefabTable.
- enum class [NetworkSceneInfoChangeSource](#)
What has contributed to the observed change in the scene info.
- enum class [NetworkSceneInfoDefaultFlags](#) : uint
Network Scene Info Default Flags
- enum class [NetworkSpawnFlags](#) : short
Network Spawn Flags
- enum class [NetworkSpawnStatus](#) : int
Network Spawn Status
- enum class [NetworkTypeldKind](#)
Enum representing the type of a NetworkObject.
- enum class [PageSizes](#)
Page Bit Shift Lookup Table
- enum class [PriorityLevel](#)
Enum representing the priority levels for network objects
- enum class [RenderSource](#)
Indicates how available snapshot data should be used to render networked properties (in the chosen RenderTimeframe).
- enum class [RenderTimeframe](#)
Indicates which point in time (or "timeframe") networked properties should be rendered in.
- enum class [RpcChannel](#)
Flags for the RPC channel.
- enum class [RpcHostMode](#)
Options for when the game is run in SimulationModes.Host mode and RPC is invoked by the host.

- enum class [RpcLocalInvokeResult](#)
Results for the local RPC Invocation of the RPC method.
- enum class [RpcSendCullResult](#)
Results for the RPC message send operation. Note: Some individual targets may be culled even if the send operation succeeds. Information about culled targets can be found in [RpcInvokeInfo.SendResult](#).
- enum class [RpcSendMessageResult](#)
Result flags for the RPC message send operation.
- enum class [RpcSources](#)
Enum representing the sources of an RPC message.
- enum class [RpcTargets](#)
Enum representing the targets of an RPC message.
- enum class [RpcTargetStatus](#)
Enum representing the status of an RPC target.
- enum class [ScriptHeaderBackColor](#)
Color of the component graphic header in the Unity inspector. None indicates no header graphic should be used.
- enum class [ScriptHeaderIcon](#)
Icon to be rendered on the component graphic header in the Unity inspector.
- enum class **ScriptHeaderStyle**
- enum class [SessionLobby](#)
Session Lobby Type
- enum class [ShutdownReason](#)
Describes a list of Reason why the [Fusion](#) Runner was Shutdown
- enum class **SimulationBehaviourRuntimeFlags**
- enum class **SimulationMessageInternalTypes**
- enum class [SimulationModes](#)
Flags for The type of network peer a simulation represents.
- enum class [SimulationStages](#)
Flags for which stage the simulation currently running. Forward is when a tick is being simulated for the first time. Resimulate is when a tick is being simulated again with corrections.
- enum class **StatAveraging**
- enum class [Topologies](#)
- enum class [Units](#)
Unit Type for a certain field. This helps to identify the unit that a certain value represents, like Seconds or Percentage
- enum class [UnityPlayerLoopSystemAddMode](#)
Enum representing the possible modes for adding a system to the Unity player loop.

Functions

- delegate FusionGlobalScriptableObjectLoadResult **FusionGlobalScriptableObjectLoadDelegate** (Type type)
- delegate void **FusionGlobalScriptableObjectUnloadDelegate** (FusionGlobalScriptableObject instance)
- delegate void [NetworkObjectSpawnDelegate](#) ([NetworkSpawnOp](#) result)
Network Object Spawn Delegate
- unsafe delegate void [RpcInvokeDelegate](#) ([NetworkBehaviour](#) behaviour, [SimulationMessage](#) *message)
Represents a delegate that can be invoked by an RPC message.
- unsafe delegate void [RpcStaticInvokeDelegate](#) ([NetworkRunner](#) runner, [SimulationMessage](#) *message)
Represents a delegate that can be invoked by an RPC message.

5.1.1 Enumeration Type Documentation

5.1.1.1 CompareOperator

```
enum CompareOperator [strong]
```

Comparison method for evaluating condition member value against compareToValues.

Enumerator

Equal	True if condition member value equals compareToValue.
NotEqual	True if condition member value is not equal to compareToValue.
Less	True if condition member value is less than compareToValue.
LessOrEqual	True if condition member value is less than or equal to compareToValue.
GreaterOrEqual	True if condition member value is greater than or equal to compareToValue.
Greater	True if condition member value is greater than compareToValue.
NotZero	Returns true if the condition member evaluates to anything other than zero. In the case of object references, this means true for any non-null value.
IsZero	Returns true if the condition member evaluates to zero. In the case of object references, this means true for any null value.

5.1.1.2 ConnectionType

```
enum ConnectionType [strong]
```

Defines the type of the current connection with the Remote Peer, either the Server or a Client

Enumerator

None	No connection is currently active
Relayed	Connection was accomplished using the Photon Relay Services
Direct	Connection was accomplished directly with the remote peer

5.1.1.3 GameMode

```
enum GameMode [strong]
```

[Fusion](#) Game Mode.

Used to select how the local simulation will act.

Enumerator

Single	Single Player Mode: it works very similar to Host Mode, but don't accept any connections.
Shared	Shared Mode: starts a Game Client, which will connect to a Game Server running in the Photon Cloud using the Fusion Plugin.
Server	Server Mode: starts a Dedicated Game Server with no local player.

Enumerator

Host	Host Mode: starts a Game Server and allows a local player.
Client	Client Mode: starts a Game Client, which will connect to a peer in either Server or Host Modes.
AutoHostOrClient	Automatically start as Host or Client. The first peer to connect to a room will be started as a Host, all others will connect as clients.

5.1.1.4 HitboxTypes

```
enum HitboxTypes [strong]
```

Defines the collision geometry type of a [Hitbox](#).

Enumerator

None	[Future Use] to represent a disabled Hitbox .
Box	Geometry is a box, fill in Extents and (optional) Offset.
Sphere	Geometry is a sphere, fill in Radius and (optional) Offset.
Capsule	Geometry is a capsule, fill in capsule Radius, capsule Height and (optional) Offset.

5.1.1.5 HitOptions

```
enum HitOptions [strong]
```

Per-query options for lag compensation (both raycast and overlap).

Enumerator

None	Default, no extra options.
IncludePhysX	Add this to include checks against PhysX colliders.
IncludeBox2D	Add this to include checks against Box2D colliders. If PhysX flag is set, it will be used instead.
SubtickAccuracy	Subtick accuracy query (exactly like seen by player).
IgnoreInputAuthority	If the HitboxRoot objects which the player performing the query (if specified) has input authority over should be ignored by the query.

5.1.1.6 NetworkObjectAcquireResult

```
enum NetworkObjectAcquireResult [strong]
```

Enum representing the possible results of acquiring a prefab instance for a network object.

Enumerator

Success	Indicates that the prefab instance was successfully acquired.
Failed	Indicates that the acquisition of the prefab instance failed.
Retry	Indicates that the acquisition of the prefab instance should be retried.
Ignore	Indicates that the acquisition of the prefab instance should be ignored.

5.1.1.7 NetworkObjectFlags

```
enum NetworkObjectFlags : int [strong]
```

Enum representing the flags for network objects in the [Fusion](#) system. This enum is marked with the `Flags` attribute, allowing it to be treated as a bit field.

Enumerator

None	Represents a state where no flags are set.
MaskVersion	Mask for isolating the version part of the flags.
V1	Represents the first version of the network object flags.
Ignore	Flag indicating that the network object should be ignored.
MasterClientObject	Flag indicating that the network object is a master client object.
DestroyWhenStateAuthorityLeaves	Flag indicating that the network object should be destroyed when the state authority leaves.
AllowStateAuthorityOverride	Flag indicating that the network object allows state authority override.

5.1.1.8 NetworkObjectHeaderFlags

```
enum NetworkObjectHeaderFlags : int [strong]
```

Enum representing various flags for a network object header. Each flag represents a different state or property of a network object.

Enumerator

GlobalObjectInterest	Flag indicating that the object is of global interest.
DestroyWhenStateAuthorityLeaves	Flag indicating that the object should be destroyed when the state authority leaves.
SpawnedByClient	Flag indicating that the object was spawned by a client.
AllowStateAuthorityOverride	Flag indicating that the state authority override is allowed.
Struct	Flag indicating that the object is a struct.
StructArray	Flag indicating that the object is an array of structs.
DontDestroyOnLoad	Flag indicating that the object should not be destroyed on load.
HasMainNetworkTRSP	Flag indicating that the object has a main network TRSP.
AreaOfInterest	Flag indicating that the object is in an area of interest.

5.1.1.9 NetworkPrefabTableGetPrefabResult

```
enum NetworkPrefabTableGetPrefabResult [strong]
```

Enum representing the possible results of attempting to get a prefab from the [NetworkPrefabTable](#).

Enumerator

Success	The prefab was successfully retrieved.
InProgress	The retrieval of the prefab is in progress.
NotFound	The prefab was not found in the NetworkPrefabTable .
LoadError	There was an error in loading the prefab.

5.1.1.10 NetworkSceneInfoChangeSource

```
enum NetworkSceneInfoChangeSource [strong]
```

What has contributed to the observed change in the scene info.

Enumerator

None	No change.
Initial	The initial local scene has changed.
Remote	The remove scene has changed.

5.1.1.11 NetworkSceneInfoDefaultFlags

```
enum NetworkSceneInfoDefaultFlags : uint [strong]
```

Network Scene Info Default Flags

Enumerator

SceneCountMask	The scene count mask
ConterMask	The counter mask

5.1.1.12 NetworkSpawnFlags

```
enum NetworkSpawnFlags : short [strong]
```


Network Spawn Flags

Enumerator

DontDestroyOnLoad	Object get spawned as DontDestroyOnLoad on all clients.
SharedModeStateAuthMasterClient	In shared mode, override the state authority to PlayerRef.MasterClient .
SharedModeStateAuthLocalPlayer	In shared mode, override the state authority to local player.

5.1.1.13 NetworkSpawnStatus

```
enum NetworkSpawnStatus : int [strong]
```

Network Spawn Status

Enumerator

Queued	Spawn is queued and will be spawned when the prefab is loaded.
Spawned	Spawned successfully.
FailedToLoadPrefabSynchronously	Failed to Load Prefab Synchronously.
FailedToCreateInstance	Failed to create instance.
FailedClientCantSpawn	Failed to spawn because the client can't spawn.
FailedLocalPlayerNotYetSet	Failed to spawn because the local player is not yet set.

5.1.1.14 NetworkTypeIdKind

```
enum NetworkTypeIdKind [strong]
```

Enum representing the type of a [NetworkObject](#).

Enumerator

Prefab	Represents a NetworkObject that is a Prefab.
Custom	Represents a NetworkObject that is a Custom type.
InternalStruct	Represents a NetworkObject that is an InternalStruct.
SceneObject	Represents a NetworkObject that is a SceneObject.
Invalid	Represents an Invalid NetworkObject type.

5.1.1.15 PageSizes

```
enum PageSizes [strong]
```

Page Bit Shift Lookup Table

5.1.1.16 PriorityLevel

```
enum PriorityLevel [strong]
```

Enum representing the priority levels for network objects

Enumerator

Player	Priority level assigned to player-related network objects.
High	High priority level, typically assigned to network objects that require frequent updates.
Medium	Medium priority level, typically assigned to network objects that require regular updates.
Low	Low priority level, typically assigned to network objects that require less frequent updates.
Lowest	Lowest priority level, typically assigned to network objects that require minimal updates.

5.1.1.17 RenderSource

```
enum RenderSource [strong]
```

Indicates how available snapshot data should be used to render networked properties (in the chosen [RenderTimeframe](#)).

Enumerator

Interpolated	The rendered value will come from interpolating the values at From and To to the desired point in time.
From	The rendered value will come from the nearest available snapshot at or before the point in time being rendered.
To	The rendered value will come from the nearest available snapshot ahead of the point in time being rendered.
Latest	The rendered value will come from the latest snapshot.

5.1.1.18 RenderTimeframe

```
enum RenderTimeframe [strong]
```

Indicates which point in time (or "timeframe") networked properties should be rendered in.

Enumerator

Auto	The timeframe will be chosen automatically.
Local	The default timeframe for owned and predicted objects.
Remote	The default timeframe for proxied objects.

5.1.1.19 RpcChannel

enum [RpcChannel](#) [strong]

Flags for the RPC channel.

Enumerator

Reliable	Rpc order preserved, delivery verified, resend in case of a failed delivery.
Unreliable	Rpc order preserved, delivery not verified, no resend attempts.

5.1.1.20 RpcHostMode

enum [RpcHostMode](#) [strong]

Options for when the game is run in [SimulationModes.Host](#) mode and RPC is invoked by the host.

Enumerator

SourcesServer	If host invokes RPC RpcInfo.Source will be set to PlayerRef.None (default).
SourcesHostPlayer	If host invokes RPC RpcInfo.Source will be set to the host's local player.

5.1.1.21 RpcLocalInvokeResult

enum [RpcLocalInvokeResult](#) [strong]

Results for the local RPC Invocation of the RPC method.

Enumerator

Invoked	RPC has been invoked locally.
NotInvokableLocally	Not invoked locally because RpcAttribute.InvokeLocal is false.
NotInvokableDuringResim	Not invoked locally because InvokeResim is false and simulation stage is SimulationStages.Resimulate
InsufficientSourceAuthority	Not invoked because source NetworkObject current authority does not match flags set in RpcAttribute.Sources
InsufficientTargetAuthority	Not invoked because target player is local and this NetworkObject current authority does not match flags set in RpcAttribute.Targets
TargetPlayerIsNotLocal	Not invoked because target player is not local.

5.1.1.22 RpcSendCullResult

```
enum RpcSendCullResult [strong]
```

Results for the RPC message send operation. Note: Some individual targets may be culled even if the send operation succeeds. Information about culled targets can be found in [RpcInvokeInfo.SendResult](#).

Enumerator

NotCulled	RPC has been sent. Check RpcInvokeInfo.SendResult for details.
NotInvokableDuringResim	Send culled because RpcAttribute.InvokeLocal is false.
InsufficientSourceAuthority	Send culled because source NetworkObject current authority does not match flags set in RpcAttribute.Sources
NoActiveConnections	Send culled because there are no active connections.
TargetPlayerUnreachable	Send culled because target player does not exist.
TargetPlayerIsLocalButRpcsNotInvokableLocally	Send culled because target player is local and RpcAttribute.InvokeLocal is false.

5.1.1.23 RpcSendMessageResult

```
enum RpcSendMessageResult [strong]
```

Result flags for the RPC message send operation.

Enumerator

None	Invalid result.
SentToServerForForwarding	Client sent to the server, server will send to the target client.
SentToTargetClient	Server sent to a specific client (a targeted message).
SentBroadcast	Server attempted to send to all the clients and at least one succeeded.
NotSentTargetObjectNotConfirmed	Target object not confirmed on the client.
NotSentTargetObjectNotInPlayerInterest	Target object not in client's interest. Likely due to being outside of player's AOI region, or needs to be explicitly set as always interested.
NotSentTargetClientNotAvailable	Target client not connected (a targeted message).
NotSentBroadcastNoActiveConnections	Server attempted to send to all the clients, but none was connected.
NotSentBroadcastNoConfirmedNorInterestedClients	Server attempted to send to all the clients, but the target object is not confirmed/not in Object Interest for all target clients.
MaskSent	Mask for sent messages.
MaskNotSent	Mask for not sent messages.
MaskBroadcast	Mask for broadcast messages.
MaskCulled	Mask for culled messages.

5.1.1.24 RpcSources

```
enum RpcSources [strong]
```

Enum representing the sources of an RPC message.

Enumerator

StateAuthority	Represents the state authority source of an RPC message.
InputAuthority	Represents the input authority source of an RPC message.
Proxies	Represents the proxy source of an RPC message.
All	Represents all possible sources of an RPC message.

5.1.1.25 RpcTargets

```
enum RpcTargets [strong]
```

Enum representing the targets of an RPC message.

Enumerator

StateAuthority	Represents the state authority target of an RPC message.
InputAuthority	Represents the input authority target of an RPC message.
Proxies	Represents the proxy target of an RPC message.
All	Represents all possible targets of an RPC message.

5.1.1.26 RpcTargetStatus

```
enum RpcTargetStatus [strong]
```

Enum representing the status of an RPC target.

Enumerator

Unreachable	Represents an unreachable RPC target.
Self	Represents the RPC target as self.
Remote	Represents a remote RPC target.

5.1.1.27 ScriptHeaderBackColor

```
enum ScriptHeaderBackColor [strong]
```

Color of the component graphic header in the Unity inspector. None indicates no header graphic should be used.

5.1.1.28 ScriptHeaderIcon

```
enum ScriptHeaderIcon [strong]
```

Icon to be rendered on the component graphic header in the Unity inspector.

5.1.1.29 SessionLobby

```
enum SessionLobby [strong]
```

Session Lobby Type

Enumerator

Invalid	Invalid Session Lobby Type
ClientServer	ClientServer Lobby
Shared	Shared Lobby
Custom	Custom Lobby - works in conjunction with a Lobby Name/ID

5.1.1.30 ShutdownReason

```
enum ShutdownReason [strong]
```

Describes a list of Reason why the [Fusion](#) Runner was Shutdown

Enumerator

Ok	OK Reason means Fusion was Shutdown by request
Error	Shutdown was caused by some internal error
IncompatibleConfiguration	Raised when the peer tries to Join a Room with a mismatching type between ClientServer Mode and Shared Mode.
ServerInRoom	Raised when the local peer started as a Server and tried to join a Room that already has a Server peer.
DisconnectedByPluginLogic	Raised when the Peer is disconnected or kicked by a Plugin Logic.
GameClosed	Raised when the Game the Peer is trying to Join is Closed
GameNotFound	Raised when the Game the Peer is trying to Join does not exist
MaxCcuReached	Raised when all CCU available for the Photon Application are in use
InvalidRegion	Raised when the peer is trying to connect to an unavailable or non-existent Region
GameIdAlreadyExists	Raised when a Session with the same name was already created

Enumerator

GamelsFull	Raised when a peer is trying to join a Room with already the max capacity of players
InvalidAuthentication	Raised when the Authentication Values are invalid
CustomAuthenticationFailed	Raised when the Custom Authentication has failed for some other reason
AuthenticationTicketExpired	Raised when the Authentication Ticket has expired
PhotonCloudTimeout	Timeout on the Connection with the Photon Cloud
AlreadyRunning	Raised when Fusion is already running and the StartGame is invoked again
InvalidArguments	Raised when any of the StartGame arguments does not meet the requirements
HostMigration	Signal this Runner is shutting down because of a Host Migration is about to happen
ConnectionTimeout	Connection with a remote server failed by timeout
ConnectionRefused	Connection with a remote server failed because it was refused
OperationTimeout	The current operation has timed out
OperationCanceled	The current operation was canceled

5.1.1.31 SimulationModes

```
enum SimulationModes [strong]
```

Flags for The type of network peer a simulation represents.

Enumerator

Server	Simulation represents a server peer, with no local player.
Host	Simulation represents a server peer, with a local player.
Client	Simulation represents a client peer, with a local player.

5.1.1.32 SimulationStages

```
enum SimulationStages [strong]
```

Flags for which stage the simulation currently running. Forward is when a tick is being simulated for the first time. Resimulate is when a tick is being simulated again with corrections.

Enumerator

Forward	Currently simulating a tick for the first time.
Resimulate	Currently simulating a previously simulated tick again, with state corrections.

5.1.1.33 Topologies

```
enum Topologies [strong]
```

Enumerator

ClientServer	Classic server and client model
Shared	Relay based shared world model

5.1.1.34 Units

```
enum Units [strong]
```

Unit Type for a certain field. This helps to identify the unit that a certain value represents, like Seconds or Percentage

Enumerator

None	
Ticks	ticks
Seconds	seconds - secs
MilliSecs	millisecs - ms
Kilobytes	kilobytes - kB
Megabytes	megabytes - MB
Normalized	normalized - norm
Multiplier	multiplier - mult
Percentage	%
NormalizedPercentage	normalized % - n%
Degrees	degrees - \u00B0
PerSecond	per sec - /sec
DegreesPerSecond	\u00B0 / sec - \u00B0/sec
Radians	radians - rad
RadiansPerSecond	radian / sec - rad/s
TicksPerSecond	ticks / sec - tck/s
Units	units - units
Bytes	bytes - bytes
Count	count - count
Packets	packets - packets
Frames	frames - frames
FramesPerSecond	fps - fps
SquareMagnitude	sqrMagnitude - sqrMag

5.1.1.35 UnityPlayerLoopSystemAddMode

```
enum UnityPlayerLoopSystemAddMode [strong]
```


Enum representing the possible modes for adding a system to the Unity player loop.

Enumerator

FirstChild	Add the system as the first child of the parent system.
LastChild	Add the system as the last child of the parent system.
Before	Add the system before the parent system in the player loop.
After	Add the system after the parent system in the player loop.

5.1.2 Function Documentation

5.1.2.1 NetworkObjectSpawnDelegate()

```
delegate void Fusion.NetworkObjectSpawnDelegate (
    NetworkSpawnOp result )
```

Network Object Spawn Delegate

5.1.2.2 RpcInvokeDelegate()

```
unsafe delegate void Fusion.RpcInvokeDelegate (
    NetworkBehaviour behaviour,
    SimulationMessage * message )
```

Represents a delegate that can be invoked by an RPC message.

Parameters

<i>behaviour</i>	The NetworkBehaviour associated with the RPC message.
<i>message</i>	The SimulationMessage associated with the RPC message.

The [RpcInvokeDelegate](#) is used to invoke an RPC message. The delegate is invoked by the [RpcSystem](#) when an RPC message is received. The delegate is invoked with the [NetworkBehaviour](#) associated with the RPC message and the [SimulationMessage](#) associated with the RPC message.

5.1.2.3 RpcStaticInvokeDelegate()

```
unsafe delegate void Fusion.RpcStaticInvokeDelegate (
    NetworkRunner runner,
    SimulationMessage * message )
```

Represents a delegate that can be invoked by an RPC message.

Parameters

<i>runner</i>	The NetworkRunner associated with the RPC message.
<i>message</i>	The SimulationMessage associated with the RPC message.

The `RpcInvokeDelegate` is used to invoke an RPC message. The delegate is invoked by the `RpcSystem` when an RPC message is received. The delegate is invoked with the [NetworkRunner](#) associated with the RPC message and the [SimulationMessage](#) associated with the RPC message.

5.2 Fusion.Analyzer Namespace Reference

Enumerations

- enum class **StaticFieldResetMode**

5.3 Fusion.Async Namespace Reference

Classes

- class [TaskManager](#)
Task Factory is used to create new Tasks and Schedule long running Tasks

5.4 Fusion.Internal Namespace Reference

Classes

- interface [IUnitySurrogate](#)
Represents an interface for Unity surrogates. This interface provides methods for reading and writing data.
- interface [IUnityValueSurrogate](#)
Represents an interface for Unity value surrogates. This interface provides a property for accessing and modifying the data.
- class [UnityArraySurrogate](#)
A base class for Unity array surrogates.
- class [UnityDictionarySurrogate](#)
A surrogate for serializing a dictionary.
- class [UnityLinkedListSurrogate](#)
A surrogate for serializing a linked list.
- class [UnitySurrogateBase](#)
Represents a base class for Unity surrogates. This class is serializable and provides abstract methods for reading, writing, and initializing data.
- class [UnityValueSurrogate](#)
Represents a base class for Unity value surrogates. This class is serializable and provides methods for reading, writing, and initializing data.

5.5 Fusion.LagCompensation Namespace Reference

Classes

- struct [AABB](#)
Represents an Axis-Aligned Bounding Box ([AABB](#)).
- class [BoxOverlapQuery](#)
Class that represents a box overlap query. Used to query against the [NetworkRunner.LagCompensation](#) API.
- struct [BoxOverlapQueryParams](#)
Base parameters needed to execute a box overlap query
- class [BVHDraw](#)
Provide a way to iterate over BVH and return a [BVHNodeDrawInfo](#) for each node.
- class [BVHNodeDrawInfo](#)
Container class to provide the necessary info to draw nodes from the BVH
- class [ColliderDrawInfo](#)
Container class to provide the necessary information to draw a hitbox collider
- class [HitboxColliderContainerDraw](#)
Provide a way to iterate over the [HitboxBuffer.HitboxSnapshot](#) and return the [ColliderDrawInfo](#) for each collider on the snapshot.
- class [LagCompensatedExt](#)
LagCompensated Extension methods
- class [LagCompensationDraw](#)
Provide access to iterate over the lag compensation system components and give the necessary information to draw them.
- struct [PositionRotationQueryParams](#)
Query parameters for position rotation query
- class [Query](#)
Base class for all Lag Compensation queries
- struct [QueryParams](#)
Base parameters needed to execute a query.
- class [RaycastAllQuery](#)
Class that represents a raycast all query. Used to query against the [NetworkRunner.LagCompensation](#) API.
- class [RaycastQuery](#)
Class that represents a raycast query. Used to query against the [NetworkRunner.LagCompensation](#) API.
- struct [RaycastQueryParams](#)
Base parameters needed to execute a raycast query
- class [SnapshotHistoryDraw](#)
Provide a way to iterate over the [HitboxBuffer](#) and return the [HitboxColliderContainerDraw](#) container for each snapshot on the buffer.
- class [SphereOverlapQuery](#)
Class that represents a sphere overlap query. Used to query against the [NetworkRunner.LagCompensation](#) API.
- struct [SphereOverlapQueryParams](#)
Base parameters needed to execute a sphere overlap query

Enumerations

- enum class [HitType](#)
Queries can hit either fusion's custom Hitbox or Unity's standard Physx/Box2D colliders.

Functions

- delegate void [PreProcessingDelegate](#) ([Query](#) query, List< [HitboxRoot](#) > rootCandidates, HashSet< int > processedColliderIndices)

Pre-processing delegate for queries.

5.5.1 Enumeration Type Documentation

5.5.1.1 HitType

```
enum HitType [strong]
```

Queries can hit either fusion's custom [Hitbox](#) or Unity's standard Physx/Box2D colliders.

Enumerator

None	Used when a raycast does not hit anything. Not used on overlaps.
Hitbox	LagCompensatedHit is a Fusion Hitbox .
PhysX	LagCompensatedHit is a Unity PhysX Collider.
Box2D	LagCompensatedHit is a Unity Box2D Collider.

5.5.2 Function Documentation

5.5.2.1 PreProcessingDelegate()

```
delegate void Fusion.LagCompensation.PreProcessingDelegate (
    Query query,
    List< HitboxRoot > rootCandidates,
    HashSet< int > processedColliderIndices )
```

Pre-processing delegate for queries.

Parameters

<i>query</i>	The query to be performed.
<i>rootCandidates</i>	The root candidates to be used for the query.
<i>processedColliderIndices</i>	The indices of the colliders that have been processed.

5.6 Fusion.Protocol Namespace Reference

Classes

- interface [IMessage](#)
Represents a [Protocol](#) Message

5.7 Fusion.Runtime Namespace Reference

5.8 Fusion.Runtime.Unity Namespace Reference

5.9 Fusion.Sockets Namespace Reference

Classes

- struct [NetAddress](#)
Represents a Network Address, which includes a IP and Port This can contains either a IPv4 or a IPv6 address
- struct [NetBitBufferList](#)
Represents a linked list of [Fusion.Sockets.NetBitBuffer](#)
- struct [NetCommandAccepted](#)
Accepted Command, sent by the server when a remote client connection is accepted
- struct [NetCommandConnect](#)
Connect Command used to signal a remote server that a client is trying to connect to it
- struct [NetCommandDisconnect](#)
Disconnect Command, it can be used by either side of the connection
- struct [NetCommandHeader](#)
Network Command Header Describe its type and usual settings for all commands
- struct [NetCommandRefused](#)
Refuse Command, sent by the server when the connection was refused. This happens when the server has reached its max connection capacity.
- struct [NetConfig](#)
General configuration used to drive the behavior of the Socket library

Enumerations

- enum class [NetCommands](#) : byte
Describe the Type of a Command Packet
- enum class [NetConnectFailedReason](#) : byte
The reason a connection with a remote server has failed
- enum class **NetConnectionStatus**
- enum class [NetDisconnectReason](#) : byte
Disconnect Reason Flag
- enum class [NetPacketType](#) : byte
Describe the type of a Networked Packet
- enum class **OnConnectionRequestReply**

5.9.1 Enumeration Type Documentation

5.9.1.1 NetCommands

```
enum NetCommands : byte [strong]
```

Describe the Type of a Command Packet

5.9.1.2 NetConnectFailedReason

```
enum NetConnectFailedReason : byte [strong]
```

The reason a connection with a remote server has failed

Enumerator

Timeout	Server is not responding.
ServerFull	Server has accepted the max allowed Players
ServerRefused	Server refused the connection

5.9.1.3 NetDisconnectReason

```
enum NetDisconnectReason : byte [strong]
```

Disconnect Reason Flag

5.9.1.4 NetPacketType

```
enum NetPacketType : byte [strong]
```

Describe the type of a Networked Packet

5.10 Fusion.Sockets.Stun Namespace Reference

Enumerations

- enum class NATType : byte
Specifies UDP network type.

5.10.1 Enumeration Type Documentation

5.10.1.1 NATType

```
enum NATType : byte [strong]
```

Specifies UDP network type.

Enumerator

Invalid	Invalid NAT Type
UdpBlocked	UDP is always blocked.
OpenInternet	No NAT, public IP, no firewall.
FullCone	A full cone NAT is one where all requests from the same internal IP address and port are mapped to the same external IP address and port. Furthermore, any external host can send a packet to the internal host, by sending a packet to the mapped external address.
Symmetric	A symmetric NAT is one where all requests from the same internal IP address and port, to a specific destination IP address and port, are mapped to the same external IP address and port. If the same host sends a packet with the same source address and port, but to a different destination, a different mapping is used. Furthermore, only the external host that receives a packet can send a UDP packet back to the internal host.

5.11 UnityEngine Namespace Reference

5.12 UnityEngine.SceneManagement Namespace Reference

5.13 UnityEngine.Scripting Namespace Reference

5.14 UnityEngine.Serialization Namespace Reference

Chapter 6

Class Documentation

6.1 `_128` Struct Reference

A `FixedStorage` that can hold up to 128 words.

Inherits `INetworkStruct`, and `IFixedStorage`.

Public Attributes

- fixed uint `Data` [128]
The data of the `FixedStorage`.

Static Public Attributes

- const int `SIZE` = 512
The size of the `FixedStorage` in bytes.

6.1.1 Detailed Description

A `FixedStorage` that can hold up to 128 words.

6.1.2 Member Data Documentation

6.1.2.1 Data

```
fixed uint Data[128]
```

The data of the `FixedStorage`.

6.1.2.2 SIZE

```
const int SIZE = 512 [static]
```

The size of the [FixedStorage](#) in bytes.

6.2 _16 Struct Reference

A [FixedStorage](#) that can hold up to 16 words.

Inherits [INetworkStruct](#), and [IFixedStorage](#).

Public Attributes

- fixed uint [Data](#) [16]
The data of the [FixedStorage](#).

Static Public Attributes

- const int [SIZE](#) = 64
The size of the [FixedStorage](#) in bytes.

6.2.1 Detailed Description

A [FixedStorage](#) that can hold up to 16 words.

6.2.2 Member Data Documentation

6.2.2.1 Data

```
fixed uint Data[16]
```

The data of the [FixedStorage](#).

6.2.2.2 SIZE

```
const int SIZE = 64 [static]
```

The size of the [FixedStorage](#) in bytes.

6.3 _2 Struct Reference

A [FixedStorage](#) that can hold up to 2 words.

Inherits [INetworkStruct](#), and [IFixedStorage](#).

Public Attributes

- fixed uint [Data](#) [2]
The data of the [FixedStorage](#).

Static Public Attributes

- const int [SIZE](#) = 8
The size of the [FixedStorage](#) in bytes.

6.3.1 Detailed Description

A [FixedStorage](#) that can hold up to 2 words.

6.3.2 Member Data Documentation

6.3.2.1 Data

```
fixed uint Data[2]
```

The data of the [FixedStorage](#).

6.3.2.2 SIZE

```
const int SIZE = 8 [static]
```

The size of the [FixedStorage](#) in bytes.

6.4 _256 Struct Reference

A [FixedStorage](#) that can hold up to 256 words.

Inherits [INetworkStruct](#), and [IFixedStorage](#).

Public Attributes

- fixed uint [Data](#) [256]
The data of the [FixedStorage](#).

Static Public Attributes

- const int [SIZE](#) = 1024
The size of the [FixedStorage](#) in bytes.

6.4.1 Detailed Description

A [FixedStorage](#) that can hold up to 256 words.

6.4.2 Member Data Documentation

6.4.2.1 Data

```
fixed uint Data[256]
```

The data of the [FixedStorage](#).

6.4.2.2 SIZE

```
const int SIZE = 1024 [static]
```

The size of the [FixedStorage](#) in bytes.

6.5 _32 Struct Reference

A [FixedStorage](#) that can hold up to 32 words.

Inherits [INetworkStruct](#), and [IFixedStorage](#).

Public Attributes

- fixed uint [Data](#) [32]
The data of the [FixedStorage](#).

Static Public Attributes

- const int [SIZE](#) = 128
The size of the [FixedStorage](#) in bytes.

6.5.1 Detailed Description

A [FixedStorage](#) that can hold up to 32 words.

6.5.2 Member Data Documentation

6.5.2.1 Data

```
fixed uint Data[32]
```

The data of the [FixedStorage](#).

6.5.2.2 SIZE

```
const int SIZE = 128 [static]
```

The size of the [FixedStorage](#) in bytes.

6.6 _4 Struct Reference

A [FixedStorage](#) that can hold up to 4 words.

Inherits [INetworkStruct](#), and [IFixedStorage](#).

Public Attributes

- fixed uint [Data](#) [4]
The data of the [FixedStorage](#).

Static Public Attributes

- const int [SIZE](#) = 16
The size of the [FixedStorage](#) in bytes.

6.6.1 Detailed Description

A [FixedStorage](#) that can hold up to 4 words.

6.6.2 Member Data Documentation

6.6.2.1 Data

```
fixed uint Data[4]
```

The data of the [FixedStorage](#).

6.6.2.2 SIZE

```
const int SIZE = 16 [static]
```

The size of the [FixedStorage](#) in bytes.

6.7 _512 Struct Reference

A [FixedStorage](#) that can hold up to 512 words.

Inherits [INetworkStruct](#), and [IFixedStorage](#).

Public Attributes

- fixed uint [Data](#) [512]
The data of the [FixedStorage](#).

Static Public Attributes

- const int [SIZE](#) = 2048
The size of the [FixedStorage](#) in bytes.

6.7.1 Detailed Description

A [FixedStorage](#) that can hold up to 512 words.

6.7.2 Member Data Documentation

6.7.2.1 Data

```
fixed uint Data[512]
```

The data of the [FixedStorage](#).

6.7.2.2 SIZE

```
const int SIZE = 2048 [static]
```

The size of the [FixedStorage](#) in bytes.

6.8 _64 Struct Reference

A [FixedStorage](#) that can hold up to 64 words.

Inherits [INetworkStruct](#), and [IFixedStorage](#).

Public Attributes

- fixed uint [Data](#) [64]
The data of the [FixedStorage](#).

Static Public Attributes

- const int [SIZE](#) = 256
The size of the [FixedStorage](#) in bytes.

6.8.1 Detailed Description

A [FixedStorage](#) that can hold up to 64 words.

6.8.2 Member Data Documentation

6.8.2.1 Data

```
fixed uint Data[64]
```

The data of the [FixedStorage](#).

6.8.2.2 SIZE

```
const int SIZE = 256 [static]
```

The size of the [FixedStorage](#) in bytes.

6.9 _8 Struct Reference

A [FixedStorage](#) that can hold up to 8 words.

Inherits [INetworkStruct](#), and [IFixedStorage](#).

Public Attributes

- fixed uint [Data](#) [8]
The data of the [FixedStorage](#).

Static Public Attributes

- const int [SIZE](#) = 32
The size of the [FixedStorage](#) in bytes.

6.9.1 Detailed Description

A [FixedStorage](#) that can hold up to 8 words.

6.9.2 Member Data Documentation

6.9.2.1 Data

```
fixed uint Data[8]
```

The data of the [FixedStorage](#).

6.9.2.2 SIZE

```
const int SIZE = 32 [static]
```

The size of the [FixedStorage](#) in bytes.

6.10 Allocator Struct Reference

Memory [Allocator](#)

Classes

- struct [Config](#)
Memory [Allocator](#) Configuration

Public Member Functions

- Block * **GetBlock** (int index)
- Block * **GetBlock** (long index)
- int **GetBlockBucket** (long index)
- Block * **GetBlockForPointer** (void *ptr)
- int **GetBlockIndexForPointer** (void *ptr)
- byte * **GetBlockMemory** (Block *block)
- byte * **GetBlockMemory** (long blockIndex)
- Bucket * **GetBucket** (int index)
- Bucket * **GetBucketForBlock** (Block *block)
- BlockList * **GetBucketList** (int index)
- bool **IsPointerInMeta** (void *p)
- void * **Meta** ([Ptr](#) ptr)
- [Ptr](#) **Meta** (void *p)

Static Public Member Functions

- static void **DebugVerifyBucketIntegrity** ([Allocator](#) *a, int index)
- static void * **TryAllocateSegmentFromBlock** ([Allocator](#) *a, Bucket *bucket, Block *block, int size)
- static int **WordCount** (int size)

Public Attributes

- Block * **_blocks**
- BlockList * **_blocksFreeList**
- Bucket * **_buckets**
- BlockList * **_bucketsLists**
- byte * **_bucketsMap**
- void * **_checksum**
- int **_checksumByteLength**
- [Config](#) **_config**
- void * **_globals**
- byte * **_heap**
- int **_maxBlockIndexUsed**
- byte * **_meta**
- void * **_replicate**
- int **_replicateByteLength**
- byte * **_root**

Static Public Attributes

- const int [BUCKET_COUNT](#) = 57
Bucket Count
- const byte [BUCKET_INVALID](#) = 255
Bucket Invalid
- const int [HEAP_ALIGNMENT](#) = 8
Heap Alignment
- const int [PTR_SIZE](#) = 8
- const int [REPLICATE_WORD_ALIGN](#) = [REPLICATE_WORD_SIZE](#)
Replicate Word Align
- const int [REPLICATE_WORD_SHIFT](#) = 2
Replicate Word Shift
- const int [REPLICATE_WORD_SIZE](#) = 1 << [REPLICATE_WORD_SHIFT](#)
Replicate Word Size
- const int [SIZE](#) = 112
- const int [WORD_BYTE_SIZE](#) = 1 << 3
- const int [WORD_SHIFT](#) = 3

6.10.1 Detailed Description

Memory [Allocator](#)

6.10.2 Member Data Documentation

6.10.2.1 BUCKET_COUNT

```
const int BUCKET_COUNT = 57 [static]
```

Bucket Count

6.10.2.2 BUCKET_INVALID

```
const byte BUCKET_INVALID = 255 [static]
```

Bucket Invalid

6.10.2.3 HEAP_ALIGNMENT

```
const int HEAP_ALIGNMENT = 8 [static]
```

Heap Alignment

6.10.2.4 REPLICATE_WORD_ALIGN

```
const int REPLICATE_WORD_ALIGN = REPLICATE_WORD_SIZE [static]
```

Replicate Word Align

6.10.2.5 REPLICATE_WORD_SHIFT

```
const int REPLICATE_WORD_SHIFT = 2 [static]
```

Replicate Word Shift

6.10.2.6 REPLICATE_WORD_SIZE

```
const int REPLICATE_WORD_SIZE = 1 << REPLICATE_WORD_SHIFT [static]
```

Replicate Word Size

6.11 Allocator.Config Struct Reference

Memory [Allocator](#) Configuration

Public Member Functions

- [Config](#) ([PageSizes](#) shift, int count, int globalsSize)
Config Constructor
- bool [Equals](#) ([Config](#) other)
Check Config equality
- override bool [Equals](#) (object obj)
Check Config equality
- override int [GetHashCode](#) ()
Get Hash Code
- override string [ToString](#) ()
Config ToString

Public Attributes

- int [BlockCount](#)
Block Count Config value
- int [BlockShift](#)
Block Shift Config value
- int [GlobalsSize](#)
Globals Size Config value

Static Public Attributes

- const int [DEFAULT_BLOCK_COUNT](#) = 256
Default Block Count
- const [PageSizes](#) [DEFAULT_BLOCK_SHIFT](#) = [PageSizes._32Kb](#)
Default Block Shift
- const int [SIZE](#) = 12
Config Size

Properties

- int [BlockByteSize](#) [get]
Block Size in Bytes
- int [BlockWordCount](#) [get]
Block Size in Words
- int [HeapSizeAllocated](#) [get]
Heap Size Allocated in Bytes
- int [HeapSizeUsable](#) [get]
Heap Size in Bytes

6.11.1 Detailed Description

Memory [Allocator](#) Configuration

6.11.2 Constructor & Destructor Documentation

6.11.2.1 Config()

```
Config (
    PageSizes shift,
    int count,
    int globalsSize )
```

[Config](#) Constructor

Parameters

<i>shift</i>	Block Shift
<i>count</i>	Block Count
<i>globalsSize</i>	Globals Size

6.11.3 Member Function Documentation

6.11.3.1 Equals() [1/2]

```
bool Equals (
    Config other )
```

Check [Config](#) equality

Parameters

<i>other</i>	Config Ref
--------------	----------------------------

Returns

True if has the same values

6.11.3.2 Equals() [2/2]

```
override bool Equals (
    object obj )
```

Check [Config](#) equality

Parameters

<i>obj</i>	Any object reference
------------	----------------------

Returns

True if *obj* is a [Config](#) and has the same values

6.11.3.3 GetHashCode()

```
override int GetHashCode ( )
```

Get Hash Code

Returns

Hash Code

6.11.3.4 ToString()

```
override string ToString ( )
```

[Config](#) ToString

6.11.4 Member Data Documentation

6.11.4.1 BlockCount

```
int BlockCount
```

Block Count [Config](#) value

6.11.4.2 BlockShift

```
int BlockShift
```

Block Shift [Config](#) value

6.11.4.3 DEFAULT_BLOCK_COUNT

```
const int DEFAULT_BLOCK_COUNT = 256 [static]
```

Default Block Count

6.11.4.4 DEFAULT_BLOCK_SHIFT

```
const PageSizes DEFAULT_BLOCK_SHIFT = PageSizes._32Kb [static]
```

Default Block Shift

6.11.4.5 GlobalsSize

```
int GlobalsSize
```

Globals Size [Config](#) value

6.11.4.6 SIZE

```
const int SIZE = 12 [static]
```

[Config](#) Size

6.11.5 Property Documentation

6.11.5.1 BlockByteSize

```
int BlockByteSize [get]
```

Block Size in Bytes

6.11.5.2 BlockWordCount

```
int BlockWordCount [get]
```

Block Size in Words

6.11.5.3 HeapSizeAllocated

```
int HeapSizeAllocated [get]
```

Heap Size Allocated in Bytes

6.11.5.4 HeapSizeUsable

```
int HeapSizeUsable [get]
```

Heap Size in Bytes

6.12 Angle Struct Reference

A Networked fusion type for degrees. This can be used with the [NetworkedAttribute](#), in RPCs, or in [NetworkInput](#) structs.

Inherits [INetworkStruct](#), and `IEquatable< Angle >`.

Public Member Functions

- void [Clamp](#) ([Angle](#) min, [Angle](#) max)
Clamps the current value to the supplied min-max range.
- bool [Equals](#) ([Angle](#) other)
Checks equality with another [Angle](#).
- override bool [Equals](#) (object obj)
Checks equality with an object.
- override int [GetHashCode](#) ()
Gets the hash code.
- override string [ToString](#) ()
String representation of the [Angle](#).

Static Public Member Functions

- static [Angle Clamp](#) ([Angle](#) value, [Angle](#) min, [Angle](#) max)
Returns a the value, clamped to the min-max range.
- static [Angle Lerp](#) ([Angle](#) a, [Angle](#) b, float t)
Lerps between two angle values.
- static [Angle Max](#) ([Angle](#) a, [Angle](#) b)
Returns the larger of two supplied angles.
- static [Angle Min](#) ([Angle](#) a, [Angle](#) b)
Returns the smaller of two supplied angles.
- static implicit [operator Angle](#) (double value)
Converts double to [Angle](#).
- static implicit [operator Angle](#) (float value)
Converts float to [Angle](#).
- static implicit [operator Angle](#) (int value)
Converts int to [Angle](#).
- static [operator double](#) ([Angle](#) value)
Converts [Angle](#) to double.
- static [operator float](#) ([Angle](#) value)
Converts [Angle](#) to float.
- static bool [operator!=](#) ([Angle](#) a, [Angle](#) b)
Inequality operator for [Angle](#) struct.
- static [Angle operator+](#) ([Angle](#) a, [Angle](#) b)
Addition operator for [Angle](#) struct.
- static [Angle operator-](#) ([Angle](#) a, [Angle](#) b)
Subtraction operator for [Angle](#) struct.
- static bool [operator<](#) ([Angle](#) a, [Angle](#) b)
Less than operator for [Angle](#) struct.
- static bool [operator<=](#) ([Angle](#) a, [Angle](#) b)
Less than or equal to operator for [Angle](#) struct.
- static bool [operator==](#) ([Angle](#) a, [Angle](#) b)
Equality operator for [Angle](#) struct.
- static bool [operator>](#) ([Angle](#) a, [Angle](#) b)
Greater than operator for [Angle](#) struct.
- static bool [operator>=](#) ([Angle](#) a, [Angle](#) b)
Greater than or equal to operator for [Angle](#) struct.

Public Attributes

- `int _value`

Static Public Attributes

- `const int _360 = 360 * ACCURACY`
- `const int ACCURACY = 10000`
- `const int DECIMALS = 4`
- `const int SIZE = 4`

Size of this struct in bytes.

6.12.1 Detailed Description

A Networked fusion type for degrees. This can be used with the [NetworkedAttribute](#), in RPCs, or in [NetworkInput](#) structs.

6.12.2 Member Function Documentation

6.12.2.1 Clamp() [1/2]

```
void Clamp (
    Angle min,
    Angle max )
```

Clamps the current value to the supplied min-max range.

6.12.2.2 Clamp() [2/2]

```
static Angle Clamp (
    Angle value,
    Angle min,
    Angle max ) [static]
```

Returns a the value, clamped to the min-max range.

6.12.2.3 Equals() [1/2]

```
bool Equals (
    Angle other )
```

Checks equality with another [Angle](#).

Parameters

<i>other</i>	Other Angle .
--------------	-------------------------------

Returns

Equality result.

6.12.2.4 Equals() [2/2]

```
override bool Equals (
    object obj )
```

Checks equality with an object.

Parameters

<i>obj</i>	Object to compare.
------------	--------------------

Returns

Equality result.

6.12.2.5 GetHashCode()

```
override int GetHashCode ( )
```

Gets the hash code.

Returns

Hash code.

6.12.2.6 Lerp()

```
static Angle Lerp (
    Angle a,
    Angle b,
    float t ) [static]
```

Lerps between two angle values.

6.12.2.7 Max()

```
static Angle Max (  
    Angle a,  
    Angle b ) [static]
```

Returns the larger of two supplied angles.

6.12.2.8 Min()

```
static Angle Min (  
    Angle a,  
    Angle b ) [static]
```

Returns the smaller of two supplied angles.

6.12.2.9 operator Angle() [1/3]

```
static implicit operator Angle (  
    double value ) [static]
```

Converts double to [Angle](#).

Parameters

<i>value</i>	Double value.
--------------	---------------

Returns

[Angle](#) instance with the value of the double.

6.12.2.10 operator Angle() [2/3]

```
static implicit operator Angle (  
    float value ) [static]
```

Converts float to [Angle](#).

Parameters

<i>value</i>	Float value.
--------------	--------------

Returns

[Angle](#) instance with the value of the float.

6.12.2.11 operator Angle() [3/3]

```
static implicit operator Angle (  
    int value ) [static]
```

Converts int to [Angle](#).

Parameters

<i>value</i>	Integer value.
--------------	----------------

Returns

[Angle](#) instance with the value of the integer.

6.12.2.12 operator double()

```
static operator double (  
    Angle value ) [explicit], [static]
```

Converts [Angle](#) to double.

Parameters

<i>value</i>	Angle instance.
--------------	---------------------------------

Returns

Double representation of the [Angle](#).

6.12.2.13 operator float()

```
static operator float (  
    Angle value ) [explicit], [static]
```

Converts [Angle](#) to float.

Parameters

<i>value</i>	Angle instance.
--------------	---------------------------------

Returns

Float representation of the [Angle](#).

6.12.2.14 operator"!=()"

```
static bool operator!= (  
    Angle a,  
    Angle b ) [static]
```

Inequality operator for [Angle](#) struct.

Parameters

<i>a</i>	First Angle instance.
<i>b</i>	Second Angle instance.

Returns

True if the value of the first [Angle](#) instance is not equal to the value of the second [Angle](#) instance, otherwise false.

6.12.2.15 operator+()

```
static Angle operator+ (  
    Angle a,  
    Angle b ) [static]
```

Addition operator for [Angle](#) struct.

Parameters

<i>a</i>	First Angle instance.
<i>b</i>	Second Angle instance.

Returns

A new [Angle](#) instance that is the sum of the first and second [Angle](#) instances, wrapped around at 360 degrees if necessary.

6.12.2.16 operator-()

```
static Angle operator- (
    Angle a,
    Angle b ) [static]
```

Subtraction operator for [Angle](#) struct.

Parameters

<i>a</i>	First Angle instance.
<i>b</i>	Second Angle instance.

Returns

A new [Angle](#) instance that is the difference of the first and second [Angle](#) instances, wrapped around at 360 degrees if necessary.

6.12.2.17 operator<()

```
static bool operator< (
    Angle a,
    Angle b ) [static]
```

Less than operator for [Angle](#) struct.

Parameters

<i>a</i>	First Angle instance.
<i>b</i>	Second Angle instance.

Returns

True if the value of the first [Angle](#) instance is less than the value of the second [Angle](#) instance, otherwise false.

6.12.2.18 operator<=()

```
static bool operator<= (
    Angle a,
    Angle b ) [static]
```

Less than or equal to operator for [Angle](#) struct.

Parameters

<i>a</i>	First Angle instance.
<i>b</i>	Second Angle instance.

Returns

True if the value of the first [Angle](#) instance is less than or equal to the value of the second [Angle](#) instance, otherwise false.

6.12.2.19 operator==()

```
static bool operator== (  
    Angle a,  
    Angle b ) [static]
```

Equality operator for [Angle](#) struct.

Parameters

<i>a</i>	First Angle instance.
<i>b</i>	Second Angle instance.

Returns

True if the value of the first [Angle](#) instance is equal to the value of the second [Angle](#) instance, otherwise false.

6.12.2.20 operator>()

```
static bool operator> (  
    Angle a,  
    Angle b ) [static]
```

Greater than operator for [Angle](#) struct.

Parameters

<i>a</i>	First Angle instance.
<i>b</i>	Second Angle instance.

Returns

True if the value of the first [Angle](#) instance is greater than the value of the second [Angle](#) instance, otherwise false.

6.12.2.21 operator>=()

```
static bool operator>= (
    Angle a,
    Angle b ) [static]
```

Greater than or equal to operator for [Angle](#) struct.

Parameters

<i>a</i>	First Angle instance.
<i>b</i>	Second Angle instance.

Returns

True if the value of the first [Angle](#) instance is greater than or equal to the value of the second [Angle](#) instance, otherwise false.

6.12.2.22 ToString()

```
override string ToString ( )
```

String representation of the [Angle](#).

6.12.3 Member Data Documentation

6.12.3.1 SIZE

```
const int SIZE = 4 [static]
```

Size of this struct in bytes.

6.13 AssetObject Class Reference

Base class for all [Fusion](#) assets.

Inherits [ScriptableObject](#).

6.13.1 Detailed Description

Base class for all [Fusion](#) assets.

6.14 TaskManager Class Reference

Task Factory is used to create new Tasks and Schedule long running Tasks

Static Public Member Functions

- static Task [ContinueWhenAll](#) (Task[] precedingTasks, Func< CancellationToken, Task > action, CancellationToken cancellationToken)
Run a continuation Task after all other Tasks have completed
- static Task [Run](#) (Func< CancellationToken, Task > action, CancellationToken cancellationToken, TaskCreationOptions options=TaskCreationOptions.None)
Run an Action asynchronously
- static Task [Service](#) (Action recurringAction, CancellationToken cancellationToken, int interval, string serviceName=null)
- static Task [Service](#) (Func< Task< bool >> recurringAction, CancellationToken cancellationToken, int interval, string serviceName=null)
Start a Service Task that will invoke a Recurring Action every each interval in millis
- static void [Setup](#) ()
Setup a new TaskFactory tailored to work with Unity

6.14.1 Detailed Description

Task Factory is used to create new Tasks and Schedule long running Tasks

6.14.2 Member Function Documentation

6.14.2.1 ContinueWhenAll()

```
static Task ContinueWhenAll (
    Task[] precedingTasks,
    Func< CancellationToken, Task > action,
    CancellationToken cancellationToken ) [static]
```

Run a continuation Task after all other Tasks have completed

Parameters

<i>precedingTasks</i>	List of pending tasks to wait
<i>action</i>	Action to run after the Tasks
<i>cancellationToken</i>	ellationToken used to stop the Action

Returns

[Async](#) Task based on the Action

6.14.2.2 Run()

```
static Task Run (
    Func< CancellationToken, Task > action,
    CancellationToken cancellationToken,
    TaskCreationOptions options = TaskCreationOptions.None ) [static]
```

Run an Action asynchronously

Parameters

<i>action</i>	Action to be invoked
<i>cancellationToken</i>	CancellationToken used to stop the Action
<i>options</i>	Extra Task Creation options

Returns

[Async](#) Task based on the Action

6.14.2.3 Service()

```
static Task Service (
    Func< Task< bool >> recurringAction,
    CancellationToken cancellationToken,
    int interval,
    string serviceName = null ) [static]
```

Start a Service Task that will invoke a Recurring Action every each interval in millis

Parameters

<i>recurringAction</i>	Action invoked every interval. It can return false to stop the service
<i>cancellationToken</i>	CancellationToken used to stop the service
<i>interval</i>	Interval between action invoke
<i>serviceName</i>	Custom id name for the Service

Returns

Service Task

6.14.2.4 Setup()

```
static void Setup ( ) [static]
```

Setup a new TaskFactory tailored to work with Unity

6.15 AuthorityMasks Class Reference

Provides constants and methods for managing authority masks.

Static Public Attributes

- const int **ALL** = **STATE** | **INPUT** | **PROXY**
Constant representing all authorities.
- const int **INPUT** = 1 << 1
Constant representing the input authority mask.
- const int **NONE** = 0
Constant representing no authority.
- const int **PROXY** = 1 << 2
Constant representing the proxy authority mask.
- const int **STATE** = 1 << 0
Constant representing the state authority mask.

6.15.1 Detailed Description

Provides constants and methods for managing authority masks.

6.15.2 Member Data Documentation

6.15.2.1 ALL

```
const int ALL = STATE | INPUT | PROXY [static]
```

Constant representing all authorities.

6.15.2.2 INPUT

```
const int INPUT = 1 << 1 [static]
```

Constant representing the input authority mask.

6.15.2.3 NONE

```
const int NONE = 0 [static]
```

Constant representing no authority.

6.15.2.4 PROXY

```
const int PROXY = 1 << 2 [static]
```

Constant representing the proxy authority mask.

6.15.2.5 STATE

```
const int STATE = 1 << 0 [static]
```

Constant representing the state authority mask.

6.16 Behaviour Class Reference

Alternative base class to Unity's `MonoBehaviour`. This allows for components that work both in Unity, as well as the Photon relays.

Inherits `MonoBehaviour`, `ILogSource`, and `ILogDumpable`.

Inherited by [Hitbox](#), [NetworkEvents](#), [NetworkObject](#), [NetworkObjectPrefabData](#), [NetworkRunner](#), and [SimulationBehaviour](#).

Public Member Functions

- [T AddBehaviour< T > \(\)](#)
Wrapper for Unity's `GameObject.AddComponent()`
- [T GetBehaviour< T > \(\)](#)
Wrapper for Unity's `GameObject.GetComponentInChildren()`
- [bool TryGetBehaviour< T > \(out T behaviour\)](#)
Wrapper for Unity's `GameObject.TryGetComponent()`

Static Public Member Functions

- [static void DestroyBehaviour \(Behaviour behaviour\)](#)
Wrapper for Unity's `GameObject.Destroy()`

6.16.1 Detailed Description

Alternative base class to Unity's MonoBehaviour. This allows for components that work both in Unity, as well as the Photon relays.

6.16.2 Member Function Documentation

6.16.2.1 AddBehaviour< T >()

```
T AddBehaviour< T > ( )
```

Wrapper for Unity's GameObject.AddComponent()

Type Constraints

T : Behaviour

6.16.2.2 DestroyBehaviour()

```
static void DestroyBehaviour (
    Behaviour behaviour ) [static]
```

Wrapper for Unity's GameObject.Destroy()

6.16.2.3 GetBehaviour< T >()

```
T GetBehaviour< T > ( )
```

Wrapper for Unity's GameObject.GetComponentInChildren()

Type Constraints

T : Behaviour

6.16.2.4 TryGetBehaviour< T >()

```
bool TryGetBehaviour< T > (
    out T behaviour )
```

Wrapper for Unity's `GameObject.TryGetComponent()`

Type Constraints

T : *Behaviour*

6.17 BehaviourStats Struct Reference

Represents statistics related to the execution of a [SimulationBehaviour](#).

Public Attributes

- OverTimeStatBuffer [FixedUpdateExecutionTime](#)
Gets or sets the buffer for tracking the execution time of FixedUpdate over time.
- OverTimeStatBuffer [FixedUpdateInvocations](#)
Gets or sets the buffer for tracking the number of FixedUpdate invocations over time.
- OverTimeStatBuffer [RenderExecutionTime](#)
Gets or sets the buffer for tracking the execution time of Render over time.
- OverTimeStatBuffer [RenderInvocations](#)
Gets or sets the buffer for tracking the number of Render invocations over time.

6.17.1 Detailed Description

Represents statistics related to the execution of a [SimulationBehaviour](#).

6.17.2 Member Data Documentation

6.17.2.1 FixedUpdateExecutionTime

```
OverTimeStatBuffer FixedUpdateExecutionTime
```

Gets or sets the buffer for tracking the execution time of FixedUpdate over time.

6.17.2.2 FixedUpdateInvocations

OverTimeStatBuffer FixedUpdateInvocations

Gets or sets the buffer for tracking the number of FixedUpdate invocations over time.

6.17.2.3 RenderExecutionTime

OverTimeStatBuffer RenderExecutionTime

Gets or sets the buffer for tracking the execution time of Render over time.

6.17.2.4 RenderInvocations

OverTimeStatBuffer RenderInvocations

Gets or sets the buffer for tracking the number of Render invocations over time.

6.18 CapacityAttribute Class Reference

Capacity Attribute

Inherits Attribute.

Public Member Functions

- [CapacityAttribute](#) (int length)
CapacityAttribute Constructor

Properties

- int [Length](#) [get]
Total Capacity

6.18.1 Detailed Description

Capacity Attribute

6.18.2 Constructor & Destructor Documentation

6.18.2.1 CapacityAttribute()

```
CapacityAttribute (
    int length )
```

[CapacityAttribute](#) Constructor

Parameters

<i>length</i>	Length
---------------	------------------------

6.18.3 Property Documentation

6.18.3.1 Length

```
int Length [get]
```

Total Capacity

6.19 DefaultForPropertyAttribute Class Reference

Default For Property Attribute

Inherits PropertyAttribute.

Public Member Functions

- [DefaultForPropertyAttribute](#) (string propertyName, int wordOffset, int wordCount)
DefaultForPropertyAttribute Constructor

Properties

- String [PropertyName](#) [get]
Property Name
- int [WordCount](#) [get]
Property Word Count
- int [WordOffset](#) [get]
Property Word Offset

6.19.1 Detailed Description

Default For Property Attribute

For non-serialized properties

6.19.2 Constructor & Destructor Documentation

6.19.2.1 DefaultForPropertyAttribute()

```
DefaultForPropertyAttribute (  
    string propertyName,  
    int wordOffset,  
    int wordCount )
```

[DefaultForPropertyAttribute](#) Constructor

Parameters

<i>propertyName</i>	PropertyName
<i>wordOffset</i>	WordOffset
<i>wordCount</i>	WordCount

6.19.3 Property Documentation

6.19.3.1 PropertyName

```
String PropertyName [get]
```

Property Name

6.19.3.2 WordCount

```
int WordCount [get]
```

Property Word Count

6.19.3.3 WordOffset

```
int WordOffset [get]
```

Property Word Offset

6.20 DisplayAsEnumAttribute Class Reference

Casts an enum or int value in the inspector to specific enum type for rendering of its popup list. Supplying a method name rather than a type allows a property with the type `Type` to be used to dynamically get the enum type.

Inherits `DrawerPropertyAttribute`.

Public Member Functions

- **DisplayAsEnumAttribute** (string enumTypeMemberName)
- **DisplayAsEnumAttribute** (Type enumType)

Properties

- Type **EnumType** [get]
- string **EnumTypeMemberName** [get]

6.20.1 Detailed Description

Casts an enum or int value in the inspector to specific enum type for rendering of its popup list. Supplying a method name rather than a type allows a property with the type Type to be used to dynamically get the enum type.

6.21 DolfAttributeBase Class Reference

Editor attribute for selective editor rendering. Condition member can be a property, field or method (with a return value).

Inherits DecoratingPropertyAttribute.

Inherited by [DrawIfAttribute](#), [ErrorIfAttribute](#), and [WarnIfAttribute](#).

Public Attributes

- double **_doubleValue**
- bool **_isDouble**
- long **_longValue**
- [CompareOperator](#) **Compare**
- string **ConditionMember**
- bool **ErrorOnConditionMemberNotFound** = true

Protected Member Functions

- **DolfAttributeBase** (string propertyPath, double compareToValue, [CompareOperator](#) compare)
- **DolfAttributeBase** (string propertyPath, long compareToValue, [CompareOperator](#) compare)

6.21.1 Detailed Description

Editor attribute for selective editor rendering. Condition member can be a property, field or method (with a return value).

Value of condition method is converted to a long. Null = 0, False = 0, True = 1, Unity Object = InstanceId

6.22 DrawIfAttribute Class Reference

Editor attribute for selectively drawing/hiding fields. Condition member can be a property, field or method (with a return value).

Inherits [DolfAttributeBase](#).

Public Member Functions

- **DrawIfAttribute** (string propertyPath)
- **DrawIfAttribute** (string propertyPath, bool compareToValue, [CompareOperator](#) compare=[CompareOperator.Equal](#), DrawIfMode mode=DrawIfMode.ReadOnly)
Constructor.
- **DrawIfAttribute** (string propertyPath, double compareToValue, [CompareOperator](#) compare=[CompareOperator.Equal](#), DrawIfMode mode=DrawIfMode.ReadOnly)
Constructor.
- **DrawIfAttribute** (string propertyPath, long compareToValue, [CompareOperator](#) compare=[CompareOperator.Equal](#), DrawIfMode mode=DrawIfMode.ReadOnly)

Public Attributes

- DrawIfMode [Mode](#)
Instructs the attribute completely hide the field if not draw, rather than the default of just disabling it.

Properties

- bool? **Hide** [get, set]

Additional Inherited Members

6.22.1 Detailed Description

Editor attribute for selectively drawing/hiding fields. Condition member can be a property, field or method (with a return value).

Value of condition method is converted to a long. Null = 0, False = 0, True = 1, Unity Object = InstanceId

6.22.2 Constructor & Destructor Documentation

6.22.2.1 DrawIfAttribute() [1/2]

```
DrawIfAttribute (
    string propertyPath,
    double compareToValue,
    CompareOperator compare = CompareOperator.Equal,
    DrawIfMode mode = DrawIfMode.ReadOnly )
```

Constructor.

Parameters

<i>propertyPath</i>	Condition member can be a property, field or method (with a return value).
---------------------	--

Value of condition method is converted to a long. Null = 0, False = 0, True = 1, Unity Object = InstanceId

Parameters

<i>compareToValue</i>	The value to compare the member value against.
<i>mode</i>	How the field should be hidden (disabled or removed)
<i>compare</i>	How the condition member value and compareToValye will be evaluated.

6.22.2.2 DrawIfAttribute() [2/2]

```
DrawIfAttribute (
    string propertyPath,
    bool compareToValue,
    CompareOperator compare = CompareOperator.Equal,
    DrawIfMode mode = DrawIfMode.ReadOnly )
```

Constructor.

Parameters

<i>propertyPath</i>	Condition member can be a property, field or method (with a return value).
---------------------	--

Value of condition method is converted to a long. Null = 0, False = 0, True = 1, Unity Object = InstanceId

Parameters

<i>compareToValue</i>	The value to compare the member value against.
<i>compare</i>	How the condition member value and compareToValye will be evaluated.
<i>mode</i>	How the field should be hidden (disabled or removed)

6.22.3 Member Data Documentation

6.22.3.1 Mode

```
DrawIfMode Mode
```

Instructs the attribute completely hide the field if not draw, rather than the default of just disabling it.

6.23 DynamicHeap Struct Reference

A dynamic heap for allocating and tracking unmanaged objects.

Classes

- class [Ignore](#)
Ignore this field when scanning for pointers.

Public Types

- enum class **ObjectFlags** : byte

Public Member Functions

- delegate void [CollectGarbageDelegate](#) ([DynamicHeap](#) *heap, void **dynamicRoots, int dynamicRootsLength)
Collect garbage delegate

Static Public Member Functions

- static void **AllocateBlock** ([DynamicHeap](#) *heap)
- static byte * **AllocateInternal** ([DynamicHeap](#) *heap, int size, out byte block)
- static Page * **AllocatePage** ([DynamicHeap](#) *heap)
- static Page * **AllocatePage_Internal** ([DynamicHeap](#) *heap, bool mustSucceed)
- static int **BitScan** (uint v)
- static int **BlocksWithAvailablePages** ([DynamicHeap](#) *heap)
- static void [CollectGarbage](#) ([DynamicHeap](#) *heap, void **dynamicRoots, int dynamicRootsLength)
Collect garbage
- static void **Destroy** (Block *block)
- static void **ExpandStack** ([DynamicHeap](#) *heap)
- static void [Free](#) ([DynamicHeap](#) *heap, void *ptr)
Free up an object
- static void **FreeInternal** ([DynamicHeap](#) *heap, void *ptr, Object objData)
- static int **GetBin** (int size)
- static Bin * **GetBinByIndex** ([DynamicHeap](#) *heap, int binIndex)
- static int **GetBinIndexForSize** ([DynamicHeap](#) *heap, int size)
- static Page * **GetPageForPtr** ([DynamicHeap](#) *heap, Block *block, void *ptr)
- static int **GetPageOffset** (Page *page, ObjectFree *obj)
- static ushort **GetTypeOffset** < T > ()
- static void **InitObj** ([DynamicHeap](#) *heap, Object *obj, ushort type, ushort array, byte block)
- static void **InitRoot** ([DynamicHeap](#) *heap, Object *obj)
- static bool **IsPtrInBlock** ([DynamicHeap](#) *heap, Block *block, void *p)
- static ushort **NextGen** ([DynamicHeap](#) *heap)
- static int **ObjectsFreeCount** (Page *p)
- static int **PagesWithAvailableObjectsInBin** (Bin *bin)
- static ObjectFree * **ResolvePageOffset** (Page *page, int offset)
- static T * [SetForcedAlive](#) < T > (T *ptr)
Mark an object with ObjectFlags.ForceAlive
- static void **ThrowHeapCorrupted** ()
- static byte * **TryAllocateFromPage** ([DynamicHeap](#) *heap, Page *page, int size, out byte block)
- static int **WordCount** (int size)

Public Attributes

- Bin * **_bins**
- Block ** **_blocks**
- BlockList **_blocksFreePages**
- int **_blocksUsed**
- Config **_config**
- int **_gcBlock**
- int **_gcBlockPage**
- ushort **_gcGen**
- Phase **_gcPhase**
- Object ** **_gcStack**
- int **_gcStackCapacity**
- int **_gcStackCount**
- int **_memoryAllocated**
- int **_objectsAllocated**
- Object ** **_rootList**
- int **_rootListCapacity**
- int **_rootListCount**
- int * **_typeMap**
- int **_typeMapLength**
- int * **_typeMapStrides**

Static Public Attributes

- static byte[] **_debruijnTable**
- static Dictionary< Type, TypeData > **_types** = null
- static Dictionary< ushort, TypeData > **_typesByOffset** = null

6.23.1 Detailed Description

A dynamic heap for allocating and tracking unmanaged objects.

6.23.2 Member Function Documentation

6.23.2.1 CollectGarbage()

```
static void CollectGarbage (
    DynamicHeap * heap,
    void ** dynamicRoots,
    int dynamicRootsLength ) [static]
```

Collect garbage

Parameters

<i>heap</i>	Dynamic heap to collect from
<i>dynamicRoots</i>	Dynamic roots
<i>dynamicRootsLength</i>	Dynamic roots length

6.23.2.2 CollectGarbageDelegate()

```
delegate void CollectGarbageDelegate (
    DynamicHeap * heap,
    void ** dynamicRoots,
    int dynamicRootsLength )
```

Collect garbage delegate

6.23.2.3 Free()

```
static void Free (
    DynamicHeap * heap,
    void * ptr ) [static]
```

Free up an object

Parameters

<i>heap</i>	Heap to free from
<i>ptr</i>	Pointer to object

Exceptions

<i>InvalidOperationException</i>	Thrown if <i>ptr</i> is not a tracked object
----------------------------------	--

6.23.2.4 SetForcedAlive< T >()

```
static T* SetForcedAlive< T > (
    T * ptr ) [static]
```

Mark an object with ObjectFlags.ForceAlive

Parameters

<i>ptr</i>	Pointer Object to mark
------------	------------------------

Template Parameters

<i>T</i>	Type of object
----------	----------------

Returns

Pointer to object

Type Constraints

T: *unmanaged*

6.23.3 Member Data Documentation**6.23.3.1 _debruijnTable**

```
byte [] _debruijnTable [static]
```

Initial value:

```
= {
    0, 9, 1, 10, 13, 21, 2, 29, 11, 14, 16, 18, 22, 25, 3, 30,
    8, 12, 20, 28, 15, 17, 24, 7, 19, 27, 23, 6, 26, 5, 4, 31
}
```

6.24 DynamicHeap.Ignore Class Reference

[Ignore](#) this field when scanning for pointers.

Inherits Attribute.

6.24.1 Detailed Description

[Ignore](#) this field when scanning for pointers.

6.25 DynamicHeapInstance Class Reference

Dynamic heap instance.

Public Member Functions

- void * [Allocate](#) (int size)
Allocate a pointer.
- void * [AllocateArray](#)< T > (int length)
Allocate a pointer array.
- void * [AllocateArrayPointers](#)< T > (int length)
Allocate an array of pointers.
- void * [AllocateTracked](#)< T > (bool root=false)
Allocate a tracked pointer.
- void * [AllocateTrackedArray](#)< T > (int length, bool root=false)
Allocate a tracked pointer array.
- void * [AllocateTrackedArrayPointers](#)< T > (int length, bool root=false)
Allocate a tracked array of pointers.
- [DynamicHeapInstance](#) (params Type[] types)
Create a dynamic heap instance.
- void [Free](#) (void *ptr)
Free a pointer.

6.25.1 Detailed Description

Dynamic heap instance.

6.25.2 Constructor & Destructor Documentation

6.25.2.1 DynamicHeapInstance()

```
DynamicHeapInstance (
    params Type[] types )
```

Create a dynamic heap instance.

Parameters

<i>types</i>	Types to allocate.
--------------	--------------------

6.25.3 Member Function Documentation

6.25.3.1 Allocate()

```
void* Allocate (
    int size )
```

Allocate a pointer.

Parameters

<i>size</i>	Size to allocate.
-------------	-------------------

Returns

Pointer to allocated memory.

6.25.3.2 AllocateArray< T >()

```
void* AllocateArray< T > (
    int length )
```

Allocate a pointer array.

Parameters

<i>length</i>	Length of array.
---------------	------------------

Template Parameters

<i>T</i>	Type of array.
----------	----------------

Returns

Pointer to allocated memory.

Type Constraints

T : unmanaged

6.25.3.3 AllocateArrayPointers< T >()

```
void* AllocateArrayPointers< T > (
    int length )
```

Allocate an array of pointers.

Parameters

<i>length</i>	Length of array.
---------------	------------------

Template Parameters

<i>T</i>	Type of array.
----------	----------------

Returns

Pointer to allocated memory.

Type Constraints

T : unmanaged

6.25.3.4 AllocateTracked< T >()

```
void* AllocateTracked< T > (
    bool root = false )
```

Allocate a tracked pointer.

Parameters

<i>root</i>	Signal if the pointer is a root.
-------------	----------------------------------

Template Parameters

<i>T</i>	Type of pointer.
----------	------------------

Returns

Pointer to allocated memory.

Type Constraints

T : unmanaged

6.25.3.5 AllocateTrackedArray< T >()

```
void* AllocateTrackedArray< T > (
    int length,
    bool root = false )
```

Allocate a tracked pointer array.

Parameters

<i>length</i>	Length of array.
<i>root</i>	Signal if the pointer is a root.

Template Parameters

<i>T</i>	Type of array.
----------	----------------

Returns

Pointer to allocated memory.

Type Constraints

T : unmanaged

6.25.3.6 AllocateTrackedArrayPointers< T >()

```
void* AllocateTrackedArrayPointers< T > (
    int length,
    bool root = false )
```

Allocate a tracked array of pointers.

Parameters

<i>length</i>	Length of array.
<i>root</i>	Signal if the pointer is a root.

Template Parameters

<i>T</i>	Type of array.
----------	----------------

Returns

Pointer to allocated memory.

Type Constraints

T* : *unmanaged

6.25.3.7 Free()

```
void Free (
    void * ptr )
```

Free a pointer.

Parameters

<i>ptr</i>	Pointer to free.
------------	------------------

6.26 FieldsMask< T > Class Template Reference

Base class for [FieldsMask<T>](#).

Inherits FieldsMask.

Public Member Functions

- [FieldsMask](#) ()
Constructor for [FieldsMask<T>](#).
- **FieldsMask** (Func< Mask256 > getDefaultsDelegate)
- **FieldsMask** (long maskA, long maskB=0, long maskC=0, long maskD=0)
- [FieldsMask](#) (Mask256 mask)
Constructor for [FieldsMask<T>](#).

Static Public Member Functions

- static implicit [operator Mask256](#) ([FieldsMask](#) mask)
Implicitly convert [FieldsMask](#) to its long mask value.

Public Attributes

- Mask256 **Mask**

Protected Member Functions

- [FieldsMask](#) ()
Constructor for [FieldsMask](#).
- [FieldsMask](#) (long a, long b, long c, long d)
Constructor for [FieldsMask](#).
- [FieldsMask](#) (Mask256 mask)
Constructor for [FieldsMask](#).

6.26.1 Detailed Description

Base class for [FieldsMask<T>](#).

Associates and displays a 64 bit mask which represents the field members of a struct. Makes it possible to treat a Struct like an Flags Enum. NOTE: A [FieldsMask<T>](#) attribute is required for proper rendering in the Inspector.

6.26.2 Constructor & Destructor Documentation

6.26.2.1 FieldsMask() [1/5]

```
FieldsMask (
    Mask256 mask ) [protected]
```

Constructor for [FieldsMask](#).

6.26.2.2 FieldsMask() [2/5]

```
FieldsMask (
    long a,
    long b,
    long c,
    long d ) [protected]
```

Constructor for [FieldsMask](#).

6.26.2.3 FieldsMask() [3/5]

```
FieldsMask ( ) [protected]
```

Constructor for [FieldsMask](#).

6.26.2.4 FieldsMask() [4/5]

```
FieldsMask (
    Mask256 mask )
```

Constructor for [FieldsMask<T>](#).

6.26.2.5 FieldsMask() [5/5]

```
FieldsMask ( )
```

Constructor for [FieldsMask<T>](#).

6.26.3 Member Function Documentation

6.26.3.1 operator Mask256()

```
static implicit operator Mask256 (
    FieldsMask< T > mask ) [static]
```

Implicitly convert [FieldsMask](#) to its long mask value.

6.27 FixedArray< T > Class Template Reference

A fixed size array that can be used in structs.

Inherits [IEnumerable< T >](#).

Classes

- struct [Enumerator](#)
[Enumerator](#) for the [FixedArray](#) struct.

Public Member Functions

- void [Clear](#) ()
Sets all elements in the array to their default value.
- void [CopyFrom](#) (List< T > source, int sourceOffset, int sourceCount)
Copies a range of elements from a source list into the [FixedArray](#).
- void [CopyFrom](#) (T[] source, int sourceOffset, int sourceCount)
Copies a range of elements from a source array into the [FixedArray](#).
- void [CopyTo](#) (List< T > list)
Adds each value to the supplied List. This does not clear the list, so values will be appended to the existing list.
- void [CopyTo](#) (T[] array, bool throwIfOverflow=true)
Copies values to the supplied array.
- [FixedArray](#) (T *array, int length)
[NetworkArray](#) constructor.
- [Enumerator GetEnumerator](#) ()
Returns an enumerator that iterates through the [FixedArray](#).
- IEnumerator< T > IEnumerable< T >. **GetEnumerator** ()
- IEnumerator IEnumerable. **GetEnumerator** ()
- T[] [ToArray](#) ()
Allocates a new array and copies values from this array. For a non-alloc alternative use [CopyTo\(List<T>\)](#).
- string [ToListString](#) ()
Returns the elements of this array as a string, with value separated by characters. Specifically for use in the Unity inspector. This is private and only is found by NetworkBehaviourEditor using reflection, so do not rename this method.
- override string [ToString](#) ()
Returns a string that represents the current object.

Static Public Member Functions

- static unsafe [FixedArray](#)< T > [Create](#)< T > (ref T firstField, int length)
Creates a [FixedArray](#) with a specified length.
- static unsafe [FixedArray](#)< TAdapted > [Create](#)< TActual, TAdapted > (ref TActual firstField, int length)
Creates a [FixedArray](#) with a specified length and adapts the type of the elements.
- static unsafe [FixedArray](#)< T > [CreateFromFieldSequence](#)< T > (ref T firstField, ref T lastField)
Creates a [FixedArray](#) from a sequence of fields.
- static int [IndexOf](#)< T > (this [FixedArray](#)< T > array, T elem)
Returns the index of the first occurrence of a value in the [FixedArray](#).

Public Attributes

- T * [_array](#)
- int [_length](#)

Static Public Attributes

- static StringBuilder [_stringBuilderCached](#)

Properties

- int [Length](#) [get]
The fixed size of the array.
- ref T [this\[int index\]](#) [get]
Indexer of array elements.

6.27.1 Detailed Description

A fixed size array that can be used in structs.

Helper methods for [FixedArray](#).

Template Parameters

<i>T</i>	
----------	--

Type Constraints

T* : *unmanaged

6.27.2 Constructor & Destructor Documentation

6.27.2.1 FixedArray()

```
FixedArray (
    T * array,
    int length )
```

[NetworkArray](#) constructor.

6.27.3 Member Function Documentation

6.27.3.1 Clear()

```
void Clear ( )
```

Sets all elements in the array to their default value.

6.27.3.2 CopyFrom() [1/2]

```
void CopyFrom (
    List< T > source,
    int sourceOffset,
    int sourceCount )
```

Copies a range of elements from a source list into the [FixedArray](#).

Parameters

<i>source</i>	The source list from which to copy elements. Must not be null.
<i>sourceOffset</i>	The zero-based index in the source list at which copying begins.
<i>sourceCount</i>	The number of elements to copy from the source list.

Exceptions

<i>ArgumentNullException</i>	Thrown when the provided source list is null.
<i>ArgumentException</i>	Thrown when the number of elements to copy is greater than the length of the FixedArray .
<i>ArgumentOutOfRangeException</i>	Thrown when the sum of sourceOffset and sourceCount is greater than the length of the source list.

6.27.3.3 CopyFrom() [2/2]

```
void CopyFrom (
    T[] source,
    int sourceOffset,
    int sourceCount )
```

Copies a range of elements from a source array into the [FixedArray](#).

Parameters

<i>source</i>	The source array from which to copy elements. Must not be null.
<i>sourceOffset</i>	The zero-based index in the source array at which copying begins.
<i>sourceCount</i>	The number of elements to copy from the source array.

Exceptions

<i>ArgumentNullException</i>	Thrown when the provided source array is null.
<i>ArgumentException</i>	Thrown when the number of elements to copy is greater than the length of the FixedArray .
<i>ArgumentOutOfRangeException</i>	Thrown when the sum of sourceOffset and sourceCount is greater than the length of the source array.

6.27.3.4 CopyTo() [1/2]

```
void CopyTo (
    List< T > list )
```

Adds each value to the supplied List. This does not clear the list, so values will be appended to the existing list.

6.27.3.5 CopyTo() [2/2]

```
void CopyTo (
    T[] array,
    bool throwIfOverflow = true )
```

Copies values to the supplied array.

Parameters

<i>array</i>	The array to copy values to. Must not be null.
<i>throwIfOverflow</i>	If true, this method will throw an error if the supplied array is smaller than this NetworkArray<T>. If false, will only copy as many elements as the target array can hold.

6.27.3.6 Create< T >()

```
static unsafe FixedArray<T> Create< T > (
    ref T firstField,
    int length ) [static]
```

Creates a [FixedArray](#) with a specified length.

Parameters

<i>firstField</i>	Reference to the first field in the array.
<i>length</i>	The length of the array.

Returns

A new [FixedArray](#) instance with the specified length.

Type Constraints

T* : *unmanaged

6.27.3.7 Create< TActual, TAdapted >()

```
static unsafe FixedArray<TAdapted> Create< TActual, TAdapted > (
    ref TActual firstField,
    int length ) [static]
```

Creates a [FixedArray](#) with a specified length and adapts the type of the elements.

Parameters

<i>firstField</i>	Reference to the first field in the array.
<i>length</i>	The length of the array.

Returns

A new [FixedArray](#) instance with the specified length and adapted type of elements.

Type Constraints

TActual : unmanaged

TAdapted : unmanaged

6.27.3.8 CreateFromFieldSequence< T >()

```
static unsafe FixedArray<T> CreateFromFieldSequence< T > (
    ref T firstField,
    ref T lastField ) [static]
```

Creates a [FixedArray](#) from a sequence of fields.

Parameters

<i>firstField</i>	Reference to the first field in the sequence.
<i>lastField</i>	Reference to the last field in the sequence.

Returns

A new [FixedArray](#) instance with the values from the sequence of fields.

Type Constraints

T : unmanaged

6.27.3.9 GetEnumerator()

```
Enumerator GetEnumerator ( )
```

Returns an enumerator that iterates through the [FixedArray](#).

6.27.3.10 IndexOf< T >()

```
static int IndexOf< T > (
    this FixedArray< T > array,
    T elem ) [static]
```

Returns the index of the first occurrence of a value in the [FixedArray](#).

Parameters

<i>array</i>	The FixedArray to search.
<i>elem</i>	The value to locate in the FixedArray .

Returns

The zero-based index of the first occurrence of *elem* within the entire [FixedArray](#), if found; otherwise, -1.

Type Constraints

T* : *unmanaged

***T* : *IEquatable*<*T*>**

6.27.3.11 ToArray()

```
T [] ToArray ( )
```

Allocates a new array and copies values from this array. For a non-alloc alternative use [CopyTo\(List<T>\)](#).

6.27.3.12 ToListString()

```
string ToListString ( )
```

Returns the elements of this array as a string, with value separated by characters. Specifically for use in the Unity inspector. This is private and only is found by NetworkBehaviourEditor using reflection, so do not rename this method.

6.27.3.13 ToString()

```
override string ToString ( )
```

Returns a string that represents the current object.

6.27.4 Property Documentation

6.27.4.1 Length

```
int Length [get]
```

The fixed size of the array.

6.27.4.2 this[int index]

```
ref T this[int index] [get]
```

Indexer of array elements.

6.28 FixedArray< T >.Enumerator Struct Reference

[Enumerator](#) for the [FixedArray](#) struct.

Inherits [IEnumerator< T >](#).

Public Member Functions

- void [Dispose](#) ()
Performs application-defined tasks associated with freeing, releasing, or resetting unmanaged resources.
- [Enumerator](#) ([FixedArray](#)< T > array)
Initializes a new instance of the [Enumerator](#) struct.
- bool [MoveNext](#) ()
Advances the enumerator to the next element of the collection.
- void [Reset](#) ()
Sets the enumerator to its initial position, which is before the first element in the collection.

Public Attributes

- [FixedArray](#)< T > **_array**
- int **_index**

Properties

- T [Current](#) [get]
Gets the current element in the collection.
- object [IEnumerator](#). **Current** [get]

6.28.1 Detailed Description

[Enumerator](#) for the [FixedArray](#) struct.

6.28.2 Constructor & Destructor Documentation

6.28.2.1 Enumerator()

```
Enumerator (  
    FixedArray< T > array )
```

Initializes a new instance of the [Enumerator](#) struct.

Parameters

<i>array</i>	The FixedArray instance to enumerate.
--------------	---

6.28.3 Member Function Documentation

6.28.3.1 Dispose()

```
void Dispose ( )
```

Performs application-defined tasks associated with freeing, releasing, or resetting unmanaged resources.

6.28.3.2 MoveNext()

```
bool MoveNext ( )
```

Advances the enumerator to the next element of the collection.

Returns

True if the enumerator was successfully advanced to the next element; false if the enumerator has passed the end of the collection.

6.28.3.3 Reset()

```
void Reset ( )
```

Sets the enumerator to its initial position, which is before the first element in the collection.

6.28.4 Property Documentation

6.28.4.1 Current

```
T Current [get]
```

Gets the current element in the collection.

6.29 FixedBufferPropertyAttribute Class Reference

Fixed Buffer Property Attribute

Inherits PropertyAttribute.

Public Member Functions

- [FixedBufferPropertyAttribute](#) ([Type](#) fieldType, [Type](#) surrogateType, int capacity)
FixedBufferPropertyAttribute Constructor

Properties

- int [Capacity](#) [get]
Fixed Buffer Capacity
- [Type](#) [SurrogateType](#) [get]
Fixed Buffer Surrogate Type
- [Type](#) [Type](#) [get]
Fixed Buffer Type

6.29.1 Detailed Description

Fixed Buffer Property Attribute

6.29.2 Constructor & Destructor Documentation

6.29.2.1 FixedBufferPropertyAttribute()

```
FixedBufferPropertyAttribute (  
    Type fieldType,  
    Type surrogateType,  
    int capacity )
```

[FixedBufferPropertyAttribute](#) Constructor

Parameters

<i>fieldType</i>	Type
<i>surrogateType</i>	SurrogateType
<i>capacity</i>	Capacity

6.29.3 Property Documentation

6.29.3.1 Capacity

`int Capacity [get]`

Fixed Buffer Capacity

6.29.3.2 SurrogateType

`Type SurrogateType [get]`

Fixed Buffer Surrogate Type

6.29.3.3 Type

`Type Type [get]`

Fixed Buffer Type

6.30 FixedStorage Class Reference

Provides utility methods for fixed storage types.

Static Public Member Functions

- static int `GetWordCount< T > ()`
Gets the word count of a fixed storage type.

6.30.1 Detailed Description

Provides utility methods for fixed storage types.

6.30.2 Member Function Documentation

6.30.2.1 GetWordCount< T >()

`static int GetWordCount< T > ( ) [static]`

Gets the word count of a fixed storage type.

Template Parameters

<i>T</i>	The type of the fixed storage.
----------	--------------------------------

Returns

The word count of the fixed storage type.

Type Constraints

T : *unmanaged*

T : *IFixedStorage*

6.31 FloatCompressed Struct Reference

Represents a compressed float value for network transmission.

Inherits [INetworkStruct](#), and [IEquatable< FloatCompressed >](#).

Public Member Functions

- bool [Equals](#) ([FloatCompressed](#) other)
Checks if the current [FloatCompressed](#) instance is equal to the other [FloatCompressed](#) instance.
- override bool [Equals](#) (object obj)
Checks if the provided object is a [FloatCompressed](#) instance and if it's equal to the current [FloatCompressed](#) instance.
- override int [GetHashCode](#) ()
Returns the hash code for the current [FloatCompressed](#) instance.

Static Public Member Functions

- static implicit [operator float](#) ([FloatCompressed](#) q)
Implicit conversion from [FloatCompressed](#) to float.
- static implicit [operator FloatCompressed](#) (float v)
Implicit conversion from float to [FloatCompressed](#).
- static bool [operator!=](#) ([FloatCompressed](#) left, [FloatCompressed](#) right)
Inequality operator for [FloatCompressed](#) struct.
- static bool [operator==](#) ([FloatCompressed](#) left, [FloatCompressed](#) right)
Equality operator for [FloatCompressed](#) struct.

Public Attributes

- int [valueEncoded](#)
Encoded value of the float.

6.31.1 Detailed Description

Represents a compressed float value for network transmission.

6.31.2 Member Function Documentation

6.31.2.1 Equals() [1/2]

```
bool Equals (
    FloatCompressed other )
```

Checks if the current [FloatCompressed](#) instance is equal to the other [FloatCompressed](#) instance.

Parameters

<i>other</i>	The other FloatCompressed instance to compare with the current FloatCompressed instance.
--------------	--

Returns

True if the values of both [FloatCompressed](#) instances are equal, otherwise false.

6.31.2.2 Equals() [2/2]

```
override bool Equals (
    object obj )
```

Checks if the provided object is a [FloatCompressed](#) instance and if it's equal to the current [FloatCompressed](#) instance.

Parameters

<i>obj</i>	The object to compare with the current FloatCompressed instance.
------------	--

Returns

True if the provided object is a [FloatCompressed](#) instance and it's equal to the current [FloatCompressed](#) instance, otherwise false.

6.31.2.3 GetHashCode()

```
override int GetHashCode ( )
```

Returns the hash code for the current [FloatCompressed](#) instance.

Returns

A hash code for the current [FloatCompressed](#) instance.

6.31.2.4 operator float()

```
static implicit operator float (  
    FloatCompressed q ) [static]
```

Implicit conversion from [FloatCompressed](#) to float.

Parameters

<i>q</i>	The FloatCompressed instance to convert.
----------	--

Returns

The decompressed float value of the [FloatCompressed](#) instance.

6.31.2.5 operator FloatCompressed()

```
static implicit operator FloatCompressed (  
    float v ) [static]
```

Implicit conversion from float to [FloatCompressed](#).

Parameters

<i>v</i>	The float value to convert.
----------	-----------------------------

Returns

A new [FloatCompressed](#) instance with the compressed value of the float.

6.31.2.6 operator"!=()

```
static bool operator!= (  
    FloatCompressed left,  
    FloatCompressed right ) [static]
```

Inequality operator for [FloatCompressed](#) struct.

Parameters

<i>left</i>	First FloatCompressed instance.
<i>right</i>	Second FloatCompressed instance.

Returns

True if the value of the first [FloatCompressed](#) instance is not equal to the value of the second [FloatCompressed](#) instance, otherwise false.

6.31.2.7 operator==()

```
static bool operator== (
    FloatCompressed left,
    FloatCompressed right ) [static]
```

Equality operator for [FloatCompressed](#) struct.

Parameters

<i>left</i>	First FloatCompressed instance.
<i>right</i>	Second FloatCompressed instance.

Returns

True if the value of the first [FloatCompressed](#) instance is equal to the value of the second [FloatCompressed](#) instance, otherwise false.

6.31.3 Member Data Documentation

6.31.3.1 valueEncoded

```
int valueEncoded
```

Encoded value of the float.

6.32 FloatUtils Class Reference

Provides utility methods for compressing and decompressing float values.

Static Public Member Functions

- static unsafe int [Compress](#) (float f, int accuracy=[DEFAULT_ACCURACY](#))
Compresses a float value.
- static unsafe float [Decompress](#) (int value, float accuracy=[DEFAULT_ACCURACY](#))
Decompresses a compressed float value.

Static Public Attributes

- const int `DEFAULT_ACCURACY` = 1 << 10
Default accuracy for float compression and decompression.

6.32.1 Detailed Description

Provides utility methods for compressing and decompressing float values.

6.32.2 Member Function Documentation

6.32.2.1 Compress()

```
static unsafe int Compress (  
    float f,  
    int accuracy = DEFAULT_ACCURACY ) [static]
```

Compresses a float value.

Parameters

<i>f</i>	The float value to compress.
<i>accuracy</i>	The accuracy to use for compression. Defaults to <code>DEFAULT_ACCURACY</code> .

Returns

The compressed float value.

6.32.2.2 Decompress()

```
static unsafe float Decompress (  
    int value,  
    float accuracy = DEFAULT_ACCURACY ) [static]
```

Decompresses a compressed float value.

Parameters

<i>value</i>	The compressed float value to decompress.
<i>accuracy</i>	The accuracy to use for decompression. Defaults to <code>DEFAULT_ACCURACY</code> .

Returns

The decompressed float value.

6.32.3 Member Data Documentation

6.32.3.1 DEFAULT_ACCURACY

```
const int DEFAULT_ACCURACY = 1 << 10 [static]
```

Default accuracy for float compression and decompression.

6.33 HeapConfiguration Class Reference

Memory Heap Settings

Public Member Functions

- [HeapConfiguration Init](#) (int globalsSize)
Initializes and creates a new [HeapConfiguration](#) based on the Global Size
- override string [ToString](#) ()
ToString

Public Attributes

- int [GlobalsSize](#)
Heap Global Size
- int [PageCount](#) = [Allocator.Config.DEFAULT_BLOCK_COUNT](#)
Default number of Heap Pages
- [PageSizes](#) [PageShift](#) = [Allocator.Config.DEFAULT_BLOCK_SHIFT](#)
Default size of each Heap Page

6.33.1 Detailed Description

Memory Heap Settings

6.33.2 Member Function Documentation

6.33.2.1 Init()

```
HeapConfiguration Init (
    int globalsSize )
```

Initializes and creates a new [HeapConfiguration](#) based on the Global Size

6.33.2.2 ToString()

```
override string ToString ( )
```

ToString

6.33.3 Member Data Documentation

6.33.3.1 GlobalsSize

```
int GlobalsSize
```

Heap Global Size

6.33.3.2 PageCount

```
int PageCount = Allocator.Config.DEFAULT_BLOCK_COUNT
```

Default number of Heap Pages

6.33.3.3 PageShift

```
PageSizes PageShift = Allocator.Config.DEFAULT_BLOCK_SHIFT
```

Default size of each Heap Page

6.34 Hitbox Class Reference

Represents a single lag-compensated collider. Multiple component instances can be added anywhere in the hierarchy of a [NetworkObject](#) which includes a [HitboxRoot](#).

Inherits [Behaviour](#).

Public Member Functions

- void [OnDrawGizmos](#) ()
Draws this hitbox gizmo on Unity editor.

Public Attributes

- Vector3 [BoxExtents](#)
When [Type](#) is set to [HitboxTypes.Box](#), this defines the local-space geometry for narrow-phase checks.
- float [CapsuleHeight](#)
When [Type](#) is set to [HitboxTypes.Capsule](#), this defines the local-space geometry for narrow-phase checks.
- float [CapsuleRadius](#)
When [Type](#) is set to [HitboxTypes.Capsule](#), this defines the local-space geometry for narrow-phase checks.
- Color [GizmosColor](#) = Color.yellow
Color used when drawing gizmos for this hitbox.
- Vector3 [Offset](#)
This [Hitbox](#)'s local-space offset from its [GameObject](#) position.
- [HitboxRoot](#) [Root](#)
Reference to the top-level [HitboxRoot](#) component for this [NetworkObject](#).
- float [SphereRadius](#)
When [Type](#) is set to [HitboxTypes.Sphere](#), this defines the local-space geometry for narrow-phase checks.
- [HitboxTypes](#) [Type](#)
The collision geometry type for this [Hitbox](#).

Protected Member Functions

- virtual void [DrawGizmos](#) (Color color, ref Matrix4x4 localToWorldMatrix)
Draw the [Hitbox](#) gizmos.

Properties

- int [ColliderIndex](#) [get]
Index assigned to the collider of this hitbox on the lag-compensated snapshots.
- bool [HitboxActive](#) [get, set]
Get or set the state of this [Hitbox](#). If a hitbox or its [HitboxRoot](#) are not active, it will not be hit by lag-compensated queries.
- Int32 [HitboxIndex](#) [get]
The index of this hitbox in the [HitboxRoot.Hitboxes](#) array on [Root](#). The value is set by the root when initializing the nested hitboxes with [HitboxRoot.InitHitboxes](#).
- Vector3 [Position](#) [get]
World-space position (includes [Offset](#)) of this [Hitbox](#).

Additional Inherited Members

6.34.1 Detailed Description

Represents a single lag-compensated collider. Multiple component instances can be added anywhere in the hierarchy of a [NetworkObject](#) which includes a [HitboxRoot](#).

6.34.2 Member Function Documentation

6.34.2.1 DrawGizmos()

```
virtual void DrawGizmos (
    Color color,
    ref Matrix4x4 localToWorldMatrix ) [protected], [virtual]
```

Draw the [Hitbox](#) gizmos.

6.34.2.2 OnDrawGizmos()

```
void OnDrawGizmos ( )
```

Draws this hitbox gizmo on Unity editor.

6.34.3 Member Data Documentation

6.34.3.1 BoxExtents

```
Vector3 BoxExtents
```

When [Type](#) is set to [HitboxTypes.Box](#), this defines the local-space geometry for narrow-phase checks.

6.34.3.2 CapsuleHeight

```
float CapsuleHeight
```

When [Type](#) is set to [HitboxTypes.Capsule](#), this defines the local-space geometry for narrow-phase checks.

6.34.3.3 CapsuleRadius

```
float CapsuleRadius
```

When [Type](#) is set to [HitboxTypes.Capsule](#), this defines the local-space geometry for narrow-phase checks.

6.34.3.4 GizmosColor

```
Color GizmosColor = Color.yellow
```

Color used when drawing gizmos for this hitbox.

6.34.3.5 Offset

```
Vector3 Offset
```

This [Hitbox](#)'s local-space offset from its `GameObject` position.

6.34.3.6 Root

```
HitboxRoot Root
```

Reference to the top-level [HitboxRoot](#) component for this [NetworkObject](#).

6.34.3.7 SphereRadius

```
float SphereRadius
```

When [Type](#) is set to [HitboxTypes.Sphere](#), this defines the local-space geometry for narrow-phase checks.

6.34.3.8 Type

```
HitboxTypes Type
```

The collision geometry type for this [Hitbox](#).

6.34.4 Property Documentation

6.34.4.1 ColliderIndex

```
int ColliderIndex [get]
```

Index assigned to the collider of this hitbox on the lag-compensated snapshots.

6.34.4.2 HitboxActive

```
bool HitboxActive [get], [set]
```

Get or set the state of this [Hitbox](#). If a hitbox or its [HitboxRoot](#) are not active, it will not be hit by lag-compensated queries.

6.34.4.3 HitboxIndex

```
Int32 HitboxIndex [get]
```

The index of this hitbox in the [HitboxRoot.Hitboxes](#) array on [Root](#). The value is set by the root when initializing the nested hitboxes with [HitboxRoot.InitHitboxes](#).

6.34.4.4 Position

```
Vector3 Position [get]
```

World-space position (includes Offset) of this [Hitbox](#).

6.35 HitboxManager Class Reference

Entry point for lag compensated [Hitbox](#) queries, which maintains a history buffer, and provides lag compensated raycast and overlap methods. Singleton instance is accessible through the property [Runner.LagCompensation](#).

Inherits [SimulationBehaviour](#), [IBeforeAllTicks](#), [IAfterTick](#), and [IAfterUpdate](#).

Public Member Functions

- void [AfterTick](#) ()
- void [AfterUpdate](#) ()
- void [BeforeAllTicks](#) (bool resimulation, int tickCount)
- int [OverlapBox](#) ([BoxOverlapQuery](#) query, List< [LagCompensatedHit](#) > hits, bool clearHits=true)

Performs a lag-compensated box overlap query against all registered hitboxes. If the [HitOptions.IncludePhysX](#) or [HitOptions.IncludeBox2D](#) flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes.
- int [OverlapBox](#) (Vector3 center, Vector3 extents, Quaternion orientation, int tick, int? tickTo, float? alpha, List< [LagCompensatedHit](#) > hits, int layerMask=-1, [HitOptions](#) options=[HitOptions.None](#), bool clearHits=true, QueryTriggerInteraction queryTriggerInteraction=QueryTriggerInteraction.UseGlobal, PreProcessingDelegate preProcessRoots=null)

Performs a lag-compensated box overlap query against all registered hitboxes. If the [HitOptions.IncludePhysX](#) or [HitOptions.IncludeBox2D](#) flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes.

- `int OverlapBox` (`Vector3` center, `Vector3` extents, `Quaternion` orientation, `PlayerRef` player, `List< LagCompensatedHit >` hits, `int` layerMask=-1, `HitOptions` options=`HitOptions.None`, `bool` clearHits=true, `QueryTriggerInteraction` queryTriggerInteraction=`QueryTriggerInteraction.UseGlobal`, `PreProcessingDelegate` preProcessRoots=null)

Performs a lag-compensated box overlap query against all registered hitboxes. If the `HitOptions.IncludePhysX` or `HitOptions.IncludeBox2D` flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes.
- `int OverlapSphere` (`SphereOverlapQuery` query, `List< LagCompensatedHit >` hits, `bool` clearHits=true)

Performs a lag-compensated sphere overlap query against all registered hitboxes. If the `HitOptions.IncludePhysX` or `HitOptions.IncludeBox2D` flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes.
- `int OverlapSphere` (`Vector3` origin, `float` radius, `int` tick, `int?` tickTo, `float?` alpha, `List< LagCompensatedHit >` hits, `int` layerMask=-1, `HitOptions` options=`HitOptions.None`, `bool` clearHits=true, `QueryTriggerInteraction` queryTriggerInteraction=`QueryTriggerInteraction.UseGlobal`, `PreProcessingDelegate` preProcessRoots=null)

Performs a lag-compensated overlap sphere query against all registered hitboxes. If the `HitOptions.IncludePhysX` or `HitOptions.IncludeBox2D` flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes.
- `int OverlapSphere` (`Vector3` origin, `float` radius, `PlayerRef` player, `List< LagCompensatedHit >` hits, `int` layerMask=-1, `HitOptions` options=`HitOptions.None`, `bool` clearHits=true, `QueryTriggerInteraction` queryTriggerInteraction=`QueryTriggerInteraction.UseGlobal`, `PreProcessingDelegate` preProcessRoots=null)

Performs a lag-compensated overlap sphere query against all registered hitboxes. If the `HitOptions.IncludePhysX` or `HitOptions.IncludeBox2D` flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes.
- `void PositionRotation` (`Hitbox` hitbox, `int` tick, `out Vector3` position, `out Quaternion` rotation, `bool` subtickAccuracy=false, `int?` tickTo=null, `float?` alpha=null)

Performs a lag-compensated query for a specific Hitbox position and rotation.
- `void PositionRotation` (`Hitbox` hitbox, `PlayerRef` player, `out Vector3` position, `out Quaternion` rotation, `bool` subTickAccuracy=false)

Performs a lag-compensated query for a specific Hitbox position and rotation.
- `bool Raycast` (`RaycastQuery` query, `out LagCompensatedHit` hit)

Performs a lag-compensated raycast query against all registered hitboxes. If the `HitOptions.IncludePhysX` or `HitOptions.IncludeBox2D` flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes.
- `bool Raycast` (`Vector3` origin, `Vector3` direction, `float` length, `int` tick, `int?` tickTo, `float?` alpha, `out LagCompensatedHit` hit, `int` layerMask=-1, `HitOptions` options=`HitOptions.None`, `QueryTriggerInteraction` queryTriggerInteraction=`QueryTriggerInteraction.UseGlobal`, `PreProcessingDelegate` preProcessRoots=null)

Performs a lag-compensated raycast query against all registered hitboxes. If the `HitOptions.IncludePhysX` or `HitOptions.IncludeBox2D` flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes.
- `bool Raycast` (`Vector3` origin, `Vector3` direction, `float` length, `PlayerRef` player, `out LagCompensatedHit` hit, `int` layerMask=-1, `HitOptions` options=`HitOptions.None`, `QueryTriggerInteraction` queryTriggerInteraction=`QueryTriggerInteraction.UseGlobal`, `PreProcessingDelegate` preProcessRoots=null)

Performs a lag-compensated raycast query against all registered hitboxes. If the `HitOptions.IncludePhysX` or `HitOptions.IncludeBox2D` flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes.
- `int RaycastAll` (`RaycastAllQuery` query, `List< LagCompensatedHit >` hits, `bool` clearHits=true)

Performs a lag-compensated raycast query against all registered hitboxes. If the `HitOptions.IncludePhysX` or `HitOptions.IncludeBox2D` flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes.
- `int RaycastAll` (`Vector3` origin, `Vector3` direction, `float` length, `int` tick, `int?` tickTo, `float?` alpha, `List< LagCompensatedHit >` hits, `int` layerMask=-1, `bool` clearHits=true, `HitOptions` options=`HitOptions.None`, `QueryTriggerInteraction` queryTriggerInteraction=`QueryTriggerInteraction.UseGlobal`, `PreProcessingDelegate` preProcessRoots=null)

Performs a lag-compensated raycast query against all registered hitboxes. If the `HitOptions.IncludePhysX` or `HitOptions.IncludeBox2D` flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes. Important: results are NOT sorted by distance.

- int [RaycastAll](#) (Vector3 origin, Vector3 direction, float length, [PlayerRef](#) player, List< [LagCompensatedHit](#) > hits, int layerMask=-1, bool clearHits=true, [HitOptions](#) options=[HitOptions.None](#), QueryTriggerInteraction=queryTriggerInteraction=QueryTriggerInteraction.UseGlobal, PreProcessingDelegate preProcessRoots=null)
Performs a lag-compensated raycast query against all registered hitboxes. If the [HitOptions.IncludePhysX](#) or [HitOptions.IncludeBox2D](#) flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes. Important: results are NOT sorted by distance.
- void [WriteBenchmarkResults](#) ()
Used internally to write the benchmark results.

Public Attributes

- int [BVHDepth](#)
Debug data from Broadphase BVH (tree depth).
- int [BVHNodes](#)
Debug data from Broadphase BVH (total nodes count).
- [LagCompensationDraw DrawInfo](#)
Debug data used to draw the BVH nodes and the lag compensation history.
- int [TotalHitboxes](#)
Debug data from lag compensation history (registered [Hitbox](#) count).

Additional Inherited Members

6.35.1 Detailed Description

Entry point for lag compensated [Hitbox](#) queries, which maintains a history buffer, and provides lag compensated raycast and overlap methods. Singleton instance is accessible through the property `Runner.LagCompensation`.

Usage - Call any of the following methods:

```
HitboxManager.Raycast()
HitboxManager.RaycastAll()
HitboxManager.PositionRotation()
HitboxManager.OverlapSphere()
```

These methods use the history buffer to perform a [Hitbox](#) query against a state consistent with how the indicated [PlayerRef](#) perceived them locally.

6.35.2 Member Function Documentation

6.35.2.1 AfterTick()

```
void AfterTick ( )
```

Called after each tick simulation completes. Register new hitboxes and updates existing ones on the Server.

Implements [IAfterTick](#).

6.35.2.2 AfterUpdate()

```
void AfterUpdate ( )
```

Called at the end of the [Fusion](#) Update loop, before all Unity MonoBehaviour.Update() callbacks. Resets the registered flag.

Implements [IAfterUpdate](#).

6.35.2.3 BeforeAllTicks()

```
void BeforeAllTicks (
    bool resimulation,
    int tickCount )
```

Called before the re-simulation loop (when applicable), and also before the forward simulation loop. Only called on Updates where re-simulation or forward ticks are processed. Register new hitboxes and updates existing ones on the client.

Implements [IBeforeAllTicks](#).

6.35.2.4 OverlapBox() [1/3]

```
int OverlapBox (
    BoxOverlapQuery query,
    List< LagCompensatedHit > hits,
    bool clearHits = true )
```

Performs a lag-compensated box overlap query against all registered hitboxes. If the [HitOptions.IncludePhysX](#) or [HitOptions.IncludeBox2D](#) flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes.

Parameters

<i>query</i>	The query containing all necessary information.
<i>hits</i>	List to be filled with hits (both hitboxes and/or static colliders, if included).
<i>clearHits</i>	Clear list of hits before filling with new ones (defaults to true).

Returns

The total number of hits found.

6.35.2.5 OverlapBox() [2/3]

```
int OverlapBox (
    Vector3 center,
```

```

Vector3 extents,
Quaternion orientation,
int tick,
int? tickTo,
float? alpha,
List< LagCompensatedHit > hits,
int layerMask = -1,
HitOptions options = HitOptions.None,
bool clearHits = true,
QueryTriggerInteraction queryTriggerInteraction = QueryTriggerInteraction.UseGlobal,
PreProcessingDelegate preProcessRoots = null )

```

Performs a lag-compensated box overlap query against all registered hitboxes. If the [HitOptions.IncludePhysX](#) or [HitOptions.IncludeBox2D](#) flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes.

Parameters

<i>center</i>	Center of the box in world space.
<i>extents</i>	Half of the size of the box in each dimension.
<i>orientation</i>	Rotation of the box.
<i>tick</i>	The exact tick to be queried
<i>tickTo</i>	Simulation tick number to use as the time reference for the lag compensation. If provided, must be combined with the <i>alpha</i> parameter for interpolation between <i>tick</i> and <i>tickTo</i> . If HitOptions.SubtickAccuracy is included on <i>options</i> , this query will be resolved against hitbox colliders interpolated between the specified ticks. Otherwise, only one of the two ticks will be considered, according to the rounded value of <i>alpha</i> .
<i>alpha</i>	Interpolation value when querying between <i>tick</i> and <i>tickTo</i> . If HitOptions.SubtickAccuracy is included on <i>options</i> , this query will be resolved against hitbox colliders interpolated between the specified ticks. Otherwise, only one of the two ticks will be considered, according to the rounded alpha value.
<i>hits</i>	List to be filled with hits (both hitboxes and/or static colliders, if included).
<i>layerMask</i>	Only objects with matching layers will be checked against.
<i>options</i>	Opt-in flags to compute with sub-tick accuracy (HitOptions.SubtickAccuracy) and/or to include PhysX (HitOptions.IncludePhysX) or Box2D (HitOptions.IncludeBox2D).
<i>clearHits</i>	Clear list of hits before filling with new ones (defaults to true).
<i>queryTriggerInteraction</i>	Trigger interaction behavior when also querying PhysX.
<i>preProcessRoots</i>	Delegate to pre-process HitboxRoots found in the broad-phase resolution of the query. Roots removed from the list will not be processed any further. Roots that remain on the candidates collection will be normally processed and fitting colliders will be evaluated in the query narrow-phase resolution. Hitbox collider indices added to the processed set will be evaluated in the narrow-phase regardless of further root processing steps (e.g. layer mask match).

Returns

The total number of hits found.

6.35.2.6 OverlapBox() [3/3]

```

int OverlapBox (
    Vector3 center,

```



```

Vector3 extents,
Quaternion orientation,
PlayerRef player,
List< LagCompensatedHit > hits,
int layerMask = -1,
HitOptions options = HitOptions.None,
bool clearHits = true,
QueryTriggerInteraction queryTriggerInteraction = QueryTriggerInteraction.UseGlobal,
PreProcessingDelegate preProcessRoots = null )

```

Performs a lag-compensated box overlap query against all registered hitboxes. If the [HitOptions.IncludePhysX](#) or [HitOptions.IncludeBox2D](#) flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes.

Parameters

<i>center</i>	Center of the box in world space.
<i>extents</i>	Half of the size of the box in each dimension.
<i>orientation</i>	Rotation of the box.
<i>player</i>	Player who "owns" this overlap. Used by the server to find the exact hitbox snapshots to check against.
<i>hits</i>	List to be filled with hits (both hitboxes and/or static colliders, if included).
<i>layerMask</i>	Only objects with matching layers will be checked against.
<i>options</i>	Opt-in flags to compute with sub-tick accuracy (HitOptions.SubtickAccuracy) and/or to include PhysX (HitOptions.IncludePhysX) or Box2D (HitOptions.IncludeBox2D).
<i>clearHits</i>	Clear list of hits before filling with new ones (defaults to true).
<i>queryTriggerInteraction</i>	Trigger interaction behavior when also querying PhysX.
<i>preProcessRoots</i>	Delegate to pre-process HitboxRoots found in the broad-phase resolution of the query. Roots removed from the list will not be processed any further. Roots that remain on the candidates collection will be normally processed and fitting colliders will be evaluated in the query narrow-phase resolution. Hitbox collider indices added to the processed set will be evaluated in the narrow-phase regardless of further root processing steps (e.g. layer mask match).

Returns

The total number of hits found.

6.35.2.7 OverlapSphere() [1/3]

```

int OverlapSphere (
    SphereOverlapQuery query,
    List< LagCompensatedHit > hits,
    bool clearHits = true )

```

Performs a lag-compensated sphere overlap query against all registered hitboxes. If the [HitOptions.IncludePhysX](#) or [HitOptions.IncludeBox2D](#) flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes.

Parameters

<i>query</i>	The query containing all necessary information.
<i>hits</i>	List to be filled with hits (both hitboxes and/or static colliders, if included).
<i>clearHits</i>	Clear list of hits before filling with new ones (defaults to true).

Returns

The total number of hits found.

6.35.2.8 **OverlapSphere()** [2/3]

```
int OverlapSphere (
    Vector3 origin,
    float radius,
    int tick,
    int? tickTo,
    float? alpha,
    List< LagCompensatedHit > hits,
    int layerMask = -1,
    HitOptions options = HitOptions.None,
    bool clearHits = true,
    QueryTriggerInteraction queryTriggerInteraction = QueryTriggerInteraction.UseGlobal,
    PreProcessingDelegate preProcessRoots = null )
```

Performs a lag-compensated overlap sphere query against all registered hitboxes. If the [HitOptions.IncludePhysX](#) or [HitOptions.IncludeBox2D](#) flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes.

Parameters

<i>origin</i>	Sphere center, in world-space
<i>radius</i>	Sphere radius
<i>tick</i>	The tick to be queried
<i>tickTo</i>	Simulation tick number to use as the time reference for the lag compensation. If provided, must be combined with the <i>alpha</i> parameter for interpolation between <i>tick</i> and <i>tickTo</i> . If HitOptions.SubtickAccuracy is included on <i>options</i> , this query will be resolved against hitbox colliders interpolated between the specified ticks. Otherwise, only one of the two ticks will be considered, according to the rounded value of <i>alpha</i> .
<i>alpha</i>	Interpolation value when querying between <i>tick</i> and <i>tickTo</i> . If HitOptions.SubtickAccuracy is included on <i>options</i> , this query will be resolved against hitbox colliders interpolated between the specified ticks. Otherwise, only one of the two ticks will be considered, according to the rounded alpha value.
<i>hits</i>	List to be filled with hits (both hitboxes and/or static colliders, if included).
<i>layerMask</i>	Only objects with matching layers will be checked against.
<i>options</i>	Opt-in flags to compute with sub-tick accuracy (HitOptions.SubtickAccuracy) and/or to include PhysX (HitOptions.IncludePhysX) or Box2D (HitOptions.IncludeBox2D).
<i>clearHits</i>	Clear list of hits before filling with new ones (defaults to true).
<i>queryTriggerInteraction</i>	Trigger interaction behavior when also querying PhysX.

Parameters

<i>preProcessRoots</i>	Delegate to pre-process HitboxRoots found in the broad-phase resolution of the query. Roots removed from the list will not be processed any further. Roots that remain on the candidates collection will be normally processed and fitting colliders will be evaluated in the query narrow-phase resolution. Hitbox collider indices added to the processed set will be evaluated in the narrow-phase regardless of further root processing steps (e.g. layer mask match).
------------------------	--

Returns

total number of hits

6.35.2.9 OverlapSphere() [3/3]

```
int OverlapSphere (
    Vector3 origin,
    float radius,
    PlayerRef player,
    List< LagCompensatedHit > hits,
    int layerMask = -1,
    HitOptions options = HitOptions.None,
    bool clearHits = true,
    QueryTriggerInteraction queryTriggerInteraction = QueryTriggerInteraction.UseGlobal,
    PreProcessingDelegate preProcessRoots = null )
```

Performs a lag-compensated overlap sphere query against all registered hitboxes. If the [HitOptions.IncludePhysX](#) or [HitOptions.IncludeBox2D](#) flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes.

Parameters

<i>origin</i>	Sphere center, in world-space
<i>radius</i>	Sphere radius
<i>player</i>	Player who "owns" this overlap. Used by the server to find the exact hitbox snapshots to check against.
<i>hits</i>	List to be filled with hits (both hitboxes and/or static colliders, if included).
<i>layerMask</i>	Only objects with matching layers will be checked against.
<i>options</i>	Opt-in flags to compute with sub-tick accuracy (HitOptions.SubtickAccuracy) and/or to include PhysX (HitOptions.IncludePhysX) or Box2D (HitOptions.IncludeBox2D).
<i>clearHits</i>	Clear list of hits before filling with new ones (defaults to true).
<i>queryTriggerInteraction</i>	Trigger interaction behavior when also querying PhysX.
<i>preProcessRoots</i>	Delegate to pre-process HitboxRoots found in the broad-phase resolution of the query. Roots removed from the list will not be processed any further. Roots that remain on the candidates collection will be normally processed and fitting colliders will be evaluated in the query narrow-phase resolution. Hitbox collider indices added to the processed set will be evaluated in the narrow-phase regardless of further root processing steps (e.g. layer mask match).

Returns

total number of hits

6.35.2.10 PositionRotation() [1/2]

```
void PositionRotation (
    Hitbox hitbox,
    int tick,
    out Vector3 position,
    out Quaternion rotation,
    bool subtickAccuracy = false,
    int? tickTo = null,
    float? alpha = null )
```

Performs a lag-compensated query for a specific [Hitbox](#) position and rotation.

Parameters

<i>hitbox</i>	The target hitbox to be queried in the past
<i>tick</i>	The tick to be queried
<i>tickTo</i>	Simulation tick number to use as the time reference for the lag compensation. If provided, must be combined with the <i>alpha</i> parameter for interpolation between <i>tick</i> and <i>tickTo</i> . If <i>subtickAccuracy</i> is requested, the query will return the hitbox state interpolated between the specified ticks. Otherwise, only one of the two ticks will be considered, according to the rounded value of <i>alpha</i> .
<i>alpha</i>	Interpolation value when querying between <i>tick</i> and <i>tickTo</i> . If <i>subtickAccuracy</i> is requested, the query will return the hitbox state interpolated between the specified ticks. Otherwise, only one of the two ticks will be considered, according to the rounded alpha value.
<i>position</i>	Will be filled with the hitbox position at the time of the tick
<i>rotation</i>	Will be filled with the hitbox rotation at the time of the tick
<i>subtickAccuracy</i>	If the query should interpolate between ticks to reflect exactly what was seen on the client.

6.35.2.11 PositionRotation() [2/2]

```
void PositionRotation (
    Hitbox hitbox,
    PlayerRef player,
    out Vector3 position,
    out Quaternion rotation,
    bool subTickAccuracy = false )
```

Performs a lag-compensated query for a specific [Hitbox](#) position and rotation.

Parameters

<i>hitbox</i>	The target hitbox to be queried in the past
---------------	---

Parameters

<i>player</i>	Player who "owns" this overlap. Used by the server to find the exact hitbox snapshots to check against.
<i>position</i>	Will be filled with the hitbox position at the time of the tick
<i>rotation</i>	Will be filled with the hitbox rotation at the time of the tick
<i>subTickAccuracy</i>	If the query should interpolate between ticks to reflect exactly what was seen on the client.

6.35.2.12 Raycast() [1/3]

```
bool Raycast (
    RaycastQuery query,
    out LagCompensatedHit hit )
```

Performs a lag-compensated raycast query against all registered hitboxes. If the [HitOptions.IncludePhysX](#) or [HitOptions.IncludeBox2D](#) flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes.

Parameters

<i>query</i>	The query containing all necessary information.
<i>hit</i>	Raycast results will be filled in here.

Returns

The total number of hits found.

6.35.2.13 Raycast() [2/3]

```
bool Raycast (
    Vector3 origin,
    Vector3 direction,
    float length,
    int tick,
    int? tickTo,
    float? alpha,
    out LagCompensatedHit hit,
    int layerMask = -1,
    HitOptions options = HitOptions.None,
    QueryTriggerInteraction queryTriggerInteraction = QueryTriggerInteraction.UseGlobal,
    PreProcessingDelegate preProcessRoots = null )
```

Performs a lag-compensated raycast query against all registered hitboxes. If the [HitOptions.IncludePhysX](#) or [HitOptions.IncludeBox2D](#) flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes.

Parameters

<i>origin</i>	Raycast origin, in world-space
<i>direction</i>	Raycast direction, in world-space
<i>length</i>	Raycast length
<i>tick</i>	Simulation tick number to use as the time reference for the lag compensation (use this for server AI, and similar).
<i>tickTo</i>	Simulation tick number to use as the time reference for the lag compensation. If provided, must be combined with the <i>alpha</i> parameter for interpolation between <i>tick</i> and <i>tickTo</i> . If HitOptions.SubtickAccuracy is included on <i>options</i> , this query will be resolved against hitbox colliders interpolated between the specified ticks. Otherwise, only one of the two ticks will be considered, according to the rounded value of <i>alpha</i> .
<i>alpha</i>	Interpolation value when querying between <i>tick</i> and <i>tickTo</i> . If HitOptions.SubtickAccuracy is included on <i>options</i> , this query will be resolved against hitbox colliders interpolated between the specified ticks. Otherwise, only one of the two ticks will be considered, according to the rounded alpha value.
<i>hit</i>	Raycast results will be filled in here.
<i>layerMask</i>	Only objects with matching layers will be checked against.
<i>options</i>	Opt-in flags to compute with sub-tick accuracy (HitOptions.SubtickAccuracy) and/or to include PhysX (HitOptions.IncludePhysX) or Box2D (HitOptions.IncludeBox2D).
<i>queryTriggerInteraction</i>	Trigger interaction behavior when also querying PhysX.
<i>preProcessRoots</i>	Delegate to pre-process HitboxRoots found in the broad-phase resolution of the query. Roots removed from the list will not be processed any further. Roots that remain on the candidates collection will be normally processed and fitting colliders will be evaluated in the query narrow-phase resolution. Hitbox collider indices added to the processed set will be evaluated in the narrow-phase regardless of further root processing steps (e.g. layer mask match).

Returns

True if something is hit

6.35.2.14 Raycast() [3/3]

```
bool Raycast (
    Vector3 origin,
    Vector3 direction,
    float length,
    PlayerRef player,
    out LagCompensatedHit hit,
    int layerMask = -1,
    HitOptions options = HitOptions.None,
    QueryTriggerInteraction queryTriggerInteraction = QueryTriggerInteraction.UseGlobal,
    PreProcessingDelegate preProcessRoots = null )
```

Performs a lag-compensated raycast query against all registered hitboxes. If the [HitOptions.IncludePhysX](#) or [HitOptions.IncludeBox2D](#) flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes.

Parameters

<i>origin</i>	Raycast origin, in world-space
<i>direction</i>	Raycast direction, in world-space
<i>length</i>	Raycast length
<i>player</i>	Player who "owns" this raycast. Used by the server to find the exact hitbox snapshots to check against.
<i>hit</i>	Raycast results will be filled in here.
<i>layerMask</i>	Only objects with matching layers will be checked against.
<i>options</i>	Opt-in flags to compute with sub-tick accuracy (HitOptions.SubtickAccuracy) and/or to include PhysX (HitOptions.IncludePhysX) or Box2D (HitOptions.IncludeBox2D).
<i>queryTriggerInteraction</i>	Trigger interaction behavior when also querying PhysX.
<i>preProcessRoots</i>	Delegate to pre-process HitboxRoots found in the broad-phase resolution of the query. Roots removed from the list will not be processed any further. Roots that remain on the candidates collection will be normally processed and fitting colliders will be evaluated in the query narrow-phase resolution. Hitbox collider indices added to the processed set will be evaluated in the narrow-phase regardless of further root processing steps (e.g. layer mask match).

Returns

True if something is hit

6.35.2.15 RaycastAll() [1/3]

```
int RaycastAll (
    RaycastAllQuery query,
    List< LagCompensatedHit > hits,
    bool clearHits = true )
```

Performs a lag-compensated raycast query against all registered hitboxes. If the [HitOptions.IncludePhysX](#) or [HitOptions.IncludeBox2D](#) flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes.

Parameters

<i>query</i>	The query containing all necessary information.
<i>hits</i>	List to be filled with hits (both hitboxes and/or static colliders, if included).
<i>clearHits</i>	Clear list of hits before filling with new ones (defaults to true).

Returns

The total number of hits found.

6.35.2.16 RaycastAll() [2/3]

```
int RaycastAll (
    Vector3 origin,
    Vector3 direction,
    float length,
    int tick,
    int? tickTo,
    float? alpha,
    List< LagCompensatedHit > hits,
    int layerMask = -1,
    bool clearHits = true,
    HitOptions options = HitOptions.None,
    QueryTriggerInteraction queryTriggerInteraction = QueryTriggerInteraction.UseGlobal,
    PreProcessingDelegate preProcessRoots = null )
```

Performs a lag-compensated raycast query against all registered hitboxes. If the [HitOptions.IncludePhysX](#) or [HitOptions.IncludeBox2D](#) flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes. Important: results are NOT sorted by distance.

Parameters

<i>origin</i>	Raycast origin, in world-space
<i>direction</i>	Raycast direction, in world-space
<i>length</i>	Raycast length
<i>tick</i>	Simulation tick number to use as the time reference for the lag compensation (use this for server AI, and similar).
<i>tickTo</i>	Simulation tick number to use as the time reference for the lag compensation. If provided, must be combined with the <i>alpha</i> parameter for interpolation between <i>tick</i> and <i>tickTo</i> . If HitOptions.SubtickAccuracy is included on <i>options</i> , this query will be resolved against hitbox colliders interpolated between the specified ticks. Otherwise, only one of the two ticks will be considered, according to the rounded value of <i>alpha</i> .
<i>alpha</i>	Interpolation value when querying between <i>tick</i> and <i>tickTo</i> . If HitOptions.SubtickAccuracy is included on <i>options</i> , this query will be resolved against hitbox colliders interpolated between the specified ticks. Otherwise, only one of the two ticks will be considered, according to the rounded alpha value.
<i>hits</i>	List to be filled with hits (both hitboxes and/or static colliders, if included).
<i>layerMask</i>	Only objects with matching layers will be checked against.
<i>options</i>	Opt-in flags to compute with sub-tick accuracy (HitOptions.SubtickAccuracy) and/or to include PhysX (HitOptions.IncludePhysX) or Box2D (HitOptions.IncludeBox2D).
<i>clearHits</i>	Clear list of hits before filling with new ones (defaults to true).
<i>queryTriggerInteraction</i>	Trigger interaction behavior when also querying PhysX.
<i>preProcessRoots</i>	Delegate to pre-process HitboxRoots found in the broad-phase resolution of the query. Roots removed from the list will not be processed any further. Roots that remain on the candidates collection will be normally processed and fitting colliders will be evaluated in the query narrow-phase resolution. Hitbox collider indices added to the processed set will be evaluated in the narrow-phase regardless of further root processing steps (e.g. layer mask match).

Returns

total number of hits

6.35.2.17 RaycastAll() [3/3]

```
int RaycastAll (
    Vector3 origin,
    Vector3 direction,
    float length,
    PlayerRef player,
    List< LagCompensatedHit > hits,
    int layerMask = -1,
    bool clearHits = true,
    HitOptions options = HitOptions.None,
    QueryTriggerInteraction queryTriggerInteraction = QueryTriggerInteraction.UseGlobal,
    PreProcessingDelegate preProcessRoots = null )
```

Performs a lag-compensated raycast query against all registered hitboxes. If the [HitOptions.IncludePhysX](#) or [HitOptions.IncludeBox2D](#) flag is indicated, query will also include static colliders, Unity colliders are recommended for static geometry, rather than Hitboxes. Important: results are NOT sorted by distance.

Parameters

<i>origin</i>	Raycast origin, in world-space
<i>direction</i>	Raycast direction, in world-space
<i>length</i>	Raycast length
<i>player</i>	Player who "owns" this raycast. Used by the server to find the exact hitbox snapshots to check against.
<i>hits</i>	List to be filled with hits (both hitboxes and/or static colliders, if included).
<i>layerMask</i>	Only objects with matching layers will be checked against.
<i>options</i>	Opt-in flags to compute with sub-tick accuracy (HitOptions.SubtickAccuracy) and/or to include PhysX (HitOptions.IncludePhysX) or Box2D (HitOptions.IncludeBox2D).
<i>clearHits</i>	Clear list of hits before filling with new ones (defaults to true).
<i>queryTriggerInteraction</i>	Trigger interaction behavior when also querying PhysX.
<i>preProcessRoots</i>	Delegate to pre-process HitboxRoots found in the broad-phase resolution of the query. Roots removed from the list will not be processed any further. Roots that remain on the candidates collection will be normally processed and fitting colliders will be evaluated in the query narrow-phase resolution. Hitbox collider indices added to the processed set will be evaluated in the narrow-phase regardless of further root processing steps (e.g. layer mask match).

Returns

total number of hits

6.35.2.18 WriteBenchmarkResults()

```
void WriteBenchmarkResults ( )
```

Used internally to write the benchmark results.

6.35.3 Member Data Documentation

6.35.3.1 BVHDepth

`int BVHDepth`

Debug data from Broadphase BVH (tree depth).

6.35.3.2 BVHNodes

`int BVHNodes`

Debug data from Broadphase BVH (total nodes count).

6.35.3.3 DrawInfo

`LagCompensationDraw DrawInfo`

Debug data used to draw the BVH nodes and the lag compensation history.

6.35.3.4 TotalHitboxes

`int TotalHitboxes`

Debug data from lag compensation history (registered [Hitbox](#) count).

6.36 HitboxRoot Class Reference

Root [Hitbox](#) group container. Manages registering/unregistering hitboxes with the group, and defines the broad-phase geometry for the group.

Inherits [NetworkBehaviour](#).

Public Types

- enum class [ConfigFlags](#) : int
Set of configuration options for a [Hitbox](#) Root behaviour.

Public Member Functions

- override void [Despawned](#) ([NetworkRunner](#) runner, bool hasState)
Called before the network object is despawned
- void [InitHitboxes](#) ()
Finds child [Hitbox](#) components, and adds them to the [Hitboxes](#) collection.
- bool [IsHitboxActive](#) ([Hitbox](#) hitbox)
Checks the state of a [Hitbox](#) instance under this root. Both the hitbox and its root must be active in order for it to be hit by lag-compensated queries.
- void [OnDrawGizmos](#) ()
[HitboxRoot](#) on draw gizmos.
- void [SetHitboxActive](#) ([Hitbox](#) hitbox, bool setActive)
Sets the state of a [Hitbox](#) instance under this root. Both the hitbox and its root must be active in order for it to be hit by lag-compensated queries.
- void [SetMinBoundingRadius](#) ()
Sets [BroadRadius](#) to a rough value which encompasses all [Hitboxes](#) in their current positions.

Public Attributes

- float [BroadRadius](#)
The radius of the broadphase bounding sphere for this [Hitbox](#) group. Used by [HitboxManager](#) to insert/update lag compensated [NetworkObjects](#) into its BVH (bounding volume hierarchy) data structure. Be sure this radius encompasses all children [Hitbox](#) components (including their full ranges of animation motion). We plan to offer an option to dynamically compute the bounding volume, but the performance trade of will still favor a hand-crafted radius.
- [ConfigFlags](#) [Config](#) = [ConfigFlags.Default](#)
Set of configuration options for this [Hitbox](#) Root behaviour. Check the API documentation for more details on what each flag represents.
- Color [GizmosColor](#) = Color.gray
Color used when drawing gizmos for this hitbox.
- [Hitbox](#)[] [Hitboxes](#)
All [Hitbox](#) instances in hierarchy. Auto-filled at Spawned.
- Vector3 [Offset](#)
Local-space offset of the broadphase bounding sphere from its transform position.

Static Public Attributes

- const Int32 [MAX_HITBOXES](#) = (sizeof(UInt32) * 8) - 1
The max number of hitboxes allowed under the same root.

Protected Member Functions

- virtual void [DrawGizmos](#) (Color color, ref Matrix4x4 localToWorldMatrix)
Draws the gizmos for the [HitboxRoot](#)

Properties

- bool [HitboxRootActive](#) [get, set]
Get or set the state of this [HitboxRoot](#). For a hitbox to be hit by lag-compensated queries, both it and its [HitboxRoot](#) must be active.
- bool [InInterest](#) [get]
If this [HitboxRoot](#) is in interest for the local player.
- [HitboxManager](#) [Manager](#) [get]
Reference to associated hitbox manager (from which lag compensated queries can be performed).

Additional Inherited Members

6.36.1 Detailed Description

Root [Hitbox](#) group container. Manages registering/unregistering hitboxes with the group, and defines the broad-phase geometry for the group.

Broadphase is the initial rough query used by raycasts/overlaps/etc to find potential hit candidates, which are then used in the final **narrowphase** query.

6.36.2 Member Enumeration Documentation

6.36.2.1 ConfigFlags

```
enum ConfigFlags : int [strong]
```

Set of configuration options for a [Hitbox](#) Root behaviour.

Enumerator

ReinitializeHitboxesBeforeRegistration	If the collection of hitboxes under a given root should be re-initialized before the Root is registered in a hitbox snapshot. If disabled, the hitboxes will be used as configured in edit-time.
IncludeInactiveHitboxes	If Hitboxes on inactive Game Objects should be registered under this root upon initialization.
Legacy	Set of configuration flags that replicate the behaviour as it was before the flag options were added.
Default	Ser of configuration flags with the default behaviour, suitable for most use-cases.

6.36.3 Member Function Documentation

6.36.3.1 DrawGizmos()

```
virtual void DrawGizmos (
    Color color,
    ref Matrix4x4 localToWorldMatrix ) [protected], [virtual]
```

Draws the gizmos for the [HitboxRoot](#)

6.36.3.2 InitHitboxes()

```
void InitHitboxes ( )
```

Finds child [Hitbox](#) components, and adds them to the [Hitboxes](#) collection.

6.36.3.3 IsHitboxActive()

```
bool IsHitboxActive (
    Hitbox hitbox )
```

Checks the state of a [Hitbox](#) instance under this root. Both the hitbox and its root must be active in order for it to be hit by lag-compensated queries.

Parameters

<i>hitbox</i>	A hitbox instance under the hierarchy of this root.
---------------	---

Returns

True if the *hitbox* is part of this root and is active.

Exceptions

<i>ArgumentOutOfRangeException</i>	If the Hitbox.HitboxIndex of the <i>hitbox</i> is outside the valid range.
<i>AssertException</i>	In Debug configuration, if the <i>hitbox</i> is not part of this root.

6.36.3.4 OnDrawGizmos()

```
void OnDrawGizmos ( )
```

[HitboxRoot](#) on draw gizmos.

6.36.3.5 SetHitboxActive()

```
void SetHitboxActive (
    Hitbox hitbox,
    bool setActive )
```

Sets the state of a [Hitbox](#) instance under this root. Both the hitbox and its root must be active in order for it to be hit by lag-compensated queries.

Parameters

<i>hitbox</i>	A hitbox instance under the hierarchy of this root.
<i>setActive</i>	If the hitbox should be activated or deactivated.

Exceptions

<i>ArgumentOutOfRangeException</i>	If the Hitbox.HitboxIndex of the <i>hitbox</i> is outside the valid range.
<i>AssertException</i>	In Debug configuration, if the <i>hitbox</i> is not part of this root.

6.36.3.6 SetMinBoundingRadius()

```
void SetMinBoundingRadius ( )
```

Sets [BroadRadius](#) to a rough value which encompasses all [Hitboxes](#) in their current positions.

6.36.4 Member Data Documentation**6.36.4.1 BroadRadius**

```
float BroadRadius
```

The radius of the broadphase bounding sphere for this [Hitbox](#) group. Used by [HitboxManager](#) to insert/update lag compensated NetworkObjects into its BVH (bounding volume hierarchy) data structure. Be sure this radius encompasses all children [Hitbox](#) components (including their full ranges of animation motion). We plan to offer an option to dynamically compute the bounding volume, but the performance trade of will still favor a hand-crafted radius.

Broadphase is the initial rough query used by raycasts/overlaps/etc to find potential hit candidates, which are then used in the final **narrowphase** query.

6.36.4.2 Config

```
ConfigFlags Config = ConfigFlags.Default
```

Set of configuration options for this [Hitbox](#) Root behaviour. Check the API documentation for more details on what each flag represents.

6.36.4.3 GizmosColor

```
Color GizmosColor = Color.gray
```

Color used when drawing gizmos for this hitbox.

6.36.4.4 Hitboxes

```
Hitbox [] Hitboxes
```

All [Hitbox](#) instances in hierarchy. Auto-filled at Spawned.

6.36.4.5 MAX_HITBOXES

```
const Int32 MAX_HITBOXES = (sizeof(UInt32) * 8) - 1 [static]
```

The max number of hitboxes allowed under the same root.

6.36.4.6 Offset

```
Vector3 Offset
```

Local-space offset of the broadphase bounding sphere from its transform position.

Adjust the [BroadRadius](#) and [Offset](#) until the sphere gizmo (shown in the Unity Scene window) encompasses all children [Hitbox](#) components (including their full ranges of animation motion).

Broadphase is the initial rough query used by raycasts/overlaps/etc to find potential hit candidates, which are then used in the final **narrowphase** query.

6.36.5 Property Documentation

6.36.5.1 HitboxRootActive

```
bool HitboxRootActive [get], [set]
```

Get or set the state of this [HitboxRoot](#). For a hitbox to be hit by lag-compensated queries, both it and its [HitboxRoot](#) must be active.

6.36.5.2 InInterest

```
bool InInterest [get]
```

If this [HitboxRoot](#) is in interest for the local player.

6.36.5.3 Manager

```
HitboxManager Manager [get]
```

Reference to associated hitbox manager (from which lag compensated queries can be performed).

6.37 HostMigrationConfig Class Reference

Project configuration settings specific to how the Host Migration behaves.

Public Attributes

- bool [EnableAutoUpdate](#)
Enabled the Host Migration feature
- int [UpdateDelay](#) = 10
Delay between Host Migration Snapshot updates

6.37.1 Detailed Description

Project configuration settings specific to how the Host Migration behaves.

6.37.2 Member Data Documentation

6.37.2.1 EnableAutoUpdate

```
bool EnableAutoUpdate
```

Enabled the Host Migration feature

6.37.2.2 UpdateDelay

```
int UpdateDelay = 10
```

Delay between Host Migration Snapshot updates

6.38 HostMigrationToken Class Reference

Transitory Holder with all necessary information to restart the [Fusion](#) Runner after the Host Migration has completed

Properties

- [GameMode](#) [GameMode](#) [get]
New GameMode the local peer will assume after the Host Migration

6.38.1 Detailed Description

Transitory Holder with all necessary information to restart the [Fusion](#) Runner after the Host Migration has completed

6.38.2 Property Documentation

6.38.2.1 GameMode

[GameMode](#) [GameMode](#) [get]

New GameMode the local peer will assume after the Host Migration

6.39 IAfterAllTicks Interface Reference

Interface for [AfterAllTicks](#) callback. Called after the re-simulation loop (when applicable), and also after the forward simulation loop. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

Inherited by [NetworkMecanimAnimator](#), and [NetworkTransform](#).

Public Member Functions

- void [AfterAllTicks](#) (bool resimulation, int tickCount)
Called after the re-simulation loop (when applicable), and also after the forward simulation loop. Only called on Updates where re-simulation or forward ticks are processed.

6.39.1 Detailed Description

Interface for [AfterAllTicks](#) callback. Called after the re-simulation loop (when applicable), and also after the forward simulation loop. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

6.39.2 Member Function Documentation

6.39.2.1 AfterAllTicks()

```
void AfterAllTicks (
    bool resimulation,
    int tickCount )
```

Called after the re-simulation loop (when applicable), and also after the forward simulation loop. Only called on Updates where re-simulation or forward ticks are processed.

Parameters

<i>resimulation</i>	True if this is being called during the re-simulation loop. False if during the forward simulation loop.
<i>tickCount</i>	How many re-simulation or forward ticks are going to be processed.

6.40 IAfterClientPredictionReset Interface Reference

Callback interface for [AfterClientPredictionReset](#). Called at the very start of the resimulation loop (on clients with prediction enabled), immediately after state is set to the latest server snapshot. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

Public Member Functions

- void [AfterClientPredictionReset](#) ()

Called at the very start of the resimulation loop (on clients with prediction enabled), immediately after state is set to the latest server snapshot.

6.40.1 Detailed Description

Callback interface for [AfterClientPredictionReset](#). Called at the very start of the resimulation loop (on clients with prediction enabled), immediately after state is set to the latest server snapshot. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

6.40.2 Member Function Documentation

6.40.2.1 AfterClientPredictionReset()

```
void AfterClientPredictionReset ( )
```

Called at the very start of the resimulation loop (on clients with prediction enabled), immediately after state is set to the latest server snapshot.

6.41 IAfterHostMigration Interface Reference

Used to mark NetworkBehaviors that need to be react after a Host Migration process

Public Member Functions

- void [AfterHostMigration](#) ()

Invoked after the Host Migration happens in order to setup non-networked data on NetworkBehaviors

6.41.1 Detailed Description

Used to mark NetworkBehaviors that need to be react after a Host Migration process

6.41.2 Member Function Documentation

6.41.2.1 AfterHostMigration()

```
void AfterHostMigration ( )
```

Invoked after the Host Migration happens in order to setup non-networked data on NetworkBehaviors

6.42 IAfterRender Interface Reference

Interface for [AfterRender](#) callback. Called after the render loop.

Public Member Functions

- void [AfterRender](#) ()
Called after the render loop.

6.42.1 Detailed Description

Interface for [AfterRender](#) callback. Called after the render loop.

6.42.2 Member Function Documentation

6.42.2.1 AfterRender()

```
void AfterRender ( )
```

Called after the render loop.

6.43 IAfterSpawned Interface Reference

Interface for [AfterSpawned](#) callback. Called after the object is spawned.

Public Member Functions

- void [AfterSpawned](#) ()
Called after the object is spawned.

6.43.1 Detailed Description

Interface for [AfterSpawned](#) callback. Called after the object is spawned.

6.43.2 Member Function Documentation

6.43.2.1 AfterSpawned()

```
void AfterSpawned ( )
```

Called after the object is spawned.

6.44 IAfterTick Interface Reference

Interface for [AfterTick](#) callback. Called after each tick simulation completes. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

Inherited by [HitboxManager](#).

Public Member Functions

- void [AfterTick](#) ()
Called after each tick simulation completes.

6.44.1 Detailed Description

Interface for [AfterTick](#) callback. Called after each tick simulation completes. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

6.44.2 Member Function Documentation

6.44.2.1 AfterTick()

```
void AfterTick ( )
```

Called after each tick simulation completes.

Implemented in [HitboxManager](#).

6.45 IAfterUpdate Interface Reference

Interface for the [AfterUpdate](#) callback, which is called at the end of each [Fusion](#) Update segment. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

Inherited by [HitboxManager](#).

Public Member Functions

- void [AfterUpdate](#) ()

Called at the end of the [Fusion](#) Update loop, before all Unity MonoBehaviour.Update() callbacks.

6.45.1 Detailed Description

Interface for the [AfterUpdate](#) callback, which is called at the end of each [Fusion](#) Update segment. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

6.45.2 Member Function Documentation

6.45.2.1 AfterUpdate()

```
void AfterUpdate ( )
```

Called at the end of the [Fusion](#) Update loop, before all Unity MonoBehaviour.Update() callbacks.

Implemented in [HitboxManager](#).

6.46 IAsyncOperation Interface Reference

Defines an asynchronous operation.

Inherited by [ICoroutine](#).

Properties

- `ExceptionDispatchInfo Error` [get]
Gets the exception information if an error occurred during the operation.
- `bool IsDone` [get]
Gets a value indicating whether the operation is done.

Events

- `Action< IAsyncOperation > Completed`
Occurs when the operation is completed.

6.46.1 Detailed Description

Defines an asynchronous operation.

6.46.2 Property Documentation

6.46.2.1 Error

`ExceptionDispatchInfo Error` [get]

Gets the exception information if an error occurred during the operation.

6.46.2.2 IsDone

`bool IsDone` [get]

Gets a value indicating whether the operation is done.

6.46.3 Event Documentation

6.46.3.1 Completed

`Action<IAsyncOperation> Completed`

Occurs when the operation is completed.

6.47 IBeforeAllTicks Interface Reference

Interface for [BeforeAllTicks](#) callback. Called before the re-simulation loop (when applicable), and also before the forward simulation loop. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

Inherited by [HitboxManager](#), and [NetworkTransform](#).

Public Member Functions

- void [BeforeAllTicks](#) (bool resimulation, int tickCount)

Called before the re-simulation loop (when applicable), and also before the forward simulation loop. Only called on Updates where re-simulation or forward ticks are processed.

6.47.1 Detailed Description

Interface for [BeforeAllTicks](#) callback. Called before the re-simulation loop (when applicable), and also before the forward simulation loop. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

6.47.2 Member Function Documentation

6.47.2.1 BeforeAllTicks()

```
void BeforeAllTicks (  
    bool resimulation,  
    int tickCount )
```

Called before the re-simulation loop (when applicable), and also before the forward simulation loop. Only called on Updates where re-simulation or forward ticks are processed.

Parameters

<i>resimulation</i>	True if this is being called during the re-simulation loop. False if during the forward simulation loop.
<i>tickCount</i>	How many re-simulation or forward ticks are going to be processed.

Implemented in [HitboxManager](#).

6.48 IBeforeClientPredictionReset Interface Reference

Callback interface for [BeforeClientPredictionReset](#). Called at the very start of the re-simulation loop (on clients with prediction enabled), before state is set to the latest server snapshot. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

Public Member Functions

- void [BeforeClientPredictionReset](#) ()

Called at the very start of the re-simulation loop (on clients with prediction enabled), before state is set to the latest server snapshot.

6.48.1 Detailed Description

Callback interface for [BeforeClientPredictionReset](#). Called at the very start of the re-simulation loop (on clients with prediction enabled), before state is set to the latest server snapshot. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

6.48.2 Member Function Documentation

6.48.2.1 BeforeClientPredictionReset()

```
void BeforeClientPredictionReset ( )
```

Called at the very start of the re-simulation loop (on clients with prediction enabled), before state is set to the latest server snapshot.

6.49 IBeforeCopyPreviousState Interface Reference

Interface for [BeforeCopyPreviousState](#) callback. Called before the copy of the previous state.

Inherited by [NetworkTransform](#).

Public Member Functions

- void [BeforeCopyPreviousState](#) ()

Called before the copy of the previous state.

6.49.1 Detailed Description

Interface for [BeforeCopyPreviousState](#) callback. Called before the copy of the previous state.

6.49.2 Member Function Documentation

6.49.2.1 BeforeCopyPreviousState()

```
void BeforeCopyPreviousState ( )
```

Called before the copy of the previous state.

6.50 IBeforeHitboxRegistration Interface Reference

Interface for [BeforeHitboxRegistration](#) callback. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

Public Member Functions

- void [BeforeHitboxRegistration](#) ()

Called immediately before the [HitboxManager](#) registers hitboxes in a snapshot.

6.50.1 Detailed Description

Interface for [BeforeHitboxRegistration](#) callback. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

6.50.2 Member Function Documentation

6.50.2.1 BeforeHitboxRegistration()

```
void BeforeHitboxRegistration ( )
```

Called immediately before the [HitboxManager](#) registers hitboxes in a snapshot.

6.51 IBeforeTick Interface Reference

Interface for [BeforeTick](#) callback. Called before each tick is simulated. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

Public Member Functions

- void [BeforeTick](#) ()

Called before each tick is simulated.

6.51.1 Detailed Description

Interface for [BeforeTick](#) callback. Called before each tick is simulated. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

6.51.2 Member Function Documentation

6.51.2.1 BeforeTick()

```
void BeforeTick ( )
```

Called before each tick is simulated.

6.52 IBeforeUpdate Interface Reference

Interface for the [BeforeUpdate](#) callback, which is called at the beginning of each [Fusion](#) Update segment. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

Public Member Functions

- void [BeforeUpdate](#) ()

Called at the start of the [Fusion](#) Update loop, before the [Fusion](#) simulation loop.

6.52.1 Detailed Description

Interface for the [BeforeUpdate](#) callback, which is called at the beginning of each [Fusion](#) Update segment. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

6.52.2 Member Function Documentation

6.52.2.1 BeforeUpdate()

```
void BeforeUpdate ( )
```

Called at the start of the [Fusion](#) Update loop, before the [Fusion](#) simulation loop.

6.53 ICoroutine Interface Reference

Defines a coroutine.

Inherits [IAsyncOperation](#), and [IEnumerator](#).

Additional Inherited Members

6.53.1 Detailed Description

Defines a coroutine.

6.54 IDespawned Interface Reference

Interface for [Despawned](#) callback. Called when a [NetworkBehaviour](#) is despawned.

Inherited by [NetworkBehaviour](#).

Public Member Functions

- void [Despawned](#) ([NetworkRunner](#) runner, bool hasState)
Called when a [NetworkBehaviour](#) is despawned.

6.54.1 Detailed Description

Interface for [Despawned](#) callback. Called when a [NetworkBehaviour](#) is despawned.

6.54.2 Member Function Documentation

6.54.2.1 Despawned()

```
void Despawned (  
    NetworkRunner runner,  
    bool hasState )
```

Called when a [NetworkBehaviour](#) is despawned.

Parameters

<i>runner</i>	NetworkRunner that despawned the NetworkBehaviour .
<i>hasState</i>	Whether the NetworkBehaviour has state.

Implemented in [HitboxRoot](#), and [NetworkBehaviour](#).

6.55 IElementReaderWriter< T > Interface Template Reference

Defines the interface for reading and writing elements in a byte array.

Public Member Functions

- int [GetElementWordCount](#) ()
Gets the word count of an element.
- T [Read](#) (byte *data, int index)
Reads an element from the specified index in the byte array.
- ref T [ReadRef](#) (byte *data, int index)
Reads a reference to an element from the specified index in the byte array.
- void [Write](#) (byte *data, int index, T element)
Writes an element to the specified index in the byte array.

6.55.1 Detailed Description

Defines the interface for reading and writing elements in a byte array.

Template Parameters

<i>T</i>	The type of the elements.
----------	---------------------------

6.55.2 Member Function Documentation

6.55.2.1 GetElementWordCount()

```
int GetElementWordCount ( )
```

Gets the word count of an element.

Returns

The word count of an element.

6.55.2.2 Read()

```
T Read (  
    byte * data,  
    int index )
```

Reads an element from the specified index in the byte array.

Parameters

<i>data</i>	The byte array.
<i>index</i>	The index of the element.

Returns

The element at the specified index.

6.55.2.3 ReadRef()

```
ref T ReadRef (
    byte * data,
    int index )
```

Reads a reference to an element from the specified index in the byte array.

Parameters

<i>data</i>	The byte array.
<i>index</i>	The index of the element.

Returns

A reference to the element at the specified index.

6.55.2.4 Write()

```
void Write (
    byte * data,
    int index,
    T element )
```

Writes an element to the specified index in the byte array.

Parameters

<i>data</i>	The byte array.
<i>index</i>	The index at which to write the element.
<i>element</i>	The element to write.

6.56 IFixedStorage Interface Reference

Interface for fixed storage types.

Inherited by [_128](#), [_16](#), [_2](#), [_256](#), [_32](#), [_4](#), [_512](#), [_64](#), and [_8](#).

6.56.1 Detailed Description

Interface for fixed storage types.

6.57 IInputAuthorityGained Interface Reference

Interface for handling the event when the input authority is gained.

Public Member Functions

- void [InputAuthorityGained](#) ()
Method to be called when the input authority is gained.

6.57.1 Detailed Description

Interface for handling the event when the input authority is gained.

6.57.2 Member Function Documentation

6.57.2.1 InputAuthorityGained()

```
void InputAuthorityGained ( )
```

Method to be called when the input authority is gained.

6.58 IInputAuthorityLost Interface Reference

Interface for handling the event when the input authority is lost.

Public Member Functions

- void [InputAuthorityLost](#) ()
Method to be called when the input authority is lost.

6.58.1 Detailed Description

Interface for handling the event when the input authority is lost.

6.58.2 Member Function Documentation

6.58.2.1 InputAuthorityLost()

```
void InputAuthorityLost ( )
```

Method to be called when the input authority is lost.

6.59 InterestEnter Interface Reference

Interface for handling the event when a player enters the area of interest.

Public Member Functions

- void [InterestEnter](#) ([PlayerRef](#) player)
Method to be called when a player enters the area of interest.

6.59.1 Detailed Description

Interface for handling the event when a player enters the area of interest.

6.59.2 Member Function Documentation

6.59.2.1 InterestEnter()

```
void InterestEnter (  
    PlayerRef player )
```

Method to be called when a player enters the area of interest.

Parameters

<i>player</i>	The player who entered the area of interest.
---------------	--

6.60 InterestExit Interface Reference

Interface for handling the event when a player exits the area of interest.

Public Member Functions

- void [InterestExit](#) ([PlayerRef](#) player)
Method to be called when a player exits the area of interest.

6.60.1 Detailed Description

Interface for handling the event when a player exits the area of interest.

6.60.2 Member Function Documentation

6.60.2.1 InterestExit()

```
void InterestExit (  
    PlayerRef player )
```

Method to be called when a player exits the area of interest.

Parameters

<i>player</i>	The player who exited the area of interest.
---------------	---

6.61 ILocalPrefabCreated Interface Reference

Interface for handling the event when a local prefab is created.

Public Member Functions

- void [LocalPrefabCreated](#) ()
Method to be called when a local prefab is created.

6.61.1 Detailed Description

Interface for handling the event when a local prefab is created.

6.61.2 Member Function Documentation

6.61.2.1 LocalPrefabCreated()

```
void LocalPrefabCreated ( )
```

Method to be called when a local prefab is created.

6.62 INetworkArray Interface Reference

Defines the interface for a networked array.

Inherits IEnumerable.

Inherited by [NetworkArray< T >](#).

Properties

- object [this\[int index\]](#) [get, set]
Gets or sets the element at the specified index.

6.62.1 Detailed Description

Defines the interface for a networked array.

6.62.2 Property Documentation

6.62.2.1 this[int index]

```
object this[int index] [get], [set]
```

Gets or sets the element at the specified index.

Parameters

<i>index</i>	The zero-based index of the element to get or set.
--------------	--

6.63 INetworkAssetSource< T > Interface Template Reference

Interface for a network asset source.

Public Member Functions

- void [Acquire](#) (bool synchronous)
Acquires the network asset.
- void [Release](#) ()
Releases the network asset.
- T [WaitForResult](#) ()
Waits for the result of the network asset acquisition.

Properties

- string [Description](#) [get]
Gets the description of the network asset.
- bool [IsCompleted](#) [get]
Checks if the network asset acquisition is completed.

6.63.1 Detailed Description

Interface for a network asset source.

Template Parameters

<i>T</i>	Type of the network asset.
----------	----------------------------

6.63.2 Member Function Documentation

6.63.2.1 Acquire()

```
void Acquire (  
    bool synchronous )
```

Acquires the network asset.

Parameters

<i>synchronous</i>	If true, the acquisition is done synchronously.
--------------------	---

6.63.2.2 Release()

```
void Release ( )
```

Releases the network asset.

6.63.2.3 WaitForResult()

```
T WaitForResult ( )
```

Waits for the result of the network asset acquisition.

Returns

The network asset.

6.63.3 Property Documentation

6.63.3.1 Description

```
string Description [get]
```

Gets the description of the network asset.

6.63.3.2 IsCompleted

```
bool IsCompleted [get]
```

Checks if the network asset acquisition is completed.

6.64 INetworkDictionary Interface Reference

Defines the interface for a networked dictionary.

Inherits IEnumerable.

Inherited by [NetworkDictionary< K, V >](#).

Public Member Functions

- void [Add](#) (object item)
Adds an item to the networked dictionary.

6.64.1 Detailed Description

Defines the interface for a networked dictionary.

6.64.2 Member Function Documentation

6.64.2.1 Add()

```
void Add (  
    object item )
```

Adds an item to the networked dictionary.

Parameters

<i>item</i>	The item to add to the dictionary.
-------------	------------------------------------

Implemented in [NetworkDictionary< K, V >](#).

6.65 INetworkInput Interface Reference

Flag interface for custom [NetworkInput](#) structs.

6.65.1 Detailed Description

Flag interface for custom [NetworkInput](#) structs.

6.66 INetworkLinkedList Interface Reference

Defines the interface for a networked linked list.

Inherits IEnumerable.

Inherited by [NetworkLinkedList< T >](#).

Public Member Functions

- void [Add](#) (object item)
Adds an item to the networked linked list.

6.66.1 Detailed Description

Defines the interface for a networked linked list.

6.66.2 Member Function Documentation

6.66.2.1 Add()

```
void Add (
    object item )
```

Adds an item to the networked linked list.

Parameters

<i>item</i>	The item to add to the linked list.
-------------	-------------------------------------

Implemented in [NetworkLinkedList< T >](#).

6.67 INetworkObjectInitializer Interface Reference

Interface for initializing network objects.

Inherited by [NetworkObjectInitializerUnity](#).

Public Member Functions

- void [InitializeNetworkState](#) ([NetworkObject](#) networkObject)
Initializes the network object.

6.67.1 Detailed Description

Interface for initializing network objects.

6.67.2 Member Function Documentation

6.67.2.1 InitializeNetworkState()

```
void InitializeNetworkState (
    NetworkObject networkObject )
```

Initializes the network object.

Parameters

<i>networkObject</i>	The network object to initialize.
----------------------	-----------------------------------

Implemented in [NetworkObjectInitializerUnity](#).

6.68 INetworkObjectProvider Interface Reference

Interface which defines the handlers for [NetworkRunner](#) Spawn() and Despawn() actions. Passing an instance of this interface to [NetworkRunner.StartGame\(StartGameArgs\)](#) as the [StartGameArgs.ObjectProvider](#) argument value will assign that instance as the handler for runner Spawn() and Despawn() actions. By default (if [StartGameArgs.ObjectProvider](#) == null) actions will use Instantiate(), and Despawn() actions will use Destroy().

Inherited by [NetworkObjectProviderDummy](#).

Public Member Functions

- [NetworkObjectAcquireResult AcquirePrefabInstance](#) ([NetworkRunner](#) runner, in [NetworkPrefabAcquireContext](#) context, out [NetworkObject](#) result)
Acquires an instance of a prefab for a network object.
- void [ReleaseInstance](#) ([NetworkRunner](#) runner, in [NetworkObjectReleaseContext](#) context)
Releases an instance of a network object.

6.68.1 Detailed Description

Interface which defines the handlers for [NetworkRunner](#) Spawn() and Despawn() actions. Passing an instance of this interface to [NetworkRunner.StartGame\(StartGameArgs\)](#) as the [StartGameArgs.ObjectProvider](#) argument value will assign that instance as the handler for runner Spawn() and Despawn() actions. By default (if [StartGameArgs.ObjectProvider](#) == null) actions will use Instantiate(), and Despawn() actions will use Destroy().

6.68.2 Member Function Documentation

6.68.2.1 AcquirePrefabInstance()

```
NetworkObjectAcquireResult AcquirePrefabInstance (
    NetworkRunner runner,
    in NetworkPrefabAcquireContext context,
    out NetworkObject result )
```

Acquires an instance of a prefab for a network object.

Parameters

<i>runner</i>	The NetworkRunner that manages the network objects.
<i>context</i>	The context that provides information for acquiring the prefab instance.
<i>result</i>	The acquired NetworkObject instance.

Returns

A [NetworkObjectAcquireResult](#) indicating the result of the operation.

Implemented in [NetworkObjectProviderDummy](#).

6.68.2.2 ReleaseInstance()

```
void ReleaseInstance (
    NetworkRunner runner,
    in NetworkObjectReleaseContext context )
```

Releases an instance of a network object.

Parameters

<i>runner</i>	The NetworkRunner that manages the network objects.
<i>context</i>	The context that provides information for releasing the network object instance.

Implemented in [NetworkObjectProviderDummy](#).

6.69 INetworkPrefabSource Interface Reference

Interface for a network prefab source.

Inherits [INetworkAssetSource](#)< [NetworkObject](#) >.

Properties

- [NetworkObjectGuid AssetGuid](#) [get]
Gets the GUID of the network object asset.

Additional Inherited Members**6.69.1 Detailed Description**

Interface for a network prefab source.

6.69.2 Property Documentation

6.69.2.1 AssetGuid

`NetworkObjectGuid` AssetGuid [get]

Gets the GUID of the network object asset.

6.70 INetworkRunnerCallbacks Interface Reference

Interface for [NetworkRunner](#) callbacks. Register a class/struct instance which implements this interface with `NetworkRunner.AddCallbacks(INetworkRunnerCallbacks[])`.

Inherited by [NetworkDelegates](#), and [NetworkEvents](#).

Public Member Functions

- void [OnConnectedToServer](#) ([NetworkRunner](#) runner)

Callback when [NetworkRunner](#) successfully connects to a server or host.
- void [OnConnectFailed](#) ([NetworkRunner](#) runner, [NetAddress](#) remoteAddress, [NetConnectFailedReason](#) reason)

Callback when [NetworkRunner](#) fails to connect to a server or host.
- void [OnConnectRequest](#) ([NetworkRunner](#) runner, [NetworkRunnerCallbackArgs.ConnectRequest](#) request, byte[] token)

Callback when [NetworkRunner](#) receives a Connection Request from a Remote Client
- void [OnCustomAuthenticationResponse](#) ([NetworkRunner](#) runner, Dictionary< string, object > data)

Callback is invoked when the Authentication procedure returns a response from the Authentication Server
- void [OnDisconnectedFromServer](#) ([NetworkRunner](#) runner, [NetDisconnectReason](#) reason)

Callback when [NetworkRunner](#) disconnects from a server or host.
- void [OnHostMigration](#) ([NetworkRunner](#) runner, [HostMigrationToken](#) hostMigrationToken)

Callback is invoked when the Host Migration process has started
- void [OnInput](#) ([NetworkRunner](#) runner, [NetworkInput](#) input)

Callback from [NetworkRunner](#) that polls for user inputs. The [NetworkInput](#) that is supplied expects:
- void [OnInputMissing](#) ([NetworkRunner](#) runner, [PlayerRef](#) player, [NetworkInput](#) input)

Callback from [NetworkRunner](#) when an input is missing.
- void [OnObjectEnterAOI](#) ([NetworkRunner](#) runner, [NetworkObject](#) obj, [PlayerRef](#) player)

Callback from a [NetworkRunner](#) when a new [NetworkObject](#) has entered the Area of Interest
- void [OnObjectExitAOI](#) ([NetworkRunner](#) runner, [NetworkObject](#) obj, [PlayerRef](#) player)

Callback from a [NetworkRunner](#) when a new [NetworkObject](#) has exit the Area of Interest
- void [OnPlayerJoined](#) ([NetworkRunner](#) runner, [PlayerRef](#) player)

Callback from a [NetworkRunner](#) when a new player has joined.
- void [OnPlayerLeft](#) ([NetworkRunner](#) runner, [PlayerRef](#) player)

Callback from a [NetworkRunner](#) when a player has disconnected.
- void [OnReliableDataProgress](#) ([NetworkRunner](#) runner, [PlayerRef](#) player, [ReliableKey](#) key, float progress)

Callback is invoked when a Reliable Data Stream is being received, reporting its progress
- void [OnReliableDataReceived](#) ([NetworkRunner](#) runner, [PlayerRef](#) player, [ReliableKey](#) key, ArraySegment< byte > data)

Callback is invoked when a Reliable Data Stream has been received
- void [OnSceneLoadDone](#) ([NetworkRunner](#) runner)

Callback is invoked when a Scene Load has finished
- void [OnSceneLoadStart](#) ([NetworkRunner](#) runner)

Callback is invoked when a Scene Load has started

- void [OnSessionListUpdated](#) ([NetworkRunner](#) runner, List< [SessionInfo](#) > sessionList)

This callback is invoked when a new List of Sessions is received from Photon Cloud

- void [OnShutdown](#) ([NetworkRunner](#) runner, [ShutdownReason](#) shutdownReason)

Called when the runner is shutdown

- void [OnUserSimulationMessage](#) ([NetworkRunner](#) runner, [SimulationMessagePtr](#) message)

This callback is invoked when a manually dispatched simulation message is received from a remote peer

6.70.1 Detailed Description

Interface for [NetworkRunner](#) callbacks. Register a class/struct instance which implements this interface with `NetworkRunner.AddCallbacks(INetworkRunnerCallbacks[])`.

6.70.2 Member Function Documentation

6.70.2.1 OnConnectedToServer()

```
void OnConnectedToServer (
    NetworkRunner runner )
```

Callback when [NetworkRunner](#) successfully connects to a server or host.

6.70.2.2 OnConnectFailed()

```
void OnConnectFailed (
    NetworkRunner runner,
    NetAddress remoteAddress,
    NetConnectFailedReason reason )
```

Callback when [NetworkRunner](#) fails to connect to a server or host.

6.70.2.3 OnConnectRequest()

```
void OnConnectRequest (
    NetworkRunner runner,
    NetworkRunnerCallbackArgs.ConnectRequest request,
    byte[] token )
```

Callback when [NetworkRunner](#) receives a Connection Request from a Remote Client

Parameters

<i>runner</i>	Local NetworkRunner
<i>request</i>	Request information
<i>token</i>	Request Token

6.70.2.4 OnCustomAuthenticationResponse()

```
void OnCustomAuthenticationResponse (
    NetworkRunner runner,
    Dictionary< string, object > data )
```

Callback is invoked when the Authentication procedure returns a response from the Authentication Server

Parameters

<i>runner</i>	The runner this object exists on
<i>data</i>	Custom Authentication Reply Values

6.70.2.5 OnDisconnectedFromServer()

```
void OnDisconnectedFromServer (
    NetworkRunner runner,
    NetDisconnectReason reason )
```

Callback when [NetworkRunner](#) disconnects from a server or host.

6.70.2.6 OnHostMigration()

```
void OnHostMigration (
    NetworkRunner runner,
    HostMigrationToken hostMigrationToken )
```

Callback is invoked when the Host Migration process has started

Parameters

<i>runner</i>	The runner this object exists on
<i>hostMigrationToken</i>	Migration Token that stores all necessary information to restart the Fusion Runner

6.70.2.7 OnInput()

```
void OnInput (
    NetworkRunner runner,
    NetworkInput input )
```

Callback from [NetworkRunner](#) that polls for user inputs. The [NetworkInput](#) that is supplied expects:

```
input.Set(new CustomINetworkInput() { /* your values */ });
```

6.70.2.8 OnInputMissing()

```
void OnInputMissing (
    NetworkRunner runner,
    PlayerRef player,
    NetworkInput input )
```

Callback from [NetworkRunner](#) when an input is missing.

Parameters

<i>runner</i>	NetworkRunner reference
<i>player</i>	PlayerRef reference which the input is missing from
<i>input</i>	NetworkInput reference which is missing

6.70.2.9 OnObjectEnterAOI()

```
void OnObjectEnterAOI (
    NetworkRunner runner,
    NetworkObject obj,
    PlayerRef player )
```

Callback from a [NetworkRunner](#) when a new [NetworkObject](#) has entered the Area of Interest

Parameters

<i>runner</i>	NetworkRunner reference
<i>obj</i>	NetworkObject reference
<i>player</i>	PlayerRef reference

6.70.2.10 OnObjectExitAOI()

```
void OnObjectExitAOI (
    NetworkRunner runner,
```

```

    NetworkObject obj,
    PlayerRef player )

```

Callback from a [NetworkRunner](#) when a new [NetworkObject](#) has exit the Area of Interest

Parameters

<i>runner</i>	NetworkRunner reference
<i>obj</i>	NetworkObject reference
<i>player</i>	PlayerRef reference

6.70.2.11 OnPlayerJoined()

```

void OnPlayerJoined (
    NetworkRunner runner,
    PlayerRef player )

```

Callback from a [NetworkRunner](#) when a new player has joined.

6.70.2.12 OnPlayerLeft()

```

void OnPlayerLeft (
    NetworkRunner runner,
    PlayerRef player )

```

Callback from a [NetworkRunner](#) when a player has disconnected.

6.70.2.13 OnReliableDataProgress()

```

void OnReliableDataProgress (
    NetworkRunner runner,
    PlayerRef player,
    ReliableKey key,
    float progress )

```

Callback is invoked when a Reliable Data Stream is being received, reporting its progress

Parameters

<i>runner</i>	NetworkRunner reference
<i>player</i>	Which PlayerRef the stream is being sent from
<i>key</i>	ReliableKey reference that identifies the data stream
<i>progress</i>	Progress of the stream

6.70.2.14 OnReliableDataReceived()

```
void OnReliableDataReceived (
    NetworkRunner runner,
    PlayerRef player,
    ReliableKey key,
    ArraySegment< byte > data )
```

Callback is invoked when a Reliable Data Stream has been received

Parameters

<i>runner</i>	NetworkRunner reference
<i>player</i>	Which PlayerRef the stream was sent from
<i>key</i>	ReliableKey reference that identifies the data stream
<i>data</i>	Data received

6.70.2.15 OnSceneLoadDone()

```
void OnSceneLoadDone (
    NetworkRunner runner )
```

Callback is invoked when a Scene Load has finished

Parameters

<i>runner</i>	NetworkRunner reference
---------------	-------------------------

6.70.2.16 OnSceneLoadStart()

```
void OnSceneLoadStart (
    NetworkRunner runner )
```

Callback is invoked when a Scene Load has started

Parameters

<i>runner</i>	NetworkRunner reference
---------------	-------------------------

6.70.2.17 OnSessionListUpdated()

```
void OnSessionListUpdated (
    NetworkRunner runner,
    List< SessionInfo > sessionList )
```

This callback is invoked when a new List of Sessions is received from Photon Cloud

Parameters

<i>runner</i>	The runner this object exists on
<i>sessionList</i>	Updated list of Session

6.70.2.18 OnShutdown()

```
void OnShutdown (
    NetworkRunner runner,
    ShutdownReason shutdownReason )
```

Called when the runner is shutdown

Parameters

<i>runner</i>	The runner being shutdown
<i>shutdownReason</i>	Describes the reason Fusion was Shutdown

6.70.2.19 OnUserSimulationMessage()

```
void OnUserSimulationMessage (
    NetworkRunner runner,
    SimulationMessagePtr message )
```

This callback is invoked when a manually dispatched simulation message is received from a remote peer

Parameters

<i>runner</i>	The runner this message is for
<i>message</i>	The message pointer

6.71 INetworkRunnerUpdater Interface Reference

Interface which defines the handlers for [NetworkRunner](#) Updates. An implementation is responsible for calling [NetworkRunner.UpdateInternal\(double\)](#) and [NetworkRunner.RenderInternal](#) periodically.

Inherited by [NetworkRunnerUpdaterDefault](#), and [NetworkRunnerUpdaterDummy](#).

Public Member Functions

- void [Initialize](#) ([NetworkRunner](#) runner)
Called when the [NetworkRunner](#) is started.
- void [Shutdown](#) ([NetworkRunner](#) runner)
Called when the [NetworkRunner](#) is stopped.

6.71.1 Detailed Description

Interface which defines the handlers for [NetworkRunner](#) Updates. An implementation is responsible for calling [NetworkRunner.UpdateInternal\(double\)](#) and [NetworkRunner.RenderInternal](#) periodically.

An instance of this interface can be passed to [NetworkRunner.StartGame\(StartGameArgs\)](#) as the [StartGameArgs.Updater](#). By default (if [StartGameArgs.Updater](#) == null) [Fusion](#) will use [NetworkRunnerUpdaterDefault](#), which invokes [NetworkRunner.UpdateInternal\(double\)](#) before script's Update and [NetworkRunner.RenderInternal](#) before LateUpdate.

6.71.2 Member Function Documentation

6.71.2.1 Initialize()

```
void Initialize (  
    NetworkRunner runner )
```

Called when the [NetworkRunner](#) is started.

Parameters

<i>runner</i>	The NetworkRunner instance.
---------------	---

6.71.2.2 Shutdown()

```
void Shutdown (  
    NetworkRunner runner )
```

Called when the [NetworkRunner](#) is stopped.

Parameters

<i>runner</i>	The NetworkRunner instance.
---------------	---

6.72 INetworkSceneManager Interface Reference

Interface for a [NetworkRunner](#) scene manager. A scene manager is responsible for loading and unloading scenes

Inherited by [NetworkSceneManagerDummy](#).

Public Member Functions

- [SceneRef](#) [GetSceneRef](#) (GameObject gameObject)
Gets a [SceneRef](#) for the scene that the given [GameObject](#) belongs to.
- [SceneRef](#) [GetSceneRef](#) (string sceneNameOrPath)
Gets a [SceneRef](#) for the given scene name or path.
- void [Initialize](#) ([NetworkRunner](#) runner)
Callback for initialization
- bool [IsRunnerScene](#) (Scene scene)
Signals if the given scene is the main runner scene. Mostly used for Multipeer logic
- [NetworkSceneAsyncOp](#) [LoadScene](#) ([SceneRef](#) sceneRef, [NetworkLoadSceneParameters](#) parameters)
Loads a given scene with the specified parameters.
- void [MakeDontDestroyOnLoad](#) (GameObject obj)
Mark an object as `DontDestroyOnLoad`.
- bool [MoveGameObjectToScene](#) (GameObject gameObject, [SceneRef](#) sceneRef)
Move a [GameObject](#) to a desired scene.
- bool [OnSceneInfoChanged](#) ([NetworkSceneInfo](#) sceneInfo, [NetworkSceneInfoChangeSource](#) changeSource)
Implement this method and return true if you want to handle scene info changes manually. Return false if the default scene info change handling should be done by the [NetworkRunner](#) instead.
- void [Shutdown](#) ()
Callback for shutdown and clean up
- bool [TryGetPhysicsScene2D](#) (out PhysicsScene2D scene2D)
Tries to get the physics scene 2D.
- bool [TryGetPhysicsScene3D](#) (out PhysicsScene scene3D)
Tries to get the physics scene 3D.
- [NetworkSceneAsyncOp](#) [UnloadScene](#) ([SceneRef](#) sceneRef)
Unloads a given scene.

Properties

- bool [IsBusy](#) [get]
Signals if the [INetworkSceneManager](#) instance is busy with any scene loading operations
- Scene [MainRunnerScene](#) [get]
The main scene of the [NetworkRunner](#). Mostly used for Multipeer logic

6.72.1 Detailed Description

Interface for a [NetworkRunner](#) scene manager. A scene manager is responsible for loading and unloading scenes

6.72.2 Member Function Documentation

6.72.2.1 GetSceneRef() [1/2]

```
SceneRef GetSceneRef (
    GameObject gameObject )
```

Gets a [SceneRef](#) for the scene that the given GameObject belongs to.

6.72.2.2 GetSceneRef() [2/2]

```
SceneRef GetSceneRef (
    string sceneNameOrPath )
```

Gets a [SceneRef](#) for the given scene name or path.

6.72.2.3 Initialize()

```
void Initialize (
    NetworkRunner runner )
```

Callback for initialization

6.72.2.4 IsRunnerScene()

```
bool IsRunnerScene (
    Scene scene )
```

Signals if the given scene is the main runner scene. Mostly used for Multipeer logic

6.72.2.5 LoadScene()

```
NetworkSceneAsyncOp LoadScene (
    SceneRef sceneRef,
    NetworkLoadSceneParameters parameters )
```

Loads a given scene with the specified parameters.

Returns

Returns a [NetworkSceneAsyncOp](#) that can be waited

6.72.2.6 MakeDontDestroyOnLoad()

```
void MakeDontDestroyOnLoad (
    GameObject obj )
```

Mark an object as DontDestroyOnLoad.

6.72.2.7 MoveGameObjectToScene()

```
bool MoveGameObjectToScene (
    GameObject gameObject,
    SceneRef sceneRef )
```

Move a GameObject to a desired scene.

Returns

Return true if the operation was successfully

6.72.2.8 OnSceneInfoChanged()

```
bool OnSceneInfoChanged (
    NetworkSceneInfo sceneInfo,
    NetworkSceneInfoChangeSource changeSource )
```

Implement this method and return true if you want to handle scene info changes manually. Return false if the default scene info change handling should be done by the [NetworkRunner](#) instead.

Returns

Return true if a custom handling is provided, false otherwise to use the default one

6.72.2.9 Shutdown()

```
void Shutdown ( )
```

Callback for shutdown and clean up

6.72.2.10 TryGetPhysicsScene2D()

```
bool TryGetPhysicsScene2D (
    out PhysicsScene2D scene2D )
```

Tries to get the physics scene 2D.

Returns

Returns true if the operation was successfully

6.72.2.11 TryGetPhysicsScene3D()

```
bool TryGetPhysicsScene3D (
    out PhysicsScene scene3D )
```

Tries to get the physics scene 3D.

Returns

Returns true if the operation was successfully

6.72.2.12 UnloadScene()

```
NetworkSceneAsyncOp UnloadScene (
    SceneRef sceneRef )
```

Unloads a given scene.

Returns

Returns a [NetworkSceneAsyncOp](#) that can be waited

6.72.3 Property Documentation

6.72.3.1 IsBusy

```
bool IsBusy [get]
```

Signals if the [INetworkSceneManager](#) instance is busy with any scene loading operations

6.72.3.2 MainRunnerScene

Scene MainRunnerScene [get]

The main scene of the [NetworkRunner](#). Mostly used for Multipeer logic

6.73 INetworkStruct Interface Reference

Base interface for all [Fusion](#) Network Structs

Inherited by [Angle](#), [BitSet128](#), [BitSet192](#), [BitSet256](#), [BitSet512](#), [BitSet64](#), [FloatCompressed](#), [NetworkBehaviourId](#), [NetworkBool](#), [NetworkButtons](#), [NetworkId](#), [NetworkObjectGuid](#), [NetworkObjectHeader](#), [NetworkObjectNestingKey](#), [NetworkObjectTypeId](#), [NetworkPhysicsInfo](#), [NetworkPrefabId](#), [NetworkPrefabRef](#), [NetworkRNG](#), [NetworkSceneInfo](#), [NetworkString< TSize >](#), [NetworkTRSPData](#), [PlayerRef](#), [Ptr](#), [QuaternionCompressed](#), [SceneRef](#), [TickTimer](#), [Vector2Compressed](#), [Vector3Compressed](#), [Vector4Compressed](#), [_128](#), [_16](#), [_2](#), [_256](#), [_32](#), [_4](#), [_512](#), [_64](#), and [_8](#).

6.73.1 Detailed Description

Base interface for all [Fusion](#) Network Structs

6.74 INetworkTRSPTeleport Interface Reference

Implement this interface on a [NetworkTRSP](#) implementation to indicate it can be teleported.

Inherited by [NetworkTransform](#).

Public Member Functions

- void [Teleport](#) (Vector3? position=null, Quaternion? rotation=null)
Teleports to the indicated values, and network the Teleport event.

6.74.1 Detailed Description

Implement this interface on a [NetworkTRSP](#) implementation to indicate it can be teleported.

6.74.2 Member Function Documentation

6.74.2.1 Teleport()

```
void Teleport (
    Vector3? position = null,
    Quaternion? rotation = null )
```

Teleports to the indicated values, and network the Teleport event.

Implemented in [NetworkTransform](#).

6.75 IUnitySurrogate Interface Reference

Represents an interface for Unity surrogates. This interface provides methods for reading and writing data.

Inherited by [IUnityValueSurrogate< T >](#), and [UnitySurrogateBase](#).

Public Member Functions

- void [Read](#) (int *data, int capacity)
Reads data from a specified memory location.
- void [Write](#) (int *data, int capacity)
Writes data to a specified memory location.

6.75.1 Detailed Description

Represents an interface for Unity surrogates. This interface provides methods for reading and writing data.

6.75.2 Member Function Documentation

6.75.2.1 Read()

```
void Read (
    int * data,
    int capacity )
```

Reads data from a specified memory location.

Parameters

<i>data</i>	The memory location to read from.
<i>capacity</i>	The number of elements to read.

Implemented in [UnityValueSurrogate< T, TReaderWriter >](#), [UnitySurrogateBase](#), [UnityLinkedListSurrogate< T, ReaderWriter >](#),

[UnityDictionarySurrogate< KeyType, KeyReaderWriter, ValueType, ValueReaderWriter >](#), and [UnityArraySurrogate< T, ReaderWriter](#)

6.75.2.2 Write()

```
void Write (
    int * data,
    int capacity )
```

Writes data to a specified memory location.

Parameters

<i>data</i>	The memory location to write to.
<i>capacity</i>	The number of elements to write.

Implemented in [UnityValueSurrogate< T, TReaderWriter >](#), [UnitySurrogateBase](#), [UnityLinkedListSurrogate< T, ReaderWriter >](#), [UnityDictionarySurrogate< KeyType, KeyReaderWriter, ValueType, ValueReaderWriter >](#), and [UnityArraySurrogate< T, ReaderWriter](#)

6.76 IUnityValueSurrogate< T > Interface Template Reference

Represents an interface for Unity value surrogates. This interface provides a property for accessing and modifying the data.

Inherits [IUnitySurrogate](#).

Inherited by [UnityValueSurrogate< T, TReaderWriter >](#).

Properties

- [T DataProperty](#) [get, set]
Gets or sets the data for the Unity value surrogate.

Additional Inherited Members

6.76.1 Detailed Description

Represents an interface for Unity value surrogates. This interface provides a property for accessing and modifying the data.

Template Parameters

<i>T</i>	The type of the data.
----------	-----------------------

6.76.2 Property Documentation

6.76.2.1 DataProperty

T DataProperty [get], [set]

Gets or sets the data for the Unity value surrogate.

6.77 UnityArraySurrogate< T, ReaderWriter > Class Template Reference

A base class for Unity array surrogates.

Inherits [UnitySurrogateBase](#).

Public Member Functions

- override void [Init](#) (int capacity)
Initializes the [UnityArraySurrogate](#) with a specified capacity.
- override void [Read](#) (int *data, int capacity)
Reads data into the [UnityArraySurrogate](#) from a specified memory location.
- override void [Write](#) (int *data, int capacity)
Writes data from the [UnityArraySurrogate](#) to a specified memory location.

Properties

- abstract T[] [DataProperty](#) [get, set]
Gets or sets the data array for the [UnityArraySurrogate](#).

6.77.1 Detailed Description

A base class for Unity array surrogates.

Template Parameters

<i>T</i>	Unmanaged type of the array elements.
<i>ReaderWriter</i>	Unmanaged type of the reader/writer for the array elements.

Type Constraints

***T* : [unmanaged](#)**
***ReaderWriter* : [unmanaged](#)**
***ReaderWriter* : [IElementReaderWriter](#)< *T* >**

6.77.2 Member Function Documentation

6.77.2.1 Init()

```
override void Init (  
    int capacity ) [virtual]
```

Initializes the [UnityArraySurrogate](#) with a specified capacity.

Parameters

<i>capacity</i>	The capacity to initialize the UnityArraySurrogate with.
-----------------	--

Implements [UnitySurrogateBase](#).

6.77.2.2 Read()

```
override void Read (  
    int * data,  
    int capacity ) [virtual]
```

Reads data into the [UnityArraySurrogate](#) from a specified memory location.

Parameters

<i>data</i>	The memory location to read from.
<i>capacity</i>	The number of elements to read.

Implements [UnitySurrogateBase](#).

6.77.2.3 Write()

```
override void Write (  
    int * data,  
    int capacity ) [virtual]
```

Writes data from the [UnityArraySurrogate](#) to a specified memory location.

Parameters

<i>data</i>	The memory location to write to.
<i>capacity</i>	The number of elements to write.

Implements [UnitySurrogateBase](#).

6.77.3 Property Documentation

6.77.3.1 DataProperty

```
abstract T [] DataProperty [get], [set]
```

Gets or sets the data array for the [UnityArraySurrogate](#).

6.78 UnityDictionarySurrogate< KeyType, KeyReaderWriter, ValueType, ValueReaderWriter > Class Template Reference

A surrogate for serializing a dictionary.

Inherits [UnitySurrogateBase](#).

Public Member Functions

- override void [Init](#) (int capacity)
Initializes the [UnityDictionarySurrogate](#) with a specified capacity.
- override void [Read](#) (int *data, int capacity)
Reads data into the [UnityDictionarySurrogate](#) from a specified memory location.
- override void [Write](#) (int *data, int capacity)
Writes data from the [UnityDictionarySurrogate](#) to a specified memory location.

Properties

- abstract [SerializableDictionary](#)< KeyType, ValueType > [DataProperty](#) [get, set]
Gets or sets the data property.

6.78.1 Detailed Description

A surrogate for serializing a dictionary.

Template Parameters

<i>KeyType</i>	The type of the key.
<i>KeyReaderWriter</i>	The type of the key reader writer.
<i>ValueType</i>	The type of the value.
<i>ValueReaderWriter</i>	The type of the value reader writer.

See also

[Fusion.Internal.UnitySurrogateBase](#)

Type Constraints

KeyType : *unmanaged*

KeyReaderWriter : *unmanaged*

KeyReaderWriter : [IElementReaderWriter](#)<**KeyType**>

ValueType : *unmanaged*

ValueReaderWriter : *unmanaged*

ValueReaderWriter : [IElementReaderWriter](#)<**ValueType**>

6.78.2 Member Function Documentation

6.78.2.1 Init()

```
override void Init (
    int capacity ) [virtual]
```

Initializes the [UnityDictionarySurrogate](#) with a specified capacity.

Parameters

<i>capacity</i>	The capacity to initialize the UnityDictionarySurrogate with.
-----------------	---

Implements [UnitySurrogateBase](#).

6.78.2.2 Read()

```
override void Read (
    int * data,
    int capacity ) [virtual]
```

Reads data into the [UnityDictionarySurrogate](#) from a specified memory location.

Parameters

<i>data</i>	The memory location to read from.
<i>capacity</i>	The number of elements to read.

Implements [UnitySurrogateBase](#).

6.78.2.3 Write()

```
override void Write (
    int * data,
    int capacity ) [virtual]
```

Writes data from the [UnityDictionarySurrogate](#) to a specified memory location.

Parameters

<i>data</i>	The memory location to write to.
<i>capacity</i>	The number of elements to write.

Implements [UnitySurrogateBase](#).

6.78.3 Property Documentation

6.78.3.1 DataProperty

```
abstract SerializableDictionary<KeyType, ValueType> DataProperty [get], [set]
```

Gets or sets the data property.

6.79 UnityLinkedListSurrogate< T, ReaderWriter > Class Template Reference

A surrogate for serializing a linked list.

Inherits [UnitySurrogateBase](#).

Public Member Functions

- override void [Init](#) (int capacity)
Initializes the [UnityLinkedListSurrogate](#) with a specified capacity.
- override void [Read](#) (int *data, int capacity)
Reads data into the [UnityLinkedListSurrogate](#) from a specified memory location.
- override void [Write](#) (int *data, int capacity)
Writes data from the [UnityLinkedListSurrogate](#) to a specified memory location.

Properties

- abstract T[] [DataProperty](#) [get, set]
Gets or sets the data property.

6.79.1 Detailed Description

A surrogate for serializing a linked list.

Template Parameters

<i>T</i>	The type of the elements in the linked list.
<i>ReaderWriter</i>	The type of the reader writer for the elements in the linked list.

Type Constraints

T : *unmanaged*

ReaderWriter : *unmanaged*

ReaderWriter : [IElementReaderWriter](#)<*T*>

6.79.2 Member Function Documentation

6.79.2.1 Init()

```
override void Init (  
    int capacity ) [virtual]
```

Initializes the [UnityLinkedListSurrogate](#) with a specified capacity.

Parameters

<i>capacity</i>	The capacity to initialize the UnityLinkedListSurrogate with.
-----------------	---

Implements [UnitySurrogateBase](#).

6.79.2.2 Read()

```
override void Read (  
    int * data,  
    int capacity ) [virtual]
```

Reads data into the [UnityLinkedListSurrogate](#) from a specified memory location.

Parameters

<i>data</i>	The memory location to read from.
<i>capacity</i>	The number of elements to read.

Implements [UnitySurrogateBase](#).

6.79.2.3 Write()

```
override void Write (
    int * data,
    int capacity ) [virtual]
```

Writes data from the [UnityLinkedListSurrogate](#) to a specified memory location.

Parameters

<i>data</i>	The memory location to write to.
<i>capacity</i>	The number of elements to write.

Implements [UnitySurrogateBase](#).

6.79.3 Property Documentation

6.79.3.1 DataProperty

```
abstract T [] DataProperty [get], [set]
```

Gets or sets the data property.

6.80 UnitySurrogateBase Class Reference

Represents a base class for Unity surrogates. This class is serializable and provides abstract methods for reading, writing, and initializing data.

Inherits [IUnitySurrogate](#).

Inherited by [UnityArraySurrogate< T, ReaderWriter >](#), [UnityDictionarySurrogate< KeyType, KeyReaderWriter, ValueType, ValueReaderWriter >](#), [UnityLinkedListSurrogate< T, ReaderWriter >](#), and [UnityValueSurrogate< T, TReaderWriter >](#).

Public Member Functions

- abstract void [Init](#) (int capacity)
Initializes the [UnitySurrogateBase](#) with a specified capacity.
- abstract void [Read](#) (int *data, int capacity)
Reads data from a specified memory location into the [UnitySurrogateBase](#).
- abstract void [Write](#) (int *data, int capacity)
Writes data from the [UnitySurrogateBase](#) to a specified memory location.

6.80.1 Detailed Description

Represents a base class for Unity surrogates. This class is serializable and provides abstract methods for reading, writing, and initializing data.

6.80.2 Member Function Documentation

6.80.2.1 Init()

```
abstract void Init (  
    int capacity ) [pure virtual]
```

Initializes the [UnitySurrogateBase](#) with a specified capacity.

Parameters

<i>capacity</i>	The capacity to initialize the UnitySurrogateBase with.
-----------------	---

Implemented in [UnityValueSurrogate< T, TReaderWriter >](#), [UnityLinkedListSurrogate< T, ReaderWriter >](#), [UnityDictionarySurrogate< KeyType, KeyReaderWriter, ValueType, ValueReaderWriter >](#), and [UnityArraySurrogate< T, ReaderWriter >](#).

6.80.2.2 Read()

```
abstract void Read (  
    int * data,  
    int capacity ) [pure virtual]
```

Reads data from a specified memory location into the [UnitySurrogateBase](#).

Parameters

<i>data</i>	The memory location to read from.
<i>capacity</i>	The number of elements to read.

Implements [IUnitySurrogate](#).

Implemented in [UnityValueSurrogate< T, TReaderWriter >](#), [UnityLinkedListSurrogate< T, ReaderWriter >](#), [UnityDictionarySurrogate< KeyType, KeyReaderWriter, ValueType, ValueReaderWriter >](#), and [UnityArraySurrogate< T, ReaderWriter >](#).

6.80.2.3 Write()

```
abstract void Write (  
    int * data,  
    int capacity ) [pure virtual]
```

Writes data from the [UnitySurrogateBase](#) to a specified memory location.

Parameters

<i>data</i>	The memory location to write to.
<i>capacity</i>	The number of elements to write.

Implements [IUnitySurrogate](#).

Implemented in [UnityValueSurrogate< T, TReaderWriter >](#), [UnityLinkedListSurrogate< T, ReaderWriter >](#), [UnityDictionarySurrogate< KeyType, KeyReaderWriter, ValueType, ValueReaderWriter >](#), and [UnityArraySurrogate< T, ReaderWriter >](#).

6.81 UnityValueSurrogate< T, TReaderWriter > Class Template Reference

Represents a base class for Unity value surrogates. This class is serializable and provides methods for reading, writing, and initializing data.

Inherits [UnitySurrogateBase](#), and [IUnityValueSurrogate< T >](#).

Public Member Functions

- override void [Init](#) (int capacity)
Initializes the [UnityValueSurrogate](#) with a specified capacity.
- override void [Read](#) (int *data, int capacity)
Reads data into the [UnityValueSurrogate](#) from a specified memory location.
- override void [Write](#) (int *data, int capacity)
Writes data from the [UnityValueSurrogate](#) to a specified memory location.

Properties

- abstract T [DataProperty](#) [get, set]
Gets or sets the data for the [UnityValueSurrogate](#).

6.81.1 Detailed Description

Represents a base class for Unity value surrogates. This class is serializable and provides methods for reading, writing, and initializing data.

Template Parameters

<i>T</i>	The type of the data.
<i>TReaderWriter</i>	The type of the reader/writer for the data. Must be unmanaged and implement IElementReaderWriter{T} .

Type Constraints

TReaderWriter : *unmanaged*

TReaderWriter : *IEnumeratorWriter*<*T*>

6.81.2 Member Function Documentation

6.81.2.1 Init()

```
override void Init (
    int capacity ) [virtual]
```

Initializes the [UnityValueSurrogate](#) with a specified capacity.

Parameters

<i>capacity</i>	The capacity to initialize the UnityValueSurrogate with.
-----------------	--

Implements [UnitySurrogateBase](#).

6.81.2.2 Read()

```
override void Read (
    int * data,
    int capacity ) [virtual]
```

Reads data into the [UnityValueSurrogate](#) from a specified memory location.

Parameters

<i>data</i>	The memory location to read from.
<i>capacity</i>	The number of elements to read.

Implements [UnitySurrogateBase](#).

6.81.2.3 Write()

```
override void Write (
    int * data,
    int capacity ) [virtual]
```

Writes data from the [UnityValueSurrogate](#) to a specified memory location.

Parameters

<i>data</i>	The memory location to write to.
<i>capacity</i>	The number of elements to write.

Implements [UnitySurrogateBase](#).

6.81.3 Property Documentation

6.81.3.1 DataProperty

```
abstract T DataProperty [get], [set]
```

Gets or sets the data for the [UnityValueSurrogate](#).

6.82 InterpolatedErrorCorrectionSettings Class Reference

A set of parameters that tune the interpolated correction of prediction error on transform data.

Public Attributes

- Single [MaxRate](#) = 10f
- Single [MinRate](#) = 3.3f
- Single [PosBlendEnd](#) = 1f
- Single [PosBlendStart](#) = 0.25f
- Single [PosMinCorrection](#) = 0.025f
- Single [PosTeleportDistance](#) = 2f
- Single [RotBlendEnd](#) = 0.5f
- Single [RotBlendStart](#) = 0.1f
- Single [RotTeleportRadians](#) = 1.5f

6.82.1 Detailed Description

A set of parameters that tune the interpolated correction of prediction error on transform data.

6.82.2 Member Data Documentation

6.82.2.1 MaxRate

Single MaxRate = 10f

A factor with dimension of 1/s (Hz) that works as a upper limit for how much of the accumulated prediction error is corrected every frame. This factor affects both the position and the rotation correction. Suggested values are greater than [MinRate](#) and smaller than half of a target rendering rate.

E.g.: MaxRate = 15, rendering delta time = (1/60)s: at maximum 25% ($15 * 1/60$) of the accumulated error will be corrected on this rendered frame.

This threshold might not be respected if the resultant correction magnitude is below the [PosMinCorrection](#) or above the [PosTeleportDistance](#), for the position error, or above the [RotTeleportRadians](#), for the rotation error.

6.82.2.2 MinRate

Single MinRate = 3.3f

A factor with dimension of 1/s (Hz) that works as a lower limit for how much of the accumulated prediction error is corrected every frame. This factor affects both the position and the rotation correction. Suggested values are greater than zero and smaller than [MaxRate](#).

E.g.: MinRate = 3, rendering delta time = (1/60)s: at least 5% ($3 * 1/60$) of the accumulated error will be corrected on this rendered frame.

This threshold might not be respected if the resultant correction magnitude is below the [PosMinCorrection](#) or above the [PosTeleportDistance](#), for the position error, or above the [RotTeleportRadians](#), for the rotation error.

6.82.2.3 PosBlendEnd

Single PosBlendEnd = 1f

The reference for the magnitude of the accumulated position error, in meters, at which the position error will be corrected at the [MaxRate](#). Suggested values are greater than [PosBlendStart](#) and smaller than [PosTeleportDistance](#).

In other words, if the magnitude of the accumulated error is equal to or greater than this threshold, it will be corrected at the [MaxRate](#). If, instead, the magnitude is between [PosBlendStart](#) and this threshold, the error is corrected at a rate between [MinRate](#) and [MaxRate](#), proportionally. If it is equal to or smaller than [PosBlendStart](#), it will be corrected at the [MinRate](#).

Note: as the factor is expressed in distance units (meters), it might need to be scaled proportionally to the overall scale of objects in the scene and speeds at which they move, which are factors that affect the expected magnitude of prediction errors.

6.82.2.4 PosBlendStart

Single PosBlendStart = 0.25f

The reference for the magnitude of the accumulated position error, in meters, at which the position error will be corrected at the [MinRate](#). Suggested values are greater than [PosMinCorrection](#) and smaller than [PosBlendEnd](#).

In other words, if the magnitude of the accumulated error is equal to or smaller than this threshold, it will be corrected at the [MinRate](#). If, instead, the magnitude is between this threshold and [PosBlendEnd](#), the error is corrected at a rate between [MinRate](#) and [MaxRate](#), proportionally. If it is equal to or greater than [PosBlendEnd](#), it will be corrected at the [MaxRate](#).

Note: as the factor is expressed in distance units (meters), it might need to be scaled proportionally to the overall scale of objects in the scene and speeds at which they move, which are factors that affect the expected magnitude of prediction errors.

6.82.2.5 PosMinCorrection

```
Single PosMinCorrection = 0.025f
```

The value, in meters, that represents the minimum magnitude of the accumulated position error that will be corrected in a single frame, until it is fully corrected.

This setting has priority over the resultant correction rate, i.e. the restriction will be respected even if it makes the effective correction rate be different than the one computed according to the min/max rates and start/end blend values. Suggested values are greater than zero and smaller than [PosBlendStart](#).

Note: as the factor is expressed in distance units (meters), it might need to be scaled proportionally to the overall scale of objects in the scene and speeds at which they move, which are factors that affect the expected magnitude of prediction errors.

6.82.2.6 PosTeleportDistance

```
Single PosTeleportDistance = 2f
```

The value, in meters, that represents the magnitude of the accumulated position error above which the error will be instantaneously corrected, effectively teleporting the rendered object to its correct position. Suggested values are greater than [PosBlendEnd](#).

This setting has priority over the resultant correction rate, i.e. the restriction will be respected even if it makes the effective correction rate be different than the one computed according to the min/max rates and start/end blend values.

Note: as the factor is expressed in distance units (meters), it might need to be scaled proportionally to the overall scale of objects in the scene and speeds at which they move, which are factors that affect the expected magnitude of prediction errors.

6.82.2.7 RotBlendEnd

```
Single RotBlendEnd = 0.5f
```

The reference for the magnitude of the accumulated rotation error, in radians, at which the rotation error will be corrected at the [MaxRate](#). Suggested values are greater than [RotBlendStart](#) and smaller than [RotTeleportRadians](#).

In other words, if the magnitude of the accumulated error is equal to or greater than this threshold, it will be corrected at the [MaxRate](#). If, instead, the magnitude is between [RotBlendStart](#) and this threshold, the error is corrected at a rate between [MinRate](#) and [MaxRate](#), proportionally. If it is equal to or smaller than [RotBlendStart](#), it will be corrected at the [MinRate](#).

6.82.2.8 RotBlendStart

```
Single RotBlendStart = 0.1f
```

The reference for the magnitude of the accumulated rotation error, in radians, at which the rotation error will be corrected at the [MinRate](#). Suggested values are smaller than [RotBlendEnd](#).

In other words, if the magnitude of the accumulated error is equal to or smaller than this threshold, it will be corrected at the [MinRate](#). If, instead, the magnitude is between this threshold and [RotBlendEnd](#), the error is corrected at a rate between [MinRate](#) and [MaxRate](#), proportionally. If it is equal to or greater than [RotBlendEnd](#), it will be corrected at the [MaxRate](#).

6.82.2.9 RotTeleportRadians

```
Single RotTeleportRadians = 1.5f
```

The value, in radians, that represents the magnitude of the accumulated rotation error above which the error will be instantaneously corrected, effectively teleporting the rendered object to its correct orientation. Suggested values are greater than [RotBlendEnd](#).

This setting has priority over the resultant correction rate, i.e. the restriction will be respected even if it makes the effective correction rate be different than the one computed according to the min/max rates and start/end blend values.

6.83 IPlayerJoined Interface Reference

Interface for handling the event when a player joins the game.

Public Member Functions

- void [PlayerJoined](#) ([PlayerRef](#) player)
Method to be called when a player joins the game.

6.83.1 Detailed Description

Interface for handling the event when a player joins the game.

6.83.2 Member Function Documentation

6.83.2.1 PlayerJoined()

```
void PlayerJoined (  
    PlayerRef player )
```

Method to be called when a player joins the game.

Parameters

<i>player</i>	The player who joined the game.
---------------	---------------------------------

6.84 IPlayerLeft Interface Reference

Interface for handling the event when a player leaves the game.

Public Member Functions

- void [PlayerLeft](#) ([PlayerRef](#) player)

Method to be called when a player leaves the game.

6.84.1 Detailed Description

Interface for handling the event when a player leaves the game.

6.84.2 Member Function Documentation

6.84.2.1 PlayerLeft()

```
void PlayerLeft (
    PlayerRef player )
```

Method to be called when a player leaves the game.

Parameters

<i>player</i>	The player who left the game.
---------------	-------------------------------

6.85 IRemotePrefabCreated Interface Reference

Interface for handling the event when a remote prefab is created.

Public Member Functions

- void [RemotePrefabCreated](#) ()

Method to be called when a remote prefab is created.

6.85.1 Detailed Description

Interface for handling the event when a remote prefab is created.

6.85.2 Member Function Documentation

6.85.2.1 RemotePrefabCreated()

```
void RemotePrefabCreated ( )
```

Method to be called when a remote prefab is created.

6.86 ISceneLoadDone Interface Reference

Interface for handling the event when a scene load operation is completed.

Public Member Functions

- void [SceneLoadDone](#) (in [SceneLoadDoneArgs](#) sceneInfo)
Method to be called when a scene load operation is completed.

6.86.1 Detailed Description

Interface for handling the event when a scene load operation is completed.

6.86.2 Member Function Documentation

6.86.2.1 SceneLoadDone()

```
void SceneLoadDone (
    in SceneLoadDoneArgs sceneInfo )
```

Method to be called when a scene load operation is completed.

Parameters

<i>sceneInfo</i>	The information about the loaded scene.
------------------	---

6.87 ISceneLoadStart Interface Reference

Interface for handling the event when a scene load operation is started.

Public Member Functions

- void [SceneLoadStart](#) ([SceneRef](#) sceneRef)
Method to be called when a scene load operation is started.

6.87.1 Detailed Description

Interface for handling the event when a scene load operation is started.

6.87.2 Member Function Documentation

6.87.2.1 SceneLoadStart()

```
void SceneLoadStart (
    SceneRef sceneRef )
```

Method to be called when a scene load operation is started.

Parameters

<i>sceneRef</i>	Reference to the scene that is being loaded.
-----------------	--

6.88 ISimulationEnter Interface Reference

Interface for [SimulationEnter](#) callback. Called when the [NetworkObject](#) joins AreaOfInterest. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

Public Member Functions

- void [SimulationEnter](#) ()

Called when the [NetworkObject](#) joins AreaOfInterest. Object is now receiving snapshot updates. Object will execute [NetworkBehaviour](#) FixedUpdateNetwork() and Render() methods until the object leaves simulation.

6.88.1 Detailed Description

Interface for [SimulationEnter](#) callback. Called when the [NetworkObject](#) joins AreaOfInterest. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

6.88.2 Member Function Documentation

6.88.2.1 SimulationEnter()

```
void SimulationEnter ( )
```

Called when the [NetworkObject](#) joins AreaOfInterest. Object is now receiving snapshot updates. Object will execute [NetworkBehaviour](#) FixedUpdateNetwork() and Render() methods until the object leaves simulation.

6.89 ISimulationExit Interface Reference

Interface for the [SimulationExit](#) callback. Called when the [NetworkObject](#) leaves AreaOfInterest. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

Public Member Functions

- void [SimulationExit](#) ()

Called when the [NetworkObject](#) leaves AreaOfInterest. Object is no longer receiving snapshot updates. Object will stop executing [NetworkBehaviour](#) FixedUpdateNetwork() and Render() methods until the object rejoins simulation.

6.89.1 Detailed Description

Interface for the [SimulationExit](#) callback. Called when the [NetworkObject](#) leaves AreaOfInterest. Implement this interface on [SimulationBehaviour](#) and [NetworkBehaviour](#) classes.

6.89.2 Member Function Documentation

6.89.2.1 SimulationExit()

```
void SimulationExit ( )
```

Called when the [NetworkObject](#) leaves AreaOfInterest. Object is no longer receiving snapshot updates. Object will stop executing [NetworkBehaviour](#) FixedUpdateNetwork() and Render() methods until the object rejoins simulation.

6.90 ISpawned Interface Reference

Interface for handling the event when an object is spawned.

Inherited by [NetworkBehaviour](#).

Public Member Functions

- void [Spawned](#) ()

Method to be called when an object is spawned.

6.90.1 Detailed Description

Interface for handling the event when an object is spawned.

6.90.2 Member Function Documentation

6.90.2.1 Spawned()

```
void Spawned ( )
```

Method to be called when an object is spawned.

Implemented in [NetworkTransform](#), [NetworkMecanimAnimator](#), and [NetworkBehaviour](#).

6.91 IStateAuthorityChanged Interface Reference

Interface for handling the event when the state authority changes.

Public Member Functions

- void [StateAuthorityChanged](#) ()
Method to be called when the state authority changes.

6.91.1 Detailed Description

Interface for handling the event when the state authority changes.

6.91.2 Member Function Documentation

6.91.2.1 StateAuthorityChanged()

```
void StateAuthorityChanged ( )
```

Method to be called when the state authority changes.

6.92 LagCompensatedHit Struct Reference

Defines a lag compensated query hit result.

Static Public Member Functions

- static [operator LagCompensatedHit](#) (RaycastHit raycastHit)
Creates a [LagCompensatedHit](#) structure from the information on a Unity RaycastHit.
- static [operator LagCompensatedHit](#) (RaycastHit2D raycastHit2D)
Creates a [LagCompensatedHit](#) structure from the information on a Unity RaycastHit2D.

Public Attributes

- Collider [Collider](#)
PhysX collider hit. Null in case hit is a [Fusion Hitbox](#) or a Box2D hit.
- Collider2D [Collider2D](#)
Box2D collider hit. Null in case hit is a [Fusion Hitbox](#) or a PhysX hit.
- float [Distance](#)
Distance (if requested) to hit, at the lag compensated time.
- GameObject [GameObject](#)
The Unity Game Object that was hit. Its data is not lag compensated. This is either the [Hitbox](#)'s or the [Collider](#)'s gameObject, depending on the object hit being a lag-compensated [Hitbox](#) or a regular Unity collider, respectively.
- [Hitbox](#) [Hitbox](#)
[Fusion](#)'s [Hitbox](#). Null in case the hit was on PhysX or Box2D.
- Vector3 [Normal](#)
Surface normal (if requested) of the hit, at the lag compensated time.
- Vector3 [Point](#)
Point of impact of the hit, at the lag compensated time.
- [HitType](#) [Type](#)
Hit object source (PhysX or [Fusion](#) Hitboxes).

6.92.1 Detailed Description

Defines a lag compensated query hit result.

6.92.2 Member Function Documentation

6.92.2.1 operator LagCompensatedHit() [1/2]

```
static operator LagCompensatedHit (
    RaycastHit raycastHit ) [explicit], [static]
```

Creates a [LagCompensatedHit](#) structure from the information on a Unity RaycastHit.

Parameters

<i>raycastHit</i>	The RaycastHit used as source.
-------------------	--------------------------------

Returns

The built [LagCompensatedHit](#) structure.

6.92.2.2 operator LagCompensatedHit() [2/2]

```
static operator LagCompensatedHit (  
    RaycastHit2D raycastHit2D ) [explicit], [static]
```

Creates a [LagCompensatedHit](#) structure from the information on a Unity RaycastHit2D.

Parameters

<i>raycastHit2D</i>	The RaycastHit2D used as source.
---------------------	----------------------------------

Returns

The built [LagCompensatedHit](#) structure.

6.92.3 Member Data Documentation

6.92.3.1 Collider

Collider Collider

PhysX collider hit. Null in case hit is a [Fusion Hitbox](#) or a Box2D hit.

6.92.3.2 Collider2D

Collider2D Collider2D

Box2D collider hit. Null in case hit is a [Fusion Hitbox](#) or a PhysX hit.

6.92.3.3 Distance

float Distance

Distance (if requested) to hit, at the lag compensated time.

6.92.3.4 GameObject

GameObject GameObject

The Unity Game Object that was hit. Its data is not lag compensated. This is either the [Hitbox](#)'s or the [Collider](#)'s gameObject, depending on the object hit being a lag-compensated [Hitbox](#) or a regular Unity collider, respectively.

6.92.3.5 Hitbox

Hitbox Hitbox

[Fusion](#)'s [Hitbox](#). Null in case the hit was on PhysX or Box2D.

6.92.3.6 Normal

Vector3 Normal

Surface normal (if requested) of the hit, at the lag compensated time.

6.92.3.7 Point

Vector3 Point

Point of impact of the hit, at the lag compensated time.

6.92.3.8 Type

HitType Type

Hit object source (PhysX or [Fusion](#) Hitboxes).

6.93 AABB Struct Reference

Represents an Axis-Aligned Bounding Box ([AABB](#)).

Public Member Functions

- [AABB](#) (Bounds bounds)
Constructs an [AABB](#) from a Unity Bounds object.
- [AABB](#) (Vector3 center, Vector3 extents)
Constructs an [AABB](#) from a center point and extents.

Public Attributes

- readonly Vector3 [Center](#)
Represents the center of the [AABB](#).
- readonly Vector3 [Extents](#)
Represents the extents (half-widths) of the [AABB](#).
- readonly Vector3 [Max](#)
Represents the maximum point (upper corner) of the [AABB](#).
- readonly Vector3 [Min](#)
Represents the minimum point (lower corner) of the [AABB](#).

6.93.1 Detailed Description

Represents an Axis-Aligned Bounding Box ([AABB](#)).

6.93.2 Constructor & Destructor Documentation

6.93.2.1 [AABB\(\)](#) [1/2]

```
AABB (
    Bounds bounds )
```

Constructs an [AABB](#) from a Unity Bounds object.

Parameters

<i>bounds</i>	The Unity Bounds object to construct the AABB from.
---------------	---

6.93.2.2 [AABB\(\)](#) [2/2]

```
AABB (
    Vector3 center,
    Vector3 extents )
```

Constructs an [AABB](#) from a center point and extents.

Parameters

<i>center</i>	The center point of the AABB .
<i>extents</i>	The extents (half-widths) of the AABB .

6.93.3 Member Data Documentation

6.93.3.1 Center

`readonly Vector3 Center`

Represents the center of the [AABB](#).

6.93.3.2 Extents

`readonly Vector3 Extents`

Represents the extents (half-widths) of the [AABB](#).

6.93.3.3 Max

`readonly Vector3 Max`

Represents the maximum point (upper corner) of the [AABB](#).

6.93.3.4 Min

`readonly Vector3 Min`

Represents the minimum point (lower corner) of the [AABB](#).

6.94 BoxOverlapQuery Class Reference

Class that represents a box overlap query. Used to query against the [NetworkRunner.LagCompensation](#) API.

Inherits [Query](#).

Public Member Functions

- [BoxOverlapQuery](#) (ref [BoxOverlapQueryParams](#) boxOverlapParams)
Create a new [BoxOverlapQuery](#) with the given boxOverlapParams .
- [BoxOverlapQuery](#) (ref [BoxOverlapQueryParams](#) boxOverlapParams, Collider[] physXOverlapHitsCache, Collider2D[] box2DOverlapHitsCache)
Create a new [BoxOverlapQuery](#) with the given boxOverlapParams . The result colliders arrays can be provided to avoid allocation.

Public Attributes

- Vector3 [Center](#)
The box query center.
- Vector3 [Extents](#)
The box query extents.
- Quaternion [Rotation](#)
The box query rotation.

Protected Member Functions

- override bool [Check](#) (ref [AABB](#) bounds)
Check if the given bounds overlaps with this query.

6.94.1 Detailed Description

Class that represents a box overlap query. Used to query against the [NetworkRunner.LagCompensation](#) API.

6.94.2 Constructor & Destructor Documentation

6.94.2.1 BoxOverlapQuery() [1/2]

```
BoxOverlapQuery (
    ref BoxOverlapQueryParams boxOverlapParams )
```

Create a new [BoxOverlapQuery](#) with the given *boxOverlapParams* .

Parameters

<i>boxOverlapParams</i>	The parameters to be used when creating the query.
-------------------------	--

6.94.2.2 BoxOverlapQuery() [2/2]

```
BoxOverlapQuery (
    ref BoxOverlapQueryParams boxOverlapParams,
    Collider[] physXOverlapHitsCache,
    Collider2D[] box2DOverlapHitsCache )
```

Create a new [BoxOverlapQuery](#) with the given *boxOverlapParams* . The result colliders arrays can be provided to avoid allocation.

Parameters

<i>boxOverlapParams</i>	The parameters to be used when creating the query.
<i>physXOverlapHitsCache</i>	Array to write the results of the PhysX query if used.
<i>box2DOverlapHitsCache</i>	Array to write the results of the Box2D query if used.

6.94.3 Member Function Documentation

6.94.3.1 Check()

```
override bool Check (  
    ref AABB bounds ) [protected], [virtual]
```

Check if the given *bounds* overlaps with this query.

Parameters

<i>bounds</i>	The bounds to check.
---------------	----------------------

Returns

True if the bounds overlaps with this query, false otherwise.

Implements [Query](#).

6.94.4 Member Data Documentation

6.94.4.1 Center

```
Vector3 Center
```

The box query center.

6.94.4.2 Extents

```
Vector3 Extents
```

The box query extents.

6.94.4.3 Rotation

Quaternion Rotation

The box query rotation.

6.95 BoxOverlapQueryParams Struct Reference

Base parameters needed to execute a box overlap query

Public Member Functions

- [BoxOverlapQueryParams](#) ([QueryParams](#) queryParams, Vector3 center, Vector3 extents, Quaternion rotation, int staticHitsCapacity)
Create a new [BoxOverlapQueryParams](#)

Public Attributes

- Vector3 [Center](#)
Represents the center of the box for the overlap query.
- Vector3 [Extents](#)
Represents the extents of the box for the overlap query.
- [QueryParams](#) [QueryParams](#)
Represents the base parameters for the query.
- Quaternion [Rotation](#)
Represents the rotation of the box for the overlap query.
- int [StaticHitsCapacity](#)
Represents the capacity for the cached PhysX and Box2D static hits.

6.95.1 Detailed Description

Base parameters needed to execute a box overlap query

6.95.2 Constructor & Destructor Documentation

6.95.2.1 BoxOverlapQueryParams()

```
BoxOverlapQueryParams (
    QueryParams queryParams,
    Vector3 center,
    Vector3 extents,
    Quaternion rotation,
    int staticHitsCapacity )
```

Create a new [BoxOverlapQueryParams](#)

Parameters

<i>queryParams</i>	Parameters to be used
<i>center</i>	The query center
<i>extents</i>	The query extents
<i>rotation</i>	The query rotation
<i>staticHitsCapacity</i>	Capacity for the cached PhysX and Box2D static hits.

6.95.3 Member Data Documentation**6.95.3.1 Center**

`Vector3 Center`

Represents the center of the box for the overlap query.

6.95.3.2 Extents

`Vector3 Extents`

Represents the extents of the box for the overlap query.

6.95.3.3 QueryParams

[QueryParams](#) `QueryParams`

Represents the base parameters for the query.

6.95.3.4 Rotation

`Quaternion Rotation`

Represents the rotation of the box for the overlap query.

6.95.3.5 StaticHitsCapacity

```
int StaticHitsCapacity
```

Represents the capacity for the cached PhysX and Box2D static hits.

6.96 BVHDraw Class Reference

Provide a way to iterate over BVH and return a [BVHNodeDrawInfo](#) for each node.

Inherits `IEnumerator< BVHNodeDrawInfo >`.

Public Member Functions

- `IEnumerator< BVHNodeDrawInfo > GetEnumerator ()`
Returns an enumerator that iterates through the [BVHNodeDrawInfo](#).

6.96.1 Detailed Description

Provide a way to iterate over BVH and return a [BVHNodeDrawInfo](#) for each node.

6.96.2 Member Function Documentation

6.96.2.1 GetEnumerator()

```
IEnumerator<BVHNodeDrawInfo> GetEnumerator ()
```

Returns an enumerator that iterates through the [BVHNodeDrawInfo](#).

6.97 BVHNodeDrawInfo Class Reference

Container class to provide the necessary info to draw nodes from the BVH

Properties

- `Bounds Bounds [get]`
Get the node Bounds
- `int Depth [get]`
Get the node depth on the BVH
- `int MaxDepth [get]`
Get the BVH max depth

6.97.1 Detailed Description

Container class to provide the necessary info to draw nodes from the BVH

6.97.2 Property Documentation

6.97.2.1 Bounds

`Bounds Bounds [get]`

Get the node Bounds

6.97.2.2 Depth

`int Depth [get]`

Get the node depth on the BVH

6.97.2.3 MaxDepth

`int MaxDepth [get]`

Get the BVH max depth

6.98 ColliderDrawInfo Class Reference

Container class to provide the necessary information to draw a hitbox collider

Properties

- `Vector3 BoxExtents [get]`
The box extends of the collider Used on [HitboxTypes](#) of types: Box
- `float CapsuleHeight [get]`
*The height for capsule colliders.
See also*
[HitboxTypes](#)
- `Matrix4x4 LocalToWorldMatrix [get]`
The local to world matrix of the collider.
- `Vector3 Offset [get]`
The offset of the collider.
- `float Radius [get]`
The radius of the collider. Used on [HitboxTypes](#) of types: Sphere and Capsule.
- `HitboxTypes Type [get]`
The [HitboxTypes](#) of the collider.

6.98.1 Detailed Description

Container class to provide the necessary information to draw a hitbox collider

6.98.2 Property Documentation

6.98.2.1 BoxExtents

`Vector3 BoxExtents [get]`

The box extends of the collider Used on [HitboxTypes](#) of types: Box

6.98.2.2 CapsuleHeight

`float CapsuleHeight [get]`

The height for capsule colliders.

See also

[HitboxTypes](#)

6.98.2.3 LocalToWorldMatrix

`Matrix4x4 LocalToWorldMatrix [get]`

The local to world matrix of the collider.

6.98.2.4 Offset

`Vector3 Offset [get]`

The offset of the collider.

6.98.2.5 Radius

```
float Radius [get]
```

The radius of the collider. Used on [HitboxTypes](#) of types: Sphere and Capsule.

6.98.2.6 Type

```
HitboxTypes Type [get]
```

The [HitboxTypes](#) of the collider.

6.99 HitboxColliderContainerDraw Class Reference

Provide a way to iterate over the HitboxBuffer.HitboxSnapshot and return the [ColliderDrawInfo](#) for each collider on the snapshot.

Inherits `IEnumerable< ColliderDrawInfo >`.

Public Member Functions

- `IEnumerator< ColliderDrawInfo > GetEnumerator ()`
Returns an enumerator that iterates through the [ColliderDrawInfo](#) of this container.

6.99.1 Detailed Description

Provide a way to iterate over the HitboxBuffer.HitboxSnapshot and return the [ColliderDrawInfo](#) for each collider on the snapshot.

6.99.2 Member Function Documentation

6.99.2.1 GetEnumerator()

```
IEnumerator<ColliderDrawInfo> GetEnumerator ( )
```

Returns an enumerator that iterates through the [ColliderDrawInfo](#) of this container.

6.100 LagCompensatedExt Class Reference

LagCompensated Extension methods

Static Public Member Functions

- static void [SortDistance](#) (this List< [LagCompensatedHit](#) > hits)
Sorts all hits in ascending order of [LagCompensatedHit.Distance](#).
- static void [SortReference](#) (this List< [LagCompensatedHit](#) > hits, Vector3 reference)
Sorts all hits in ascending order of distance from [LagCompensatedHit.Point](#) to the reference point.

6.100.1 Detailed Description

LagCompensated Extension methods

6.100.2 Member Function Documentation

6.100.2.1 SortDistance()

```
static void SortDistance (  
    this List< LagCompensatedHit > hits ) [static]
```

Sorts all *hits* in ascending order of [LagCompensatedHit.Distance](#).

Parameters

<i>hits</i>	List containing hits to be sorted.
-------------	------------------------------------

Exceptions

<i>NullReferenceException</i>	If <i>hits</i> are null.
-------------------------------	--------------------------

6.100.2.2 SortReference()

```
static void SortReference (  
    this List< LagCompensatedHit > hits,  
    Vector3 reference ) [static]
```

Sorts all *hits* in ascending order of distance from [LagCompensatedHit.Point](#) to the *reference* point.

Parameters

<i>hits</i>	List containing hits to be sorted.
<i>reference</i>	Used as reference point to compute distance from hit points.

Exceptions

<code>NullReferenceException</code>	If <i>hits</i> are null.
-------------------------------------	--------------------------

6.101 LagCompensationDraw Class Reference

Provide access to iterate over the lag compensation system components and give the necessary information to draw them.

Static Public Member Functions

- static void [GizmosDrawWireCapsule](#) (Vector3 topCenter, Vector3 bottomCenter, float capsuleRadius)
Method to draw capsules out of simple shapes.

Public Attributes

- [BVHDraw](#) [BVHDraw](#)
Iterate over to get the BVH node draw data.
- [SnapshotHistoryDraw](#) [SnapshotHistoryDraw](#)
Iterate over to get the hitbox snapshots draw data. Iterate the received hitbox snapshot draw data to get all the colliders draw info for that snapshot.

6.101.1 Detailed Description

Provide access to iterate over the lag compensation system components and give the necessary information to draw them.

6.101.2 Member Function Documentation

6.101.2.1 GizmosDrawWireCapsule()

```
static void GizmosDrawWireCapsule (
    Vector3 topCenter,
    Vector3 bottomCenter,
    float capsuleRadius ) [static]
```

Method to draw capsules out of simple shapes.

Parameters

<i>topCenter</i>	The top capsule end position
<i>bottomCenter</i>	The bottom capsule end position
<i>capsuleRadius</i>	The capsule radius

6.101.3 Member Data Documentation

6.101.3.1 BVHDraw

`BVHDraw` `BVHDraw`

Iterate over to get the BVH node draw data.

6.101.3.2 SnapshotHistoryDraw

`SnapshotHistoryDraw` `SnapshotHistoryDraw`

Iterate over to get the hitbox snapshots draw data. Iterate the received hitbox snapshot draw data to get all the colliders draw info for that snapshot.

6.102 LagCompensationUtils.ContactData Struct Reference

Details regarding a shape intersection. It does not carry information about the intersection happening or not.

Public Attributes

- Vector3 `Normal`
Vector that described the plane of smallest penetration between the shapes.
- float `Penetration`
Penetration along the normal plane.
- Vector3 `Point`
Contact point.

6.102.1 Detailed Description

Details regarding a shape intersection. It does not carry information about the intersection happening or not.

6.102.2 Member Data Documentation

6.102.2.1 Normal

`Vector3` `Normal`

Vector that described the plane of smallest penetration between the shapes.

6.102.2.2 Penetration

`float Penetration`

Penetration along the normal plane.

6.102.2.3 Point

`Vector3 Point`

Contact point.

6.103 PositionRotationQueryParams Struct Reference

[Query](#) parameters for position rotation query

Public Member Functions

- [PositionRotationQueryParams](#) ([QueryParams](#) queryParams, [Hitbox](#) hitbox)
Create a new [PositionRotationQueryParams](#).

Public Attributes

- [Hitbox](#) Hitbox
Represents the hitbox to be queried.
- [QueryParams](#) QueryParams
Represents the base parameters for the query.

6.103.1 Detailed Description

[Query](#) parameters for position rotation query

6.103.2 Constructor & Destructor Documentation

6.103.2.1 PositionRotationQueryParams()

```
PositionRotationQueryParams (
    QueryParams queryParams,
    Hitbox hitbox )
```

Create a new [PositionRotationQueryParams](#).

Parameters

<code>queryParams</code>	Parameters to be used
<code>hitbox</code>	The hitbox to be queried

6.103.3 Member Data Documentation

6.103.3.1 Hitbox

`Hitbox Hitbox`

Represents the hitbox to be queried.

6.103.3.2 QueryParams

`QueryParams QueryParams`

Represents the base parameters for the query.

6.104 Query Class Reference

Base class for all Lag Compensation queries

Inherits `IBoundsTraversalTest`.

Inherited by [BoxOverlapQuery](#), [RaycastQuery](#), and [SphereOverlapQuery](#).

Public Attributes

- float? [Alpha](#)
Represents the interpolation factor between the current and next simulation tick.
- LayerMask [LayerMask](#)
Represents the layer mask to selectively ignore colliders when performing the query.
- [HitOptions Options](#)
Represents the options for the hit detection of the query.
- [PlayerRef Player](#)
Represents the player who initiated the query.
- PreProcessingDelegate [PreProcessingDelegate](#)
Represents the delegate to be called for pre-processing before the query is performed.
- int? [Tick](#)
Represents the simulation tick at which the query was initiated.
- int? [TickTo](#)
Represents the simulation tick to which the query is performed.
- QueryTriggerInteraction [TriggerInteraction](#)
Represents the interaction type of the query with triggers.
- void * [UserArgs](#)
Represents the user arguments for the query.

Protected Member Functions

- abstract bool [Check](#) (ref [AABB](#) bounds)
Checks if the provided bounds should be included in the query.
- [Query](#) (ref [QueryParams](#) qParams)
Initializes a new instance of the [Query](#) class using the provided [QueryParams](#).

6.104.1 Detailed Description

Base class for all Lag Compensation queries

6.104.2 Constructor & Destructor Documentation

6.104.2.1 Query()

```
Query (
    ref QueryParams qParams ) [protected]
```

Initializes a new instance of the [Query](#) class using the provided [QueryParams](#).

Parameters

<i>qParams</i>	The QueryParams to use for initializing the Query .
----------------	---

6.104.3 Member Function Documentation

6.104.3.1 Check()

```
abstract bool Check (
    ref AABB bounds ) [protected], [pure virtual]
```

Checks if the provided bounds should be included in the query.

Parameters

<i>bounds</i>	The bounds to check.
---------------	----------------------

Returns

True if the bounds should be included in the query, false otherwise.

Implemented in [SphereOverlapQuery](#), [RaycastQuery](#), and [BoxOverlapQuery](#).

6.104.4 Member Data Documentation

6.104.4.1 Alpha

`float?` Alpha

Represents the interpolation factor between the current and next simulation tick.

6.104.4.2 LayerMask

`LayerMask` LayerMask

Represents the layer mask to selectively ignore colliders when performing the query.

6.104.4.3 Options

`HitOptions` Options

Represents the options for the hit detection of the query.

6.104.4.4 Player

`PlayerRef` Player

Represents the player who initiated the query.

6.104.4.5 PreProcessingDelegate

`PreProcessingDelegate` PreProcessingDelegate

Represents the delegate to be called for pre-processing before the query is performed.

6.104.4.6 Tick

`int? Tick`

Represents the simulation tick at which the query was initiated.

6.104.4.7 TickTo

`int? TickTo`

Represents the simulation tick to which the query is performed.

6.104.4.8 TriggerInteraction

`QueryTriggerInteraction TriggerInteraction`

Represents the interaction type of the query with triggers.

6.104.4.9 UserArgs

`void* UserArgs`

Represents the user arguments for the query.

6.105 QueryParams Struct Reference

Base parameters needed to execute a query.

Public Attributes

- `float? Alpha`
Represents the interpolation factor between the current and next simulation tick.
- `LayerMask LayerMask`
Represents the layer mask to selectively ignore colliders when performing the query.
- `HitOptions Options`
Represents the options for the hit detection of the query.
- `PlayerRef Player`
Represents the player who initiated the query.
- `PreProcessingDelegate PreProcessingDelegate`
Represents the delegate to be called for pre-processing before the query is performed.
- `int Tick`
Represents the simulation tick at which the query was initiated.
- `int? TickTo`
Represents the simulation tick to which the query is performed.
- `QueryTriggerInteraction TriggerInteraction`
Represents the interaction type of the query with triggers.
- `void * UserArgs`
Represents the user arguments for the query.

6.105.1 Detailed Description

Base parameters needed to execute a query.

6.105.2 Member Data Documentation

6.105.2.1 Alpha

`float? Alpha`

Represents the interpolation factor between the current and next simulation tick.

6.105.2.2 LayerMask

`LayerMask LayerMask`

Represents the layer mask to selectively ignore colliders when performing the query.

6.105.2.3 Options

`HitOptions Options`

Represents the options for the hit detection of the query.

6.105.2.4 Player

`PlayerRef Player`

Represents the player who initiated the query.

6.105.2.5 PreProcessingDelegate

`PreProcessingDelegate PreProcessingDelegate`

Represents the delegate to be called for pre-processing before the query is performed.

6.105.2.6 Tick

`int Tick`

Represents the simulation tick at which the query was initiated.

6.105.2.7 TickTo

`int? TickTo`

Represents the simulation tick to which the query is performed.

6.105.2.8 TriggerInteraction

`QueryTriggerInteraction TriggerInteraction`

Represents the interaction type of the query with triggers.

6.105.2.9 UserArgs

`void* UserArgs`

Represents the user arguments for the query.

6.106 RaycastAllQuery Class Reference

Class that represents a raycast all query. Used to query against the [NetworkRunner.LagCompensation](#) API.

Inherits [RaycastQuery](#).

Public Member Functions

- [RaycastAllQuery](#) (ref [RaycastQueryParams](#) raycastQueryParams)
Create a new [RaycastAllQuery](#) with the given [RaycastQueryParams](#).
- [RaycastAllQuery](#) (ref [RaycastQueryParams](#) raycastQueryParams, RaycastHit[] physXRaycastHitsCache, RaycastHit2D[] box2DRaycastHitCache)
Create a new [RaycastAllQuery](#) with the given [RaycastQueryParams](#). The result colliders arrays can be provided to avoid allocation.

Additional Inherited Members

6.106.1 Detailed Description

Class that represents a raycast all query. Used to query against the [NetworkRunner.LagCompensation](#) API.

6.106.2 Constructor & Destructor Documentation

6.106.2.1 RaycastAllQuery() [1/2]

```
RaycastAllQuery (
    ref RaycastQueryParams raycastQueryParams )
```

Create a new [RaycastAllQuery](#) with the given [RaycastQueryParams](#).

Parameters

<i>raycastQueryParams</i>	The parameters to be used when creating the query.
---------------------------	--

6.106.2.2 RaycastAllQuery() [2/2]

```
RaycastAllQuery (
    ref RaycastQueryParams raycastQueryParams,
    RaycastHit[] physXRaycastHitsCache,
    RaycastHit2D[] box2DRaycastHitCache )
```

Create a new [RaycastAllQuery](#) with the given [RaycastQueryParams](#). The result colliders arrays can be provided to avoid allocation.

Parameters

<i>raycastQueryParams</i>	The parameters to be used when creating the query.
<i>physXRaycastHitsCache</i>	Array to write the results of the PhysX query if used.
<i>box2DRaycastHitCache</i>	Array to write the results of the Box2D query if used.

6.107 RaycastQuery Class Reference

Class that represents a raycast query. Used to query against the [NetworkRunner.LagCompensation](#) API.

Inherits [Query](#).

Inherited by [RaycastAllQuery](#).

Public Member Functions

- [RaycastQuery](#) (ref [RaycastQueryParams](#) raycastQueryParams)
Create a new [RaycastQuery](#) with the given [RaycastQueryParams](#)

Public Attributes

- Vector3 [Direction](#)
Represents the direction of the raycast for the query.
- float [Length](#)
Represents the maximum length of the raycast for the query.
- Vector3 [Origin](#)
Represents the origin point of the raycast for the query.

Protected Member Functions

- override bool [Check](#) (ref [AABB](#) bounds)
Check if the provided bounds should be included in the query.

6.107.1 Detailed Description

Class that represents a raycast query. Used to query against the [NetworkRunner.LagCompensation](#) API.

6.107.2 Constructor & Destructor Documentation

6.107.2.1 RaycastQuery()

```
RaycastQuery (  
    ref RaycastQueryParams raycastQueryParams )
```

Create a new [RaycastQuery](#) with the given [RaycastQueryParams](#)

Parameters

raycastQueryParams	The parameters to be used when creating the query.
------------------------------------	--

6.107.3 Member Function Documentation

6.107.3.1 Check()

```
override bool Check (
    ref AABB bounds ) [protected], [virtual]
```

Check if the provided bounds should be included in the query.

Parameters

<i>bounds</i>	The bounds to check.
---------------	----------------------

Returns

True if the bounds should be included in the query, false otherwise.

Implements [Query](#).

6.107.4 Member Data Documentation

6.107.4.1 Direction

```
Vector3 Direction
```

Represents the direction of the raycast for the query.

6.107.4.2 Length

```
float Length
```

Represents the maximum length of the raycast for the query.

6.107.4.3 Origin

```
Vector3 Origin
```

Represents the origin point of the raycast for the query.

6.108 RaycastQueryParams Struct Reference

Base parameters needed to execute a raycast query

Public Member Functions

- [RaycastQueryParams](#) ([QueryParams](#) queryParams, Vector3 origin, Vector3 direction, float length, int staticHitsCapacity=64)

Create a new [RaycastQueryParams](#)

Public Attributes

- Vector3 [Direction](#)
Represents the direction of the raycast for the query.
- float [Length](#)
Represents the maximum length of the raycast for the query.
- Vector3 [Origin](#)
Represents the origin point of the raycast for the query.
- [QueryParams](#) [QueryParams](#)
Represents the base parameters for the raycast query.
- int [StaticHitsCapacity](#)
Represents the capacity for the cached PhysX and Box2D static hits.

6.108.1 Detailed Description

Base parameters needed to execute a raycast query

6.108.2 Constructor & Destructor Documentation

6.108.2.1 RaycastQueryParams()

```
RaycastQueryParams (
    QueryParams queryParams,
    Vector3 origin,
    Vector3 direction,
    float length,
    int staticHitsCapacity = 64 )
```

Create a new [RaycastQueryParams](#)

Parameters

<i>queryParams</i>	Parameters to be used
<i>origin</i>	The raycast origin
<i>direction</i>	The raycast direction
<i>length</i>	The raycast max length
<i>staticHitsCapacity</i>	Capacity for the cached PhysX and Box2D static hits.

6.108.3 Member Data Documentation

6.108.3.1 Direction

`Vector3 Direction`

Represents the direction of the raycast for the query.

6.108.3.2 Length

`float Length`

Represents the maximum length of the raycast for the query.

6.108.3.3 Origin

`Vector3 Origin`

Represents the origin point of the raycast for the query.

6.108.3.4 QueryParams

`QueryParams QueryParams`

Represents the base parameters for the raycast query.

6.108.3.5 StaticHitsCapacity

`int StaticHitsCapacity`

Represents the capacity for the cached PhysX and Box2D static hits.

6.109 SnapshotHistoryDraw Class Reference

Provide a way to iterate over the HitboxBuffer and return the [HitboxColliderContainerDraw](#) container for each snapshot on the buffer.

Inherits `IEnumerable< HitboxColliderContainerDraw >`.

Public Member Functions

- `IEnumerator< HitboxColliderContainerDraw > GetEnumerator ()`
Returns an enumerator that iterates through the [HitboxColliderContainerDraw](#).

6.109.1 Detailed Description

Provide a way to iterate over the `HitboxBuffer` and return the [HitboxColliderContainerDraw](#) container for each snapshot on the buffer.

6.109.2 Member Function Documentation

6.109.2.1 GetEnumerator()

```
IEnumerator<HitboxColliderContainerDraw> GetEnumerator ( )
```

Returns an enumerator that iterates through the [HitboxColliderContainerDraw](#).

6.110 SphereOverlapQuery Class Reference

Class that represents a sphere overlap query. Used to query against the [NetworkRunner.LagCompensation](#) API.

Inherits [Query](#).

Public Member Functions

- [SphereOverlapQuery](#) (ref [SphereOverlapQueryParams](#) sphereOverlapParams)
Create a new [SphereOverlapQuery](#) with the given [SphereOverlapQueryParams](#).
- [SphereOverlapQuery](#) (ref [SphereOverlapQueryParams](#) sphereOverlapParams, Collider[] physXOverlapHitsCache, Collider2D[] box2DOverlapHitsCache)
Create a new [SphereOverlapQuery](#) with the given [SphereOverlapQueryParams](#).

Public Attributes

- Vector3 [Center](#)
Represents the center of the sphere for the overlap query.
- float [Radius](#)
Represents the radius of the sphere for the overlap query.

Protected Member Functions

- override bool [Check](#) (ref [AABB](#) bounds)
Check if the given [AABB](#) intersects with the sphere overlap query.

6.110.1 Detailed Description

Class that represents a sphere overlap query. Used to query against the [NetworkRunner.LagCompensation](#) API.

6.110.2 Constructor & Destructor Documentation

6.110.2.1 SphereOverlapQuery() [1/2]

```
SphereOverlapQuery (
    ref SphereOverlapQueryParams sphereOverlapParams )
```

Create a new [SphereOverlapQuery](#) with the given [SphereOverlapQueryParams](#).

Parameters

<i>sphereOverlapParams</i>	The parameters to be used when creating the query.
----------------------------	--

6.110.2.2 SphereOverlapQuery() [2/2]

```
SphereOverlapQuery (
    ref SphereOverlapQueryParams sphereOverlapParams,
    Collider[] physXOverlapHitsCache,
    Collider2D[] box2DOverlapHitsCache )
```

Create a new [SphereOverlapQuery](#) with the given [SphereOverlapQueryParams](#).

Parameters

<i>sphereOverlapParams</i>	The parameters to be used when creating the query.
<i>physXOverlapHitsCache</i>	Array to write the results of the PhysX query if used.
<i>box2DOverlapHitsCache</i>	Array to write the results of the Box2D query if used.

6.110.3 Member Function Documentation

6.110.3.1 Check()

```
override bool Check (
    ref AABB bounds ) [protected], [virtual]
```

Check if the given [AABB](#) intersects with the sphere overlap query.

Parameters

<code>bounds</code>	The bounds to check against.
---------------------	------------------------------

Returns

True if the bounds intersects with the sphere overlap query, false otherwise.

Implements [Query](#).

6.110.4 Member Data Documentation

6.110.4.1 Center

`Vector3 Center`

Represents the center of the sphere for the overlap query.

6.110.4.2 Radius

`float Radius`

Represents the radius of the sphere for the overlap query.

6.111 SphereOverlapQueryParams Struct Reference

Base parameters needed to execute a sphere overlap query

Public Member Functions

- [SphereOverlapQueryParams](#) ([QueryParams](#) queryParams, `Vector3` center, `float` radius, `int` staticHitsCapacity)

Create a new [SphereOverlapQueryParams](#).

Public Attributes

- `Vector3` [Center](#)
Represents the center of the sphere for the overlap query.
- [QueryParams](#) [QueryParams](#)
Represents the base parameters for the sphere overlap query.
- `float` [Radius](#)
Represents the radius of the sphere for the overlap query.
- `int` [StaticHitsCapacity](#)
Represents the capacity for the cached PhysX and Box2D static hits.

6.111.1 Detailed Description

Base parameters needed to execute a sphere overlap query

6.111.2 Constructor & Destructor Documentation

6.111.2.1 SphereOverlapQueryParams()

```
SphereOverlapQueryParams (
    QueryParams queryParams,
    Vector3 center,
    float radius,
    int staticHitsCapacity )
```

Create a new [SphereOverlapQueryParams](#).

Parameters

<i>queryParams</i>	Parameters to be used
<i>center</i>	The query center
<i>radius</i>	The query radius
<i>staticHitsCapacity</i>	Capacity for the cached PhysX and Box2D static hits.

6.111.3 Member Data Documentation

6.111.3.1 Center

Vector3 Center

Represents the center of the sphere for the overlap query.

6.111.3.2 QueryParams

QueryParams QueryParams

Represents the base parameters for the sphere overlap query.

6.111.3.3 Radius

`float Radius`

Represents the radius of the sphere for the overlap query.

6.111.3.4 StaticHitsCapacity

`int StaticHitsCapacity`

Represents the capacity for the cached PhysX and Box2D static hits.

6.112 LagCompensationSettings Class Reference

Settings for lag compensation history.

Public Attributes

- int [CachedStaticCollidersSize](#) = 64
The size of the cached static colliders (PhysX or Box2D) array of the default Lag Compensation Queries.
- bool [Enabled](#) = false
Indicates if a [HitboxManager](#) instance should be added when the [NetworkRunner](#) is initialized.
- int [HitboxBufferLengthInMs](#) = 200
[Hitbox](#) snapshot history length in milliseconds.
- int [HitboxDefaultCapacity](#) = 512
[Hitbox](#) capacity per snapshot.

Properties

- float [ExpansionFactor](#) [get]
Broadphase BVH node expansion factor (default 20%) for leaf nodes, so updates are not too frequent.
- bool [Optimize](#) [get]
Optional: tries to optimize broadphase BVH every update. May be removed in the future.

6.112.1 Detailed Description

Settings for lag compensation history.

6.112.2 Member Data Documentation

6.112.2.1 CachedStaticCollidersSize

```
int CachedStaticCollidersSize = 64
```

The size of the cached static colliders (PhysX or Box2D) array of the default Lag Compensation Queries.

6.112.2.2 Enabled

```
bool Enabled = false
```

Indicates if a [HitboxManager](#) instance should be added when the [NetworkRunner](#) is initialized.

6.112.2.3 HitboxBufferLengthInMs

```
int HitboxBufferLengthInMs = 200
```

[Hitbox](#) snapshot history length in milliseconds.

6.112.2.4 HitboxDefaultCapacity

```
int HitboxDefaultCapacity = 512
```

[Hitbox](#) capacity per snapshot.

6.112.3 Property Documentation

6.112.3.1 ExpansionFactor

```
float ExpansionFactor [get]
```

Broadphase BVH node expansion factor (default 20%) for leaf nodes, so updates are not too frequent.

6.112.3.2 Optimize

```
bool Optimize [get]
```

Optional: tries to optimize broadphase BVH every update. May be removed in the future.

6.113 LobbyInfo Class Reference

Holds information about a Lobby

Properties

- bool `IsValid` [get]
Flag to signal if the [LobbyInfo](#) is ready for use. This is only true if the peer is currently connected to a Lobby.
- string `Name` [get]
Lobby Name
- string `Region` [get]
Stores the current connected Region

6.113.1 Detailed Description

Holds information about a Lobby

6.113.2 Property Documentation

6.113.2.1 IsValid

```
bool IsValid [get]
```

Flag to signal if the [LobbyInfo](#) is ready for use. This is only true if the peer is currently connected to a Lobby.

6.113.2.2 Name

```
string Name [get]
```

Lobby Name

6.113.2.3 Region

```
string Region [get]
```

Stores the current connected Region

6.114 LogSimpleUnity Class Reference

Log Simple Unity

Inherits ILogger.

Public Member Functions

- void [Log](#) (LogType logType, object message, in LogContext logContext)
- void [LogException](#) (Exception ex, in LogContext logContext)

6.114.1 Detailed Description

Log Simple Unity

6.115 NestedComponentUtilities Class Reference

Tools to replace GetComponent variants that respects nested objects. These are used to find components of a NetworkedObjects without also finding components that belong to parent or child NetworkedObjects.

Static Public Member Functions

- static T [EnsureRootComponentExists](#)< T, TStopOn > (this Transform transform)
Ensures that a component of type T exists on the root object of the provided transform. If a component of type T does not exist, it is added. The search for the root object stops if a component of type TStopOn is found.
- static T[] [FindObjectsOfTypeInOrder](#)< T > (this UnityEngine.SceneManagement.Scene scene, bool includeInactive=false)
Find All instances of Component type in a scene. Attempts to respect the hierarchy of the scene objects to produce a more deterministic order. This is a slower operation, and does produce garbage collection.
- static void [FindObjectsOfTypeInOrder](#)< T > (this UnityEngine.SceneManagement.Scene scene, List< T > list, bool includeInactive=false)
Find All instances of Component type in a scene. Attempts to respect the hierarchy of the scene objects to produce a more deterministic order. This is a slower operation which should not be run every update.
- static TCast[] [FindObjectsOfTypeInOrder](#)< T, TCast > (this UnityEngine.SceneManagement.Scene scene, bool includeInactive=false)
Find All instances of Component type in a scene. Attempts to respect the hierarchy of the scene objects to produce a more deterministic order. This is a slow operation, and does produce garbage collection.
- static void [FindObjectsOfTypeInOrder](#)< T, TCast > (this UnityEngine.SceneManagement.Scene scene, List< TCast > list, bool includeInactive=false)
Find All instances of Component type in a scene. Attempts to respect the hierarchy of the scene objects to produce a more deterministic order. This is a slower operation and should not be run every update.
- static T [GetNestedComponentInChildren](#)< T, TStopOn > (this Transform t, bool includeInactive)
Finds the first component of type T in the children of the provided transform, stopping the search if a component of type TStopOn is found.
- static T [GetNestedComponentInParent](#)< T, TStopOn > (this Transform t)
Same as GetComponentInParent, but will always include inactive objects in search. Will also stop recursing up the hierarchy when the StopOnT is found.
- static T [GetNestedComponentInParents](#)< T, TStopOn > (this Transform t)

Finds the first component of type T in the parents of the provided transform, stopping the search if a component of type $TStopOn$ is found.

- static List< T > [GetNestedComponentsInChildren< \$T\$ >](#) (this Transform t , List< T > list, bool includeInactive=true, params System.Type[] stopOn)

Same as [GetComponentInChildren](#), but will not recurse into children with any component of the types in the stopOn array.

- static void [GetNestedComponentsInChildren< \$T\$, \$TSearch\$, \$TStop\$ >](#) (this Transform t , bool includeInactive, List< T > list)

Same as [GetComponentInChildren](#), but will not recurse into children with component of the $StopT$ type.

- static List< T > [GetNestedComponentsInChildren< \$T\$, \$TStopOn\$ >](#) (this Transform t , List< T > list, bool includeInactive=true)

Same as [GetComponentInChildren](#), but will not recurse into children with component of the $StopT$ type.

- static void [GetNestedComponentsInParents< \$T\$ >](#) (this Transform t , List< T > list)

Returns all T found between the child transform and its root. Order in List from child to parent, with the root/parent most being last.

- static void [GetNestedComponentsInParents< \$T\$, \$TStop\$ >](#) (this Transform t , List< T > list)

Finds components of type T on supplied transform, and every parent above that node, inclusively stopping on node $StopT$ component.

- static T [GetParentComponent< \$T\$ >](#) (this Transform t)

Find T on supplied transform or any parent. Unlike [GetComponentInParent](#), GameObjects do not need to be active to be found.

6.115.1 Detailed Description

Tools to replace GetComponent variants that respects nested objects. These are used to find components of a NetworkedObjects without also finding components that belong to parent or child NetworkedObjects.

6.115.2 Member Function Documentation

6.115.2.1 EnsureRootComponentExists< T , $TStopOn$ >()

```
static T EnsureRootComponentExists<  $T$ ,  $TStopOn$  > (
    this Transform transform ) [static]
```

Ensures that a component of type T exists on the root object of the provided transform. If a component of type T does not exist, it is added. The search for the root object stops if a component of type $TStopOn$ is found.

Template Parameters

T	The type of component to ensure exists on the root object.
$TStopOn$	The type of component that stops the search for the root object.

Parameters

<i>transform</i>	The transform to start the search from.
------------------	---

Returns

The component of type *T* on the root object. Returns null if no root object is found.

Type Constraints

***T* : Component**

***TStopOn* : Component**

6.115.2.2 FindObjectsOfTypeInOrder< T >() [1/2]

```
static T [] FindObjectsOfTypeInOrder< T > (
    this UnityEngine.SceneManagement.Scene scene,
    bool includeInactive = false ) [static]
```

Find All instances of Component type in a scene. Attempts to respect the hierarchy of the scene objects to produce a more deterministic order. This is a slower operation, and does produce garbage collection.

Type Constraints

***T* : class**

6.115.2.3 FindObjectsOfTypeInOrder< T >() [2/2]

```
static void FindObjectsOfTypeInOrder< T > (
    this UnityEngine.SceneManagement.Scene scene,
    List< T > list,
    bool includeInactive = false ) [static]
```

Find All instances of Component type in a scene. Attempts to respect the hierarchy of the scene objects to produce a more deterministic order. This is a slower operation which should not be run every update.

Template Parameters

<i>T</i>	The type being searched for.
----------	------------------------------

Parameters

<i>scene</i>	Scene to search.
<i>list</i>	Supplied list that will be populated by this find.
<i>includeInactive</i>	Whether results should include inactive components.

Type Constraints

***T* : class**

6.115.2.4 FindObjectsOfTypeInOrder< T, TCast >() [1/2]

```
static TCast [] FindObjectsOfTypeInOrder< T, TCast > (
    this UnityEngine.SceneManagement.Scene scene,
    bool includeInactive = false ) [static]
```

Find All instances of Component type in a scene. Attempts to respect the hierarchy of the scene objects to produce a more deterministic order. This is a slow operation, and does produce garbage collection.

Template Parameters

<i>T</i>	The type being searched for.
<i>TCast</i>	Casts all found objects to this type, and returns collection of this type. Objects that fail cast are excluded.

Parameters

<i>scene</i>	Scene to search.
<i>includeInactive</i>	Whether results should include inactive components.

Type Constraints

***T* : class**

***TCast* : class**

6.115.2.5 FindObjectsOfTypeInOrder< T, TCast >() [2/2]

```
static void FindObjectsOfTypeInOrder< T, TCast > (
    this UnityEngine.SceneManagement.Scene scene,
    List< TCast > list,
    bool includeInactive = false ) [static]
```

Find All instances of Component type in a scene. Attempts to respect the hierarchy of the scene objects to produce a more deterministic order. This is a slower operation and should not be run every update.

Template Parameters

<i>T</i>	Type being searched for.
<i>TCast</i>	Type to cast found objects to.

Parameters

<i>scene</i>	Scene to search.
<i>list</i>	Supplied list that will be filled with found objects.
<i>includeInactive</i>	Whether results should include inactive components.

Type Constraints

T* : class**TCast* : class****6.115.2.6 GetNestedComponentInChildren< T, TStopOn >()**

```
static T GetNestedComponentInChildren< T, TStopOn > (
    this Transform t,
    bool includeInactive ) [static]
```

Finds the first component of type T in the children of the provided transform, stopping the search if a component of type TStopOn is found.

Template Parameters

<i>T</i>	The type of component to find.
<i>TStopOn</i>	The type of component that stops the search.

Parameters

<i>t</i>	The transform to start the search from.
<i>includeInactive</i>	Whether to include inactive game objects in the search.

Returns

The first component of type T found. Returns null if no component is found.

Type Constraints

T* : class**TStopOn* : class****6.115.2.7 GetNestedComponentInParent< T, TStopOn >()**

```
static T GetNestedComponentInParent< T, TStopOn > (
    this Transform t ) [static]
```

Same as GetComponentInParent, but will always include inactive objects in search. Will also stop recursing up the hierarchy when the StopOnT is found.

Type Constraints

T* : class**TStopOn* : class**

6.115.2.8 GetNestedComponentInParents< T, TStopOn >()

```
static T GetNestedComponentInParents< T, TStopOn > (
    this Transform t ) [static]
```

Finds the first component of type T in the parents of the provided transform, stopping the search if a component of type TStopOn is found.

Template Parameters

<i>T</i>	The type of component to find.
<i>TStopOn</i>	The type of component that stops the search.

Parameters

<i>t</i>	The transform to start the search from.
----------	---

Returns

The first component of type T found in the parents. Returns null if no component is found or a component of type TStopOn is found.

Type Constraints

***T* : class**

***TStopOn* : class**

6.115.2.9 GetNestedComponentsInChildren< T >()

```
static List<T> GetNestedComponentsInChildren< T > (
    this Transform t,
    List< T > list,
    bool includeInactive = true,
    params System.Type[] stopOn ) [static]
```

Same as GetComponentInChildren, but will not recurse into children with any component of the types in the stopOn array.

Type Constraints

***T* : class**

6.115.2.10 GetNestedComponentsInChildren< T, TSearch, TStop >()

```
static void GetNestedComponentsInChildren< T, TSearch, TStop > (
    this Transform t,
    bool includeInactive,
    List< T > list ) [static]
```

Same as GetComponentInChildren, but will not recurse into children with component of the StopT type.

Template Parameters

<i>T</i>	Cast found components to this type. Typically Component, but any other class/interface will work as long as they are assignable from SearchT.
<i>TSearch</i>	Find components of this class or interface type.
<i>TStop</i>	When this component is found, no further recursing will be performed on that node.

Type Constraints

T : class***TSearch : class*****6.115.2.11 GetNestedComponentsInChildren< T, TStopOn >()**

```
static List<T> GetNestedComponentsInChildren< T, TStopOn > (
    this Transform t,
    List< T > list,
    bool includeInactive = true ) [static]
```

Same as GetComponentInChildren, but will not recurse into children with component of the StopT type.

Type Constraints

T : class***TStopOn : class*****6.115.2.12 GetNestedComponentsInParents< T >()**

```
static void GetNestedComponentsInParents< T > (
    this Transform t,
    List< T > list ) [static]
```

Returns all T found between the child transform and its root. Order in List from child to parent, with the root/parent most being last.

Type Constraints

T : Component

6.115.2.13 GetNestedComponentsInParents< T, TStop >()

```
static void GetNestedComponentsInParents< T, TStop > (
    this Transform t,
    List< T > list ) [static]
```

Finds components of type T on supplied transform, and every parent above that node, inclusively stopping on node StopT component.

Type Constraints

T : class

TStop : class

6.115.2.14 GetParentComponent< T >()

```
static T GetParentComponent< T > (
    this Transform t ) [static]
```

Find T on supplied transform or any parent. Unlike GetComponentInParent, GameObjects do not need to be active to be found.

Type Constraints

T : Component

6.116 NetworkArray< T > Struct Template Reference

[Fusion](#) type for networking arrays. Maximum capacity is fixed, and is set with the [CapacityAttribute](#).

Inherits IEnumerable< T >, and [INetworkArray](#).

Classes

- struct [Enumerator](#)
Enumerator for NetworkArray.

Public Member Functions

- void [Clear](#) ()
Clears the array, setting all values to default.
- void [CopyFrom](#) (List< T > source, int sourceOffset, int sourceCount)
Copies a range of values from a supplied source list into the [NetworkArray](#).
- void [CopyFrom](#) (T[] source, int sourceOffset, int sourceCount)
Copies a range of elements from a source array into the [NetworkArray](#).
- void [CopyTo](#) (List< T > list)
Adds each value to the supplied List. This does not clear the list, so values will be appended to the existing list.
- void [CopyTo](#) (NetworkArray< T > array)
Copies values to the supplied array.
- void [CopyTo](#) (T[] array, bool throwIfOverflow=true)
Copies values to the supplied array.
- T [Get](#) (int index)
Returns the array value at supplied index.
- [Enumerator](#) [GetEnumerator](#) ()
Returns an enumerator that iterates through the collection.
- [IEnumerator](#)< T > [IEnumerable](#)< T >. [GetEnumerator](#) ()
- [IEnumerator](#) [IEnumerable](#). [GetEnumerator](#) ()
- [NetworkArray](#) (byte *array, int length, [IElementReaderWriter](#)< T > readerWriter)
[NetworkArray](#) constructor.
- T [Set](#) (int index, T value)
Sets the array value at the supplied index.
- T[] [ToArray](#) ()
Allocates a new array and copies values from this array. For a non-alloc alternative use [CopyTo\(List< T >\)](#).
- string [ToListString](#) ()
Returns the elements of this array as a string, with value separated by characters. Specifically for use in the Unity inspector. This is private and only is found by NetworkBehaviourEditor using reflection, so do not rename this method.
- [NetworkArrayReadOnly](#)< T > [ToReadOnly](#) ()
Returns a [NetworkArrayReadOnly](#) view of this array.
- override string [ToString](#) ()
Returns a string that represents the current object.

Static Public Member Functions

- static implicit [operator](#) [NetworkArrayReadOnly](#)< T > ([NetworkArray](#)< T > value)
Returns a [NetworkArrayReadOnly](#) view of this array.

Public Attributes

- byte * [_array](#)
- int [_length](#)
- [IElementReaderWriter](#)< T > [_readerWriter](#)

Static Public Attributes

- static StringBuilder [_stringBuilderCached](#)

Properties

- `int Length` [get]
The fixed size of the array.
- `T this[int index]` [get, set]
Indexer of array elements.
- object `INetworkArray`. `this[int index]` [get, set]

6.116.1 Detailed Description

`Fusion` type for networking arrays. Maximum capacity is fixed, and is set with the `CapacityAttribute`.

Typical Usage: `[Networked, Capacity(4)]`
`NetworkArray<float> syncedArray => default;`

Optional usage (for `NetworkBehaviours` ONLY - this is not legal in `INetworkStructs`): `[Networked, Capacity(4)]`
`NetworkArray<int> syncedArray { get; } = MakeInitializer(new int[] { 1, 2, 3, 4 });`

Usage for modifying data: `array.Set(123); array[0] = 456;`

Template Parameters

<code>T</code>	T can be a primitive, or an <code>INetworkStruct</code> .
----------------	---

6.116.2 Constructor & Destructor Documentation

6.116.2.1 NetworkArray()

```
NetworkArray (
    byte * array,
    int length,
    IElementReaderWriter< T > readerWriter )
```

`NetworkArray` constructor.

6.116.3 Member Function Documentation

6.116.3.1 Clear()

```
void Clear ( )
```

Clears the array, setting all values to default.

6.116.3.2 CopyFrom() [1/2]

```
void CopyFrom (
    List< T > source,
    int sourceOffset,
    int sourceCount )
```

Copies a range of values from a supplied source list into the [NetworkArray](#).

Parameters

<i>source</i>	The source list from which to copy elements.
<i>sourceOffset</i>	The zero-based index in the source list at which copying begins.
<i>sourceCount</i>	The number of elements to copy from the source list.

Exceptions

<i>ArgumentNullException</i>	Thrown when the provided source list is null.
<i>ArgumentException</i>	Thrown when the number of elements to copy is greater than the length of the NetworkArray .
<i>ArgumentOutOfRangeException</i>	Thrown when the sum of sourceOffset and sourceCount is greater than the length of the source list.

6.116.3.3 CopyFrom() [2/2]

```
void CopyFrom (
    T[] source,
    int sourceOffset,
    int sourceCount )
```

Copies a range of elements from a source array into the [NetworkArray](#).

Parameters

<i>source</i>	The source array from which to copy elements. Must not be null.
<i>sourceOffset</i>	The zero-based index in the source array at which copying begins.
<i>sourceCount</i>	The number of elements to copy from the source array.

Exceptions

<i>ArgumentNullException</i>	Thrown when the provided source array is null.
<i>ArgumentException</i>	Thrown when the number of elements to copy is greater than the length of the NetworkArray .
<i>ArgumentOutOfRangeException</i>	Thrown when the sum of sourceOffset and sourceCount is greater than the length of the source array.

6.116.3.4 CopyTo() [1/3]

```
void CopyTo (
    List< T > list )
```

Adds each value to the supplied List. This does not clear the list, so values will be appended to the existing list.

6.116.3.5 CopyTo() [2/3]

```
void CopyTo (
    NetworkArray< T > array )
```

Copies values to the supplied array.

Parameters

<i>array</i>	NetworkArray to copy to.
--------------	--

Exceptions

<i>ArgumentException</i>	Thrown if the supplied array is smaller than this NetworkArray<T> .
--------------------------	---

6.116.3.6 CopyTo() [3/3]

```
void CopyTo (
    T[] array,
    bool throwIfOverflow = true )
```

Copies values to the supplied array.

Parameters

<i>array</i>	Array to copy to.
<i>throwIfOverflow</i>	If true, this method will throw an error if the supplied array is smaller than this NetworkArray<T> . If false, will only copy as many elements as the target array can hold.

6.116.3.7 Get()

```
T Get (
    int index )
```

Returns the array value at supplied index.

6.116.3.8 GetEnumerator()

```
Enumerator GetEnumerator ( )
```

Returns an enumerator that iterates through the collection.

6.116.3.9 operator NetworkArrayReadOnly< T >()

```
static implicit operator NetworkArrayReadOnly< T > (
    NetworkArray< T > value ) [static]
```

Returns a [NetworkArrayReadOnly](#) view of this array.

Parameters

<i>value</i>	NetworkArray to convert.
--------------	--

Returns

[NetworkArrayReadOnly](#) view of this array.

6.116.3.10 Set()

```
T Set (
    int index,
    T value )
```

Sets the array value at the supplied index.

6.116.3.11 ToArray()

```
T [] ToArray ( )
```

Allocates a new array and copies values from this array. For a non-alloc alternative use [CopyTo\(List<T>\)](#).

6.116.3.12 ToListString()

```
string ToListString ( )
```

Returns the elements of this array as a string, with value separated by characters. Specifically for use in the Unity inspector. This is private and only is found by NetworkBehaviourEditor using reflection, so do not rename this method.

6.116.3.13 ToReadOnly()

```
NetworkArrayReadOnly<T> ToReadOnly ( )
```

Returns a [NetworkArrayReadOnly](#) view of this array.

6.116.3.14 ToString()

```
override string ToString ( )
```

Returns a string that represents the current object.

6.116.4 Property Documentation

6.116.4.1 Length

```
int Length [get]
```

The fixed size of the array.

6.116.4.2 this[int index]

```
T this[int index] [get], [set]
```

Indexer of array elements.

6.117 `NetworkArray< T >.Enumerator` Struct Reference

`Enumerator` for `NetworkArray`.

Inherits `IEnumerator< T >`.

Public Member Functions

- void `Dispose` ()
Releases all resources used by the `Enumerator`.
- `Enumerator` (`NetworkArray< T > array`)
Initializes a new instance of the `Enumerator` with the specified `NetworkArray`.
- bool `MoveNext` ()
Advances the enumerator to the next element of the collection.
- void `Reset` ()
Sets the enumerator to its initial position, which is before the first element in the collection.

Public Attributes

- `NetworkArray< T > _array`
- int `_index`

Properties

- T `Current` [get]
Gets the current element in the collection.
- object `IEnumerator.Current` [get]
Gets the current element in the collection.

6.117.1 Detailed Description

`Enumerator` for `NetworkArray`.

6.117.2 Constructor & Destructor Documentation

6.117.2.1 `Enumerator()`

```
Enumerator (  
    NetworkArray< T > array )
```

Initializes a new instance of the `Enumerator` with the specified `NetworkArray`.

Parameters

<code>array</code>	The NetworkArray to enumerate.
--------------------	--

6.117.3 Member Function Documentation

6.117.3.1 Dispose()

```
void Dispose ( )
```

Releases all resources used by the [Enumerator](#).

6.117.3.2 MoveNext()

```
bool MoveNext ( )
```

Advances the enumerator to the next element of the collection.

Returns

true if the enumerator was successfully advanced to the next element; false if the enumerator has passed the end of the collection.

6.117.3.3 Reset()

```
void Reset ( )
```

Sets the enumerator to its initial position, which is before the first element in the collection.

6.117.4 Property Documentation

6.117.4.1 Current [1/2]

```
T Current [get]
```

Gets the current element in the collection.

6.117.4.2 Current [2/2]

```
object IEnumerator. Current [get]
```

Gets the current element in the collection.

6.118 NetworkArrayExtensions Class Reference

Provides extension methods for the [NetworkArray](#) class.

Static Public Member Functions

- static ref T [GetRef< T >](#) (this [NetworkArray< T >](#) array, int index)
Returns a reference to the element at a specified position in the [NetworkArray](#).
- static int [IndexOf< T >](#) (this [NetworkArray< T >](#) array, T elem)
Finds the index of the first occurrence of a specified element in the [NetworkArray](#).

6.118.1 Detailed Description

Provides extension methods for the [NetworkArray](#) class.

6.118.2 Member Function Documentation

6.118.2.1 GetRef< T >()

```
static ref T GetRef< T > (  
    this NetworkArray< T > array,  
    int index ) [static]
```

Returns a reference to the element at a specified position in the [NetworkArray](#).

Parameters

<i>array</i>	The NetworkArray to search.
<i>index</i>	The zero-based index of the element to get a reference for.

Returns

A reference to the element at the specified position in the [NetworkArray](#).

Type Constraints

T: *unmanaged*

6.118.2.2 IndexOf< T >()

```
static int IndexOf< T > (
    this NetworkArray< T > array,
    T elem ) [static]
```

Finds the index of the first occurrence of a specified element in the [NetworkArray](#).

Parameters

<i>array</i>	The NetworkArray to search.
<i>elem</i>	The element to locate in the NetworkArray .

Returns

The zero-based index of the first occurrence of elem within the entire [NetworkArray](#), if found; otherwise, -1.

Type Constraints

T* : *unmanaged

***T* : *IEquatable*<*T*>**

6.119 [NetworkArrayReadOnly](#)< T > Struct Template Reference

Provides a read-only view of a network array.

Public Attributes

- readonly byte * **_array**
- readonly int **_length**
- readonly [IElementReaderWriter](#)< T > **_readerWriter**

Properties

- int [Length](#) [get]
The fixed size of the array.
- T [this\[int index\]](#) [get]
Indexer of array elements.

6.119.1 Detailed Description

Provides a read-only view of a network array.

Template Parameters

<i>T</i>	The type of the elements.
----------	---------------------------

6.119.2 Property Documentation

6.119.2.1 Length

```
int Length [get]
```

The fixed size of the array.

6.119.2.2 this[int index]

```
T this[int index] [get]
```

Indexer of array elements.

6.120 NetworkAssemblyIgnoreAttribute Class Reference

Network Assembly Ignore Attribute

Inherits Attribute.

6.120.1 Detailed Description

Network Assembly Ignore Attribute

6.121 NetworkAssemblyWeavedAttribute Class Reference

Network Assembly Weaved Attribute

Inherits Attribute.

6.121.1 Detailed Description

Network Assembly Weaved Attribute

6.122 NetworkBehaviour Class Reference

Base class for [Fusion](#) network components, which are associated with a [NetworkObject](#).

Inherits [SimulationBehaviour](#), [ISpawned](#), and [IDespawned](#).

Inherited by [HitboxRoot](#), [NetworkMecanimAnimator](#), and [NetworkTRSP](#).

Classes

- struct [ArrayReader](#)
Provides a reader for network arrays of type T.
- struct [BehaviourReader](#)
Provides a reader for network behaviours of type T.
- class [ChangeDetector](#)
Change detector for a [NetworkBehaviour](#)
- struct [DictionaryReader](#)
Provides a reader for network dictionaries with keys of type K and values of type V.
- struct [LinkedListReader](#)
Provides a reader for network linked lists of type T.
- struct [PropertyReader](#)
Provides a reader for properties of type T in a network behaviour.

Public Member Functions

- virtual void [CopyBackingFieldsToState](#) (bool firstTime)
Copies the backing fields to the state. This method is meant to be overridden in derived classes.
- void [CopyStateFrom](#) ([NetworkBehaviour](#) source)
Copies entire state of passed in source [NetworkBehaviour](#)
- virtual void [CopyStateToBackingFields](#) ()
Copies the state to the backing fields. This method is meant to be overridden in derived classes.
- virtual void [Despawned](#) ([NetworkRunner](#) runner, bool hasState)
Called before the network object is despawned
- override void [FixedUpdateNetwork](#) ()
Fixed update callback for networked behaviours.
- [ArrayReader](#)< T > [GetArrayReader](#)< T > (string property)
Gets an [ArrayReader](#) for a network array of type T.
- [BehaviourReader](#)< T > [GetBehaviourReader](#)< T > (string property)
Gets a [BehaviourReader](#) for a network behaviour of type T.
- [ChangeDetector](#) [GetChangeDetector](#) ([ChangeDetector.Source](#) source, bool copyInitial=true)
Creates a [ChangeDetector](#) for this network behaviour.
- [DictionaryReader](#)< K, V > [GetDictionaryReader](#)< K, V > (string property)
Gets a [DictionaryReader](#) for a network dictionary with keys of type K and values of type V.
- T? [GetInput](#)< T > ()
- bool [GetInput](#)< T > (out T input)
Returns true if it a valid [INetworkInput](#) can be found for the current simulation tick (Typically this is used in [FixedUpdateNetwork](#)).
- [LinkedListReader](#)< T > [GetLinkedListReader](#)< T > (string property)
Gets a [LinkedListReader](#) for a network linked list of type T.
- int [GetLocalAuthorityMask](#) ()
Gets a bitmask of [AuthorityMasks](#) flags, representing the current local authority over this [NetworkObject](#).
- [PropertyReader](#)< T > [GetPropertyReader](#)< T > (string property)
Gets a [PropertyReader](#) for a property of type T in this network behaviour.
- ref T [ReinterpretState](#)< T > (int offset=0)
Allows read and write access to the internal state buffer
- void [ResetState](#) ()
Resets the state of the object to the original state
- virtual void [Spawned](#) ()
Post spawn callback.
- bool [TryGetSnapshotsBuffers](#) (out [NetworkBehaviourBuffer](#) from, out [NetworkBehaviourBuffer](#) to, out float alpha)
Tries to get the snapshot buffers for this network behaviour.

Static Public Member Functions

- static [ArrayReader](#)< T > [GetArrayReader](#)< T > (Type behaviourType, string property)
Gets an [ArrayReader](#) for a network array of type T in a network behaviour of a specific type.
- static [BehaviourReader](#)< T > [GetBehaviourReader](#)< T > ([NetworkRunner](#) runner, Type behaviourType, string property)
Gets a [BehaviourReader](#) for a network behaviour of type T.
- static [BehaviourReader](#)< TProperty > [GetBehaviourReader](#)< TBehaviour, TProperty > ([NetworkRunner](#) runner, string property)
Gets a [BehaviourReader](#) for a network behaviour with a specific property of type TProperty.
- static [DictionaryReader](#)< K, V > [GetDictionaryReader](#)< K, V > (Type behaviourType, string property)
Gets a [DictionaryReader](#) for a network dictionary with keys of type K and values of type V in a network behaviour of a specific type.
- static [LinkedListReader](#)< T > [GetLinkedListReader](#)< T > (Type behaviourType, string property)
Gets a [LinkedListReader](#) for a network linked list of type T in a network behaviour of a specific type.
- static [PropertyReader](#)< T > [GetPropertyReader](#)< T > (Type behaviourType, string property)
Gets a [PropertyReader](#) for a property of type T in a network behaviour of a specific type.
- static [PropertyReader](#)< TProperty > [GetPropertyReader](#)< TBehaviour, TProperty > (string property)
Gets a [PropertyReader](#) for a property of type TProperty in a network behaviour of type TBehaviour.
- static [NetworkBehaviourUtils.DictionaryInitializer](#)< K, V > [MakeInitializer](#)< K, V > (Dictionary< K, V > dictionary)
This is a special method that is meant to be used only for [Networked] properties inline initialization.
- static [NetworkBehaviourUtils.ArrayInitializer](#)< T > [MakeInitializer](#)< T > (T[] array)
This is a special method that is meant to be used only for [Networked] properties inline initialization.
- static T * [MakePtr](#)< T > ()
Creates a pointer to a value of type T. This method is meant to be used only for [Networked] properties inline initialization.
- static T * [MakePtr](#)< T > (T defaultValue)
Creates a pointer to a value of type T, initializing it with the provided default value. This method is meant to be used only for [Networked] properties inline initialization.
- static ref T [MakeRef](#)< T > ()
Creates a reference to a value of type T. This method is meant to be used only for [Networked] properties inline initialization.
- static ref T [MakeRef](#)< T > (T defaultValue)
Creates a reference to a value of type T, initializing it with the provided default value. This method is meant to be used only for [Networked] properties inline initialization.
- static int [NetworkDeserialize](#) ([NetworkRunner](#) runner, byte *data, ref [NetworkBehaviour](#) result)
Deserializes a [NetworkBehaviour](#) from a byte array.
- static int [NetworkSerialize](#) ([NetworkRunner](#) runner, [NetworkBehaviour](#) obj, byte *data)
Serializes a [NetworkBehaviour](#) into a byte array.
- static [NetworkBehaviour](#) [NetworkUnwrap](#) ([NetworkRunner](#) runner, [NetworkBehaviourId](#) wrapper)
Converts a [NetworkBehaviourId](#) to a [NetworkBehaviour](#).
- static [NetworkBehaviourId](#) [NetworkWrap](#) ([NetworkRunner](#) runner, [NetworkBehaviour](#) obj)
Converts a [NetworkBehaviour](#) to a [NetworkBehaviourId](#).
- static implicit operator [NetworkBehaviourId](#) ([NetworkBehaviour](#) behaviour)
Converts [NetworkBehaviour](#) to [NetworkBehaviourId](#)

Public Attributes

- int [offset](#)
Gives access to the offset (in 32 bit words) and count (in 32 bit words) of this behaviour backing data

Protected Member Functions

- virtual bool [ReplicateTo](#) ([PlayerRef](#) player)

Determines whether to replicate the network behaviour to the specified player. This method can be overridden in derived classes to implement custom replication logic.

Properties

- [Tick ChangedTick](#) [get]

The tick the data on this networked behaviour changed

- virtual ? int [DynamicWordCount](#) [get]

Override this value for custom memory allocations. This is for advanced use cases only, and cannot be used if [NetworkedAttribute](#) is used in the derived class.

- bool? [HasInputAuthority](#) [get]

Returns true if the [Simulation.LocalPlayer](#) of the associated [NetworkRunner](#) is the designated as Input Source for this network entity.

- bool? [HasStateAuthority](#) [get]

Returns true if the associated [NetworkRunner](#) is the State Source for this network entity.

- [NetworkBehaviourId](#)? Id [get]

The unique identifier for this network behaviour.

- bool? [IsProxy](#) [get]

Returns true if the associated [NetworkRunner](#) is neither the Input nor State Authority for this network entity. It is recommended to use [!HasStateAuthority](#) or [!HasInputAuthority](#) when possible instead, as this check requires evaluating both authorities - and is therefore less performant than the individual checks.

- [NetworkBehaviourBuffer](#) [StateBuffer](#) [get]

Gets the state buffer associated with the network behaviour.

- bool [StateBufferIsValid](#) [get]

Gets a value indicating whether the state buffer is valid.

6.122.1 Detailed Description

Base class for [Fusion](#) network components, which are associated with a [NetworkObject](#).

Derived from [SimulationBehaviour](#), components derived from this class are associated with a [NetworkRunner](#) and [Simulation](#). Components derived from this class are associated with a parent [NetworkObject](#). and can use the [NetworkedAttribute](#) on properties to automate state synchronization, and can use the [RpcAttribute](#) on methods, to automate messaging.

6.122.2 Member Function Documentation

6.122.2.1 CopyBackingFieldsToState()

```
virtual void CopyBackingFieldsToState (
    bool firstTime ) [virtual]
```

Copies the backing fields to the state. This method is meant to be overridden in derived classes.

Parameters

<i>firstTime</i>	Indicates whether this is the first time the method is called.
------------------	--

6.122.2.2 CopyStateFrom()

```
void CopyStateFrom (
    NetworkBehaviour source )
```

Copies entire state of passed in source [NetworkBehaviour](#)

Parameters

<i>source</i>	Source NetworkBehaviour to copy data from
---------------	---

6.122.2.3 CopyStateToBackingFields()

```
virtual void CopyStateToBackingFields ( ) [virtual]
```

Copies the state to the backing fields. This method is meant to be overridden in derived classes.

6.122.2.4 Despawned()

```
virtual void Despawned (
    NetworkRunner runner,
    bool hasState ) [virtual]
```

Called before the network object is despawned

Parameters

<i>runner</i>	The runner that owns the object
<i>hasState</i>	If the state of the behaviour is still accessible

Implements [IDespawned](#).

Reimplemented in [HitboxRoot](#).

6.122.2.5 FixedUpdateNetwork()

```
override void FixedUpdateNetwork ( ) [virtual]
```

Fixed update callback for networked behaviours.

Reimplemented from [SimulationBehaviour](#).

6.122.2.6 GetArrayReader< T >() [1/2]

```
ArrayReader<T> GetArrayReader< T > (
    string property )
```

Gets an [ArrayReader](#) for a network array of type T.

Template Parameters

<i>T</i>	The type of elements in the network array.
----------	--

Parameters

<i>property</i>	The name of the property to be read.
-----------------	--------------------------------------

Returns

An [ArrayReader](#) for the network array of type T.

6.122.2.7 GetArrayReader< T >() [2/2]

```
static ArrayReader<T> GetArrayReader< T > (
    Type behaviourType,
    string property ) [static]
```

Gets an [ArrayReader](#) for a network array of type T in a network behaviour of a specific type.

Template Parameters

<i>T</i>	The type of elements in the network array.
----------	--

Parameters

<i>behaviourType</i>	The type of the network behaviour.
<i>property</i>	The name of the property to be read.

Returns

An [ArrayReader](#) for the network array of type T in the network behaviour of the specified type.

6.122.2.8 GetBehaviourReader< T >() [1/2]

```
static BehaviourReader<T> GetBehaviourReader< T > (
    NetworkRunner runner,
    Type behaviourType,
    string property ) [static]
```

Gets a [BehaviourReader](#) for a network behaviour of type T.

Template Parameters

<i>T</i>	The type of the network behaviour.
----------	------------------------------------

Parameters

<i>runner</i>	The NetworkRunner associated with the network behaviour.
<i>behaviourType</i>	The type of the behaviour to be read.
<i>property</i>	The name of the property to be read.

Returns

A [BehaviourReader](#) for the network behaviour of type T.

Type Constraints

***T* : [NetworkBehaviour](#)**

6.122.2.9 GetBehaviourReader< T >() [2/2]

```
BehaviourReader<T> GetBehaviourReader< T > (
    string property )
```

Gets a [BehaviourReader](#) for a network behaviour of type T.

Template Parameters

<i>T</i>	The type of the network behaviour.
----------	------------------------------------

Parameters

<i>property</i>	The name of the property to be read.
-----------------	--------------------------------------

Returns

A [BehaviourReader](#) for the network behaviour of type T.

Type Constraints

T : NetworkBehaviour

6.122.2.10 GetBehaviourReader< TBehaviour, TProperty >()

```
static BehaviourReader<TProperty> GetBehaviourReader< TBehaviour, TProperty > (
    NetworkRunner runner,
    string property ) [static]
```

Gets a [BehaviourReader](#) for a network behaviour with a specific property of type TProperty.

Template Parameters

<i>TBehaviour</i>	The type of the network behaviour.
<i>TProperty</i>	The type of the property in the network behaviour.

Parameters

<i>runner</i>	The NetworkRunner associated with the network behaviour.
<i>property</i>	The name of the property to be read.

Returns

A [BehaviourReader](#) for the network behaviour with the specific property of type TProperty.

Type Constraints

TBehaviour : NetworkBehaviour

TProperty : NetworkBehaviour

6.122.2.11 GetChangeDetector()

```
ChangeDetector GetChangeDetector (
    ChangeDetector.Source source,
    bool copyInitial = true )
```

Creates a [ChangeDetector](#) for this network behaviour.

Parameters

<i>source</i>	The source of the change detector.
<i>copyInitial</i>	Indicates whether to copy the initial state of the network behaviour.

Returns

A [ChangeDetector](#) for this network behaviour.

6.122.2.12 GetDictionaryReader< K, V >() [1/2]

```
DictionaryReader<K, V> GetDictionaryReader< K, V > (
    string property )
```

Gets a [DictionaryReader](#) for a network dictionary with keys of type K and values of type V.

Template Parameters

<i>K</i>	The type of keys in the network dictionary.
<i>V</i>	The type of values in the network dictionary.

Parameters

<i>property</i>	The name of the property to be read.
-----------------	--------------------------------------

Returns

A [DictionaryReader](#) for the network dictionary with keys of type K and values of type V.

6.122.2.13 GetDictionaryReader< K, V >() [2/2]

```
static DictionaryReader<K, V> GetDictionaryReader< K, V > (
    Type behaviourType,
    string property ) [static]
```

Gets a [DictionaryReader](#) for a network dictionary with keys of type K and values of type V in a network behaviour of a specific type.

Template Parameters

<i>K</i>	The type of keys in the network dictionary.
<i>V</i>	The type of values in the network dictionary.

Parameters

<i>behaviourType</i>	The type of the network behaviour.
<i>property</i>	The name of the property to be read.

Returns

A [DictionaryReader](#) for the network dictionary with keys of type K and values of type V in the network behaviour of the specified type.

6.122.2.14 GetInput< T >() [1/2]

```
T? GetInput< T > ( )
```

Template Parameters

<i>T</i>	
----------	--

Type Constraints

T : [unmanaged](#)

T : [INetworkInput](#)

6.122.2.15 GetInput< T >() [2/2]

```
bool GetInput< T > (
    out T input )
```

Returns true if it a valid [INetworkInput](#) can be found for the current simulation tick (Typically this is used in [FixedUpdateNetwork](#)).

The returned input struct originates from the [NetworkObject.InputAuthority](#), and if valid contains the inputs supplied by that [PlayerRef](#) for the current simulation tick.

Type Constraints

T : [unmanaged](#)

T : [INetworkInput](#)

6.122.2.16 GetLinkListReader< T >() [1/2]

```
LinkListReader<T> GetLinkListReader< T > (
    string property )
```

Gets a [LinkListReader](#) for a network linked list of type T.

Template Parameters

<i>T</i>	The type of elements in the network linked list.
----------	--

Parameters

<i>property</i>	The name of the property to be read.
-----------------	--------------------------------------

Returns

A [LinkedListReader](#) for the network linked list of type T.

6.122.2.17 GetLinkedListReader< T >() [2/2]

```
static LinkedListReader<T> GetLinkedListReader< T > (
    Type behaviourType,
    string property ) [static]
```

Gets a [LinkedListReader](#) for a network linked list of type T in a network behaviour of a specific type.

Template Parameters

<i>T</i>	The type of elements in the network linked list.
----------	--

Parameters

<i>behaviourType</i>	The type of the network behaviour.
<i>property</i>	The name of the property to be read.

Returns

A [LinkedListReader](#) for the network linked list of type T in the network behaviour of the specified type.

6.122.2.18 GetLocalAuthorityMask()

```
int GetLocalAuthorityMask ( )
```

Gets a bitmask of [AuthorityMasks](#) flags, representing the current local authority over this [NetworkObject](#).

6.122.2.19 GetPropertyReader< T >() [1/2]

```
PropertyReader<T> GetPropertyReader< T > (
    string property )
```

Gets a [PropertyReader](#) for a property of type T in this network behaviour.

Template Parameters

<i>T</i>	The type of the property in the network behaviour. Must be unmanaged.
----------	---

Parameters

<i>property</i>	The name of the property to be read.
-----------------	--------------------------------------

Returns

A [PropertyReader](#) for the property of type *T* in this network behaviour.

Type Constraints

T : unmanaged

6.122.2.20 GetPropertyReader< T >() [2/2]

```
static PropertyReader<T> GetPropertyReader< T > (
    Type behaviourType,
    string property ) [static]
```

Gets a [PropertyReader](#) for a property of type *T* in a network behaviour of a specific type.

Template Parameters

<i>T</i>	The type of the property in the network behaviour. Must be unmanaged.
----------	---

Parameters

<i>behaviourType</i>	The type of the network behaviour.
<i>property</i>	The name of the property to be read.

Returns

A [PropertyReader](#) for the property of type *T* in the network behaviour of the specified type.

Type Constraints

T : unmanaged

6.122.2.21 GetPropertyReader< TBehaviour, TProperty >()

```
static PropertyReader<TProperty> GetPropertyReader< TBehaviour, TProperty > (
    string property ) [static]
```

Gets a [PropertyReader](#) for a property of type *TProperty* in a network behaviour of type *TBehaviour*.

Template Parameters

<i>TBehaviour</i>	The type of the network behaviour.
<i>TProperty</i>	The type of the property in the network behaviour. Must be unmanaged.

Parameters

<i>property</i>	The name of the property to be read.
-----------------	--------------------------------------

Returns

A [PropertyReader](#) for the property of type *TProperty* in the network behaviour of type *TBehaviour*.

Type Constraints

TBehaviour* : *NetworkBehaviour

TProperty* : *unmanaged

6.122.2.22 MakeInitializer< K, V >()

```
static NetworkBehaviourUtils.DictionaryInitializer<K, V> MakeInitializer< K, V > (
    Dictionary< K, V > dictionary ) [static]
```

This is a special method that is meant to be used only for [Networked] properties inline initialization.

6.122.2.23 MakeInitializer< T >()

```
static NetworkBehaviourUtils.ArrayInitializer<T> MakeInitializer< T > (
    T[] array ) [static]
```

This is a special method that is meant to be used only for [Networked] properties inline initialization.

6.122.2.24 MakePtr< T >() [1/2]

```
static T* MakePtr< T > ( ) [static]
```

Creates a pointer to a value of type *T*. This method is meant to be used only for [Networked] properties inline initialization.

Template Parameters

<i>T</i>	The type of the value. Must be unmanaged.
----------	---

Returns

A pointer to a value of type T.

Exceptions

<i>NotImplementedException</i>	Thrown because this method is meant to be used only for [Networked] properties inline initialization.
--------------------------------	---

Type Constraints

T : unmanaged

6.122.2.25 MakePtr< T >() [2/2]

```
static T* MakePtr< T > (  
    T defaultValue ) [static]
```

Creates a pointer to a value of type T, initializing it with the provided default value. This method is meant to be used only for [Networked] properties inline initialization.

Template Parameters

<i>T</i>	The type of the value. Must be unmanaged.
-----------------	---

Parameters

<i>defaultValue</i>	The default value to initialize the value with.
----------------------------	---

Returns

A pointer to a value of type T.

Exceptions

<i>NotImplementedException</i>	Thrown because this method is meant to be used only for [Networked] properties inline initialization.
--------------------------------	---

Type Constraints

T : unmanaged

6.122.2.26 MakeRef< T >() [1/2]

```
static ref T MakeRef< T > ( ) [static]
```

Creates a reference to a value of type T. This method is meant to be used only for [Networked] properties inline initialization.

Template Parameters

<i>T</i>	The type of the value. Must be unmanaged.
----------	---

Returns

A reference to a value of type T.

Exceptions

<i>NotImplementedException</i>	Thrown because this method is meant to be used only for [Networked] properties inline initialization.
--------------------------------	---

Type Constraints

T : unmanaged

6.122.2.27 MakeRef< T >(T defaultValue) [2/2]

```
static ref T MakeRef< T > (
    T defaultValue ) [static]
```

Creates a reference to a value of type T, initializing it with the provided default value. This method is meant to be used only for [Networked] properties inline initialization.

Template Parameters

<i>T</i>	The type of the value. Must be unmanaged.
----------	---

Parameters

<i>defaultValue</i>	The default value to initialize the value with.
---------------------	---

Returns

A reference to a value of type T.

Exceptions

<i>NotImplementedException</i>	Thrown because this method is meant to be used only for [Networked] properties inline initialization.
--------------------------------	---

Type Constraints

T : unmanaged

6.122.2.28 NetworkDeserialize()

```
static int NetworkDeserialize (  
    NetworkRunner runner,  
    byte * data,  
    ref NetworkBehaviour result ) [static]
```

Deserializes a [NetworkBehaviour](#) from a byte array.

Parameters

<i>runner</i>	The NetworkRunner associated with the NetworkBehaviour .
<i>data</i>	The byte pointer to read the serialized data from.
<i>result</i>	The NetworkBehaviour to store the deserialized data in.

Returns

The size of the deserialized data in bytes.

6.122.2.29 NetworkSerialize()

```
static int NetworkSerialize (  
    NetworkRunner runner,  
    NetworkBehaviour obj,  
    byte * data ) [static]
```

Serializes a [NetworkBehaviour](#) into a byte array.

Parameters

<i>runner</i>	The NetworkRunner associated with the NetworkBehaviour .
<i>obj</i>	The NetworkBehaviour to be serialized.
<i>data</i>	The byte pointer to write the serialized data to.

Returns

The size of the serialized data in bytes.

6.122.2.30 NetworkUnwrap()

```
static NetworkBehaviour NetworkUnwrap (  
    NetworkRunner runner,  
    NetworkBehaviourId wrapper ) [static]
```

Converts a [NetworkBehaviourId](#) to a [NetworkBehaviour](#).

Parameters

<i>runner</i>	The NetworkRunner associated with the NetworkBehaviour .
<i>wrapper</i>	The NetworkBehaviourId to be converted.

Returns

The [NetworkBehaviour](#) represented by the [NetworkBehaviourId](#). If the [NetworkBehaviourId](#) is not valid or a [NetworkBehaviour](#) with the [NetworkBehaviourId](#) does not exist, returns null.

6.122.2.31 NetworkWrap()

```
static NetworkBehaviourId NetworkWrap (  
    NetworkRunner runner,  
    NetworkBehaviour obj ) [static]
```

Converts a [NetworkBehaviour](#) to a [NetworkBehaviourId](#).

Parameters

<i>runner</i>	The NetworkRunner associated with the NetworkBehaviour .
<i>obj</i>	The NetworkBehaviour to be converted.

Returns

A [NetworkBehaviourId](#) representing the [NetworkBehaviour](#). If the [NetworkBehaviour](#) is null or its [NetworkObject](#)'s Id is default, returns a default [NetworkBehaviourId](#).

6.122.2.32 operator NetworkBehaviourId()

```
static implicit operator NetworkBehaviourId (  
    NetworkBehaviour behaviour ) [static]
```

Converts [NetworkBehaviour](#) to [NetworkBehaviourId](#)

Parameters

<i>behaviour</i>	NetworkBehaviour to convert
------------------	---

Returns

[NetworkBehaviourId](#) representing the [NetworkBehaviour](#)

6.122.2.33 ReinterpretState< T >()

```
ref T ReinterpretState< T > (
    int offset = 0 )
```

Allows read and write access to the internal state buffer

Parameters

<i>offset</i>	The offset to generate a ref for, in integer words
---------------	--

Template Parameters

<i>T</i>	The type of the ref to generate
----------	---------------------------------

Returns

Reference to the location in memory defined by offset

Type Constraints

T : unmanaged

6.122.2.34 ReplicateTo()

```
virtual bool ReplicateTo (
    PlayerRef player ) [protected], [virtual]
```

Determines whether to replicate the network behaviour to the specified player. This method can be overridden in derived classes to implement custom replication logic.

Parameters

<i>player</i>	The player to potentially replicate the network behaviour to.
---------------	---

Returns

True if the network behaviour should be replicated to the player, false otherwise. The default implementation always returns true.

6.122.2.35 ResetState()

```
void ResetState ( )
```

Resets the state of the object to the original state

6.122.2.36 Spawned()

```
virtual void Spawned ( ) [virtual]
```

Post spawn callback.

Implements [ISpawned](#).

Reimplemented in [NetworkTransform](#), and [NetworkMecanimAnimator](#).

6.122.2.37 TryGetSnapshotsBuffers()

```
bool TryGetSnapshotsBuffers (
    out NetworkBehaviourBuffer from,
    out NetworkBehaviourBuffer to,
    out float alpha )
```

Tries to get the snapshot buffers for this network behaviour.

Parameters

<i>from</i>	The buffer representing the state of the network behaviour at the start of the render frame.
<i>to</i>	The buffer representing the state of the network behaviour at the end of the render frame.
<i>alpha</i>	The interpolation factor between the start and end of the render frame.

Returns

True if the snapshot buffers are valid, false otherwise.

6.122.3 Member Data Documentation

6.122.3.1 offset

```
int offset
```

Gives access to the offset (in 32 bit words) and count (in 32 bit words) of this behaviour backing data

6.122.4 Property Documentation

6.122.4.1 ChangedTick

```
Tick ChangedTick [get]
```

The tick the data on this networked behaviour changed

6.122.4.2 DynamicWordCount

```
virtual ? int DynamicWordCount [get]
```

Override this value for custom memory allocations. This is for advanced use cases only, and cannot be used if [NetworkedAttribute](#) is used in the derived class.

6.122.4.3 HasInputAuthority

```
bool? HasInputAuthority [get]
```

Returns true if the [Simulation.LocalPlayer](#) of the associated [NetworkRunner](#) is the designated as Input Source for this network entity.

6.122.4.4 HasStateAuthority

```
bool? HasStateAuthority [get]
```

Returns true if the associated [NetworkRunner](#) is the State Source for this network entity.

6.122.4.5 Id

`NetworkBehaviourId?` Id [get]

The unique identifier for this network behaviour.

6.122.4.6 IsProxy

`bool?` IsProxy [get]

Returns true if the associated [NetworkRunner](#) is neither the Input nor State Authority for this network entity. It is recommended to use [!HasStateAuthority](#) or [!HasInputAuthority](#) when possible instead, as this check requires evaluating both authorities - and is therefore less performant than the individual checks.

6.122.4.7 StateBuffer

`NetworkBehaviourBuffer` StateBuffer [get]

Gets the state buffer associated with the network behaviour.

6.122.4.8 StateBufferIsValid

`bool` StateBufferIsValid [get]

Gets a value indicating whether the state buffer is valid.

6.123 NetworkBehaviour.ArrayReader< T > Struct Template Reference

Provides a reader for network arrays of type T.

Public Member Functions

- [NetworkArrayReadOnly](#)< T > [Read](#) ([NetworkBehaviourBuffer](#) first)
Reads a network array from the provided network behaviour buffer.

6.123.1 Detailed Description

Provides a reader for network arrays of type T.

Template Parameters

<i>T</i>	The type of elements in the network array.
----------	--

6.123.2 Member Function Documentation

6.123.2.1 Read()

```
NetworkArrayReadOnly<T> Read (  
    NetworkBehaviourBuffer first )
```

Reads a network array from the provided network behaviour buffer.

Parameters

<i>first</i>	The network behaviour buffer to read the network array from.
--------------	--

Returns

A read-only view of the network array.

6.124 NetworkBehaviour.BehaviourReader< T > Struct Template Reference

Provides a reader for network behaviours of type T.

Public Member Functions

- **T Read** ([NetworkBehaviourBuffer](#) first)
Reads a network behaviour from the provided network behaviour buffer.
- **T Read** ([NetworkBehaviourBuffer](#) first, [NetworkBehaviourBuffer](#) second)

Public Attributes

- **T**
Reads two network behaviours from the provided network behaviour buffers.

6.124.1 Detailed Description

Provides a reader for network behaviours of type T.

Template Parameters

<i>T</i>	The type of the network behaviour.
----------	------------------------------------

Type Constraints

T: [NetworkBehaviour](#)

6.124.2 Member Function Documentation

6.124.2.1 Read()

```
T Read (
    NetworkBehaviourBuffer first )
```

Reads a network behaviour from the provided network behaviour buffer.

Parameters

<i>first</i>	The network behaviour buffer to read the network behaviour from.
--------------	--

Returns

The network behaviour of type *T* read from the buffer. Returns null if the behaviour is not found.

6.124.3 Member Data Documentation

6.124.3.1 T

T

Reads two network behaviours from the provided network behaviour buffers.

Parameters

<i>first</i>	The first network behaviour buffer to read the network behaviour from.
<i>second</i>	The second network behaviour buffer to read the network behaviour from.

Returns

A tuple containing the two network behaviours of type *T* read from the buffers.

6.125 NetworkBehaviour.ChangeDetector Class Reference

Change detector for a [NetworkBehaviour](#)

Classes

- struct [Enumerable](#)
Struct representing a collection of changes detected in a [NetworkBehaviour](#).
- struct [Enumerator](#)
[Enumerator](#) for the collection of changes detected in a [NetworkBehaviour](#).

Public Types

- enum class [Source](#)
Enum representing the source of a [NetworkBehaviour](#)'s state.

Public Member Functions

- [Enumerable](#) [DetectChanges](#) ([NetworkBehaviour](#) b, bool copyChanges=true)
Detects changes in a [NetworkBehaviour](#) and returns an [Enumerable](#) of the changes.
- [Enumerable](#) [DetectChanges](#) ([NetworkBehaviour](#) b, out [NetworkBehaviourBuffer](#) previous, out [NetworkBehaviourBuffer](#) current, bool copyChanges=true)
Detects changes in a [NetworkBehaviour](#) and returns an [Enumerable](#) of the changes.
- void [Init](#) ([NetworkBehaviour](#) networkBehaviour, [Source](#) source, bool copyInitial=true)
Initializes the [ChangeDetector](#) for a given [NetworkBehaviour](#).

6.125.1 Detailed Description

Change detector for a [NetworkBehaviour](#)

This class is used to detect changes in a [NetworkBehaviour](#). It can be used to detect changes in a [NetworkBehaviour](#) between two snapshots, or between the current state and a snapshot.

6.125.2 Member Enumeration Documentation

6.125.2.1 Source

```
enum Source [strong]
```

Enum representing the source of a [NetworkBehaviour](#)'s state.

Enumerator

SimulationState	The state is the current simulation state of the NetworkBehaviour .
SnapshotFrom	The state is from a previous snapshot of the NetworkBehaviour .
SnapshotTo	The state is from a future snapshot of the NetworkBehaviour .

6.125.3 Member Function Documentation

6.125.3.1 DetectChanges() [1/2]

```
Enumerable DetectChanges (
    NetworkBehaviour b,
    bool copyChanges = true )
```

Detects changes in a [NetworkBehaviour](#) and returns an [Enumerable](#) of the changes.

Parameters

<i>b</i>	The NetworkBehaviour instance to detect changes in.
<i>copyChanges</i>	Whether to copy the changes detected. Defaults to true.

Returns

An [Enumerable](#) of the changes detected in the [NetworkBehaviour](#).

6.125.3.2 DetectChanges() [2/2]

```
Enumerable DetectChanges (
    NetworkBehaviour b,
    out NetworkBehaviourBuffer previous,
    out NetworkBehaviourBuffer current,
    bool copyChanges = true )
```

Detects changes in a [NetworkBehaviour](#) and returns an [Enumerable](#) of the changes.

Parameters

<i>b</i>	The NetworkBehaviour instance to detect changes in.
<i>previous</i>	The previous state of the NetworkBehaviour .
<i>current</i>	The current state of the NetworkBehaviour .
<i>copyChanges</i>	Whether to copy the changes detected. Defaults to true.

Returns

An [Enumerable](#) of the changes detected in the [NetworkBehaviour](#).

6.125.3.3 Init()

```
void Init (
    NetworkBehaviour networkBehaviour,
    Source source,
    bool copyInitial = true )
```

Initializes the [ChangeDetector](#) for a given [NetworkBehaviour](#).

Parameters

<i>networkBehaviour</i>	The NetworkBehaviour instance to initialize the ChangeDetector for.
<i>source</i>	The source of the NetworkBehaviour 's state.
<i>copyInitial</i>	Whether to copy the initial state of the NetworkBehaviour . Defaults to true.

6.126 NetworkBehaviour.ChangeDetector.Enumerable Struct Reference

Struct representing a collection of changes detected in a [NetworkBehaviour](#).

Public Member Functions

- bool [Changed](#) (string name)
Checks if a property has changed.
- [Enumerator GetEnumerator](#) ()
Gets an enumerator for the collection of changes.

6.126.1 Detailed Description

Struct representing a collection of changes detected in a [NetworkBehaviour](#).

6.126.2 Member Function Documentation

6.126.2.1 Changed()

```
bool Changed (
    string name )
```

Checks if a property has changed.

Parameters

<i>name</i>	The name of the property to check.
-------------	------------------------------------

Returns

True if the property has changed, false otherwise.

6.126.2.2 GetEnumerator()

`Enumerator GetEnumerator ( )`

Gets an enumerator for the collection of changes.

Returns

An [Enumerator](#) for the collection of changes.

6.127 NetworkBehaviour.ChangeDetector.Enumerator Struct Reference

[Enumerator](#) for the collection of changes detected in a [NetworkBehaviour](#).

Public Member Functions

- bool [MoveNext](#) ()
Advances the enumerator to the next property in the array of changed properties.
- void [Reset](#) ()
Resets the enumerator to its initial state.

Properties

- string [Current](#) [get]
Gets the current property name in the array of changed properties.

6.127.1 Detailed Description

[Enumerator](#) for the collection of changes detected in a [NetworkBehaviour](#).

6.127.2 Member Function Documentation

6.127.2.1 MoveNext()

```
bool MoveNext ( )
```

Advances the enumerator to the next property in the array of changed properties.

Returns

True if the enumerator was successfully advanced to the next property, false if the enumerator has passed the end of the array.

6.127.2.2 Reset()

```
void Reset ( )
```

Resets the enumerator to its initial state.

6.127.3 Property Documentation

6.127.3.1 Current

```
string Current [get]
```

Gets the current property name in the array of changed properties.

6.128 NetworkBehaviour.DictionaryReader< K, V > Struct Template Reference

Provides a reader for network dictionaries with keys of type K and values of type V.

Public Member Functions

- [NetworkDictionaryReadOnly](#)< K, V > [Read](#) ([NetworkBehaviourBuffer](#) first)
Reads a network dictionary from the provided network behaviour buffer.

6.128.1 Detailed Description

Provides a reader for network dictionaries with keys of type K and values of type V.

Template Parameters

<i>K</i>	The type of keys in the network dictionary.
<i>V</i>	The type of values in the network dictionary.

6.128.2 Member Function Documentation**6.128.2.1 Read()**

```
NetworkDictionaryReadOnly<K, V> Read (
    NetworkBehaviourBuffer first )
```

Reads a network dictionary from the provided network behaviour buffer.

Parameters

<i>first</i>	The network behaviour buffer to read the network dictionary from.
--------------	---

Returns

A read-only view of the network dictionary.

6.129 NetworkBehaviour.LinkListReader< T > Struct Template Reference

Provides a reader for network linked lists of type T.

Public Member Functions

- [NetworkLinkedListReadOnly< T > Read \(NetworkBehaviourBuffer first\)](#)
Reads a network linked list from the provided network behaviour buffer.

6.129.1 Detailed Description

Provides a reader for network linked lists of type T.

Template Parameters

<i>T</i>	The type of elements in the network linked list.
----------	--

6.129.2 Member Function Documentation

6.129.2.1 Read()

```
NetworkLinkedListReadOnly<T> Read (
    NetworkBehaviourBuffer first )
```

Reads a network linked list from the provided network behaviour buffer.

Parameters

<i>first</i>	The network behaviour buffer to read the network linked list from.
--------------	--

Returns

A read-only view of the network linked list.

6.130 NetworkBehaviour.PropertyReader< T > Struct Template Reference

Provides a reader for properties of type T in a network behaviour.

Public Member Functions

- [PropertyReader](#) (int *offset*)
Constructs a new [PropertyReader](#) with the provided offset.
- [T Read](#) ([NetworkBehaviourBuffer](#) *first*)
Reads a property of type T from the provided network behaviour buffer.
- [T Read](#) ([NetworkBehaviourBuffer](#) *first*, [NetworkBehaviourBuffer](#) *second*)

Public Attributes

- [T](#)
Reads a property of type T from the provided network behaviour buffers.

6.130.1 Detailed Description

Provides a reader for properties of type T in a network behaviour.

Template Parameters

<i>T</i>	The type of the property in the network behaviour. Must be unmanaged.
----------	---

Type Constraints

T : *unmanaged*

6.130.2 Constructor & Destructor Documentation

6.130.2.1 PropertyReader()

```
PropertyReader (
    int offset )
```

Constructs a new [PropertyReader](#) with the provided offset.

Parameters

<i>offset</i>	The offset of the property in the network behaviour buffer.
---------------	---

6.130.3 Member Function Documentation

6.130.3.1 Read()

```
T Read (
    NetworkBehaviourBuffer first )
```

Reads a property of type T from the provided network behaviour buffer.

Parameters

<i>first</i>	The network behaviour buffer to read the property from.
--------------	---

Returns

The property of type T read from the buffer.

6.130.4 Member Data Documentation

6.130.4.1 T

T

Reads a property of type T from the provided network behaviour buffers.

Parameters

<i>first</i>	The first network behaviour buffer to read the property from.
<i>second</i>	The second network behaviour buffer to read the property from.

Returns

A tuple containing the property of type T read from the first and second buffers.

6.131 NetworkBehaviourBuffer Struct Reference

Provides low level accesss to data buffers that can be read using a NetworkBehaviour.Reader

Public Member Functions

- float [Read](#) ([NetworkBehaviour.PropertyReader](#)< float > reader)
Reads a float property from the buffer using the provided PropertyReader.
- Quaternion [Read](#) ([NetworkBehaviour.PropertyReader](#)< Quaternion > reader)
Reads a Quaternion property from the buffer using the provided PropertyReader.
- Vector2 [Read](#) ([NetworkBehaviour.PropertyReader](#)< Vector2 > reader)
Reads a Vector2 property from the buffer using the provided PropertyReader.
- Vector3 [Read](#) ([NetworkBehaviour.PropertyReader](#)< Vector3 > reader)
Reads a Vector3 property from the buffer using the provided PropertyReader.
- Vector4 [Read](#) ([NetworkBehaviour.PropertyReader](#)< Vector4 > reader)
Reads a Vector4 property from the buffer using the provided PropertyReader.
- T [Read](#)< T > ([NetworkBehaviour.BehaviourReader](#)< T > reader)
Reads a [NetworkBehaviour](#) from the buffer using the provided BehaviourReader.
- T [Read](#)< T > ([NetworkBehaviour.PropertyReader](#)< T > reader)
Reads a property from the buffer using the provided PropertyReader.
- unsafe T [ReinterpretState](#)< T > (int offset=0)
Reinterprets the state of the buffer at a given offset as a specific type.

Static Public Member Functions

- static implicit [operator bool](#) ([NetworkBehaviourBuffer](#) buffer)
Implicit conversion operator to bool. This allows a [NetworkBehaviourBuffer](#) instance to be used in conditions directly.

Properties

- int [Length](#) [get]
Gets the length of the buffer.
- int [this\[int index\]](#) [get]
Indexer to get the value at a specific index in the buffer.
- [Tick Tick](#) [get]
Gets the tick at which the buffer was created.
- bool [Valid](#) [get]
Gets a value indicating whether the buffer is valid. A buffer is considered valid if the pointer to the start of the buffer is not null and the length of the buffer is greater than 0.

6.131.1 Detailed Description

Provides low level access to data buffers that can be read using a `NetworkBehaviourReader`

6.131.2 Member Function Documentation

6.131.2.1 `operator bool()`

```
static implicit operator bool (  
    NetworkBehaviourBuffer buffer ) [static]
```

Implicit conversion operator to `bool`. This allows a [NetworkBehaviourBuffer](#) instance to be used in conditions directly.

Parameters

<i>buffer</i>	The NetworkBehaviourBuffer instance to convert.
---------------	---

Returns

True if the buffer is valid, false otherwise.

6.131.2.2 `Read()` [1/5]

```
float Read (  
    NetworkBehaviour.PropertyReader< float > reader )
```

Reads a float property from the buffer using the provided `PropertyReader`.

Parameters

<i>reader</i>	The <code>PropertyReader</code> to use for reading the float property.
---------------	--

Returns

The read float property.

6.131.2.3 `Read()` [2/5]

```
Quaternion Read (  
    NetworkBehaviour.PropertyReader< Quaternion > reader )
```

Reads a Quaternion property from the buffer using the provided `PropertyReader`.

Parameters

<i>reader</i>	The PropertyReader to use for reading the Quaternion property.
---------------	--

Returns

The read Quaternion property.

6.131.2.4 Read() [3/5]

```
Vector2 Read (  
    NetworkBehaviour.PropertyReader< Vector2 > reader )
```

Reads a Vector2 property from the buffer using the provided PropertyReader.

Parameters

<i>reader</i>	The PropertyReader to use for reading the Vector2 property.
---------------	---

Returns

The read Vector2 property.

6.131.2.5 Read() [4/5]

```
Vector3 Read (  
    NetworkBehaviour.PropertyReader< Vector3 > reader )
```

Reads a Vector3 property from the buffer using the provided PropertyReader.

Parameters

<i>reader</i>	The PropertyReader to use for reading the Vector3 property.
---------------	---

Returns

The read Vector3 property.

6.131.2.6 Read() [5/5]

```
Vector4 Read (  
    NetworkBehaviour.PropertyReader< Vector4 > reader )
```

Reads a Vector4 property from the buffer using the provided PropertyReader.

Parameters

<i>reader</i>	The PropertyReader to use for reading the Vector4 property.
---------------	---

Returns

The read Vector4 property.

6.131.2.7 Read< T >() [1/2]

```
T Read< T > (
    NetworkBehaviour.BehaviourReader< T > reader )
```

Reads a [NetworkBehaviour](#) from the buffer using the provided BehaviourReader.

Template Parameters

<i>T</i>	The type of NetworkBehaviour to read. Must be a subclass of NetworkBehaviour .
----------	--

Parameters

<i>reader</i>	The BehaviourReader to use for reading the NetworkBehaviour .
---------------	---

Returns

The read [NetworkBehaviour](#).

Type Constraints

***T* : [NetworkBehaviour](#)**

6.131.2.8 Read< T >() [2/2]

```
T Read< T > (
    NetworkBehaviour.PropertyReader< T > reader )
```

Reads a property from the buffer using the provided PropertyReader.

Template Parameters

<i>T</i>	The type of the property to read. Must be unmanaged.
----------	--

Parameters

<i>reader</i>	The PropertyReader to use for reading the property.
---------------	---

Returns

The read property.

Type Constraints

T* : *unmanaged

6.131.2.9 ReinterpretState< T >()

```
unsafe T ReinterpretState< T > (  
    int offset = 0 )
```

Reinterprets the state of the buffer at a given offset as a specific type.

Template Parameters

<i>T</i>	The type to reinterpret the state as. Must be unmanaged.
----------	--

Parameters

<i>offset</i>	The offset at which to start reinterpreting. Defaults to 0.
---------------	---

Returns

The state of the buffer at the given offset, reinterpreted as the specified type.

Type Constraints

T* : *unmanaged

6.131.3 Property Documentation**6.131.3.1 Length**

```
int Length [get]
```

Gets the length of the buffer.

6.131.3.2 `this[int index]`

```
int this[int index] [get]
```

Indexer to get the value at a specific index in the buffer.

Parameters

<i>index</i>	The index to get the value from.
--------------	----------------------------------

Returns

The value at the specified index in the buffer.

6.131.3.3 `Tick`

```
Tick Tick [get]
```

Gets the tick at which the buffer was created.

6.131.3.4 `Valid`

```
bool Valid [get]
```

Gets a value indicating whether the buffer is valid. A buffer is considered valid if the pointer to the start of the buffer is not null and the length of the buffer is greater than 0.

6.132 NetworkBehaviourBufferInterpolator Struct Reference

The [NetworkBehaviourBufferInterpolator](#) struct is used to interpolate between two [NetworkBehaviourBuffer](#) instances. This is a read-only, ref struct, meaning it cannot be boxed and it can only be used on the stack.

Public Member Functions

- float [Angle](#) ([NetworkBehaviour.PropertyReader](#)< [Angle](#) > property)
Gets the interpolated angle of a property.
- float [Angle](#) (string property)
Gets the interpolated angle of a property.
- bool [Bool](#) ([NetworkBehaviour.PropertyReader](#)< bool > property)
Gets the interpolated boolean value of a property.
- bool [Bool](#) (string property)
Gets the interpolated boolean value of a property.
- float [Float](#) ([NetworkBehaviour.PropertyReader](#)< float > property)
Gets the interpolated float value of a property.
- float [Float](#) (string property)
Gets the interpolated float value of a property.
- int [Int](#) ([NetworkBehaviour.PropertyReader](#)< int > property)
Gets the interpolated integer value of a property.
- int [Int](#) (string property)
Gets the interpolated integer value of a property.
- [NetworkBehaviourBufferInterpolator](#) ([NetworkBehaviour](#) nb)
Constructor for the [NetworkBehaviourBufferInterpolator](#) struct.
- Quaternion [Quaternion](#) ([NetworkBehaviour.PropertyReader](#)< Quaternion > property)
Gets the interpolated Quaternion value of a property.
- Quaternion [Quaternion](#) (string property)
Gets the interpolated Quaternion value of a property.
- T [Select](#)< T > ([NetworkBehaviour.PropertyReader](#)< T > property)
Selects the interpolated value of a property.
- T [Select](#)< T > (string property)
Selects the interpolated value of a property by its name.
- Vector2 [Vector2](#) ([NetworkBehaviour.PropertyReader](#)< Vector2 > property)
Gets the interpolated Vector2 value of a property.
- Vector2 [Vector2](#) (string property)
Gets the interpolated Vector2 value of a property.
- Vector3 [Vector3](#) ([NetworkBehaviour.PropertyReader](#)< Vector3 > property)
Gets the interpolated Vector3 value of a property.
- Vector3 [Vector3](#) (string property)
Gets the interpolated Vector3 value of a property.
- Vector4 [Vector4](#) ([NetworkBehaviour.PropertyReader](#)< Vector4 > property)
Gets the interpolated Vector4 value of a property.
- Vector4 [Vector4](#) (string property)
Gets the interpolated Vector4 value of a property.

Static Public Member Functions

- static implicit [operator bool](#) ([NetworkBehaviourBufferInterpolator](#) i)
Implicit conversion operator to bool. This allows a [NetworkBehaviourBufferInterpolator](#) instance to be used in conditions directly.

Public Attributes

- readonly float [Alpha](#)
The interpolation factor, ranging from 0 to 1. This value is used to interpolate between the "from" and "to" states.
- readonly [NetworkBehaviour Behaviour](#)
The [NetworkBehaviour](#) instance that this interpolator is associated with.
- readonly [NetworkBehaviourBuffer From](#)
The [NetworkBehaviourBuffer](#) instance representing the "from" state for interpolation.
- readonly [NetworkBehaviourBuffer To](#)
The [NetworkBehaviourBuffer](#) instance representing the "to" state for interpolation.
- readonly bool [Valid](#)
A value indicating whether this interpolator is valid. An interpolator is considered valid if it has successfully retrieved the "from" and "to" buffers.

6.132.1 Detailed Description

The [NetworkBehaviourBufferInterpolator](#) struct is used to interpolate between two [NetworkBehaviourBuffer](#) instances. This is a read-only, ref struct, meaning it cannot be boxed and it can only be used on the stack.

6.132.2 Constructor & Destructor Documentation

6.132.2.1 NetworkBehaviourBufferInterpolator()

```
NetworkBehaviourBufferInterpolator (
    NetworkBehaviour nb )
```

Constructor for the [NetworkBehaviourBufferInterpolator](#) struct.

Parameters

<i>nb</i>	The NetworkBehaviour instance that this interpolator is associated with.
-----------	--

6.132.3 Member Function Documentation

6.132.3.1 Angle() [1/2]

```
float Angle (
    NetworkBehaviour.PropertyReader< Angle > property )
```

Gets the interpolated angle of a property.

Parameters

<i>property</i>	The PropertyReader for the property to get the angle of.
-----------------	--

Returns

The interpolated angle of the property.

6.132.3.2 Angle() [2/2]

```
float Angle (  
    string property )
```

Gets the interpolated angle of a property.

Parameters

<i>property</i>	The name of the property to get the angle of.
-----------------	---

Returns

The interpolated angle of the property.

6.132.3.3 Bool() [1/2]

```
bool Bool (  
    NetworkBehaviour.PropertyReader< bool > property )
```

Gets the interpolated boolean value of a property.

Parameters

<i>property</i>	The PropertyReader for the property to get the boolean value of.
-----------------	--

Returns

The interpolated boolean value of the property.

6.132.3.4 Bool() [2/2]

```
bool Bool (  
    string property )
```


Gets the interpolated boolean value of a property.

Parameters

<i>property</i>	The name of the property to get the boolean value of.
-----------------	---

Returns

The interpolated boolean value of the property.

6.132.3.5 Float() [1/2]

```
float Float (
    NetworkBehaviour.PropertyReader< float > property )
```

Gets the interpolated float value of a property.

Parameters

<i>property</i>	The PropertyReader for the property to get the float value of.
-----------------	--

Returns

The interpolated float value of the property.

6.132.3.6 Float() [2/2]

```
float Float (
    string property )
```

Gets the interpolated float value of a property.

Parameters

<i>property</i>	The name of the property to get the float value of.
-----------------	---

Returns

The interpolated float value of the property.

6.132.3.7 Int() [1/2]

```
int Int (
    NetworkBehaviour.PropertyReader< int > property )
```

Gets the interpolated integer value of a property.

Parameters

<i>property</i>	The PropertyReader for the property to get the integer value of.
-----------------	--

Returns

The interpolated integer value of the property.

6.132.3.8 Int() [2/2]

```
int Int (
    string property )
```

Gets the interpolated integer value of a property.

Parameters

<i>property</i>	The name of the property to get the integer value of.
-----------------	---

Returns

The interpolated integer value of the property.

6.132.3.9 operator bool()

```
static implicit operator bool (
    NetworkBehaviourBufferInterpolator i ) [static]
```

Implicit conversion operator to bool. This allows a [NetworkBehaviourBufferInterpolator](#) instance to be used in conditions directly.

Parameters

<i>i</i>	The NetworkBehaviourBufferInterpolator instance to convert.
----------	---

Returns

True if the interpolator is valid, false otherwise.

6.132.3.10 Quaternion() [1/2]

```
Quaternion Quaternion (
    NetworkBehaviour.PropertyReader< Quaternion > property )
```

Gets the interpolated Quaternion value of a property.

Parameters

<i>property</i>	The PropertyReader for the property to get the Quaternion value of.
-----------------	---

Returns

The interpolated Quaternion value of the property.

6.132.3.11 Quaternion() [2/2]

```
Quaternion Quaternion (
    string property )
```

Gets the interpolated Quaternion value of a property.

Parameters

<i>property</i>	The name of the property to get the Quaternion value of.
-----------------	--

Returns

The interpolated Quaternion value of the property.

6.132.3.12 Select< T >() [1/2]

```
T Select< T > (
    NetworkBehaviour.PropertyReader< T > property )
```

Selects the interpolated value of a property.

Template Parameters

<i>T</i>	The type of the property to select. Must be unmanaged.
----------	--

Parameters

<i>property</i>	The PropertyReader for the property to select.
-----------------	--

Returns

The interpolated value of the property.

Type Constraints

T : unmanaged

6.132.3.13 Select< T >() [2/2]

```
T Select< T > (
    string property )
```

Selects the interpolated value of a property by its name.

Template Parameters

<i>T</i>	The type of the property to select. Must be unmanaged.
----------	--

Parameters

<i>property</i>	The name of the property to select.
-----------------	-------------------------------------

Returns

The interpolated value of the property.

Type Constraints

T : unmanaged

6.132.3.14 Vector2() [1/2]

```
Vector2 Vector2 (
    NetworkBehaviour.PropertyReader< Vector2 > property )
```

Gets the interpolated Vector2 value of a property.

Parameters

<i>property</i>	The PropertyReader for the property to get the Vector2 value of.
-----------------	--

Returns

The interpolated Vector2 value of the property.

6.132.3.15 Vector2() [2/2]

```
Vector2 Vector2 (
    string property )
```

Gets the interpolated Vector2 value of a property.

Parameters

<i>property</i>	The name of the property to get the Vector2 value of.
-----------------	---

Returns

The interpolated Vector2 value of the property.

6.132.3.16 Vector3() [1/2]

```
Vector3 Vector3 (
    NetworkBehaviour.PropertyReader< Vector3 > property )
```

Gets the interpolated Vector3 value of a property.

Parameters

<i>property</i>	The PropertyReader for the property to get the Vector3 value of.
-----------------	--

Returns

The interpolated Vector3 value of the property.

6.132.3.17 Vector3() [2/2]

```
Vector3 Vector3 (
    string property )
```

Gets the interpolated Vector3 value of a property.

Parameters

<i>property</i>	The name of the property to get the Vector3 value of.
-----------------	---

Returns

The interpolated Vector3 value of the property.

6.132.3.18 Vector4() [1/2]

```
Vector4 Vector4 (
    NetworkBehaviour.PropertyReader< Vector4 > property )
```

Gets the interpolated Vector4 value of a property.

Parameters

<i>property</i>	The PropertyReader for the property to get the Vector4 value of.
-----------------	--

Returns

The interpolated Vector4 value of the property.

6.132.3.19 Vector4() [2/2]

```
Vector4 Vector4 (
    string property )
```

Gets the interpolated Vector4 value of a property.

Parameters

<i>property</i>	The name of the property to get the Vector4 value of.
-----------------	---

Returns

The interpolated Vector4 value of the property.

6.132.4 Member Data Documentation

6.132.4.1 Alpha

```
readonly float Alpha
```

The interpolation factor, ranging from 0 to 1. This value is used to interpolate between the "from" and "to" states.

6.132.4.2 Behaviour

readonly [NetworkBehaviour](#) Behaviour

The [NetworkBehaviour](#) instance that this interpolator is associated with.

6.132.4.3 From

readonly [NetworkBehaviourBuffer](#) From

The [NetworkBehaviourBuffer](#) instance representing the "from" state for interpolation.

6.132.4.4 To

readonly [NetworkBehaviourBuffer](#) To

The [NetworkBehaviourBuffer](#) instance representing the "to" state for interpolation.

6.132.4.5 Valid

readonly bool Valid

A value indicating whether this interpolator is valid. An interpolator is considered valid if it has successfully retrieved the "from" and "to" buffers.

6.133 NetworkBehaviourId Struct Reference

Represents the unique identifier for a [NetworkBehaviour](#) instance.

Inherits [INetworkStruct](#), and [IEquatable< NetworkBehaviourId >](#).

Public Member Functions

- bool [Equals](#) ([NetworkBehaviourId](#) other)
Checks if this [NetworkBehaviourId](#) is equal to another [NetworkBehaviourId](#). Two [NetworkBehaviourIds](#) are equal if their [Objects](#) and [Behaviours](#) are equal.
- override bool [Equals](#) (object obj)
Checks if this [NetworkBehaviourId](#) is equal to another object. The object is considered equal if it is a [NetworkBehaviourId](#) and its [Object](#) and [Behaviour](#) are equal to this [NetworkBehaviourId](#)'s.
- override int [GetHashCode](#) ()
Returns a hash code for this [NetworkBehaviourId](#). The hash code is computed based on the [Object](#)'s hash code and the [Behaviour](#).
- override string [ToString](#) ()
Returns a string representation of the [NetworkBehaviourId](#). The string representation is in the format: [Object↔:{Object}, Behaviour:{Behaviour}].

Static Public Member Functions

- static bool `operator!=` (`NetworkBehaviourId` a, `NetworkBehaviourId` b)
Determines whether two `NetworkBehaviourId` instances are not equal. Two `NetworkBehaviourId` instances are considered not equal if their Objects or Behaviours are not equal.
- static bool `operator==` (`NetworkBehaviourId` a, `NetworkBehaviourId` b)
Determines whether two `NetworkBehaviourId` instances are equal. Two `NetworkBehaviourId` instances are considered equal if their Objects and Behaviours are equal.

Public Attributes

- int `Behaviour`
The identifier for the behaviour within the object.
- `NetworkId` Object
The `NetworkId` of the object this behaviour belongs to.

Static Public Attributes

- const int `SIZE` = `NetworkId.SIZE` + `sizeof(int)`
Size of the `NetworkBehaviourId` structure in bytes.

Properties

- bool `IsValid` [get]
Checks if the `NetworkBehaviourId` is valid. A `NetworkBehaviourId` is valid if its Object is valid and its `Behaviour` is non-negative.
- static `NetworkBehaviourId` `None` [get]
Returns a new `NetworkBehaviourId` with default values.

6.133.1 Detailed Description

Represents the unique identifier for a `NetworkBehaviour` instance.

6.133.2 Member Function Documentation

6.133.2.1 `Equals()` [1/2]

```
bool Equals (
    NetworkBehaviourId other )
```

Checks if this `NetworkBehaviourId` is equal to another `NetworkBehaviourId`. Two `NetworkBehaviourIds` are equal if their Objects and Behaviours are equal.

Parameters

<i>other</i>	The other NetworkBehaviourId to compare with.
--------------	---

Returns

True if the NetworkBehaviourIds are equal, false otherwise.

6.133.2.2 Equals() [2/2]

```
override bool Equals (  
    object obj )
```

Checks if this [NetworkBehaviourId](#) is equal to another object. The object is considered equal if it is a [NetworkBehaviourId](#) and its Object and [Behaviour](#) are equal to this [NetworkBehaviourId](#)'s.

Parameters

<i>obj</i>	The object to compare with.
------------	-----------------------------

Returns

True if the object is a [NetworkBehaviourId](#) and is equal to this, false otherwise.

6.133.2.3 GetHashCode()

```
override int GetHashCode ( )
```

Returns a hash code for this [NetworkBehaviourId](#). The hash code is computed based on the Object's hash code and the [Behaviour](#).

Returns

A hash code for this [NetworkBehaviourId](#).

6.133.2.4 operator"!=()"

```
static bool operator!= (  
    NetworkBehaviourId a,  
    NetworkBehaviourId b ) [static]
```

Determines whether two [NetworkBehaviourId](#) instances are not equal. Two [NetworkBehaviourId](#) instances are considered not equal if their Objects or Behaviours are not equal.

Parameters

<i>a</i>	The first NetworkBehaviourId to compare.
<i>b</i>	The second NetworkBehaviourId to compare.

Returns

True if the [NetworkBehaviourId](#) instances are not equal, false otherwise.

6.133.2.5 operator==()

```
static bool operator== (
    NetworkBehaviourId a,
    NetworkBehaviourId b ) [static]
```

Determines whether two [NetworkBehaviourId](#) instances are equal. Two [NetworkBehaviourId](#) instances are considered equal if their Objects and Behaviours are equal.

Parameters

<i>a</i>	The first NetworkBehaviourId to compare.
<i>b</i>	The second NetworkBehaviourId to compare.

Returns

True if the [NetworkBehaviourId](#) instances are equal, false otherwise.

6.133.2.6 ToString()

```
override string ToString ( )
```

Returns a string representation of the [NetworkBehaviourId](#). The string representation is in the format: [Object↔:{Object}, Behaviour:{Behaviour}].

Returns

A string representation of the [NetworkBehaviourId](#).

6.133.3 Member Data Documentation

6.133.3.1 Behaviour

`int Behaviour`

The identifier for the behaviour within the object.

6.133.3.2 Object

`NetworkId Object`

The [NetworkId](#) of the object this behaviour belongs to.

6.133.3.3 SIZE

`const int SIZE = NetworkId.SIZE + sizeof(int) [static]`

Size of the [NetworkBehaviourId](#) structure in bytes.

6.133.4 Property Documentation

6.133.4.1 IsValid

`bool IsValid [get]`

Checks if the [NetworkBehaviourId](#) is valid. A [NetworkBehaviourId](#) is valid if its Object is valid and its [Behaviour](#) is non-negative.

6.133.4.2 None

`NetworkBehaviourId None [static], [get]`

Returns a new [NetworkBehaviourId](#) with default values.

6.134 NetworkBehaviourUtils Class Reference

This static class provides utility methods for working with [NetworkBehaviour](#) objects.

Classes

- struct [ArrayInitializer](#)
A utility structure for initializing [NetworkArray](#) and [NetworkLinkedList](#) with inline initialization.
- struct [DictionaryInitializer](#)
A utility structure for initializing [NetworkDictionary](#) with inline initialization.
- struct [MetaData](#)
This structure holds metadata for a [NetworkBehaviour](#) object.

Static Public Member Functions

- static [T\[\] CloneArray< T >](#) ([T\[\]](#) array)
Creates a new array that is a clone of the specified array.
- static void [CopyFromNetworkArray< T >](#) ([NetworkArray< T >](#) networkArray, [ref T\[\]](#) dstArray)
Copies the values from a [NetworkArray](#) to a destination array.
- static void [CopyFromNetworkDictionary< D, K, V >](#) ([NetworkDictionary< K, V >](#) networkDictionary, [ref D](#) dictionary)
Copies the values from a [NetworkDictionary](#) to a destination dictionary.
- static void [CopyFromNetworkList< T >](#) ([NetworkLinkedList< T >](#) networkList, [ref T\[\]](#) dstArray)
Copies the values from a [NetworkLinkedList](#) to a destination array.
- static [MetaData GetMetaData](#) ([Type](#) type)
Retrieves the metadata for a given type.
- static int [GetRpcStaticIndexOrThrow](#) (string key)
Retrieves the index of a static RPC (Remote Procedure Call) based on its key.
- static int [GetStaticWordCount](#) ([Type](#) type)
Retrieves the static word count for a given type. If the word count for the type has not been computed yet, it is computed and stored.
- static int [GetWordCount](#) ([NetworkBehaviour](#) behaviour)
Retrieves the word count for a given [NetworkBehaviour](#). If the [NetworkBehaviour](#) has a dynamic word count, it is returned. Otherwise, the static word count for the type of the [NetworkBehaviour](#) is returned.
- static bool [HasStaticWordCount](#) ([Type](#) type)
Checks if a given type has a static word count. A type has a static word count if it is a subclass of [NetworkBehaviour](#) and its word count is non-negative.
- static void [InitializeNetworkArray< T >](#) ([NetworkArray< T >](#) networkArray, [T\[\]](#) sourceArray, string name)
Initializes a [NetworkArray](#) with the values from a source array.
- static void [InitializeNetworkDictionary< D, K, V >](#) ([NetworkDictionary< K, V >](#) networkDictionary, [D](#) dictionary, string name)
Initializes a [NetworkDictionary](#) with the values from a source dictionary.
- static void [InitializeNetworkList< T >](#) ([NetworkLinkedList< T >](#) networkList, [T\[\]](#) sourceArray, string name)
Initializes a [NetworkLinkedList](#) with the values from a source array.
- static void [InternalOnDestroy](#) ([SimulationBehaviour](#) obj)
This method is not meant to be called directly. Calls are injected by the Weaver.
- static void [InternalOnDisable](#) ([SimulationBehaviour](#) obj)
This method is not meant to be called directly. Calls are injected by the Weaver.
- static void [InternalOnEnable](#) ([SimulationBehaviour](#) obj)
This method is not meant to be called directly. Calls are injected by the Weaver.
- static [SerializableDictionary< K, V >](#) [MakeSerializableDictionary< K, V >](#) ([Dictionary< K, V >](#) dictionary)
Wraps a Dictionary in a [SerializableDictionary](#).
- static void [NotifyLocalSimulationNotAllowedToSendRpc](#) (string rpc, [NetworkObject](#) obj, int sources)
Logs an error message indicating that a local simulation is not allowed to send a specific RPC.
- static void [NotifyLocalTargetedRpcCulled](#) ([PlayerRef](#) player, string methodName)

- Logs a warning message indicating that a local targeted RPC was culled.*
- static void [NotifyNetworkUnwrapFailed< T >](#) (T wrapper, Type valueType)
 - Logs a warning message indicating that a network unwrap operation failed.*
- static void [NotifyNetworkWrapFailed< T >](#) (T value)
 - Logs a warning message indicating that a network wrap operation failed.*
- static void [NotifyNetworkWrapFailed< T >](#) (T value, Type wrapperType)
 - Logs a warning message indicating that a network wrap operation failed for a specific wrapper type.*
- static void [NotifyRpcTargetUnreachable](#) ([PlayerRef](#) player, string rpc)
 - Logs an error message indicating that the target of a Remote Procedure Call (RPC) is not reachable.*
- static void [RegisterMetaData](#) (Type type)
 - Registers the metadata for a given type. This method checks if the type has an override for the "ReplicateTo" method and stores this information in the metadata. If the metadata for the type already exists, this method does nothing.*
- static void [RegisterRpcInvokeDelegates](#) (Type type)
 - Registers the RPC (Remote Procedure Call) invoke delegates for a given type. This method is only available when the FUSION_UNITY compilation symbol is defined.*
- static bool [ShouldRegisterRpcInvokeDelegates](#) (Type type)
 - Determines whether the RPC (Remote Procedure Call) invoke delegates should be registered for a given type.*
- static void [ThrowIfBehaviourNotInitialized](#) ([NetworkBehaviour](#) behaviour)
 - Checks if the [NetworkBehaviour](#) object is initialized and throws an exception if it is not.*
- static bool [TryGetRpcInvokeDelegateArray](#) (Type type, out [RpcInvokeData\[\]](#) delegates)
 - Tries to get the RPC (Remote Procedure Call) invoke delegate array for a given type.*
- static bool [TryGetRpcStaticInvokeDelegate](#) (int index, out [RpcStaticInvokeDelegate](#) del)
 - Tries to get the static RPC (Remote Procedure Call) invoke delegate based on its index.*

Static Public Attributes

- static bool [InvokeRpc](#) = false
 - A static field that determines whether to invoke RPC (Remote Procedure Call). When set to true, RPCs are invoked. When set to false, RPCs are not invoked. Default value is false.*

6.134.1 Detailed Description

This static class provides utility methods for working with [NetworkBehaviour](#) objects.

6.134.2 Member Function Documentation

6.134.2.1 CloneArray< T >()

```
static T [] CloneArray< T > (
    T[] array ) [static]
```

Creates a new array that is a clone of the specified array.

Template Parameters

T	The type of the elements in the array.
-------------------	--

Parameters

<i>array</i>	The array to clone.
--------------	---------------------

Returns

A new array that is a clone of the specified array. If the specified array is null, an empty array is returned.

6.134.2.2 CopyFromNetworkArray< T >()

```
static void CopyFromNetworkArray< T > (
    NetworkArray< T > networkArray,
    ref T[] dstArray ) [static]
```

Copies the values from a [NetworkArray](#) to a destination array.

Template Parameters

<i>T</i>	The type of the elements in the NetworkArray and destination array.
----------	---

Parameters

<i>networkArray</i>	The NetworkArray from which to copy the values.
<i>dstArray</i>	The destination array to which to copy the values.

If the length of the destination array is not equal to the length of the [NetworkArray](#), a new array of the correct length is created and assigned to the destination array.

Type Constraints

T : unmanaged

6.134.2.3 CopyFromNetworkDictionary< D, K, V >()

```
static void CopyFromNetworkDictionary< D, K, V > (
    NetworkDictionary< K, V > networkDictionary,
    ref D dictionary ) [static]
```

Copies the values from a [NetworkDictionary](#) to a destination dictionary.

Template Parameters

<i>D</i>	The type of the destination dictionary. Must implement IDictionary{K, V} and have a parameterless constructor.
<i>K</i>	The type of the keys in the NetworkDictionary and destination dictionary. Must be unmanaged.
<i>V</i>	The type of the values in the NetworkDictionary and destination dictionary. Must be unmanaged.

Parameters

<i>networkDictionary</i>	The NetworkDictionary from which to copy the values.
<i>dictionary</i>	The destination dictionary to which to copy the values. If the destination dictionary is null, a new dictionary of type D is created.

Type Constraints

D : IDictionary***D : K******D : V******D : new()******K : unmanaged******V : unmanaged*****6.134.2.4 CopyFromNetworkList< T >()**

```
static void CopyFromNetworkList< T > (
    NetworkLinkedList< T > networkList,
    ref T[] dstArray ) [static]
```

Copies the values from a [NetworkLinkedList](#) to a destination array.

Template Parameters

<i>T</i>	The type of the elements in the NetworkLinkedList and destination array.
----------	--

Parameters

<i>networkList</i>	The NetworkLinkedList from which to copy the values.
<i>dstArray</i>	The destination array to which to copy the values. If the length of the destination array is not equal to the count of the NetworkLinkedList , a new array of the correct length is created and assigned to the destination array.

Type Constraints

T : unmanaged**6.134.2.5 GetMetaData()**

```
static MetaData GetMetaData (
    Type type ) [static]
```

Retrieves the metadata for a given type.

Parameters

<i>type</i>	The type for which to retrieve the metadata.
-------------	--

Returns

The metadata for the given type if it exists; otherwise, the default value.

6.134.2.6 GetRpcStaticIndexOrThrow()

```
static int GetRpcStaticIndexOrThrow (  
    string key ) [static]
```

Retrieves the index of a static RPC (Remote Procedure Call) based on its key.

Parameters

<i>key</i>	The key of the static RPC.
------------	----------------------------

Returns

The index of the static RPC if it exists.

Exceptions

<i>System.ArgumentOutOfRangeException</i>	Thrown when the static RPC does not exist.
---	--

6.134.2.7 GetStaticWordCount()

```
static int GetStaticWordCount (  
    Type type ) [static]
```

Retrieves the static word count for a given type. If the word count for the type has not been computed yet, it is computed and stored.

Parameters

<i>type</i>	The type for which to retrieve the static word count.
-------------	---

Returns

The static word count for the given type.

Exceptions

<i>System.ArgumentException</i>	Thrown when the provided type is not a subclass of NetworkBehaviour .
<i>System.InvalidOperationException</i>	Thrown when the provided type does not have a weaved attribute or its word count is negative.

6.134.2.8 GetWordCount()

```
static int GetWordCount (
    NetworkBehaviour behaviour ) [static]
```

Retrieves the word count for a given [NetworkBehaviour](#). If the [NetworkBehaviour](#) has a dynamic word count, it is returned. Otherwise, the static word count for the type of the [NetworkBehaviour](#) is returned.

Parameters

<i>behaviour</i>	The NetworkBehaviour for which to retrieve the word count.
------------------	--

Returns

The word count for the given [NetworkBehaviour](#).

Exceptions

<i>System.InvalidOperationException</i>	Thrown when the dynamic word count or the static word count is negative.
---	--

6.134.2.9 HasStaticWordCount()

```
static bool HasStaticWordCount (
    Type type ) [static]
```

Checks if a given type has a static word count. A type has a static word count if it is a subclass of [NetworkBehaviour](#) and its word count is non-negative.

Parameters

<i>type</i>	The type to check.
-------------	--------------------

Returns

True if the type has a static word count, false otherwise.

Exceptions

<i>System.ArgumentException</i>	Thrown when the provided type is not a subclass of NetworkBehaviour .
<i>System.InvalidOperationException</i>	Thrown when the provided type does not have a weaved attribute.

6.134.2.10 InitializeNetworkArray< T >()

```
static void InitializeNetworkArray< T > (
    NetworkArray< T > networkArray,
    T[] sourceArray,
    string name ) [static]
```

Initializes a [NetworkArray](#) with the values from a source array.

Template Parameters

<i>T</i>	The type of the elements in the NetworkArray and source array.
----------	--

Parameters

<i>networkArray</i>	The NetworkArray to initialize.
<i>sourceArray</i>	The source array from which to copy the values.
<i>name</i>	The name of the NetworkArray for logging purposes.

If the length of the source array is greater than the length of the [NetworkArray](#), a warning is logged and only the first elements up to the length of the [NetworkArray](#) are copied.

Type Constraints

***T* : [unmanaged](#)**

6.134.2.11 InitializeNetworkDictionary< D, K, V >()

```
static void InitializeNetworkDictionary< D, K, V > (
    NetworkDictionary< K, V > networkDictionary,
    D dictionary,
    string name ) [static]
```

Initializes a [NetworkDictionary](#) with the values from a source dictionary.

Template Parameters

<i>D</i>	The type of the source dictionary. Must implement <code>IDictionary{K, V}</code> .
<i>K</i>	The type of the keys in the NetworkDictionary and source dictionary. Must be unmanaged.
<i>V</i>	The type of the values in the NetworkDictionary and source dictionary. Must be unmanaged.

Parameters

<i>networkDictionary</i>	The NetworkDictionary to initialize.
<i>dictionary</i>	The source dictionary from which to copy the values.
<i>name</i>	The name of the NetworkDictionary for logging purposes.

If the count of the source dictionary is greater than the capacity of the [NetworkDictionary](#), a warning is logged and only the first elements up to the capacity of the [NetworkDictionary](#) are copied.

Type Constraints

D : IDictionary

D : K

D : V

K : unmanaged

V : unmanaged

6.134.2.12 InitializeNetworkList< T >()

```
static void InitializeNetworkList< T > (
    NetworkLinkedList< T > networkList,
    T[] sourceArray,
    string name ) [static]
```

Initializes a [NetworkLinkedList](#) with the values from a source array.

Template Parameters

<i>T</i>	The type of the elements in the NetworkLinkedList and source array. Must be unmanaged.
----------	--

Parameters

<i>networkList</i>	The NetworkLinkedList to initialize.
<i>sourceArray</i>	The source array from which to copy the values.
<i>name</i>	The name of the NetworkLinkedList for logging purposes.

If the length of the source array is greater than the capacity of the [NetworkLinkedList](#), a warning is logged and only the first elements up to the capacity of the [NetworkLinkedList](#) are copied.

Type Constraints

T : unmanaged

6.134.2.13 InternalOnDestroy()

```
static void InternalOnDestroy (
    SimulationBehaviour obj ) [static]
```

This method is not meant to be called directly. Calls are injected by the Weaver.

Parameters

<i>obj</i>	SimulationBehaviour object.
------------	-----------------------------

6.134.2.14 InternalOnDisable()

```
static void InternalOnDisable (
    SimulationBehaviour obj ) [static]
```

This method is not meant to be called directly. Calls are injected by the Weaver.

Parameters

<i>obj</i>	SimulationBehaviour object.
------------	-----------------------------

6.134.2.15 InternalOnEnable()

```
static void InternalOnEnable (
    SimulationBehaviour obj ) [static]
```

This method is not meant to be called directly. Calls are injected by the Weaver.

Parameters

<i>obj</i>	SimulationBehaviour object.
------------	-----------------------------

6.134.2.16 MakeSerializableDictionary< K, V >()

```
static SerializableDictionary<K, V> MakeSerializableDictionary< K, V > (
    Dictionary< K, V > dictionary ) [static]
```

Wraps a Dictionary in a [SerializableDictionary](#).

Template Parameters

<i>K</i>	The type of the keys in the dictionary. Must be unmanaged.
<i>V</i>	The type of the values in the dictionary. Must be unmanaged.

Parameters

<i>dictionary</i>	The dictionary to wrap.
-------------------	-------------------------

Returns

A [SerializableDictionary](#) that wraps the specified dictionary.

Type Constraints

K* : *unmanaged

V* : *unmanaged

6.134.2.17 NotifyLocalSimulationNotAllowedToSendRpc()

```
static void NotifyLocalSimulationNotAllowedToSendRpc (
    string rpc,
    NetworkObject obj,
    int sources ) [static]
```

Logs an error message indicating that a local simulation is not allowed to send a specific RPC.

Parameters

<i>rpc</i>	The name of the RPC that was attempted.
<i>obj</i>	The network object on which the RPC was attempted.
<i>sources</i>	The sources from which the RPC was attempted.

6.134.2.18 NotifyLocalTargetedRpcCulled()

```
static void NotifyLocalTargetedRpcCulled (
    PlayerRef player,
    string methodName ) [static]
```

Logs a warning message indicating that a local targeted RPC was culled.

Parameters

<i>player</i>	The player reference for which the RPC was culled.
<i>methodName</i>	The name of the method that was culled.

6.134.2.19 NotifyNetworkUnwrapFailed< T >()

```
static void NotifyNetworkUnwrapFailed< T > (
    T wrapper,
    Type valueType ) [static]
```

Logs a warning message indicating that a network unwrap operation failed.

Template Parameters

<i>T</i>	The type of the wrapper that failed to be unwrapped.
----------	--

Parameters

<i>wrapper</i>	The wrapper that failed to be unwrapped.
<i>valueType</i>	The type that was attempted to be obtained from the unwrap operation.

6.134.2.20 NotifyNetworkWrapFailed< T >() [1/2]

```
static void NotifyNetworkWrapFailed< T > (
    T value ) [static]
```

Logs a warning message indicating that a network wrap operation failed.

Template Parameters

<i>T</i>	The type of the value that failed to be wrapped.
----------	--

Parameters

<i>value</i>	The value that failed to be wrapped.
--------------	--------------------------------------

6.134.2.21 NotifyNetworkWrapFailed< T >() [2/2]

```
static void NotifyNetworkWrapFailed< T > (
    T value,
    Type wrapperType ) [static]
```

Logs a warning message indicating that a network wrap operation failed for a specific wrapper type.

Template Parameters

<i>T</i>	The type of the value that failed to be wrapped.
----------	--

Parameters

<i>value</i>	The value that failed to be wrapped.
<i>wrapperType</i>	The type that was attempted to be used as a wrapper.

6.134.2.22 NotifyRpcTargetUnreachable()

```
static void NotifyRpcTargetUnreachable (
    PlayerRef player,
    string rpc ) [static]
```

Logs an error message indicating that the target of a Remote Procedure Call (RPC) is not reachable.

Parameters

<i>player</i>	The player reference that is not reachable.
<i>rpc</i>	The name of the RPC that was attempted.

6.134.2.23 RegisterMetaData()

```
static void RegisterMetaData (
    Type type ) [static]
```

Registers the metadata for a given type. This method checks if the type has an override for the "ReplicateTo" method and stores this information in the metadata. If the metadata for the type already exists, this method does nothing.

Parameters

<i>type</i>	The type for which to register the metadata.
-------------	--

6.134.2.24 RegisterRpcInvokeDelegates()

```
static void RegisterRpcInvokeDelegates (
    Type type ) [static]
```

Registers the RPC (Remote Procedure Call) invoke delegates for a given type. This method is only available when the FUSION_UNITY compilation symbol is defined.

Parameters

<i>type</i>	The type for which to register the RPC invoke delegates.
-------------	--

Exceptions

<i>System.ArgumentException</i>	Thrown when the provided type is not a subclass of NetworkBehaviour .
<i>System.InvalidOperationException</i>	Thrown when the provided type does not have a weaved attribute or its word count is negative.

6.134.2.25 ShouldRegisterRpcInvokeDelegates()

```
static bool ShouldRegisterRpcInvokeDelegates (  
    Type type ) [static]
```

Determines whether the RPC (Remote Procedure Call) invoke delegates should be registered for a given type.

Parameters

<i>type</i>	The type for which to check the registration of RPC invoke delegates.
-------------	---

Returns

True if the RPC invoke delegates should be registered for the type, false otherwise.

6.134.2.26 ThrowIfBehaviourNotInitialized()

```
static void ThrowIfBehaviourNotInitialized (  
    NetworkBehaviour behaviour ) [static]
```

Checks if the [NetworkBehaviour](#) object is initialized and throws an exception if it is not.

Parameters

<i>behaviour</i>	The NetworkBehaviour object to check.
------------------	---

Exceptions

<i>System.InvalidOperationException</i>	Thrown when the NetworkBehaviour object is not initialized.
---	---

6.134.2.27 TryGetRpcInvokeDelegateArray()

```
static bool TryGetRpcInvokeDelegateArray (
    Type type,
    out RpcInvokeData[] delegates ) [static]
```

Tries to get the RPC (Remote Procedure Call) invoke delegate array for a given type.

Parameters

<i>type</i>	The type for which to get the RPC invoke delegate array.
<i>delegates</i>	When this method returns, contains the RPC invoke delegate array if the type has one; otherwise, null.

Returns

true if the type has an RPC invoke delegate array; otherwise, false.

6.134.2.28 TryGetRpcStaticInvokeDelegate()

```
static bool TryGetRpcStaticInvokeDelegate (
    int index,
    out RpcStaticInvokeDelegate del ) [static]
```

Tries to get the static RPC (Remote Procedure Call) invoke delegate based on its index.

Parameters

<i>index</i>	The index of the static RPC.
<i>del</i>	When this method returns, contains the static RPC invoke delegate if it exists; otherwise, default.

Returns

True if the static RPC invoke delegate exists; otherwise, false.

6.134.3 Member Data Documentation**6.134.3.1 InvokeRpc**

```
bool InvokeRpc = false [static]
```

A static field that determines whether to invoke RPC (Remote Procedure Call). When set to true, RPCs are invoked. When set to false, RPCs are not invoked. Default value is false.

6.135 NetworkBehaviourUtils.ArrayInitializer< T > Struct Template Reference

A utility structure for initializing [NetworkArray](#) and [NetworkLinkedList](#) with inline initialization.

Static Public Member Functions

- static implicit [operator NetworkArray< T > \(ArrayInitializer< T > arr\)](#)
Implicitly converts an [ArrayInitializer](#) to a [NetworkArray](#).
- static implicit [operator NetworkLinkedList< T > \(ArrayInitializer< T > arr\)](#)
Implicitly converts an [ArrayInitializer](#) to a [NetworkLinkedList](#).

6.135.1 Detailed Description

A utility structure for initializing [NetworkArray](#) and [NetworkLinkedList](#) with inline initialization.

Template Parameters

<i>T</i>	The type of the elements in the NetworkArray and NetworkLinkedList .
----------	--

6.135.2 Member Function Documentation

6.135.2.1 operator NetworkArray< T >()

```
static implicit operator NetworkArray< T > (
    ArrayInitializer< T > arr ) [static]
```

Implicitly converts an [ArrayInitializer](#) to a [NetworkArray](#).

Parameters

<i>arr</i>	The ArrayInitializer to convert.
------------	--

Returns

A [NetworkArray](#) initialized with the values from the [ArrayInitializer](#).

Exceptions

<i>System.NotImplementedException</i>	Thrown always as this method is meant to be used only for [Networked] properties inline initialization.
---------------------------------------	---

6.135.2.2 operator NetworkLinkedList< T >()

```
static implicit operator NetworkLinkedList< T > (
    ArrayInitializer< T > arr ) [static]
```

Implicitly converts an [ArrayInitializer](#) to a [NetworkLinkedList](#).

Parameters

<i>arr</i>	The ArrayInitializer to convert.
------------	--

Returns

A [NetworkLinkedList](#) initialized with the values from the [ArrayInitializer](#).

Exceptions

<i>System.NotImplementedException</i>	Thrown always as this method is meant to be used only for [Networked] properties inline initialization.
---------------------------------------	---

6.136 NetworkBehaviourUtils.DictionaryInitializer< K, V > Struct Template Reference

A utility structure for initializing [NetworkDictionary](#) with inline initialization.

Static Public Member Functions

- static implicit [operator NetworkDictionary< K, V > \(DictionaryInitializer< K, V > arr\)](#)
Implicitly converts a [DictionaryInitializer](#) to a [NetworkDictionary](#).

6.136.1 Detailed Description

A utility structure for initializing [NetworkDictionary](#) with inline initialization.

Template Parameters

<i>K</i>	The type of the keys in the NetworkDictionary .
<i>V</i>	The type of the values in the NetworkDictionary .

6.136.2 Member Function Documentation

6.136.2.1 operator `NetworkDictionary< K, V >()`

```
static implicit operator NetworkDictionary< K, V > (  
    DictionaryInitializer< K, V > arr ) [static]
```

Implicitly converts a [DictionaryInitializer](#) to a [NetworkDictionary](#).

Parameters

<i>arr</i>	The DictionaryInitializer to convert.
------------	---

Returns

A [NetworkDictionary](#) initialized with the values from the [DictionaryInitializer](#).

Exceptions

<i>System.NotImplementedException</i>	Thrown always as this method is meant to be used only for [Networked] properties inline initialization.
---------------------------------------	---

6.137 NetworkBehaviourUtils.Metadata Struct Reference

This structure holds metadata for a [NetworkBehaviour](#) object.

Public Attributes

- bool [HasReplicateToOverride](#)
Indicates whether the [NetworkBehaviour](#) object has an override for the `ReplicateTo` method.

6.137.1 Detailed Description

This structure holds metadata for a [NetworkBehaviour](#) object.

6.137.2 Member Data Documentation

6.137.2.1 HasReplicateToOverride

bool HasReplicateToOverride

Indicates whether the [NetworkBehaviour](#) object has an override for the ReplicateTo method.

6.138 NetworkBehaviourWeavedAttribute Class Reference

Network [Behaviour](#) Weaved Attribute

Inherits Attribute.

Public Member Functions

- [NetworkBehaviourWeavedAttribute](#) (int wordCount)
[NetworkBehaviourWeavedAttribute](#) Constructor

Properties

- int [WordCount](#) [get]
[NetworkBehaviour](#) Word Count

6.138.1 Detailed Description

Network [Behaviour](#) Weaved Attribute

6.138.2 Constructor & Destructor Documentation

6.138.2.1 NetworkBehaviourWeavedAttribute()

```
NetworkBehaviourWeavedAttribute (  
    int wordCount )
```

[NetworkBehaviourWeavedAttribute](#) Constructor

Parameters

<i>wordCount</i>	WordCount
------------------	---------------------------

6.138.3 Property Documentation

6.138.3.1 WordCount

`int WordCount [get]`

[NetworkBehaviour](#) Word Count

6.139 NetworkBool Struct Reference

Represents a boolean value that can be networked.

Inherits [INetworkStruct](#), and `IEquatable< NetworkBool >`.

Public Member Functions

- `bool Equals (NetworkBool other)`
Determines whether the specified [NetworkBool](#) is equal to the current [NetworkBool](#).
- `override bool Equals (object obj)`
Determines whether the specified object is equal to the current [NetworkBool](#).
- `override int GetHashCode ()`
Serves as the default hash function.
- `NetworkBool (bool value)`
Initializes a new instance of the [NetworkBool](#) struct with the specified value.
- `override string ToString ()`
Returns a string that represents the current [NetworkBool](#).

Static Public Member Functions

- `static implicit operator bool (NetworkBool val)`
Defines an implicit conversion of a [NetworkBool](#) to a bool.
- `static implicit operator NetworkBool (bool val)`
Defines an implicit conversion of a bool to a [NetworkBool](#).

Public Attributes

- `int _value`

6.139.1 Detailed Description

Represents a boolean value that can be networked.

6.139.2 Constructor & Destructor Documentation

6.139.2.1 NetworkBool()

```
NetworkBool (
    bool value )
```

Initializes a new instance of the [NetworkBool](#) struct with the specified value.

Parameters

<i>value</i>	The boolean value.
--------------	--------------------

6.139.3 Member Function Documentation

6.139.3.1 Equals() [1/2]

```
bool Equals (  
    NetworkBool other )
```

Determines whether the specified [NetworkBool](#) is equal to the current [NetworkBool](#).

Parameters

<i>other</i>	The NetworkBool to compare with the current NetworkBool .
--------------	---

Returns

true if the specified [NetworkBool](#) is equal to the current [NetworkBool](#); otherwise, false.

6.139.3.2 Equals() [2/2]

```
override bool Equals (  
    object obj )
```

Determines whether the specified object is equal to the current [NetworkBool](#).

Parameters

<i>obj</i>	The object to compare with the current NetworkBool .
------------	--

Returns

true if the specified object is equal to the current [NetworkBool](#); otherwise, false.

6.139.3.3 GetHashCode()

```
override int GetHashCode ( )
```

Serves as the default hash function.

Returns

A hash code for the current [NetworkBool](#).

6.139.3.4 operator bool()

```
static implicit operator bool (  
    NetworkBool val ) [static]
```

Defines an implicit conversion of a [NetworkBool](#) to a bool.

Parameters

<i>val</i>	The NetworkBool to convert.
------------	---

6.139.3.5 operator NetworkBool()

```
static implicit operator NetworkBool (  
    bool val ) [static]
```

Defines an implicit conversion of a bool to a [NetworkBool](#).

Parameters

<i>val</i>	The bool to convert.
------------	----------------------

6.139.3.6 ToString()

```
override string ToString ( )
```

Returns a string that represents the current [NetworkBool](#).

Returns

A string that represents the current [NetworkBool](#).

6.140 NetworkButtons Struct Reference

Represents a set of buttons that can be networked.

Inherits [INetworkStruct](#), and `IEquatable< NetworkButtons >`.

Public Member Functions

- bool [Equals](#) ([NetworkButtons](#) other)
Determines whether the specified [NetworkButtons](#) is equal to the current [NetworkButtons](#).
- override bool [Equals](#) (object obj)
Determines whether the specified object is equal to the current [NetworkButtons](#).
- override int [GetHashCode](#) ()
Serves as the default hash function.
- [NetworkButtons](#) [GetPressed](#) ([NetworkButtons](#) previous)
Gets the buttons that were pressed since the previous state.
- [NetworkButtons](#) [GetPressedOrReleased](#) ([NetworkButtons](#) previous)
- [NetworkButtons](#) [GetReleased](#) ([NetworkButtons](#) previous)
Gets the buttons that were released since the previous state.
- bool [IsSet](#) (int button)
Checks if the button at the specified index is set.
- bool [IsSet](#)< T > (T button)
Checks if the button of the specified enum type is set.
- [NetworkButtons](#) ([NetworkButtons](#) buttons)
Initializes a new instance of the [NetworkButtons](#) struct with the specified buttons state.
- void [Set](#) (int button, bool state)
Sets the button at the specified index to the specified state.
- void [Set](#)< T > (T button, bool state)
Sets the button of the specified enum type to the specified state.
- void [SetAllDown](#) ()
Sets all buttons to down.
- void [SetAllUp](#) ()
Sets all buttons to up.
- void [SetDown](#) (int button)
Sets the button at the specified index to down.
- void [SetDown](#)< T > (T button)
Sets the button of the specified enum type to down.
- void [SetUp](#) (int button)
Sets the button at the specified index to up.
- void [SetUp](#)< T > (T button)
Sets the button of the specified enum type to up.
- bool [WasPressed](#) ([NetworkButtons](#) previous, int button)
Checks if the button at the specified index was pressed since the previous state.
- bool [WasPressed](#)< T > ([NetworkButtons](#) previous, T button)
Checks if the button of the specified enum type was pressed since the previous state.
- bool [WasReleased](#) ([NetworkButtons](#) previous, int button)
Checks if the button at the specified index was released since the previous state.
- bool [WasReleased](#)< T > ([NetworkButtons](#) previous, T button)
Checks if the button of the specified enum type was released since the previous state.

Public Attributes

- int [_bits](#)
- [NetworkButtons](#)
Gets the buttons that were pressed or released since the previous state.

Properties

- int [Bits](#) [get]

Gets the bits representing the state of the buttons.

6.140.1 Detailed Description

Represents a set of buttons that can be networked.

6.140.2 Constructor & Destructor Documentation

6.140.2.1 NetworkButtons()

```
NetworkButtons (
    int buttons )
```

Initializes a new instance of the [NetworkButtons](#) struct with the specified buttons state.

Parameters

<i>buttons</i>	The integer representing the state of the buttons.
----------------	--

6.140.3 Member Function Documentation

6.140.3.1 Equals() [1/2]

```
bool Equals (
    NetworkButtons other )
```

Determines whether the specified [NetworkButtons](#) is equal to the current [NetworkButtons](#).

Parameters

<i>other</i>	The NetworkButtons to compare with the current NetworkButtons .
--------------	---

Returns

true if the specified [NetworkButtons](#) is equal to the current [NetworkButtons](#); otherwise, false.

6.140.3.2 Equals() [2/2]

```
override bool Equals (
    object obj )
```

Determines whether the specified object is equal to the current [NetworkButtons](#).

Parameters

<i>obj</i>	The object to compare with the current NetworkButtons .
------------	---

Returns

true if the specified object is equal to the current [NetworkButtons](#); otherwise, false.

6.140.3.3 GetHashCode()

```
override int GetHashCode ( )
```

Serves as the default hash function.

Returns

A hash code for the current [NetworkButtons](#).

6.140.3.4 GetPressed()

```
NetworkButtons GetPressed (
    NetworkButtons previous )
```

Gets the buttons that were pressed since the previous state.

Parameters

<i>previous</i>	The previous state of the buttons.
-----------------	------------------------------------

Returns

The buttons that were pressed.

6.140.3.5 GetReleased()

```
NetworkButtons GetReleased (
    NetworkButtons previous )
```

Gets the buttons that were released since the previous state.

Parameters

<i>previous</i>	The previous state of the buttons.
-----------------	------------------------------------

Returns

The buttons that were released.

6.140.3.6 IsSet()

```
bool IsSet (
    int button )
```

Checks if the button at the specified index is set.

Parameters

<i>button</i>	The index of the button to check.
---------------	-----------------------------------

Returns

true if the button is set; otherwise, false.

6.140.3.7 IsSet< T >()

```
bool IsSet< T > (
    T button )
```

Checks if the button of the specified enum type is set.

Template Parameters

<i>T</i>	The enum type of the button.
----------	------------------------------

Parameters

<i>button</i>	The button of type T to check.
---------------	--------------------------------

Returns

true if the button is set; otherwise, false.

Type Constraints

T* : *unmanaged

T* : *Enum

6.140.3.8 Set()

```
void Set (
    int button,
    bool state )
```

Sets the button at the specified index to the specified state.

Parameters

<i>button</i>	The index of the button to set.
<i>state</i>	The state to set the button to.

6.140.3.9 Set< T >()

```
void Set< T > (
    T button,
    bool state )
```

Sets the button of the specified enum type to the specified state.

Template Parameters

<i>T</i>	The enum type of the button.
----------	------------------------------

Parameters

<i>button</i>	The button of type T to set.
<i>state</i>	The state to set the button to.

Type Constraints

T* : *unmanaged

T* : *Enum

6.140.3.10 SetAllDown()

```
void SetAllDown ( )
```

Sets all buttons to down.

6.140.3.11 SetAllUp()

```
void SetAllUp ( )
```

Sets all buttons to up.

6.140.3.12 SetDown()

```
void SetDown (
    int button )
```

Sets the button at the specified index to down.

Parameters

<i>button</i>	The index of the button to set to down.
---------------	---

6.140.3.13 SetDown< T >()

```
void SetDown< T > (
    T button )
```

Sets the button of the specified enum type to down.

Template Parameters

<i>T</i>	The enum type of the button.
----------	------------------------------

Parameters

<i>button</i>	The button of type T to set to down.
---------------	--------------------------------------

Type Constraints

T: *unmanaged*

T : Enum

6.140.3.14 SetUp()

```
void SetUp (
    int button )
```

Sets the button at the specified index to up.

Parameters

<i>button</i>	The index of the button to set to up.
---------------	---------------------------------------

6.140.3.15 SetUp< T >()

```
void SetUp< T > (
    T button )
```

Sets the button of the specified enum type to up.

Template Parameters

<i>T</i>	The enum type of the button.
----------	------------------------------

Parameters

<i>button</i>	The button of type T to set to up.
---------------	------------------------------------

Type Constraints

T : unmanaged

T : Enum

6.140.3.16 WasPressed()

```
bool WasPressed (
    NetworkButtons previous,
    int button )
```

Checks if the button at the specified index was pressed since the previous state.

Parameters

<i>previous</i>	The previous state of the buttons.
<i>button</i>	The index of the button to check.

Returns

true if the button was pressed; otherwise, false.

6.140.3.17 WasPressed< T >()

```
bool WasPressed< T > (
    NetworkButtons previous,
    T button )
```

Checks if the button of the specified enum type was pressed since the previous state.

Template Parameters

<i>T</i>	The enum type of the button.
----------	------------------------------

Parameters

<i>previous</i>	The previous state of the buttons.
<i>button</i>	The button of type T to check.

Returns

true if the button was pressed; otherwise, false.

Type Constraints

T* : *unmanaged

T* : *Enum

6.140.3.18 WasReleased()

```
bool WasReleased (
    NetworkButtons previous,
    int button )
```

Checks if the button at the specified index was released since the previous state.

Parameters

<i>previous</i>	The previous state of the buttons.
<i>button</i>	The index of the button to check.

Returns

true if the button was released; otherwise, false.

6.140.3.19 WasReleased< T >()

```
bool WasReleased< T > (
    NetworkButtons previous,
    T button )
```

Checks if the button of the specified enum type was released since the previous state.

Template Parameters

<i>T</i>	The enum type of the button.
----------	------------------------------

Parameters

<i>previous</i>	The previous state of the buttons.
<i>button</i>	The button of type T to check.

Returns

true if the button was released; otherwise, false.

Type Constraints

T* : *unmanaged

T* : *Enum

6.140.4 Member Data Documentation**6.140.4.1 NetworkButtons**

`NetworkButtons`

Gets the buttons that were pressed or released since the previous state.

Parameters

<i>previous</i>	The previous state of the buttons.
-----------------	------------------------------------

Returns

A tuple containing the buttons that were pressed and the buttons that were released.

6.140.5 Property Documentation

6.140.5.1 Bits

```
int Bits [get]
```

Gets the bits representing the state of the buttons.

6.141 NetworkConfiguration Class Reference

Main network configuration class.

Public Types

- enum class [ReliableDataTransfers](#)
Flag for allowed Reliable Data transfer modes.

Public Member Functions

- [NetworkConfiguration Init \(\)](#)
Initializes and creates a copy of this [NetworkProjectConfig](#).

Public Attributes

- double [ConnectionShutdownTime](#) = 1
Default delay between connection changes status to Shutdown (disconnected/invalid), and it actually being released (freeing all references to that particular connection).
- double [ConnectionTimeout](#) = 10
Max allowed time in seconds that the local peer can run without receiving any update from a remote peer. If a client does not receive any update from the server within this period, it will disconnect itself. If a server does not receive any update from a remote client within this period, it will disconnect that particular client.
- [ReliableDataTransfers](#) [ReliableDataTransferModes](#)
Current [ReliableDataTransferModes](#) mode.

Properties

- int [ConnectAttempts](#) [get]
Max number of connection attempts that a Client will run when trying to connect to a remote Server.
- double [ConnectInterval](#) [get]
Interval in seconds between each connection attempt from a Client.
- double [ConnectionDefaultRtt](#) [get]
Default assumed RTT in seconds for new connections (before actual RTT has been determined). The real RTT is calculated over time once the connection is established.
- double [ConnectionPingInterval](#) [get]
Interval in seconds between PING messages sent to a remote connection, in order to keep that connection alive.
- int [MtuDefault](#) [get]
Max number of bytes that can be used by [Fusion](#) to fill up a UDP package.
- int [SocketRecvBufferSize](#) [get]
Size in Kilobytes of the underlying socket receive buffer.
- int [SocketSendBufferSize](#) [get]
Size in Kilobytes of the underlying socket send buffer.

6.141.1 Detailed Description

Main network configuration class.

6.141.2 Member Enumeration Documentation

6.141.2.1 ReliableDataTransfers

```
enum ReliableDataTransfers [strong]
```

Flag for allowed Reliable Data transfer modes.

Enumerator

ClientToServer	Allow Client to Server.
ClientToClientWithServerProxy	Allow Client to Client using Server as Proxy.

6.141.3 Member Function Documentation

6.141.3.1 Init()

```
NetworkConfiguration Init ( )
```

Initializes and creates a copy of this [NetworkProjectConfig](#).

Returns

A copy of this [NetworkProjectConfig](#).

6.141.4 Member Data Documentation

6.141.4.1 ConnectionShutdownTime

```
double ConnectionShutdownTime = 1
```

Default delay between connection changes status to Shutdown (disconnected/invalid), and it actually being released (freeing all references to that particular connection).

6.141.4.2 ConnectionTimeout

```
double ConnectionTimeout = 10
```

Max allowed time in seconds that the local peer can run without receiving any update from a remote peer. If a client does not receive any update from the server within this period, it will disconnect itself. If a server does not receive any update from a remote client within this period, it will disconnect that particular client.

6.141.4.3 ReliableDataTransferModes

```
ReliableDataTransfers ReliableDataTransferModes
```

Initial value:

```
=  
    ReliableDataTransfers.ClientToServer |  
    ReliableDataTransfers.ClientToClientWithServerProxy
```

Current [ReliableDataTransferModes](#) mode.

6.141.5 Property Documentation

6.141.5.1 ConnectAttempts

```
int ConnectAttempts [get]
```

Max number of connection attempts that a Client will run when trying to connect to a remote Server.

6.141.5.2 ConnectInterval

```
double ConnectInterval [get]
```

Interval in seconds between each connection attempt from a Client.

6.141.5.3 ConnectionDefaultRtt

```
double ConnectionDefaultRtt [get]
```

Default assumed RTT in seconds for new connections (before actual RTT has been determined). The real RTT is calculated over time once the connection is established.

6.141.5.4 ConnectionPingInterval

```
double ConnectionPingInterval [get]
```

Interval in seconds between PING messages sent to a remote connection, in order to keep that connection alive.

Currently unused.

6.141.5.5 MtuDefault

```
int MtuDefault [get]
```

Max number of bytes that can be used by [Fusion](#) to fill up a UDP package.

6.141.5.6 SocketRecvBufferSize

```
int SocketRecvBufferSize [get]
```

Size in Kilobytes of the underlying socket receive buffer.

6.141.5.7 SocketSendBufferSize

```
int SocketSendBufferSize [get]
```

Size in Kilobytes of the underlying socket send buffer.

6.142 NetworkDelegates Class Reference

Network Runner Callbacks Delegates

Inherits [INetworkRunnerCallbacks](#).

Public Attributes

- Action< [NetworkRunner](#) > [OnConnectedToServer](#)
- Action< [NetworkRunner](#), [NetAddress](#), [NetConnectFailedReason](#) > [OnConnectFailed](#)
- Action< [NetworkRunner](#), [NetworkRunnerCallbackArgs.ConnectRequest](#), [byte\[\]](#)> [OnConnectRequest](#)
- Action< [NetworkRunner](#), Dictionary< string, object > > [OnCustomAuthenticationResponse](#)
- Action< [NetworkRunner](#), [NetDisconnectReason](#) > [OnDisconnectedFromServer](#)
- Action< [NetworkRunner](#), [HostMigrationToken](#) > [OnHostMigration](#)
- Action< [NetworkRunner](#), [NetworkInput](#) > [OnInput](#)
- Action< [NetworkRunner](#), [PlayerRef](#), [NetworkInput](#) > [OnInputMissing](#)
- Action< [NetworkRunner](#), [NetworkObject](#), [PlayerRef](#) > [OnObjectEnterAOI](#)
- Action< [NetworkRunner](#), [NetworkObject](#), [PlayerRef](#) > [OnObjectExitAOI](#)
- Action< [NetworkRunner](#), [PlayerRef](#) > [OnPlayerJoined](#)
- Action< [NetworkRunner](#), [PlayerRef](#) > [OnPlayerLeft](#)
- Action< [NetworkRunner](#), [PlayerRef](#), [ReliableKey](#), float > [OnReliableDataProgress](#)
- Action< [NetworkRunner](#), [PlayerRef](#), [ReliableKey](#), [ArraySegment< byte >](#) > [OnReliableDataReceived](#)
- Action< [NetworkRunner](#) > [OnSceneLoadDone](#)
- Action< [NetworkRunner](#) > [OnSceneLoadStart](#)
- Action< [NetworkRunner](#), List< [SessionInfo](#) > > [OnSessionListUpdated](#)
- Action< [NetworkRunner](#), [ShutdownReason](#) > [OnShutdown](#)
- Action< [NetworkRunner](#), [SimulationMessagePtr](#) > [OnUserSimulationMessage](#)

Additional Inherited Members

6.142.1 Detailed Description

Network Runner Callbacks Delegates

6.143 NetworkDeserializeMethodAttribute Class Reference

Network Deserialize Method Attribute

Inherits [Attribute](#).

6.143.1 Detailed Description

Network Deserialize Method Attribute

6.144 NetworkDictionary< K, V > Struct Template Reference

[Fusion](#) type for networking Dictionaries. Maximum capacity is fixed, and is set with the [CapacityAttribute](#).

Inherits [IEnumerable< KeyValuePair< K, V >>](#), and [INetworkDictionary](#).

Classes

- struct [Enumerator](#)
[Enumerator](#) for [NetworkDictionary](#).

Public Member Functions

- bool [Add](#) (K key, V value)
Adds a new key value pair to the Dictionary. If the key already exists, will return false.
- void [INetworkDictionary.Add](#) (object item)
Adds an item to the networked dictionary.
- void [Clear](#) ()
Remove all entries from the Dictionary, and clear backing memory.
- void [ClrEntry](#) (int entry)
- bool [ContainsKey](#) (K key)
Returns true if the Dictionary contains an entry for the given key.
- bool [ContainsValue](#) (V value, [IEqualityComparer< V > equalityComparer=null](#))
Returns true if the Dictionary contains an entry value which compares as equal to given value.
- int [Find](#) (K key)
- V [Get](#) (K key)
Returns the value for the given key. Will throw an error if the key is not found.
- uint [GetBucketFromHashCode](#) (int hash)
- [Enumerator GetEnumerator](#) ()
Returns an enumerator that iterates through the [NetworkDictionary](#).
- [IEnumerable< KeyValuePair< K, V >> IEnumerable< KeyValuePair< K, V >>. GetEnumerator](#) ()
- [IEnumerator IEnumerable. GetEnumerator](#) ()
- K [GetKey](#) (int entry)
- int [GetNxt](#) (int entry)
- V [GetVal](#) (int entry)
- int [Insert](#) (K key, V val)
- [NetworkDictionary](#) (int *data, int capacity, [IElementReaderWriter< K > keyReaderWriter](#), [IElementReaderWriter< V > valReaderWriter](#))
Initializes a new instance of the [NetworkDictionary](#) struct with the specified data, capacity, and reader/writers.
- bool [Remove](#) (K key)
Remove entry from Dictionary.
- bool [Remove](#) (K key, out V value)
Removes entry from Dictionary. If successful (key existed), returns true and the value of removed item.
- V [Set](#) (K key, V value)
Sets the value for the given key. Will add a new key if the key does not already exist.
- void [SetKey](#) (int entry, K key)
- void [SetNxt](#) (int entry, int next)
- void [SetVal](#) (int entry, V val)
- [NetworkDictionaryReadOnly< K, V > ToReadOnly](#) ()
Converts the current [NetworkDictionary](#) to a read-only version.
- bool [TryGet](#) (K key, out V value)
Attempts to get the value for a given key. If found, returns true.

Static Public Member Functions

- static implicit [operator NetworkDictionaryReadOnly< K, V > \(NetworkDictionary< K, V > value\)](#)
Converts the current [NetworkDictionary](#) to a read-only version.

Public Attributes

- int **_bucketsOffset**
- int **_capacity**
- int * **_data**
- int **_entriesOffset**
- int **_entryStride**
- EqualityComparer< K > **_equalityComparer**
- int **_keyOffset**
- [IElementReaderWriter< K >](#) **_keyReaderWriter**
- int **_nxtOffset**
- int **_valOffset**
- [IElementReaderWriter< V >](#) **_valReaderWriter**

Static Public Attributes

- const int **FREE_COUNT_OFFSET** = 1
- const int **FREE_OFFSET** = 0
- const int **INVALID_ENTRY** = 0
- const int **META_WORD_COUNT** = 3
Meta word count for [NetworkDictionary](#).
- const int **USED_COUNT_OFFSET** = 2

Properties

- int **_free** [get, set]
- int **_freeCount** [get, set]
- int **_usedCount** [get, set]
- int [Capacity](#) [get]
The maximum number of entries this dictionary may contain.
- int [Count](#) [get]
Current number of key/value entries in the Dictionary.
- V [this\[K key\]](#) [get, set]
Key indexer. Gets/Sets value for specified key.

6.144.1 Detailed Description

[Fusion](#) type for networking Dictionaries. Maximum capacity is fixed, and is set with the [CapacityAttribute](#).

Typical Usage: `[Networked, Capacity(10)]
NetworkDictionary<int, float> syncedDict => default;`

Usage for modifying data: `var dict = syncedDict; dict.Add(5, 123); dict[5] = 456;
dict.Remove(5);`

Template Parameters

<i>K</i>	Key can be a primitive, or an INetworkStruct .
<i>V</i>	Value can be a primitive, or an INetworkStruct .

6.144.2 Constructor & Destructor Documentation

6.144.2.1 NetworkDictionary()

```
NetworkDictionary (
    int * data,
    int capacity,
    IElementReaderWriter< K > keyReaderWriter,
    IElementReaderWriter< V > valReaderWriter )
```

Initializes a new instance of the [NetworkDictionary](#) struct with the specified data, capacity, and reader/writers.

Parameters

<i>data</i>	The pointer to the data of the dictionary.
<i>capacity</i>	The capacity of the dictionary.
<i>keyReaderWriter</i>	The reader/writer for the keys of the dictionary.
<i>valReaderWriter</i>	The reader/writer for the values of the dictionary.

6.144.3 Member Function Documentation

6.144.3.1 Add() [1/2]

```
bool Add (
    K key,
    V value )
```

Adds a new key value pair to the Dictionary. If the key already exists, will return false.

6.144.3.2 Add() [2/2]

```
void INetworkDictionary. Add (
    object item )
```

Adds an item to the networked dictionary.

Parameters

<i>item</i>	The item to add to the dictionary.
-------------	------------------------------------

Implements [INetworkDictionary](#).

6.144.3.3 Clear()

```
void Clear ( )
```

Remove all entries from the Dictionary, and clear backing memory.

6.144.3.4 ContainsKey()

```
bool ContainsKey (
    K key )
```

Returns true if the Dictionary contains an entry for the given key.

6.144.3.5 ContainsValue()

```
bool ContainsValue (
    V value,
    IEqualityComparer< V > equalityComparer = null )
```

Returns true if the Dictionary contains an entry value which compares as equal to given value.

Parameters

<i>value</i>	The value to compare against.
<i>equalityComparer</i>	Specify custom IEqualityComparer to be used for compare.

6.144.3.6 Get()

```
V Get (
    K key )
```

Returns the value for the given key. Will throw an error if the key is not found.

6.144.3.7 GetEnumerator()

```
Enumerator GetEnumerator ( )
```

Returns an enumerator that iterates through the [NetworkDictionary](#).

6.144.3.8 operator NetworkDictionaryReadOnly< K, V >()

```
static implicit operator NetworkDictionaryReadOnly< K, V > (  
    NetworkDictionary< K, V > value ) [static]
```

Converts the current [NetworkDictionary](#) to a read-only version.

Parameters

<i>value</i>	The NetworkDictionary to convert.
--------------	---

Returns

A new instance of [NetworkDictionaryReadOnly](#) with the same data, capacity, and reader/writers as the current [NetworkDictionary](#).

6.144.3.9 Remove() [1/2]

```
bool Remove (  
    K key )
```

Remove entry from Dictionary.

Parameters

<i>key</i>	The key to remove.
------------	--------------------

Returns

Returns true if key was found.

6.144.3.10 Remove() [2/2]

```
bool Remove (  
    K key,  
    out V value )
```

Removes entry from Dictionary. If successful (key existed), returns true and the value of removed item.

Parameters

<i>key</i>	The key to remove.
<i>value</i>	Returns value of removed item. Returns default value if key did not exist.

Returns

Returns true if key was found.

6.144.3.11 Set()

```
V Set (
    K key,
    V value )
```

Sets the value for the given key. Will add a new key if the key does not already exist.

6.144.3.12 ToReadOnly()

```
NetworkDictionaryReadOnly<K, V> ToReadOnly ( )
```

Converts the current [NetworkDictionary](#) to a read-only version.

Returns

A new instance of [NetworkDictionaryReadOnly](#) with the same data, capacity, and reader/writers as the current [NetworkDictionary](#).

6.144.3.13 TryGet()

```
bool TryGet (
    K key,
    out V value )
```

Attempts to get the value for a given key. If found, returns true.

Parameters

<i>key</i>	The key to remove.
<i>value</i>	Returns value of removed item. Returns default value if key did not exist.

Returns

Returns true if key was found.

6.144.4 Member Data Documentation

6.144.4.1 META_WORD_COUNT

```
const int META_WORD_COUNT = 3 [static]
```

Meta word count for [NetworkDictionary](#).

6.144.5 Property Documentation

6.144.5.1 Capacity

```
int Capacity [get]
```

The maximum number of entries this dictionary may contain.

6.144.5.2 Count

```
int Count [get]
```

Current number of key/value entries in the Dictionary.

6.144.5.3 this[K key]

```
V this[K key] [get], [set]
```

Key indexer. Gets/Sets value for specified key.

6.145 NetworkDictionary< K, V >.Enumerator Struct Reference

[Enumerator](#) for [NetworkDictionary](#).

Inherits [IEnumerator< KeyValuePair< K, V >>](#).

Public Member Functions

- void [Dispose](#) ()
Dispose enumerator.
- bool [MoveNext](#) ()
Move to next entry in dictionary.
- void [Reset](#) ()
Reset enumerator.

Public Attributes

- int **_bucket**
- [NetworkDictionary](#)< K, V > **_dict**
- int **_entry**

Properties

- KeyValuePair< K, V > [Current](#) [get]
Current key/value pair.
- object IEnumerator. **Current** [get]

6.145.1 Detailed Description

[Enumerator](#) for [NetworkDictionary](#).

6.145.2 Member Function Documentation

6.145.2.1 Dispose()

```
void Dispose ( )
```

Dispose enumerator.

6.145.2.2 MoveNext()

```
bool MoveNext ( )
```

Move to next entry in dictionary.

Returns

Returns true if there is a next entry.

6.145.2.3 Reset()

```
void Reset ( )
```

Reset enumerator.

6.145.3 Property Documentation

6.145.3.1 Current

```
KeyValuePair<K, V> Current [get]
```

Current key/value pair.

Exceptions

<i>InvalidOperationException</i>	Thrown if enumerator is not valid.
----------------------------------	------------------------------------

6.146 NetworkDictionaryReadOnly< K, V > Struct Template Reference

A read-only version of NetworkDictionary<TKey,TValue>.

Public Member Functions

- int **Find** (K key)
- V **Get** (K key)
Returns the value for the given key. Will throw an error if the key is not found.
- uint **GetBucketFromHashCode** (int hash)
- K **GetKey** (int entry)
- int **GetNxt** (int entry)
- V **GetVal** (int entry)
- bool **TryGet** (K key, out V value)
Attempts to get the value for a given key. If found, returns true.

Public Attributes

- readonly int **_bucketsOffset**
- readonly int **_capacity**
- readonly int * **_data**
- readonly int **_entriesOffset**
- readonly int **_entryStride**
- readonly EqualityComparer< K > **_equalityComparer**
- readonly int **_keyOffset**
- readonly **IEnumeratorReaderWriter**< K > **_keyReaderWriter**
- readonly int **_nxtOffset**
- readonly int **_valOffset**
- readonly **IEnumeratorReaderWriter**< V > **_valReaderWriter**

Static Public Attributes

- const int **FREE_COUNT_OFFSET** = 1
- const int **FREE_OFFSET** = 0
- const int **INVALID_ENTRY** = 0
- const int **USED_COUNT_OFFSET** = 2

Properties

- int **_free** [get]
- int **_freeCount** [get]
- int **_usedCount** [get]
- int **Capacity** [get]
The maximum number of entries this dictionary may contain.
- int **Count** [get]
Current number of key/value entries in the Dictionary.

6.146.1 Detailed Description

A read-only version of `NetworkDictionary<TKey,TValue>`.

Template Parameters

<i>K</i>	The type of the key.
<i>V</i>	The type of the value.

6.146.2 Member Function Documentation

6.146.2.1 Get()

```
V Get (
    K key )
```

Returns the value for the given key. Will throw an error if the key is not found.

6.146.2.2 TryGet()

```
bool TryGet (
    K key,
    out V value )
```

Attempts to get the value for a given key. If found, returns true.

Parameters

<i>key</i>	The key to remove.
<i>value</i>	Returns value of removed item. Returns default value if key did not exist.

Returns

Returns true if key was found.

6.146.3 Property Documentation

6.146.3.1 Capacity

`int Capacity [get]`

The maximum number of entries this dictionary may contain.

6.146.3.2 Count

`int Count [get]`

Current number of key/value entries in the Dictionary.

6.147 NetworkedAttribute Class Reference

Inherits Attribute.

Public Member Functions

- [NetworkedAttribute](#) ()
Default constructor for [NetworkedAttribute](#)

Properties

- string [Default](#) [get, set]
Name of the field that holds the default value for this networked property.

6.147.1 Detailed Description

Flags a property of [NetworkBehaviour](#) for network state synchronization. The property should have empty get and set defines, which will automatically be replaced with networking code via IL Weaving. OnChanged can be assigned with the name of a method in the same [NetworkBehaviour](#). The named method will get called whenever this property value has been changed by the State Authority. | [Networked(OnDataReceived = nameof(MyCallbackMethod)]

```
| public int MyProperty { get; set; } | | protected static void MyCallback↵
Method(Changed<ChangedCallbackParent> changed) { | changed.LoadNew(); | var
newval = changed.Behaviour.MyProperty; | changed.LoadOld(); | var oldval =
changed.Behaviour.MyProperty; | Debug.Log($"Changed from {oldval} to {newval}");
| }
```

Inside of [INetworkStruct](#), do not use AutoProperties (get; set;), as these will introduce managed types into the struct, which are not allowed. Instead use '=> default'. | [Networked]

```
| public string StringProp { get => default; set { } }
```

6.147.2 Constructor & Destructor Documentation

6.147.2.1 NetworkedAttribute()

```
NetworkedAttribute ( )
```

Default constructor for [NetworkedAttribute](#)

6.147.3 Property Documentation

6.147.3.1 Default

```
string Default [get], [set]
```

Name of the field that holds the default value for this networked property.

6.148 NetworkedWeavedAttribute Class Reference

Networked Weaved Attribute

Inherits [Attribute](#).

Public Member Functions

- [NetworkedWeavedAttribute](#) (int wordOffset, int wordCount)
NetworkedWeavedAttribute Constructor

Properties

- int [WordCount](#) [get]
Networked Property Word Count
- int [WordOffset](#) [get]
Networked Property Word Offset

6.148.1 Detailed Description

Networked Weaved Attribute

Networked Property Attribute

6.148.2 Constructor & Destructor Documentation

6.148.2.1 NetworkedWeavedAttribute()

```
NetworkedWeavedAttribute (  
    int wordOffset,  
    int wordCount )
```

[NetworkedWeavedAttribute](#) Constructor

Parameters

<i>wordOffset</i>	WordOffset
<i>wordCount</i>	WordCount

6.148.3 Property Documentation

6.148.3.1 WordCount

```
int WordCount [get]
```

Networked Property Word Count

6.148.3.2 WordOffset

```
int WordOffset [get]
```

Networked Property Word Offset

6.149 NetworkEvents Class Reference

Companion component for [NetworkRunner](#). Exposes [INetworkRunnerCallbacks](#) as UnityEvents, which can be wired up to other components in the inspector.

Inherits [Behaviour](#), and [INetworkRunnerCallbacks](#).

Classes

- class [ConnectFailedEvent](#)
UnityEvent for ConnectFailed
- class [ConnectRequestEvent](#)
UnityEvent for ConnectRequest
- class [CustomAuthenticationResponse](#)
UnityEvent for Custom Authentication
- class [DisconnectFromServerEvent](#)
UnityEvent for DisconnectFromServer
- class [HostMigrationEvent](#)
UnityEvent for HostMigration
- class [InputEvent](#)
UnityEvent for [NetworkInput](#)
- class [InputPlayerEvent](#)
UnityEvent for [NetworkInput](#) with [PlayerRef](#)
- class [ObjectEvent](#)
UnityEvent for [NetworkObject](#)
- class [ObjectPlayerEvent](#)
UnityEvent for [NetworkObject](#) with [PlayerRef](#)
- class [PlayerEvent](#)
UnityEvent for [PlayerRef](#)
- class [ReliableDataEvent](#)
UnityEvent for Reliable Data
- class [ReliableProgressEvent](#)
UnityEvent for Reliable Data Progress
- class [RunnerEvent](#)
UnityEvent for [NetworkRunner](#)
- class [SessionListUpdateEvent](#)
UnityEvent for [SessionInfo](#) List
- class [ShutdownEvent](#)
UnityEvent for Shutdown
- class [SimulationMessageEvent](#)
UnityEvent for [SimulationMessage](#)

Public Attributes

- [RunnerEvent](#) [OnConnectedToServer](#)
- [ConnectFailedEvent](#) [OnConnectFailed](#)
- [ConnectRequestEvent](#) [OnConnectRequest](#)
- [CustomAuthenticationResponse](#) [OnCustomAuthenticationResponse](#)
- [DisconnectFromServerEvent](#) [OnDisconnectedFromServer](#)
- [HostMigrationEvent](#) [OnHostMigration](#)
- [InputEvent](#) [OnInput](#)
- [InputPlayerEvent](#) [OnInputMissing](#)
- [ObjectPlayerEvent](#) [OnObjectEnterAOI](#)
- [ObjectPlayerEvent](#) [OnObjectExitAOI](#)
- [ReliableDataEvent](#) [OnReliableData](#)
- [ReliableProgressEvent](#) [OnReliableProgress](#)
- [RunnerEvent](#) [OnSceneLoadDone](#)
- [RunnerEvent](#) [OnSceneLoadStart](#)
- [SessionListUpdateEvent](#) [OnSessionListUpdate](#)
- [ShutdownEvent](#) [OnShutdown](#)
- [SimulationMessageEvent](#) [OnSimulationMessage](#)
- [PlayerEvent](#) [PlayerJoined](#)
- [PlayerEvent](#) [PlayerLeft](#)

Additional Inherited Members

6.149.1 Detailed Description

Companion component for [NetworkRunner](#). Exposes [INetworkRunnerCallbacks](#) as UnityEvents, which can be wired up to other components in the inspector.

6.150 NetworkEvents.ConnectFailedEvent Class Reference

UnityEvent for ConnectFailed

Inherits `UnityEvent< NetworkRunner, NetAddress, NetConnectFailedReason >`.

6.150.1 Detailed Description

UnityEvent for ConnectFailed

6.151 NetworkEvents.ConnectRequestEvent Class Reference

UnityEvent for ConnectRequest

Inherits `UnityEvent< NetworkRunner, NetworkRunnerCallbackArgs.ConnectRequest, byte[] >`.

6.151.1 Detailed Description

UnityEvent for ConnectRequest

6.152 NetworkEvents.CustomAuthenticationResponse Class Reference

UnityEvent for Custom Authentication

Inherits UnityEvent< NetworkRunner, Dictionary< string, object >>.

6.152.1 Detailed Description

UnityEvent for Custom Authentication

6.153 NetworkEvents.DisconnectFromServerEvent Class Reference

UnityEvent for DisconnectFromServer

Inherits UnityEvent< NetworkRunner, NetDisconnectReason >.

6.153.1 Detailed Description

UnityEvent for DisconnectFromServer

6.154 NetworkEvents.HostMigrationEvent Class Reference

UnityEvent for HostMigration

Inherits UnityEvent< NetworkRunner, HostMigrationToken >.

6.154.1 Detailed Description

UnityEvent for HostMigration

6.155 NetworkEvents.InputEvent Class Reference

UnityEvent for [NetworkInput](#)

Inherits UnityEvent< NetworkRunner, NetworkInput >.

6.155.1 Detailed Description

UnityEvent for [NetworkInput](#)

6.156 NetworkEvents.InputPlayerEvent Class Reference

UnityEvent for [NetworkInput](#) with [PlayerRef](#)

Inherits UnityEvent< [NetworkRunner](#), [PlayerRef](#), [NetworkInput](#) >.

6.156.1 Detailed Description

UnityEvent for [NetworkInput](#) with [PlayerRef](#)

6.157 NetworkEvents.ObjectEvent Class Reference

UnityEvent for [NetworkObject](#)

Inherits UnityEvent< [NetworkRunner](#), [NetworkObject](#) >.

6.157.1 Detailed Description

UnityEvent for [NetworkObject](#)

6.158 NetworkEvents.ObjectPlayerEvent Class Reference

UnityEvent for [NetworkObject](#) with [PlayerRef](#)

Inherits UnityEvent< [NetworkRunner](#), [NetworkObject](#), [PlayerRef](#) >.

6.158.1 Detailed Description

UnityEvent for [NetworkObject](#) with [PlayerRef](#)

6.159 NetworkEvents.PlayerEvent Class Reference

UnityEvent for [PlayerRef](#)

Inherits UnityEvent< [NetworkRunner](#), [PlayerRef](#) >.

6.159.1 Detailed Description

UnityEvent for [PlayerRef](#)

6.160 NetworkEvents.ReliableDataEvent Class Reference

UnityEvent for Reliable Data

Inherits UnityEvent< NetworkRunner, PlayerRef, ReliableKey, ArraySegment< byte >>.

6.160.1 Detailed Description

UnityEvent for Reliable Data

6.161 NetworkEvents.ReliableProgressEvent Class Reference

UnityEvent for Reliable Data Progress

Inherits UnityEvent< NetworkRunner, PlayerRef, ReliableKey, float >.

6.161.1 Detailed Description

UnityEvent for Reliable Data Progress

6.162 NetworkEvents.RunnerEvent Class Reference

UnityEvent for [NetworkRunner](#)

Inherits UnityEvent< NetworkRunner >.

6.162.1 Detailed Description

UnityEvent for [NetworkRunner](#)

6.163 NetworkEvents.SessionListUpdateEvent Class Reference

UnityEvent for [SessionInfo](#) List

Inherits UnityEvent< NetworkRunner, List< SessionInfo >>.

6.163.1 Detailed Description

UnityEvent for [SessionInfo](#) List

6.164 NetworkEvents.ShutdownEvent Class Reference

UnityEvent for Shutdown

Inherits UnityEvent< NetworkRunner, ShutdownReason >.

6.164.1 Detailed Description

UnityEvent for Shutdown

6.165 NetworkEvents.SimulationMessageEvent Class Reference

UnityEvent for [SimulationMessage](#)

Inherits UnityEvent< NetworkRunner, SimulationMessagePtr >.

6.165.1 Detailed Description

UnityEvent for [SimulationMessage](#)

6.166 NetworkId Struct Reference

The unique identifier for a network entity.

Inherits [INetworkStruct](#), IEquatable< NetworkId >, IComparable, and IComparable< NetworkId >.

Classes

- class [EqualityComparer](#)
IEqualityComparer interface for [NetworkId](#) objects.

Public Member Functions

- int [CompareTo](#) ([NetworkId](#) other)
Compares the current [NetworkId](#) object with another [NetworkId](#) object.
- int IComparable. **CompareTo** (object obj)
- bool [Equals](#) ([NetworkId](#) other)
Determines whether the current [NetworkId](#) object is equal to another [NetworkId](#) object.
- override bool [Equals](#) (object obj)
Determines whether the specified object is equal to the current [NetworkId](#) object.
- override int [GetHashCode](#) ()
Get the hash code for this [NetworkId](#).
- string [ToNamePrefixString](#) ()
String conversion specifically for use in prefixing names of GameObjects.
- override string [ToString](#) ()
String representation of the [NetworkId](#).
- void [Write](#) (NetBitBuffer *buffer)
Writes this [NetworkId](#) to the provided NetBitBuffer.

Static Public Member Functions

- static implicit [operator bool](#) ([NetworkId](#) id)
Converts the [NetworkId](#) object to a boolean value.
- static bool [operator!=](#) ([NetworkId](#) a, [NetworkId](#) b)
Determines whether two [NetworkId](#) objects are not equal.
- static bool [operator==](#) ([NetworkId](#) a, [NetworkId](#) b)
Determines whether two [NetworkId](#) objects are equal.
- static [NetworkId](#) [Read](#) (NetBitBuffer *buffer)
Reads a [NetworkId](#) from the provided NetBitBuffer.
- static void [Write](#) (NetBitBuffer *buffer, [NetworkId](#) id)
Writes the [NetworkId](#) to the provided NetBitBuffer.

Public Attributes

- uint [Raw](#)
The raw value of the network id.

Static Public Attributes

- const int [ALIGNMENT](#) = 4
The alignment of the network id in bytes.
- const int [BLOCK_SIZE](#) = 8
The size of the network id block in bytes.
- const uint [RAW_PHYSICS_INFO](#) = 4u
- const uint [RAW_PLAYER_REF_DATA_ARRAY](#) = 2u
- const uint [RAW_RUNTIME_CONFIG](#) = 1u
- const uint [RAW_SCENE_INFO](#) = 3u
- const int [SIZE](#) = 4
The size of the network id in bytes.

Properties

- static [EqualityComparer Comparer](#) = new [EqualityComparer\(\)](#) [get]
The IEqualityComparer for [NetworkId](#) objects.
- bool [IsReserved](#) [get]
Signal if the network id is reserved.
- bool [IsValid](#) [get]
Signal if the network id is valid.

6.166.1 Detailed Description

The unique identifier for a network entity.

6.166.2 Member Function Documentation

6.166.2.1 CompareTo()

```
int CompareTo (  
    NetworkId other )
```

Compares the current [NetworkId](#) object with another [NetworkId](#) object.

Parameters

<i>other</i>	A NetworkId object to compare with this object.
--------------	---

Returns

A value that indicates the relative order of the objects being compared.

6.166.2.2 Equals() [1/2]

```
bool Equals (  
    NetworkId other )
```

Determines whether the current [NetworkId](#) object is equal to another [NetworkId](#) object.

Parameters

<i>other</i>	A NetworkId object to compare with this object.
--------------	---

Returns

true if the current object is equal to the other parameter; otherwise, false.

6.166.2.3 Equals() [2/2]

```
override bool Equals (  
    object obj )
```

Determines whether the specified object is equal to the current [NetworkId](#) object.

Parameters

<i>obj</i>	The object to compare with the current object.
------------	--

Returns

true if the specified object is equal to the current object; otherwise, false.

6.166.2.4 GetHashCode()

```
override int GetHashCode ( )
```

Get the hash code for this [NetworkId](#).

6.166.2.5 operator bool()

```
static implicit operator bool (  
    NetworkId id ) [static]
```

Converts the [NetworkId](#) object to a boolean value.

6.166.2.6 operator"!=()"

```
static bool operator!= (  
    NetworkId a,  
    NetworkId b ) [static]
```

Determines whether two [NetworkId](#) objects are not equal.

6.166.2.7 operator==()

```
static bool operator== (
    NetworkId a,
    NetworkId b ) [static]
```

Determines whether two [NetworkId](#) objects are equal.

6.166.2.8 Read()

```
static NetworkId Read (
    NetBitBuffer * buffer ) [static]
```

Reads a [NetworkId](#) from the provided NetBitBuffer.

Parameters

<i>buffer</i>	The buffer to read the NetworkId from.
---------------	--

Returns

The [NetworkId](#) read from the buffer.

6.166.2.9 ToNamePrefixString()

```
string ToNamePrefixString ( )
```

String conversion specifically for use in prefixing names of GameObjects.

6.166.2.10 ToString()

```
override string ToString ( )
```

String representation of the [NetworkId](#).

6.166.2.11 Write() [1/2]

```
void Write (
    NetBitBuffer * buffer )
```

Writes this [NetworkId](#) to the provided NetBitBuffer.

Parameters

<i>buffer</i>	The buffer to write this NetworkId to.
---------------	--

6.166.2.12 Write() [2/2]

```
static void Write (  
    NetBitBuffer * buffer,  
    NetworkId id ) [static]
```

Writes the [NetworkId](#) to the provided NetBitBuffer.

Parameters

<i>buffer</i>	The buffer to write the NetworkId to.
<i>id</i>	The NetworkId to write.

6.166.3 Member Data Documentation**6.166.3.1 ALIGNMENT**

```
const int ALIGNMENT = 4 [static]
```

The alignment of the network id in bytes.

6.166.3.2 BLOCK_SIZE

```
const int BLOCK_SIZE = 8 [static]
```

The size of the network id block in bytes.

6.166.3.3 Raw

```
uint Raw
```

The raw value of the network id.

6.166.3.4 SIZE

```
const int SIZE = 4 [static]
```

The size of the network id in bytes.

6.166.4 Property Documentation

6.166.4.1 Comparer

```
EqualityComparer Comparer = new EqualityComparer() [static], [get]
```

The IEqualityComparer for [NetworkId](#) objects.

6.166.4.2 IsReserved

```
bool IsReserved [get]
```

Signal if the network id is reserved.

6.166.4.3 IsValid

```
bool IsValid [get]
```

Signal if the network id is valid.

6.167 NetworkId.EqualityComparer Class Reference

IEqualityComparer interface for [NetworkId](#) objects.

Inherits IEqualityComparer< [NetworkId](#) >.

Public Member Functions

- bool [Equals](#) ([NetworkId](#) a, [NetworkId](#) b)
Determines whether the specified [NetworkId](#) objects are equal.
- int [GetHashCode](#) ([NetworkId](#) id)
Returns a hash code for the specified [NetworkId](#) object.

6.167.1 Detailed Description

IEqualityComparer interface for [NetworkId](#) objects.

6.167.2 Member Function Documentation

6.167.2.1 Equals()

```
bool Equals (
    NetworkId a,
    NetworkId b )
```

Determines whether the specified [NetworkId](#) objects are equal.

6.167.2.2 GetHashCode()

```
int GetHashCode (
    NetworkId id )
```

Returns a hash code for the specified [NetworkId](#) object.

6.168 NetworkInput Struct Reference

[NetworkInput](#) Struct

Public Member Functions

- bool [Convert](#) ([Type](#) type)
- bool [Convert](#)< [T](#) > ()
Converts the Type of this [INetworkInput](#) to another type
- [T](#) [Get](#)< [T](#) > ()
Gets the content of this [INetworkInput](#) as another type
- bool [Is](#)< [T](#) > ()
Checks if this [INetworkInput](#) is of a certain type
- bool [Set](#)< [T](#) > ([T](#) value)
Sets the content of this [INetworkInput](#) to another type
- bool [TryGet](#)< [T](#) > (out [T](#) input)
Tries to export data as the indicated [T](#) [INetworkInput](#) struct.
- bool [TrySet](#)< [T](#) > ([T](#) input)
Tries to import data from a [INetworkInput](#) struct.

Properties

- `uint * Data` [get]
Data pointer of the [NetworkInput](#)
- `bool IsValid` [get]
Signal if the [NetworkInput](#) is valid or not
- `Type Type` [get]
Get the Type associated with this [NetworkInput](#)
- `int WordCount` [get]
Number of Words for the [NetworkInput](#)

6.168.1 Detailed Description

[NetworkInput](#) Struct

6.168.2 Member Function Documentation

6.168.2.1 `Convert< T >()`

```
bool Convert< T > ( )
```

Converts the Type of this [INetworkInput](#) to another type

Type Constraints

T : [unmanaged](#)
T : [INetworkInput](#)
T : [Convert](#)
T : [typeof](#)
T : T

6.168.2.2 `Get< T >()`

```
T Get< T > ( )
```

Gets the content of this [INetworkInput](#) as another type

Type Constraints

T : [unmanaged](#)
T : [INetworkInput](#)

6.168.2.3 Is< T >()

```
bool Is< T > ( )
```

Checks if this [INetworkInput](#) is of a certain type

Type Constraints

T : unmanaged

T : INetworkInput

6.168.2.4 Set< T >()

```
bool Set< T > (
    T value )
```

Sets the content of this [INetworkInput](#) to another type

Type Constraints

T : unmanaged

T : INetworkInput

6.168.2.5 TryGet< T >()

```
bool TryGet< T > (
    out T input )
```

Tries to export data as the indicated T [INetworkInput](#) struct.

Type Constraints

T : unmanaged

T : INetworkInput

6.168.2.6 TrySet< T >()

```
bool TrySet< T > (
    T input )
```

Tries to import data from a [INetworkInput](#) struct.

Type Constraints

T : unmanaged

T : INetworkInput

6.168.3 Property Documentation

6.168.3.1 Data

`uint* Data [get]`

Data pointer of the [NetworkInput](#)

6.168.3.2 IsValid

`bool IsValid [get]`

Signal if the [NetworkInput](#) is valid or not

6.168.3.3 Type

`Type Type [get]`

Get the Type associated with this [NetworkInput](#)

6.168.3.4 WordCount

`int WordCount [get]`

Number of Words for the [NetworkInput](#)

6.169 NetworkInputUtils Class Reference

Utility methods for [NetworkInput](#)

Static Public Member Functions

- static int [GetMaxWordCount](#) ()
Get the max word count from all registered types
- static Type [GetType](#) (int typeKey)
Get the Type based on its associate Key
- static int [GetTypeKey](#) (Type type)
Get the Key associate with the argument Type
- static int [GetWordCount](#) (Type type)
Get Type Word Count if it is of type [NetworkInput](#)

6.169.1 Detailed Description

Utility methods for [NetworkInput](#)

6.169.2 Member Function Documentation

6.169.2.1 GetMaxWordCount()

```
static int GetMaxWordCount ( ) [static]
```

Get the max word count from all registered types

6.169.2.2 GetType()

```
static Type GetType (
    int typeKey ) [static]
```

Get the Type based on its associate Key

Parameters

<i>typeKey</i>	Key associated with a Type
----------------	----------------------------

Returns

Type associated with the Key, or null otherwise

6.169.2.3 GetTypeKey()

```
static int GetTypeKey (
    Type type ) [static]
```

Get the Key associate with the argument Type

Parameters

<i>type</i>	Type to check for the key
-------------	---------------------------

Returns

Associated Type Key, or an exception if not found

6.169.2.4 GetWordCount()

```
static int GetWordCount (
    Type type ) [static]
```

Get Type Word Count if it is of type [NetworkInput](#)

Parameters

<i>type</i>	Type to check for word count
-------------	------------------------------

Returns

Number of words for the [NetworkInput](#)

6.170 NetworkInputWeavedAttribute Class Reference

Network Input Weaved Attribute

Inherits Attribute.

Public Member Functions

- [NetworkInputWeavedAttribute](#) (int wordCount)
[NetworkInputWeavedAttribute](#) Constructor

Properties

- int [WordCount](#) [get]
[NetworkInput](#) Word Count

6.170.1 Detailed Description

Network Input Weaved Attribute

6.170.2 Constructor & Destructor Documentation**6.170.2.1 NetworkInputWeavedAttribute()**

```
NetworkInputWeavedAttribute (
    int wordCount )
```

[NetworkInputWeavedAttribute](#) Constructor

Parameters

<code>wordCount</code>	WordCount
------------------------	---------------------------

6.170.3 Property Documentation

6.170.3.1 WordCount

```
int WordCount [get]
```

[NetworkInput](#) Word Count

6.171 NetworkLinkedList< T > Struct Template Reference

[Fusion](#) type for networking LinkedLists. Maximum capacity is fixed, and is set with the [CapacityAttribute](#).

Typical Usage:

Inherits [IEnumerable< T >](#), and [INetworkLinkedList](#).

Classes

- struct [Enumerator](#)
[Enumerator](#) for [NetworkLinkedList< T >](#).

Public Member Functions

- void [INetworkLinkedList](#). [Add](#) (object item)
Adds an item to the networked linked list.
- void [Add](#) (T value)
Adds a value to the end of the list.
- void [Clear](#) ()
Removes and clears all list elements.
- bool [Contains](#) (T value)
Returns true if the value already exists in the list.
- bool [Contains](#) (T value, [IEqualityComparer< T >](#) comparer)
Returns true if the value already exists in the list.
- int * [Entry](#) (int index)
- int * [FindFreeEntry](#) (out int index)
- T [Get](#) (int index)
Returns the value at supplied index.
- int * [GetEntryByListIndex](#) (int listIndex)
- [Enumerator](#) [GetEnumerator](#) ()
Get the enumerator for the list.

- `IEnumerator< T > IEnumerable< T >. GetEnumerator ()`
- `IEnumerator IEnumerable. GetEnumerator ()`
- `int IndexOf (T value)`
Returns the index with this value. Returns -1 if not found.
- `int IndexOf (T value, IEqualityComparer< T > equalityComparer)`
Returns the index of the first occurrence of a value in the [NetworkLinkedList](#).
- `NetworkLinkedList (byte *data, int capacity, IElementReaderWriter< T > rw)`
Initializes a new instance of the [NetworkLinkedList](#) struct with the specified data, capacity, and reader/writer.
- `T Read (int *entry)`
- `NetworkLinkedList< T > Remap (void *list)`
Remaps the current [NetworkLinkedList](#) to a new memory location.
- `bool Remove (T value)`
Removes the first found element with indicated value.
- `bool Remove (T value, IEqualityComparer< T > equalityComparer)`
Removes the first found element with indicated value.
- `void RemoveEntry (int *entry, int entryIndex)`
- `T Set (int index, T value)`
Sets the value at supplied index.
- `void Write (int *entry, T value)`

Public Attributes

- `int _capacity`
- `int * _data`
- `IElementReaderWriter< T > _rw`
- `int _stride`

Static Public Attributes

- `const int COUNT = 0`
- `const int ELEMENT_WORDS = 2`
Returns the number of words required to store a single element.
- `const int HEAD = 1`
- `const int INVALID = 0`
- `const int META_WORDS = 3`
Returns the number of words required to store the list metadata.
- `const int NEXT = 1`
- `const int OFFSET = 1`
- `const int PREV = 0`
- `const int TAIL = 2`

Properties

- `int Capacity [get]`
Returns the max element count.
- `int Count [get]`
Returns the current element count.
- `int Head [get, set]`
- `int Tail [get, set]`
- `T this[int index] [get, set]`
Element indexer.

6.171.1 Detailed Description

[Fusion](#) type for networking LinkedLists. Maximum capacity is fixed, and is set with the [CapacityAttribute](#).

Typical Usage:

```
[Networked, Capacity(10)]
NetworkLinkedList<int> syncedLinkedList => default;
```

Optional usage (for NetworkBehaviours ONLY - this is not legal in INetworkStructs): [Networked, Capacity(4)]

```
NetworkLinkedList<int> syncedLinkedList { get; } = MakeInitializer(new int[]
{ 1, 2, 3, 4 });
```

Usage for modifying data: `var list = syncedLinkedList; list.Add(123); list[0] = 456; list.Remove(0);`

Template Parameters

<i>T</i>	T can be a primitive, or an INetworkStruct .
----------	--

6.171.2 Constructor & Destructor Documentation

6.171.2.1 NetworkLinkedList()

```
NetworkLinkedList (
    byte * data,
    int capacity,
    IElementReaderWriter< T > rw )
```

Initializes a new instance of the [NetworkLinkedList](#) struct with the specified data, capacity, and reader/writer.

Parameters

<i>data</i>	The pointer to the data of the list.
<i>capacity</i>	The capacity of the list.
<i>rw</i>	The reader/writer for the elements of the list.

6.171.3 Member Function Documentation

6.171.3.1 Add() [1/2]

```
void INetworkLinkedList. Add (
    object item )
```

Adds an item to the networked linked list.

Parameters

<i>item</i>	The item to add to the linked list.
-------------	-------------------------------------

Implements [INetworkLinkedList](#).

6.171.3.2 Add() [2/2]

```
void Add (
    T value )
```

Adds a value to the end of the list.

Parameters

<i>value</i>	Value to add.
--------------	---------------

6.171.3.3 Clear()

```
void Clear ( )
```

Removes and clears all list elements.

6.171.3.4 Contains() [1/2]

```
bool Contains (
    T value )
```

Returns true if the value already exists in the list.

6.171.3.5 Contains() [2/2]

```
bool Contains (
    T value,
    IEqualityComparer< T > comparer )
```

Returns true if the value already exists in the list.

6.171.3.6 Get()

```
T Get (
    int index )
```

Returns the value at supplied index.

6.171.3.7 GetEnumerator()

```
Enumerator GetEnumerator ( )
```

Get the enumerator for the list.

6.171.3.8 IndexOf() [1/2]

```
int IndexOf (
    T value )
```

Returns the index with this value. Returns -1 if not found.

6.171.3.9 IndexOf() [2/2]

```
int IndexOf (
    T value,
    IEqualityComparer< T > equalityComparer )
```

Returns the index of the first occurrence of a value in the [NetworkLinkedList](#).

Parameters

<i>value</i>	The value to locate in the NetworkLinkedList . The value can be null for reference types.
<i>equalityComparer</i>	An equality comparer to compare values. Must not be null.

Returns

The zero-based index of the first occurrence of value within the entire [NetworkLinkedList](#), if found; otherwise, -1.

This method performs a linear search; therefore, this method is an O(n) operation, where n is Capacity.

6.171.3.10 Remap()

```
NetworkLinkedList<T> Remap (
    void * list )
```

Remaps the current [NetworkLinkedList](#) to a new memory location.

Parameters

<i>list</i>	The pointer to the new memory location.
-------------	---

Returns

A new instance of [NetworkLinkedList](#) with the same capacity and reader/writer, but mapped to the new memory location.

6.171.3.11 Remove() [1/2]

```
bool Remove (
    T value )
```

Removes the first found element with indicated value.

6.171.3.12 Remove() [2/2]

```
bool Remove (
    T value,
    IEqualityComparer< T > equalityComparer )
```

Removes the first found element with indicated value.

6.171.3.13 Set()

```
T Set (
    int index,
    T value )
```

Sets the value at supplied index.

6.171.4 Member Data Documentation

6.171.4.1 ELEMENT_WORDS

```
const int ELEMENT_WORDS = 2 [static]
```

Returns the number of words required to store a single element.

6.171.4.2 META_WORDS

```
const int META_WORDS = 3 [static]
```

Returns the number of words required to store the list metadata.

6.171.5 Property Documentation

6.171.5.1 Capacity

```
int Capacity [get]
```

Returns the max element count.

6.171.5.2 Count

```
int Count [get]
```

Returns the current element count.

6.171.5.3 this[int index]

```
T this[int index] [get], [set]
```

Element indexer.

6.172 NetworkLinkedList< T >.Enumerator Struct Reference

[Enumerator](#) for [NetworkLinkedList<T>](#).

Inherits [IEnumerator< T >](#).

Public Member Functions

- void [Dispose](#) ()
Releases all resources used by the [NetworkLinkedList<T>.Enumerator](#).
- bool [MoveNext](#) ()
Advances the enumerator to the next element of the [NetworkLinkedList<T>](#).
- void [Reset](#) ()
Resets the enumerator to its initial position, which is before the first element in the collection.

Public Attributes

- `bool _first`
- `int _head`
- `NetworkLinkedList< T > _list`

Properties

- `T Current` [get]
Gets the current element in the collection.
- `object IEnumerator. Current` [get]

6.172.1 Detailed Description

Enumerator for `NetworkLinkedList<T>`.

6.172.2 Member Function Documentation

6.172.2.1 Dispose()

```
void Dispose ( )
```

Releases all resources used by the `NetworkLinkedList<T>.Enumerator`.

6.172.2.2 MoveNext()

```
bool MoveNext ( )
```

Advances the enumerator to the next element of the `NetworkLinkedList<T>`.

Returns

Returns true if the enumerator advanced to the next element.

6.172.2.3 Reset()

```
void Reset ( )
```

Resets the enumerator to its initial position, which is before the first element in the collection.

6.172.3 Property Documentation

6.172.3.1 Current

```
T Current [get]
```

Gets the current element in the collection.

Returns

The current element in the collection.

Exceptions

<i>InvalidOperationException</i>	Thrown when the enumerator is positioned before the first element or after the last element.
----------------------------------	--

6.173 NetworkLinkedListReadOnly< T > Struct Template Reference

Read-only version of NetworkLinkedList<T>.

Public Member Functions

- bool [Contains](#) (T value)
Returns true if the value already exists in the list.
- bool [Contains](#) (T value, IEqualityComparer< T > comparer)
Returns true if the value already exists in the list.
- int * **Entry** (int index)
- T [Get](#) (int index)
Returns the value at supplied index.
- int * **GetEntryByListIndex** (int listIndex)
- int [IndexOf](#) (T value)
Returns the index with this value. Returns -1 if not found.
- int [IndexOf](#) (T value, IEqualityComparer< T > equalityComparer)
Returns the index of the first occurrence of a value in the [FixedArray](#).
- T **Read** (int *entry)

Public Attributes

- int **_capacity**
- int * **_data**
- [IElementReaderWriter](#)< T > **_rw**
- int **_stride**

Static Public Attributes

- const int **COUNT** = 0
- const int [ELEMENT_WORDS](#) = 2
Returns the number of words required to store a single element.
- const int **HEAD** = 1
- const int **INVALID** = 0
- const int [META_WORDS](#) = 3
Returns the number of words required to store the list metadata.
- const int **NEXT** = 1
- const int **OFFSET** = 1
- const int **PREV** = 0
- const int **TAIL** = 2

Properties

- int [Capacity](#) [get]
Returns the max element count.
- int [Count](#) [get]
Returns the current element count.
- int [Head](#) [get]
- int [Tail](#) [get]
- T [this\[int index\]](#) [get]
Element indexer.

6.173.1 Detailed Description

Read-only version of NetworkLinkedList<T>.

Template Parameters

<i>T</i>	Custom struct type.
----------	---------------------

6.173.2 Member Function Documentation

6.173.2.1 Contains() [1/2]

```
bool Contains (
    T value )
```

Returns true if the value already exists in the list.

6.173.2.2 Contains() [2/2]

```
bool Contains (
    T value,
    IEqualityComparer< T > comparer )
```

Returns true if the value already exists in the list.

6.173.2.3 Get()

```
T Get (
    int index )
```

Returns the value at supplied index.

6.173.2.4 IndexOf() [1/2]

```
int IndexOf (
    T value )
```

Returns the index with this value. Returns -1 if not found.

6.173.2.5 IndexOf() [2/2]

```
int IndexOf (
    T value,
    IEqualityComparer< T > equalityComparer )
```

Returns the index of the first occurrence of a value in the [FixedArray](#).

Parameters

<i>value</i>	The value to locate in the FixedArray . The value can be null for reference types.
<i>equalityComparer</i>	An equality comparer to compare values. Must not be null.

Returns

The zero-based index of the first occurrence of value within the entire [FixedArray](#), if found; otherwise, -1.

This method performs a linear search; therefore, this method is an O(n) operation, where n is Capacity.

6.173.3 Member Data Documentation

6.173.3.1 ELEMENT_WORDS

```
const int ELEMENT_WORDS = 2 [static]
```

Returns the number of words required to store a single element.

6.173.3.2 META_WORDS

```
const int META_WORDS = 3 [static]
```

Returns the number of words required to store the list metadata.

6.173.4 Property Documentation

6.173.4.1 Capacity

`int Capacity [get]`

Returns the max element count.

6.173.4.2 Count

`int Count [get]`

Returns the current element count.

6.173.4.3 this[int index]

`T this[int index] [get]`

Element indexer.

6.174 NetworkLoadSceneParameters Struct Reference

Parameters for loading a scene

Inherits `IEquatable< NetworkLoadSceneParameters >`.

Public Member Functions

- `bool Equals (NetworkLoadSceneParameters other)`
Compares two [NetworkLoadSceneParameters](#) for equality
- `override bool Equals (object obj)`
Compares two [NetworkLoadSceneParameters](#) for equality
- `override int GetHashCode ()`
Returns the hash code of the [NetworkLoadSceneParameters](#)
- `override string ToString ()`
Returns a string representation of the [NetworkLoadSceneParameters](#)

Static Public Member Functions

- static bool `operator!=` ([NetworkLoadSceneParameters](#) left, [NetworkLoadSceneParameters](#) right)
Compares two [NetworkLoadSceneParameters](#) for inequality
- static bool `operator==` ([NetworkLoadSceneParameters](#) left, [NetworkLoadSceneParameters](#) right)
Compares two [NetworkLoadSceneParameters](#) for equality

Public Attributes

- readonly [NetworkSceneLoadId](#) `LoadId`
The unique id of the scene load operation

Properties

- bool [IsActiveOnLoad](#) [get]
Signals if the scene should be active on load
- bool [IsLocalPhysics2D](#) [get]
Signals if the scene should have local 2D physics
- bool [IsLocalPhysics3D](#) [get]
Signals if the scene should have local 3D physics
- bool [IsSingleLoad](#) [get]
Signals if the scene should be single loaded
- LoadSceneMode [LoadSceneMode](#) [get]
The [LoadSceneMode](#) to use when loading the scene
- LoadSceneParameters [LoadSceneParameters](#) [get]
The [LoadSceneParameters](#) to use when loading the scene
- LocalPhysicsMode [LocalPhysicsMode](#) [get]
The [LocalPhysicsMode](#) to use when loading the scene

6.174.1 Detailed Description

Parameters for loading a scene

6.174.2 Member Function Documentation

6.174.2.1 Equals() [1/2]

```
bool Equals (
    NetworkLoadSceneParameters other )
```

Compares two [NetworkLoadSceneParameters](#) for equality

Parameters

<i>other</i>	The other NetworkLoadSceneParameters
--------------	--

Returns

Returns true if the two [NetworkLoadSceneParameters](#) are equal

6.174.2.2 Equals() [2/2]

```
override bool Equals (  
    object obj )
```

Compares two [NetworkLoadSceneParameters](#) for equality

Parameters

<i>obj</i>	The other NetworkLoadSceneParameters
------------	--

Returns

Returns true if the two [NetworkLoadSceneParameters](#) are equal

6.174.2.3 GetHashCode()

```
override int GetHashCode ( )
```

Returns the hash code of the [NetworkLoadSceneParameters](#)

6.174.2.4 operator"!="()

```
static bool operator!= (  
    NetworkLoadSceneParameters left,  
    NetworkLoadSceneParameters right ) [static]
```

Compares two [NetworkLoadSceneParameters](#) for inequality

Parameters

<i>left</i>	Left NetworkLoadSceneParameters
<i>right</i>	Right NetworkLoadSceneParameters

Returns

Returns true if the two [NetworkLoadSceneParameters](#) are not equal

6.174.2.5 operator==()

```
static bool operator== (
    NetworkLoadSceneParameters left,
    NetworkLoadSceneParameters right ) [static]
```

Compares two [NetworkLoadSceneParameters](#) for equality

Parameters

<i>left</i>	Left NetworkLoadSceneParameters
<i>right</i>	Right NetworkLoadSceneParameters

Returns

Returns true if the two [NetworkLoadSceneParameters](#) are equal

6.174.2.6 ToString()

```
override string ToString ( )
```

Returns a string representation of the [NetworkLoadSceneParameters](#)

6.174.3 Member Data Documentation

6.174.3.1 LoadId

```
readonly NetworkSceneLoadId LoadId
```

The unique id of the scene load operation

6.174.4 Property Documentation

6.174.4.1 IsActiveOnLoad

```
bool IsActiveOnLoad [get]
```

Signals if the scene should be active on load

6.174.4.2 IsLocalPhysics2D

```
bool IsLocalPhysics2D [get]
```

Signals if the scene should have local 2D physics

6.174.4.3 IsLocalPhysics3D

```
bool IsLocalPhysics3D [get]
```

Signals if the scene should have local 3D physics

6.174.4.4 IsSingleLoad

```
bool IsSingleLoad [get]
```

Signals if the scene should be single loaded

6.174.4.5 LoadSceneMode

```
LoadSceneMode LoadSceneMode [get]
```

The [LoadSceneMode](#) to use when loading the scene

6.174.4.6 LoadSceneParameters

```
LoadSceneParameters LoadSceneParameters [get]
```

The [LoadSceneParameters](#) to use when loading the scene

6.174.4.7 LocalPhysicsMode

```
LocalPhysicsMode LocalPhysicsMode [get]
```

The [LocalPhysicsMode](#) to use when loading the scene

6.175 NetworkMecanimAnimator Class Reference

A component for synchronizing the Animator controller state from the State Authority to network proxies. Requires a Unity Animator component, and a [NetworkObject](#) component. NOTE: Animator Root Motion is not compatible with re-simulation and prediction.

Inherits [NetworkBehaviour](#), and [IAfterAllTicks](#).

Public Member Functions

- override void [Render](#) ()
Post simulation frame rendering callback. Runs after all simulations have finished. Use in place of Unity's Update when [Fusion](#) is handling Physics.
- void [SetTrigger](#) (int triggerHash, bool passThroughOnInputAuthority=false)
Queues a [SetTrigger\(\)](#) call for the associated Animator on the State Authority. Call this instead of Animator.SetTrigger() for the State Authority to ensure that triggers are captured. On State Authority, this call will defer the [SetTrigger\(\)](#) pass-through to the Animator until [FixedUpdateNetwork\(\)](#) is called, where all queued triggers will be executed (this is to ensure tick agreement between server and clients).
- void [SetTrigger](#) (string trigger, bool passThroughOnInputAuthority=false)
Queues a [SetTrigger\(\)](#) call for the associated Animator on the State Authority. Call this instead of Animator.SetTrigger() for the State Authority to ensure that triggers are captured. On State Authority, this call will defer the [SetTrigger\(\)](#) pass-through to the Animator until [FixedUpdateNetwork\(\)](#) is called, where all queued triggers will be executed (this is to ensure tick agreement between server and clients).
- override void [Spawned](#) ()
Post spawn callback.

Public Attributes

- Animator [Animator](#)
The Animator being synced. If unset, will attempt to find one on this GameObject.
- [RenderSource ApplyTiming](#) = [RenderSource.To](#)
The source of the State which is applied in Render.

Properties

- override? int [DynamicWordCount](#) [get]
Gets the dynamic word count for the [NetworkMecanimAnimator](#).

Additional Inherited Members

6.175.1 Detailed Description

A component for synchronizing the Animator controller state from the State Authority to network proxies. Requires a Unity Animator component, and a [NetworkObject](#) component. NOTE: Animator Root Motion is not compatible with re-simulation and prediction.

6.175.2 Member Function Documentation

6.175.2.1 SetTrigger() [1/2]

```
void SetTrigger (
    int triggerHash,
    bool passThroughOnInputAuthority = false )
```

Queues a [SetTrigger\(\)](#) call for the associated Animator on the State Authority. Call this instead of [Animator.SetTrigger\(\)](#) for the State Authority to ensure that triggers are captured. On State Authority, this call will defer the [SetTrigger\(\)](#) pass-through to the Animator until [FixedUpdateNetwork\(\)](#) is called, where all queued triggers will be executed (this is to ensure tick agreement between server and clients).

Parameters

<i>triggerHash</i>	Trigger hash to set
<i>passThroughOnInputAuthority</i>	Will call Animator.SetTrigger() immediately on the InputAuthority. If false, SetTrigger() will not be called on the Input Authority at all and Animator.SetTrigger() should be called explicitly as needed.

6.175.2.2 SetTrigger() [2/2]

```
void SetTrigger (
    string trigger,
    bool passThroughOnInputAuthority = false )
```

Queues a [SetTrigger\(\)](#) call for the associated Animator on the State Authority. Call this instead of [Animator.SetTrigger\(\)](#) for the State Authority to ensure that triggers are captured. On State Authority, this call will defer the [SetTrigger\(\)](#) pass-through to the Animator until [FixedUpdateNetwork\(\)](#) is called, where all queued triggers will be executed (this is to ensure tick agreement between server and clients).

Parameters

<i>trigger</i>	Trigger name to set
<i>passThroughOnInputAuthority</i>	Will call Animator.SetTrigger() immediately on the InputAuthority. If false, SetTrigger() will not be called on the Input Authority at all and Animator.SetTrigger() should be called explicitly as needed.

6.175.3 Member Data Documentation**6.175.3.1 Animator**

```
Animator Animator
```

The Animator being synced. If unset, will attempt to find one on this GameObject.

6.175.3.2 ApplyTiming

`RenderSource ApplyTiming = RenderSource.To`

The source of the State which is applied in Render.

6.175.4 Property Documentation

6.175.4.1 DynamicWordCount

`override? int DynamicWordCount [get]`

Gets the dynamic word count for the [NetworkMecanimAnimator](#).

The dynamic word count, which is the maximum of the current total words and the runtime counts, if the application is playing.

Exceptions

<code>System.InvalidOperationException</code>	Thrown when this property is accessed outside of playing.
---	---

6.176 NetworkObject Class Reference

The primary [Fusion](#) component for networked GameObject entities. This stores the object's network identity and manages the object's state and input authority.

Inherits [Behaviour](#).

Public Member Functions

- void [AssignInputAuthority](#) ([PlayerRef](#) player)
Sets which [PlayerRef](#) has Input Authority for this Object.
- void [CopyStateFrom](#) ([NetworkObject](#) source)
Copies the entire State from another [NetworkObject](#)
- void [CopyStateFrom](#) ([NetworkObjectHeaderPtr](#) source)
Copies the entire State from another [NetworkObject](#) based on the [NetworkObjectHeaderPtr](#)
- int [GetLocalAuthorityMask](#) ()
Gets a bitmask of [AuthorityMasks](#) flags, representing the current local authority over this [NetworkObject](#).
- delegate [PriorityLevel](#) [PriorityLevelDelegate](#) ([NetworkObject](#) networkObject, [PlayerRef](#) player)
Delegate for determining the priority level of a network object for a specific player.
- void [ReleaseStateAuthority](#) ()
Release the state authority over this [NetworkObject](#) on shared mode.
- void [RemoveInputAuthority](#) ()
Removes input authority from whichever player has it for this object. Only valid when called on a Host or Server peer.

- delegate bool [ReplicateToDelegate](#) ([NetworkObject](#) networkObject, [PlayerRef](#) player)
Delegate for determining if a network object should be replicated to a specific player.
- void [RequestStateAuthority](#) ()
Request state authority over this [NetworkObject](#) on shared mode.
- void [SetPlayerAlwaysInterested](#) ([PlayerRef](#) player, bool alwaysInterested)
Add or remove specific player interest in this [NetworkObject](#). Only the [NetworkObject](#) State Authority can set interest.

Static Public Member Functions

- static int [GetWordCount](#) ([NetworkObject](#) obj)
Calculates the total word count for a given [NetworkObject](#).
- static void [NetworkUnwrap](#) ([NetworkRunner](#) runner, [NetworkId](#) wrapper, ref [NetworkObject](#) result)
Return the [NetworkObject](#) reference on result that matches the provided [NetworkId](#)
- static [NetworkId](#) [NetworkWrap](#) ([NetworkRunner](#) runner, [NetworkObject](#) obj)
Return the obj [NetworkId](#).
- static implicit [operator NetworkId](#) ([NetworkObject](#) obj)
Converts the Network Object to it's [NetworkId](#).

Public Attributes

- [NetworkObjectFlags](#) [Flags](#)
Flags used for network object prefabs and similar
- bool [IsResume](#)
Signal that this [NetworkObject](#) comes from a Resume Spawn
- [NetworkObject\[\]](#) [NestedObjects](#)
Array of initial child nested [NetworkObject](#) entities, that are children of this Object.
- [NetworkBehaviour\[\]](#) [NetworkedBehaviours](#)
Array of all [NetworkBehaviours](#) associated with this network entity.
- [NetworkObjectTypeId](#) [NetworkTypeId](#)
The type ID for this prefab or scene object, set when adding to the prefab table and registering scene objects, respectively. All spawned instances of this object will retain this value. Use [NetworkId](#) for the unique ID of network entries.
- [PriorityLevelDelegate](#) [PriorityCallback](#)
Delegate callback used to override priority value for a specific object-player pair
- [ReplicateToDelegate](#) [ReplicateTo](#)
Delegate callback used to override if an object should be replicate to a client or not
- uint [SortKey](#)
Used for whenever objects need to be sorted in a deterministic order, like when registering scene objects.

Protected Member Functions

- virtual void [Awake](#) ()
Awake is called when the script instance is being loaded.
- virtual void [OnDestroy](#) ()
OnDestroy is called when the script instance is being destroyed.

Properties

- bool [HasInputAuthority](#) [get]
Returns if [Simulation.LocalPlayer](#) is the designated Input Source for this network entity.
- bool [HasStateAuthority](#) [get]
Returns if [Simulation.LocalPlayer](#) is the designated State Source for this network entity.
- [NetworkId? Id](#) [get]
The unique identifier for this network entity.
- [PlayerRef InputAuthority](#) [get]
Returns the [PlayerRef](#) that has Input Authority over this network entity. PlayerRefs are assigned in order from 0 to MaxPlayers-1 and are re-used as players join and leave. The only caveat is that the server player (if one exists), always gets the last index no matter how many clients are connected.
- bool [IsInSimulation](#) [get]
If this object is inserted into the simulation
- bool [IsProxy](#) [get]
Returns if [Simulation.LocalPlayer](#) is neither the Input nor State Source for this network entity.
- bool [IsSpawnable](#) [get, set]
Toggles if this [NetworkObject](#) is included in the [NetworkProjectConfig.PrefabTable](#), which will include the prefab in builds as a Spawnable object.
- bool [IsValid](#) [get]
Returns if this network entity is associated with its [NetworkRunner](#), and that runner is not null.
- [Tick LastReceiveTick](#) [get]
Last tick this object received an update.
- string [Name](#) [get]
The ID + Unity GameObject name for this entity.
- [RenderSource RenderSource](#) [get, set]
Returns the [Fusion.RenderSource](#) for this [Fusion.NetworkBehaviour](#) instance, indicating how snapshot data will be used to render it.
- float [RenderTime](#) [get]
Returns the current interpolation time for this object
- [RenderTimeframe??? RenderTimeframe](#) [get, set]
Returns the [Fusion.RenderTimeframe](#) for this [Fusion.NetworkBehaviour](#) instance, indicating what snapshot data will be used to render it.
- [NetworkRunner Runner](#) [get]
The [NetworkRunner](#) this entity is associated with.
- [PlayerRef StateAuthority](#) [get]
Returns the [PlayerRef](#) that has State Authority over this network entity. PlayerRefs are assigned in order from 0 to MaxPlayers-1 and are re-used as players join and leave. The only caveat is that the server player (if one exists), always gets the last index no matter how many clients are connected.

6.176.1 Detailed Description

The primary [Fusion](#) component for networked GameObject entities. This stores the object's network identity and manages the object's state and input authority.

6.176.2 Member Function Documentation

6.176.2.1 AssignInputAuthority()

```
void AssignInputAuthority (
    PlayerRef player )
```

Sets which [PlayerRef](#) has Input Authority for this Object.

6.176.2.2 Awake()

```
virtual void Awake ( ) [protected], [virtual]
```

Awake is called when the script instance is being loaded.

6.176.2.3 CopyStateFrom() [1/2]

```
void CopyStateFrom (
    NetworkObject source )
```

Copies the entire State from another [NetworkObject](#)

Parameters

<i>source</i>	NetworkObject to copy the State from
---------------	--

6.176.2.4 CopyStateFrom() [2/2]

```
void CopyStateFrom (
    NetworkObjectHeaderPtr source )
```

Copies the entire State from another [NetworkObject](#) based on the [NetworkObjectHeaderPtr](#)

Parameters

<i>source</i>	NetworkObjectHeaderPtr to copy the state from
---------------	---

6.176.2.5 GetLocalAuthorityMask()

```
int GetLocalAuthorityMask ( )
```

Gets a bitmask of [AuthorityMasks](#) flags, representing the current local authority over this [NetworkObject](#).

6.176.2.6 GetWordCount()

```
static int GetWordCount (
    NetworkObject obj ) [static]
```

Calculates the total word count for a given [NetworkObject](#).

Parameters

<i>obj</i>	The NetworkObject for which the word count is to be calculated.
------------	---

Returns

The total word count of the [NetworkObject](#). Returns 0 if the [NetworkObject](#) is not alive.

Exceptions

<i>System.Exception</i>	Thrown when a NetworkBehaviour reference is missing in the NetworkBehaviour array of the NetworkObject .
-------------------------	--

6.176.2.7 NetworkUnwrap()

```
static void NetworkUnwrap (
    NetworkRunner runner,
    NetworkId wrapper,
    ref NetworkObject result ) [static]
```

Return the [NetworkObject](#) reference on *result* that matches the provided [NetworkId](#)

Parameters

<i>runner</i>	The NetworkRunner that will be used to try to find a NetworkObject with ID equals to <i>wrapper</i>
<i>wrapper</i>	The NetworkId to be searched
<i>result</i>	The found NetworkObject . null if the provided NetworkId is not valid

6.176.2.8 NetworkWrap()

```
static NetworkId NetworkWrap (
    NetworkRunner runner,
    NetworkObject obj ) [static]
```

Return the *obj* [NetworkId](#).

Parameters

<i>runner</i>	The NetworkRunner that <i>obj</i> is assigned to
<i>obj</i>	The NetworkObject to get the ID from

Returns

The [NetworkId](#) of the object. Default if the object is not alive (null or destroyed)

6.176.2.9 OnDestroy()

```
virtual void OnDestroy ( ) [protected], [virtual]
```

OnDestroy is called when the script instance is being destroyed.

6.176.2.10 operator NetworkId()

```
static implicit operator NetworkId (  
    NetworkObject obj ) [static]
```

Converts the Network Object to it's [NetworkId](#).

Parameters

<i>obj</i>	The object to convert
------------	-----------------------

Returns

The [NetworkId](#) of the object. Default if the object is not alive (null or destroyed)

6.176.2.11 PriorityLevelDelegate()

```
delegate PriorityLevel PriorityLevelDelegate (  
    NetworkObject networkObject,  
    PlayerRef player )
```

Delegate for determining the priority level of a network object for a specific player.

Parameters

<i>networkObject</i>	The network object in question.
<i>player</i>	The player for whom the priority level is being determined.

Returns

The priority level of the network object for the player.

6.176.2.12 ReleaseStateAuthority()

```
void ReleaseStateAuthority ( )
```

Release the state authority over this [NetworkObject](#) on shared mode.

6.176.2.13 RemoveInputAuthority()

```
void RemoveInputAuthority ( )
```

Removes input authority from whichever player has it for this object. Only valid when called on a Host or Server peer.

6.176.2.14 ReplicateToDelegate()

```
delegate bool ReplicateToDelegate (
    NetworkObject networkObject,
    PlayerRef player )
```

Delegate for determining if a network object should be replicated to a specific player.

Parameters

<i>networkObject</i>	The network object in question.
<i>player</i>	The player to potentially replicate to.

Returns

True if the object should be replicated to the player, false otherwise.

6.176.2.15 RequestStateAuthority()

```
void RequestStateAuthority ( )
```

Request state authority over this [NetworkObject](#) on shared mode.

6.176.2.16 SetPlayerAlwaysInterested()

```
void SetPlayerAlwaysInterested (
    PlayerRef player,
    bool alwaysInterested )
```

Add or remove specific player interest in this [NetworkObject](#). Only the [NetworkObject](#) State Authority can set interest.

Parameters

<i>player</i>	The player to set interest for
<i>alwaysInterested</i>	If the player should always be interested in this object

6.176.3 Member Data Documentation

6.176.3.1 Flags

[NetworkObjectFlags](#) Flags

Flags used for network object prefabs and similar

6.176.3.2 IsResume

bool IsResume

Signal that this [NetworkObject](#) comes from a Resume Spawn

6.176.3.3 NestedObjects

[NetworkObject](#) [] NestedObjects

Array of initial child nested [NetworkObject](#) entities, that are children of this Object.

6.176.3.4 NetworkedBehaviours

[NetworkBehaviour](#) [] NetworkedBehaviours

Array of all [NetworkBehaviour](#)s associated with this network entity.

6.176.3.5 NetworkTypeId

`NetworkObjectId` `NetworkTypeId`

The type ID for this prefab or scene object, set when adding to the prefab table and registering scene objects, respectively. All spawned instances of this object will retain this value. Use [NetworkId](#) for the unique ID of network entries.

6.176.3.6 PriorityCallback

`PriorityLevelDelegate` `PriorityCallback`

Delegate callback used to override priority value for a specific object-player pair

6.176.3.7 ReplicateTo

`ReplicateToDelegate` `ReplicateTo`

Delegate callback used to override if an object should be replicate to a client or not

6.176.3.8 SortKey

`uint` `SortKey`

Used for whenever objects need to be sorted in a deterministic order, like when registering scene objects.

6.176.4 Property Documentation

6.176.4.1 HasInputAuthority

`bool` `HasInputAuthority` `[get]`

Returns if [Simulation.LocalPlayer](#) is the designated Input Source for this network entity.

6.176.4.2 HasStateAuthority

```
bool HasStateAuthority [get]
```

Returns if [Simulation.LocalPlayer](#) is the designated State Source for this network entity.

6.176.4.3 Id

```
NetworkId? Id [get]
```

The unique identifier for this network entity.

6.176.4.4 InputAuthority

```
PlayerRef InputAuthority [get]
```

Returns the [PlayerRef](#) that has Input Authority over this network entity. PlayerRefs are assigned in order from 0 to MaxPlayers-1 and are re-used as players join and leave. The only caveat is that the server player (if one exists), always gets the last index no matter how many clients are connected.

6.176.4.5 IsInSimulation

```
bool IsInSimulation [get]
```

If this object is inserted into the simulation

6.176.4.6 IsProxy

```
bool IsProxy [get]
```

Returns if [Simulation.LocalPlayer](#) is neither the Input nor State Source for this network entity.

6.176.4.7 IsSpawnable

```
bool IsSpawnable [get], [set]
```

Toggles if this [NetworkObject](#) is included in the [NetworkProjectConfig.PrefabTable](#), which will include the prefab in builds as a Spawnable object.

6.176.4.8 IsValid

```
bool IsValid [get]
```

Returns if this network entity is associated with its [NetworkRunner](#), and that runner is not null.

6.176.4.9 LastReceiveTick

```
Tick LastReceiveTick [get]
```

Last tick this object received an update.

6.176.4.10 Name

```
string Name [get]
```

The ID + Unity GameObject name for this entity.

6.176.4.11 RenderSource

```
RenderSource RenderSource [get], [set]
```

Returns the [Fusion.RenderSource](#) for this [Fusion.NetworkBehaviour](#) instance, indicating how snapshot data will be used to render it.

6.176.4.12 RenderTime

```
float RenderTime [get]
```

Returns the current interpolation time for this object

6.176.4.13 RenderTimeframe

```
RenderTimeframe??? RenderTimeframe [get], [set]
```

Returns the [Fusion.RenderTimeframe](#) for this [Fusion.NetworkBehaviour](#) instance, indicating what snapshot data will be used to render it.

6.176.4.14 Runner

`NetworkRunner` `Runner` [get]

The `NetworkRunner` this entity is associated with.

6.176.4.15 StateAuthority

`PlayerRef` `StateAuthority` [get]

Returns the `PlayerRef` that has State Authority over this network entity. PlayerRefs are assigned in order from 0 to MaxPlayers-1 and are re-used as players join and leave. The only caveat is that the server player (if one exists), always gets the last index no matter how many clients are connected.

6.177 NetworkObjectFlagsExtensions Class Reference

Extension methods for the `NetworkObjectFlags` enum.

Static Public Member Functions

- static int `GetVersion` (this `NetworkObjectFlags` flags)
Returns the version of the flags.
- static bool `IsIgnored` (this `NetworkObjectFlags` flags)
Check if the flags are ignored.
- static bool `IsVersionCurrent` (this `NetworkObjectFlags` flags)
Check if the flags are the current version.
- static `NetworkObjectFlags` `SetCurrentVersion` (this `NetworkObjectFlags` flags)
Sets the flags to the current version.
- static `NetworkObjectFlags` `SetIgnored` (this `NetworkObjectFlags` flags, bool value)
Sets the ignored flag on the flags.

6.177.1 Detailed Description

Extension methods for the `NetworkObjectFlags` enum.

6.177.2 Member Function Documentation

6.177.2.1 GetVersion()

```
static int GetVersion (  
    this NetworkObjectFlags flags ) [static]
```

Returns the version of the flags.

Parameters

<i>flags</i>	The flags to get the version of.
--------------	----------------------------------

Returns

The version of the flags.

6.177.2.2 IsIgnored()

```
static bool IsIgnored (  
    this NetworkObjectFlags flags ) [static]
```

Check if the flags are ignored.

Parameters

<i>flags</i>	The flags to check.
--------------	---------------------

Returns

True if the flags are ignored, false otherwise.

6.177.2.3 IsVersionCurrent()

```
static bool IsVersionCurrent (  
    this NetworkObjectFlags flags ) [static]
```

Check if the flags are the current version.

Parameters

<i>flags</i>	The flags to check.
--------------	---------------------

Returns

True if the flags are the current version, false otherwise.

6.177.2.4 SetCurrentVersion()

```
static NetworkObjectFlags SetCurrentVersion (  
    this NetworkObjectFlags flags ) [static]
```

Sets the flags to the current version.

Parameters

<i>flags</i>	The flags to set.
--------------	-------------------

Returns

The flags with the version set to the current version.

6.177.2.5 SetIgnored()

```
static NetworkObjectFlags SetIgnored (
    this NetworkObjectFlags flags,
    bool value ) [static]
```

Sets the ignored flag on the flags.

Parameters

<i>flags</i>	Flags to set the ignored flag on.
<i>value</i>	Ignored flag value.

Returns

The flags with the ignored flag set to the given value.

6.178 NetworkObjectGuid Struct Reference[NetworkObjectGuid](#)

Inherits [INetworkStruct](#), [IEquatable](#)< [NetworkObjectGuid](#) >, and [IComparable](#)< [NetworkObjectGuid](#) >.

Classes

- class [EqualityComparer](#)
[EqualityComparer](#) for [NetworkObjectGuid](#)

Public Member Functions

- int [CompareTo](#) ([NetworkObjectGuid](#) other)
Compare the [NetworkObjectGuid](#) to another [NetworkObjectGuid](#)
- bool [Equals](#) ([NetworkObjectGuid](#) other)
Check if the [NetworkObjectGuid](#) is equal to another [NetworkObjectGuid](#)
- override bool [Equals](#) (object obj)
Check if the [NetworkObjectGuid](#) is equal to another object

- override int [GetHashCode](#) ()
Get the hashcode for a [NetworkObjectGuid](#)
- [NetworkObjectGuid](#) (byte *guid)
*Create a [NetworkObjectGuid](#) from a byte**
- [NetworkObjectGuid](#) (byte[] guid)
Create a [NetworkObjectGuid](#) from a byte array
- [NetworkObjectGuid](#) (long data0, long data1)
Create a new [NetworkObjectGuid](#)
- [NetworkObjectGuid](#) (string guid)
Create a new [NetworkObjectGuid](#)
- override string [ToString](#) ()
Returns a string representation of the [NetworkObjectGuid](#).
- string [ToString](#) (string format)
Returns a string representation of the [NetworkObjectGuid](#).
- string [ToUnityGuidString](#) ()
Returns a string representation of the [NetworkObjectGuid](#).

Static Public Member Functions

- static implicit [operator Guid](#) ([NetworkObjectGuid](#) guid)
Implicit conversion from [NetworkObjectGuid](#) to [Guid](#)
- static implicit [operator NetworkObjectGuid](#) ([Guid](#) guid)
Implicit conversion from [Guid](#) to [NetworkObjectGuid](#)
- static [operator NetworkPrefabRef](#) ([NetworkObjectGuid](#) t)
Explicit conversion from [NetworkObjectGuid](#) to [NetworkPrefabRef](#)
- static bool [operator!=](#) ([NetworkObjectGuid](#) a, [NetworkObjectGuid](#) b)
Compare two [NetworkObjectGuid](#)
- static bool [operator==](#) ([NetworkObjectGuid](#) a, [NetworkObjectGuid](#) b)
Compare two [NetworkObjectGuid](#)
- static [NetworkObjectGuid](#) [Parse](#) (string str)
Parse a [NetworkObjectGuid](#) from a string.
- static bool [TryParse](#) (string str, out [NetworkObjectGuid](#) guid)
Try to parse a string into a [NetworkObjectGuid](#)

Public Attributes

- fixed long [RawGuidValue](#) [2]
The Raw Guid Value of the [NetworkObjectGuid](#)

Static Public Attributes

- const int [ALIGNMENT](#) = 4
The alignment of the [NetworkObjectGuid](#)
- const int [SIZE](#) = 16
The Size of the [NetworkObjectGuid](#) in bytes

Properties

- static [NetworkObjectGuid Empty](#) [get]
The default value of a [NetworkObjectGuid](#)
- bool [IsValid](#) [get]
Signal if the [NetworkObjectGuid](#) is valid.

6.178.1 Detailed Description

[NetworkObjectGuid](#)

6.178.2 Constructor & Destructor Documentation

6.178.2.1 [NetworkObjectGuid\(\)](#) [1/4]

```
NetworkObjectGuid (  
    string guid )
```

Create a new [NetworkObjectGuid](#)

Parameters

<i>guid</i>	The guid to use
-------------	-----------------

6.178.2.2 [NetworkObjectGuid\(\)](#) [2/4]

```
NetworkObjectGuid (  
    long data0,  
    long data1 )
```

Create a new [NetworkObjectGuid](#)

Parameters

<i>data0</i>	Data0 of the Guid
<i>data1</i>	Data1 of the Guid

6.178.2.3 [NetworkObjectGuid\(\)](#) [3/4]

```
NetworkObjectGuid (  
    byte[] guid )
```

Create a [NetworkObjectGuid](#) from a byte array

Parameters

<i>guid</i>	The byte array to create the NetworkObjectGuid from
-------------	---

6.178.2.4 NetworkObjectGuid() [4/4]

```
NetworkObjectGuid (  
    byte * guid )
```

Create a [NetworkObjectGuid](#) from a byte*

Parameters

<i>guid</i>	The byte* to create the NetworkObjectGuid from
-------------	--

6.178.3 Member Function Documentation

6.178.3.1 CompareTo()

```
int CompareTo (  
    NetworkObjectGuid other )
```

Compare the [NetworkObjectGuid](#) to another [NetworkObjectGuid](#)

Parameters

<i>other</i>	The other NetworkObjectGuid to compare against
--------------	--

Returns

0 if the [NetworkObjectGuid](#) are equal, -1 if this [NetworkObjectGuid](#) is less than the other, 1 if this [NetworkObjectGuid](#) is greater than the other

6.178.3.2 Equals() [1/2]

```
bool Equals (  
    NetworkObjectGuid other )
```

Check if the [NetworkObjectGuid](#) is equal to another [NetworkObjectGuid](#)

Parameters

<i>other</i>	The other NetworkObjectGuid to check against
--------------	--

Returns

True if the NetworkObjectGuids are equal, false otherwise

6.178.3.3 Equals() [2/2]

```
override bool Equals (  
    object obj )
```

Check if the [NetworkObjectGuid](#) is equal to another object

Parameters

<i>obj</i>	The other object to check against
------------	-----------------------------------

Returns

True if the objects are equal, false otherwise

6.178.3.4 GetHashCode()

```
override int GetHashCode ( )
```

Get the hashcode for a [NetworkObjectGuid](#)

6.178.3.5 operator Guid()

```
static implicit operator Guid (  
    NetworkObjectGuid guid ) [static]
```

Implicit conversion from [NetworkObjectGuid](#) to Guid

Parameters

<i>guid</i>	NetworkObjectGuid to convert from
-------------	---

Returns

Guid

6.178.3.6 operator NetworkObjectGuid()

```
static implicit operator NetworkObjectGuid (  
    Guid guid ) [static]
```

Implicit conversion from Guid to [NetworkObjectGuid](#)

Parameters

<i>guid</i>	Guid to convert from
-------------	----------------------

Returns

[NetworkObjectGuid](#)**6.178.3.7 operator NetworkPrefabRef()**

```
static operator NetworkPrefabRef (  
    NetworkObjectGuid t ) [explicit], [static]
```

Explicit conversion from [NetworkObjectGuid](#) to [NetworkPrefabRef](#)

Parameters

<i>t</i>	NetworkObjectGuid to convert from
----------	---

Returns

[NetworkPrefabRef](#)**6.178.3.8 operator "!="()**

```
static bool operator!= (  
    NetworkObjectGuid a,  
    NetworkObjectGuid b ) [static]
```

Compare two [NetworkObjectGuid](#)

Returns

True if the [NetworkObjectGuid](#) are not equal, false otherwise

6.178.3.9 operator==()

```
static bool operator== (
    NetworkObjectGuid a,
    NetworkObjectGuid b ) [static]
```

Compare two [NetworkObjectGuid](#)

Returns

True if the [NetworkObjectGuid](#) are equal, false otherwise

6.178.3.10 Parse()

```
static NetworkObjectGuid Parse (
    string str ) [static]
```

Parse a [NetworkObjectGuid](#) from a string.

Parameters

<i>str</i>	The string to parse.
------------	----------------------

Returns

The parsed [NetworkObjectGuid](#).

6.178.3.11 ToString() [1/2]

```
override string ToString ( )
```

Returns a string representation of the [NetworkObjectGuid](#).

6.178.3.12 ToString() [2/2]

```
string ToString (
    string format )
```

Returns a string representation of the [NetworkObjectGuid](#).

6.178.3.13 ToUnityGuidString()

```
string ToUnityGuidString ( )
```

Returns a string representation of the [NetworkObjectGuid](#).

6.178.3.14 TryParse()

```
static bool TryParse (
    string str,
    out NetworkObjectGuid guid ) [static]
```

Try to parse a string into a [NetworkObjectGuid](#)

Parameters

<i>str</i>	String to parse
<i>guid</i>	Parsed NetworkObjectGuid

Returns

True if the string was parsed successfully, false otherwise

6.178.4 Member Data Documentation

6.178.4.1 ALIGNMENT

```
const int ALIGNMENT = 4 [static]
```

The alignment of the [NetworkObjectGuid](#)

6.178.4.2 RawGuidValue

```
fixed long RawGuidValue[2]
```

The Raw Guid Value of the [NetworkObjectGuid](#)

6.178.4.3 SIZE

```
const int SIZE = 16 [static]
```

The Size of the [NetworkObjectGuid](#) in bytes

6.178.5 Property Documentation

6.178.5.1 Empty

```
NetworkObjectGuid Empty [static], [get]
```

The default value of a [NetworkObjectGuid](#)

6.178.5.2 IsValid

```
bool IsValid [get]
```

Signal if the [NetworkObjectGuid](#) is valid.

6.179 NetworkObjectGuid.EqualityComparer Class Reference

[EqualityComparer](#) for [NetworkObjectGuid](#)

Inherits [IEqualityComparer< NetworkObjectGuid >](#).

Public Member Functions

- bool [Equals](#) ([NetworkObjectGuid](#) x, [NetworkObjectGuid](#) y)
Check if two [NetworkObjectGuid](#) are equals
- int [GetHashCode](#) ([NetworkObjectGuid](#) obj)
Get the hashcode for a [NetworkObjectGuid](#)

6.179.1 Detailed Description

[EqualityComparer](#) for [NetworkObjectGuid](#)

6.179.2 Member Function Documentation

6.179.2.1 Equals()

```
bool Equals (
    NetworkObjectGuid x,
    NetworkObjectGuid y )
```

Check if two [NetworkObjectGuid](#) are equals

6.179.2.2 GetHashCode()

```
int GetHashCode (
    NetworkObjectGuid obj )
```

Get the hashcode for a [NetworkObjectGuid](#)

6.180 NetworkObjectHeader Struct Reference

Network object header information for a [NetworkObject](#).

Inherits [INetworkStruct](#), and [IEquatable< NetworkObjectHeader >](#).

Public Member Functions

- bool [Equals](#) ([NetworkObjectHeader](#) other)
Checks if the current instance of [NetworkObjectHeader](#) is equal to another instance of the same type.
- override bool [Equals](#) (object obj)
Checks if the current instance of [NetworkObjectHeader](#) is equal to another object.
- override int [GetHashCode](#) ()
Generates a hash code for the current instance of [NetworkObjectHeader](#).
- override string [ToString](#) ()
The string representation of the [NetworkObjectHeader](#).

Static Public Member Functions

- static int * [GetBehaviourChangedTickArray](#) ([NetworkObjectHeader](#) *header)
Returns a pointer to the array of behaviour change ticks in a [NetworkObjectHeader](#).
- static int * [GetDataPointer](#) ([NetworkObjectHeader](#) *header)
Returns a pointer to the data of a [NetworkObjectHeader](#).
- static int [GetDataWordCount](#) ([NetworkObjectHeader](#) *header)
Returns the count of data words in a [NetworkObjectHeader](#).
- static [NetworkTRSPData](#) * [GetMainNetworkTRSPData](#) ([NetworkObjectHeader](#) *header)
Returns a pointer to the main network TRSP data of a [NetworkObjectHeader](#), if it exists.
- static bool [HasMainNetworkTRSP](#) ([NetworkObjectHeader](#) *header)
Checks if a [NetworkObjectHeader](#) has a main network TRSP.
- static bool [operator!=](#) ([NetworkObjectHeader](#) left, [NetworkObjectHeader](#) right)
Determines if two instances of [NetworkObjectHeader](#) are not equal.
- static bool [operator==](#) ([NetworkObjectHeader](#) left, [NetworkObjectHeader](#) right)
Determines if two instances of [NetworkObjectHeader](#) are equal.

Public Attributes

- fixed int [_reserved](#) [10]
Reserved space for future use.
- short [BehaviourCount](#)
The number of behaviours in the network object.
- [NetworkObjectHeaderFlags](#) [Flags](#)
The flags indicating various states or properties of the network object.
- [NetworkId](#) [Id](#)
The unique identifier of the network object.
- [PlayerRef](#) [InputAuthority](#)
The player reference who has input authority over the network object.
- [NetworkObjectNestingKey](#) [NestingKey](#)
The nesting key of the network object.
- [NetworkId](#) [NestingRoot](#)
The unique identifier of the root network object in the nesting hierarchy.
- [PlayerRef](#) [StateAuthority](#)
The player reference who has state authority over the network object.
- [NetworkObjectType](#) [Id](#) [Type](#)
The type identifier of the network object.
- short [WordCount](#)
The number of words in the network object header.

Static Public Attributes

- const int [PLAYER_DATA_WORD](#) = 36 / [Allocator.REPLICATE_WORD_SIZE](#)
The word index of the player data in the [NetworkObjectHeader](#).
- const int [SIZE](#) = 80
The size of the [NetworkObjectHeader](#) in bytes.
- const int [WORDS](#) = [SIZE](#) / [Allocator.REPLICATE_WORD_SIZE](#)
The size of the [NetworkObjectHeader](#) in words.

Properties

- int [ByteCount](#) [get]
how many bytes this headers object is

6.180.1 Detailed Description

Network object header information for a [NetworkObject](#).

6.180.2 Member Function Documentation

6.180.2.1 Equals() [1/2]

```
bool Equals (
    NetworkObjectHeader other )
```

Checks if the current instance of [NetworkObjectHeader](#) is equal to another instance of the same type.

6.180.2.2 Equals() [2/2]

```
override bool Equals (
    object obj )
```

Checks if the current instance of [NetworkObjectHeader](#) is equal to another object.

6.180.2.3 GetBehaviourChangedTickArray()

```
static int* GetBehaviourChangedTickArray (
    NetworkObjectHeader * header ) [static]
```

Returns a pointer to the array of behaviour change ticks in a [NetworkObjectHeader](#).

Parameters

<i>header</i>	Pointer to the NetworkObjectHeader .
---------------	--

Returns

Pointer to the array of behaviour change ticks in the [NetworkObjectHeader](#).

6.180.2.4 GetDataPointer()

```
static int* GetDataPointer (
    NetworkObjectHeader * header ) [static]
```

Returns a pointer to the data of a [NetworkObjectHeader](#).

Parameters

<i>header</i>	Pointer to the NetworkObjectHeader .
---------------	--

Returns

Pointer to the data of the [NetworkObjectHeader](#).

6.180.2.5 GetDataWordCount()

```
static int GetDataWordCount (
    NetworkObjectHeader * header ) [static]
```

Returns the count of data words in a [NetworkObjectHeader](#).

Parameters

<i>header</i>	Pointer to the NetworkObjectHeader .
---------------	--

Returns

The count of data words in the [NetworkObjectHeader](#).

6.180.2.6 GetHashCode()

```
override int GetHashCode ( )
```

Generates a hash code for the current instance of [NetworkObjectHeader](#).

6.180.2.7 GetMainNetworkTRSPData()

```
static NetworkTRSPData* GetMainNetworkTRSPData (
    NetworkObjectHeader * header ) [static]
```

Returns a pointer to the main network TRSP data of a [NetworkObjectHeader](#), if it exists.

Parameters

<i>header</i>	Pointer to the NetworkObjectHeader .
---------------	--

Returns

Pointer to the main network TRSP data of the [NetworkObjectHeader](#) if it exists, null otherwise.

6.180.2.8 HasMainNetworkTRSP()

```
static bool HasMainNetworkTRSP (
    NetworkObjectHeader * header ) [static]
```

Checks if a [NetworkObjectHeader](#) has a main network TRSP.

Parameters

<i>header</i>	Pointer to the NetworkObjectHeader .
---------------	--

Returns

True if the [NetworkObjectHeader](#) has a main network TRSP, false otherwise.

6.180.2.9 operator"!="()

```
static bool operator!= (
    NetworkObjectHeader left,
    NetworkObjectHeader right ) [static]
```

Determines if two instances of [NetworkObjectHeader](#) are not equal.

Returns

True if the instances are not equal; otherwise, false.

6.180.2.10 operator=="()

```
static bool operator== (
    NetworkObjectHeader left,
    NetworkObjectHeader right ) [static]
```

Determines if two instances of [NetworkObjectHeader](#) are equal.

Returns

True if the instances are equal; otherwise, false.

6.180.2.11 ToString()

```
override string ToString ( )
```

The string representation of the [NetworkObjectHeader](#).

6.180.3 Member Data Documentation

6.180.3.1 `_reserved`

```
fixed int _reserved[10]
```

Reserved space for future use.

6.180.3.2 `BehaviourCount`

```
short BehaviourCount
```

The number of behaviours in the network object.

6.180.3.3 `Flags`

```
NetworkObjectHeaderFlags Flags
```

The flags indicating various states or properties of the network object.

6.180.3.4 `Id`

```
NetworkId Id
```

The unique identifier of the network object.

6.180.3.5 `InputAuthority`

```
PlayerRef InputAuthority
```

The player reference who has input authority over the network object.

6.180.3.6 NestingKey

[NetworkObjectNestingKey](#) NestingKey

The nesting key of the network object.

6.180.3.7 NestingRoot

[NetworkId](#) NestingRoot

The unique identifier of the root network object in the nesting hierarchy.

6.180.3.8 PLAYER_DATA_WORD

```
const int PLAYER_DATA_WORD = 36 / Allocator.REPLICATE\_WORD\_SIZE [static]
```

The word index of the player data in the [NetworkObjectHeader](#).

6.180.3.9 SIZE

```
const int SIZE = 80 [static]
```

The size of the [NetworkObjectHeader](#) in bytes.

6.180.3.10 StateAuthority

[PlayerRef](#) StateAuthority

The player reference who has state authority over the network object.

6.180.3.11 Type

[NetworkObjectId](#) Type

The type identifier of the network object.

6.180.3.12 WordCount

```
short WordCount
```

The number of words in the network object header.

6.180.3.13 WORDS

```
const int WORDS = SIZE / Allocator.REPLICATE_WORD_SIZE [static]
```

The size of the [NetworkObjectHeader](#) in words.

6.180.4 Property Documentation

6.180.4.1 ByteCount

```
int ByteCount [get]
```

how many bytes this headers object is

6.181 NetworkObjectHeaderPtr Struct Reference

Represents a pointer to a [NetworkObjectHeader](#). This struct is unsafe because it uses pointers.

Public Attributes

- [NetworkObjectHeader](#) * [Ptr](#)
Pointer to a [NetworkObjectHeader](#).

Properties

- [NetworkId](#) [Id](#) [get]
Gets the Id of the [NetworkObjectHeader](#) this struct points to.
- [NetworkObjectType](#) [Id](#) [Type](#) [get]
Gets the Type of the [NetworkObjectHeader](#) this struct points to.

6.181.1 Detailed Description

Represents a pointer to a [NetworkObjectHeader](#). This struct is unsafe because it uses pointers.

6.181.2 Member Data Documentation

6.181.2.1 Ptr

`NetworkObjectHeader* Ptr`

Pointer to a [NetworkObjectHeader](#).

6.181.3 Property Documentation

6.181.3.1 Id

`NetworkId Id [get]`

Gets the Id of the [NetworkObjectHeader](#) this struct points to.

6.181.3.2 Type

`NetworkObjectId Type [get]`

Gets the Type of the [NetworkObjectHeader](#) this struct points to.

6.182 NetworkObjectInitializerUnity Class Reference

Initializes network objects for Unity.

Inherits [INetworkObjectInitializer](#).

Public Member Functions

- void [InitializeNetworkState](#) ([NetworkObject](#) networkObject)
Initializes the network object.

6.182.1 Detailed Description

Initializes network objects for Unity.

6.182.2 Member Function Documentation

6.182.2.1 InitializeNetworkState()

```
void InitializeNetworkState (  
    NetworkObject networkObject )
```

Initializes the network object.

Parameters

<code>networkObject</code>	The network object to initialize.
----------------------------	-----------------------------------

Implements [INetworkObjectInitializer](#).

6.183 NetworkObjectMeta Class Reference

Meta information about a network object.

Properties

- [NetworkId Id](#) [get]
Get the [NetworkId](#) of this object.
- [PlayerRef InputAuthority](#) [get]
Get the Player that has input authority over this object.
- [PlayerRef StateAuthority](#) [get]
Get the Player that has state authority over this object.
- [NetworkObjectTypeId Type](#) [get]
Get the [NetworkObjectTypeId](#) of this object.

6.183.1 Detailed Description

Meta information about a network object.

6.183.2 Property Documentation

6.183.2.1 Id

[NetworkId](#) Id [get]

Get the [NetworkId](#) of this object.

6.183.2.2 InputAuthority

[PlayerRef](#) InputAuthority [get]

Get the Player that has input authority over this object.

6.183.2.3 StateAuthority

`PlayerRef` StateAuthority [get]

Get the Player that has state authority over this object.

6.183.2.4 Type

`NetworkObjectId` Type [get]

Get the `NetworkObjectId` of this object.

6.184 NetworkObjectNestingKey Struct Reference

A key used to identify a network object nesting.

Inherits `INetworkStruct`, and `IEquatable< NetworkObjectNestingKey >`.

Classes

- class `EqualityComparer`
Implements the `IEqualityComparer` interface.

Public Member Functions

- bool `Equals` (`NetworkObjectNestingKey` other)
Checks if the current instance of `NetworkObjectNestingKey` is equal to another instance of the same type.
- override bool `Equals` (object obj)
Checks if the current instance of `NetworkObjectNestingKey` is equal to another object.
- override int `GetHashCode` ()
Serves as the default hash function.
- `NetworkObjectNestingKey` (int value)
Initializes a new instance of the `NetworkObjectNestingKey` struct with a specified value.
- override string `ToString` ()
Returns a string that represents the current object.

Public Attributes

- int `Value`
The value of the `NetworkObjectNestingKey`.

Static Public Attributes

- const int [ALIGNMENT](#) = 4
The alignment of the [NetworkObjectNestingKey](#) in bytes.
- const int [SIZE](#) = 4
The size of the [NetworkObjectNestingKey](#) in bytes.

Properties

- bool [IsNone](#) [get]
Checks if the [NetworkObjectNestingKey](#) is none.
- bool [IsValid](#) [get]
Checks if the [NetworkObjectNestingKey](#) is valid.

6.184.1 Detailed Description

A key used to identify a network object nesting.

6.184.2 Constructor & Destructor Documentation

6.184.2.1 NetworkObjectNestingKey()

```
NetworkObjectNestingKey (  
    int value )
```

Initializes a new instance of the [NetworkObjectNestingKey](#) struct with a specified value.

Parameters

<i>value</i>	The value of the NetworkObjectNestingKey .
--------------	--

6.184.3 Member Function Documentation

6.184.3.1 Equals() [1/2]

```
bool Equals (  
    NetworkObjectNestingKey other )
```

Checks if the current instance of [NetworkObjectNestingKey](#) is equal to another instance of the same type.

Parameters

<i>other</i>	An instance of NetworkObjectNestingKey to compare with the current instance.
--------------	--

Returns

True if the current instance is equal to the other parameter; otherwise, false.

6.184.3.2 Equals() [2/2]

```
override bool Equals (  
    object obj )
```

Checks if the current instance of [NetworkObjectNestingKey](#) is equal to another object.

Parameters

<i>obj</i>	An object to compare with the current instance.
------------	---

Returns

True if the current instance is equal to the obj parameter; otherwise, false.

6.184.3.3 GetHashCode()

```
override int GetHashCode ( )
```

Serves as the default hash function.

Returns

A hash code for the current object.

6.184.3.4 ToString()

```
override string ToString ( )
```

Returns a string that represents the current object.

Returns

A string that represents the current object.

6.184.4 Member Data Documentation

6.184.4.1 ALIGNMENT

```
const int ALIGNMENT = 4 [static]
```

The alignment of the [NetworkObjectNestingKey](#) in bytes.

6.184.4.2 SIZE

```
const int SIZE = 4 [static]
```

The size of the [NetworkObjectNestingKey](#) in bytes.

6.184.4.3 Value

```
int Value
```

The value of the [NetworkObjectNestingKey](#).

6.184.5 Property Documentation

6.184.5.1 IsNone

```
bool IsNone [get]
```

Checks if the [NetworkObjectNestingKey](#) is none.

Returns

True if the value of the [NetworkObjectNestingKey](#) is 0; otherwise, false.

6.184.5.2 IsValid

```
bool IsValid [get]
```

Checks if the [NetworkObjectNestingKey](#) is valid.

Returns

True if the value of the [NetworkObjectNestingKey](#) is greater than 0; otherwise, false.

6.185 NetworkObjectNestingKey.EqualityComparer Class Reference

Implements the [IEqualityComparer](#) interface.

Inherits [IEqualityComparer< NetworkObjectNestingKey >](#).

Public Member Functions

- [bool Equals](#) ([NetworkObjectNestingKey](#) x, [NetworkObjectNestingKey](#) y)
Determines whether two [NetworkObjectNestingKey](#) objects are equal.
- [int GetHashCode](#) ([NetworkObjectNestingKey](#) obj)
Returns a hash code for the specified [NetworkObjectNestingKey](#).

6.185.1 Detailed Description

Implements the [IEqualityComparer](#) interface.

6.185.2 Member Function Documentation

6.185.2.1 Equals()

```
bool Equals (  
    NetworkObjectNestingKey x,  
    NetworkObjectNestingKey y )
```

Determines whether two [NetworkObjectNestingKey](#) objects are equal.

6.185.2.2 GetHashCode()

```
int GetHashCode (  
    NetworkObjectNestingKey obj )
```

Returns a hash code for the specified [NetworkObjectNestingKey](#).

6.186 NetworkObjectPrefabData Class Reference

This class represents the data for a network object prefab.

Inherits [Behaviour](#).

Public Attributes

- [NetworkObjectGuid](#) Guid

The unique identifier for the network object.

Additional Inherited Members

6.186.1 Detailed Description

This class represents the data for a network object prefab.

6.186.2 Member Data Documentation

6.186.2.1 Guid

[NetworkObjectGuid](#) Guid

The unique identifier for the network object.

6.187 NetworkObjectProviderDummy Class Reference

A dummy implementation of the [INetworkObjectProvider](#) interface. This class is used for testing purposes and throws a NotImplementedException for all its methods.

Inherits [INetworkObjectProvider](#).

Public Member Functions

- [NetworkObjectAcquireResult](#) [AcquirePrefabInstance](#) ([NetworkRunner](#) runner, in [NetworkPrefabAcquireContext](#) context, out [NetworkObject](#) instance)
Acquires an instance of a prefab for a network object.
- void [ReleaseInstance](#) ([NetworkRunner](#) runner, in [NetworkObjectReleaseContext](#) context)
Releases an instance of a network object.

6.187.1 Detailed Description

A dummy implementation of the [INetworkObjectProvider](#) interface. This class is used for testing purposes and throws a `NotImplementedException` for all its methods.

6.188 NetworkObjectReleaseContext Struct Reference

Represents the context for releasing a network object. This struct is unsafe because it uses pointers.

Public Member Functions

- [NetworkObjectReleaseContext](#) ([NetworkObject](#) obj, [NetworkObjectId](#) typeId, bool isBeingDestroyed, bool isNested)
Initializes a new instance of the [NetworkObjectReleaseContext](#) struct with the specified parameters.
- override string [ToString](#) ()
Returns a string that represents the current object.

Public Attributes

- readonly bool [IsBeingDestroyed](#)
Indicates whether the network object is being destroyed.
- readonly bool [IsNestedObject](#)
Indicates whether the network object is a nested object.
- readonly [NetworkObject](#) Object
The network object to be released.
- readonly [NetworkObjectId](#) typeId
The type identifier of the network object.

6.188.1 Detailed Description

Represents the context for releasing a network object. This struct is unsafe because it uses pointers.

6.188.2 Constructor & Destructor Documentation

6.188.2.1 NetworkObjectReleaseContext()

```
NetworkObjectReleaseContext (
    NetworkObject obj,
    NetworkObjectId typeId,
    bool isBeingDestroyed,
    bool isNested )
```

Initializes a new instance of the [NetworkObjectReleaseContext](#) struct with the specified parameters.

Parameters

<i>obj</i>	The network object to be released.
<i>typeId</i>	The type identifier of the network object.
<i>isBeingDestroyed</i>	Indicates whether the network object is being destroyed.
<i>isNested</i>	Indicates whether the network object is a nested object.

6.188.3 Member Function Documentation

6.188.3.1 ToString()

```
override string ToString ( )
```

Returns a string that represents the current object.

Returns

A string that represents the current object.

6.188.4 Member Data Documentation

6.188.4.1 IsBeingDestroyed

```
readonly bool IsBeingDestroyed
```

Indicates whether the network object is being destroyed.

6.188.4.2 IsNestedObject

```
readonly bool IsNestedObject
```

Indicates whether the network object is a nested object.

6.188.4.3 Object

```
readonly NetworkObject Object
```

The network object to be released.

6.188.4.4 TypeId

readonly [NetworkObjectId](#) TypeId

The type identifier of the network object.

6.189 NetworkObjectSortKeyComparer Class Reference

This class is used to compare two [NetworkObject](#) instances based on their SortKey. It implements the IComparer interface.

Inherits IComparer< [NetworkObject](#) >.

Public Member Functions

- int [Compare](#) ([NetworkObject](#) x, [NetworkObject](#) y)
Compares two [NetworkObject](#) instances based on their SortKey.

Static Public Attributes

- static readonly [NetworkObjectSortKeyComparer](#) Instance = new [NetworkObjectSortKeyComparer](#)()
An instance of the [NetworkObjectSortKeyComparer](#) class.

6.189.1 Detailed Description

This class is used to compare two [NetworkObject](#) instances based on their SortKey. It implements the IComparer interface.

6.189.2 Member Function Documentation

6.189.2.1 Compare()

```
int Compare (  
    NetworkObject x,  
    NetworkObject y )
```

Compares two [NetworkObject](#) instances based on their SortKey.

Parameters

x	The first NetworkObject to compare.
y	The second NetworkObject to compare.

Returns

A signed integer that indicates the relative values of x and y.

6.189.3 Member Data Documentation**6.189.3.1 Instance**

```
readonly NetworkObjectSortKeyComparer Instance = new NetworkObjectSortKeyComparer() [static]
```

An instance of the [NetworkObjectSortKeyComparer](#) class.

6.190 NetworkObjectSpawnException Class Reference

Network Object Spawn Exception

Inherits Exception.

Public Member Functions

- [NetworkObjectSpawnException](#) ([NetworkSpawnStatus](#) status, [NetworkObjectTypeId?](#) id=null)
Network Object Spawn Exception Constructor

Properties

- override string [Message](#) [get]
Exception Message
- [NetworkSpawnStatus](#) [Status](#) [get]
Network Spawn Status
- [NetworkObjectTypeId?](#) [TypeId](#) [get]
Network Object Type Id

6.190.1 Detailed Description

Network Object Spawn Exception

6.190.2 Constructor & Destructor Documentation**6.190.2.1 NetworkObjectSpawnException()**

```
NetworkObjectSpawnException (
    NetworkSpawnStatus status,
    NetworkObjectTypeId? id = null )
```

Network Object Spawn Exception Constructor

Parameters

<i>status</i>	Network Spawn Status
<i>id</i>	Network Object Type Id

6.190.3 Property Documentation

6.190.3.1 Message

```
override string Message [get]
```

Exception Message

6.190.3.2 Status

```
NetworkSpawnStatus Status [get]
```

Network Spawn Status

6.190.3.3 Typeld

```
NetworkObjectId? typeId [get]
```

Network Object Type Id

6.191 NetworkObjectStats Class Reference

The [NetworkObjectStats](#) class provides statistics related to a network object. It includes bandwidth, updates, and player count within the area of interest.

Public Member Functions

- void [Reset](#) ()
Resets all the statistics of the network object to their default values.

Public Attributes

- OverTimeStatBuffer [AreaOfInterestPlayerCount](#)
Represents the count of players within the area of interest of the network object.
- OverTimeStatBuffer [InBandwidth](#)
Represents the inbound bandwidth of the network object.
- OverTimeStatBuffer [InUpdates](#)
Represents the inbound updates of the network object.
- OverTimeStatBuffer [OutBandwidth](#)
Represents the outbound bandwidth of the network object.
- OverTimeStatBuffer [OutUpdates](#)
Represents the outbound updates of the network object.

6.191.1 Detailed Description

The [NetworkObjectStats](#) class provides statistics related to a network object. It includes bandwidth, updates, and player count within the area of interest.

6.191.2 Member Function Documentation

6.191.2.1 Reset()

```
void Reset ( )
```

Resets all the statistics of the network object to their default values.

6.191.3 Member Data Documentation

6.191.3.1 AreaOfInterestPlayerCount

```
OverTimeStatBuffer AreaOfInterestPlayerCount
```

Represents the count of players within the area of interest of the network object.

6.191.3.2 InBandwidth

```
OverTimeStatBuffer InBandwidth
```

Represents the inbound bandwidth of the network object.

6.191.3.3 InUpdates

OverTimeStatBuffer InUpdates

Represents the inbound updates of the network object.

6.191.3.4 OutBandwidth

OverTimeStatBuffer OutBandwidth

Represents the outbound bandwidth of the network object.

6.191.3.5 OutUpdates

OverTimeStatBuffer OutUpdates

Represents the outbound updates of the network object.

6.192 NetworkObjectTypeId Struct Reference

ID for a [NetworkObject](#) Prefab which has been cataloged in a [NetworkProjectConfig.PrefabTable](#).

Inherits [INetworkStruct](#), and [IEquatable< NetworkObjectTypeId >](#).

Classes

- class [EqualityComparer](#)
[NetworkObjectTypeId](#) Comparer

Public Member Functions

- bool [Equals](#) ([NetworkObjectTypeId](#) other)
Checks if the current [NetworkObjectTypeId](#) instance is equal to another [NetworkObjectTypeId](#) instance.
- override bool [Equals](#) (object obj)
Determines whether the specified object is equal to the current [NetworkObjectTypeId](#) instance.
- override int [GetHashCode](#) ()
Generates a hash code for the current [NetworkObjectTypeId](#) instance.
- override string [ToString](#) ()
Returns a string that represents the current [NetworkObjectTypeId](#) instance.

Static Public Member Functions

- static [NetworkObjectTypeId FromCustom](#) (uint raw)
Creates a [NetworkObjectTypeId](#) from a raw uint value representing a Custom type.
- static [NetworkObjectTypeId FromPrefabId](#) ([NetworkPrefabId](#) prefabId)
Creates a [NetworkObjectTypeId](#) from a [NetworkPrefabId](#).
- static [NetworkObjectTypeId FromSceneRefAndObjectIndex](#) ([SceneRef](#) sceneRef, int objIndex, [NetworkSceneLoadId](#) loadId=default)
Creates a [NetworkObjectTypeId](#) from a [SceneRef](#), an object index, and an optional [NetworkSceneLoadId](#).
- static [NetworkObjectTypeId FromStruct](#) (ushort structId)
Creates a [NetworkObjectTypeId](#) from a ushort value representing an InternalStruct type.
- static implicit [operator NetworkObjectTypeId](#) ([NetworkPrefabId](#) prefabId)
Converts a [NetworkPrefabId](#) instance to a [NetworkObjectTypeId](#) instance.
- static bool [operator!=](#) ([NetworkObjectTypeId](#) a, [NetworkObjectTypeId](#) b)
Determines whether two [NetworkObjectTypeId](#) instances are not equal.
- static bool [operator==](#) ([NetworkObjectTypeId](#) a, [NetworkObjectTypeId](#) b)
Determines whether two [NetworkObjectTypeId](#) instances are equal.

Public Attributes

- uint [_value0](#)
Represents the first part of the value of a [NetworkObjectTypeId](#).
- uint [_value1](#)
Represents the second part of the value of a [NetworkObjectTypeId](#).

Static Public Attributes

- const int [ALIGNMENT](#) = 4
Represents the alignment of a [NetworkObjectTypeId](#) in memory.
- const int [MAX_SCENE_OBJECT_INDEX](#) = (1 << [SCENE_OBJECT_INDEX_BITS](#)) - 1
Represents the maximum number of SceneObjects that can be represented by a [NetworkObjectTypeId](#).
- const int [SIZE](#) = 8
Represents the size of a [NetworkObjectTypeId](#) in bytes.
- const ushort [STRUCT_TYPE_PLAYERDATA](#) = 1

Properties

- uint [AsCustom](#) [get]
Gets the raw uint value representation of the [NetworkObjectTypeId](#) assuming it is a Custom type.
- ushort [AsInternalStructId](#) [get]
Gets the ushort value representation of the [NetworkObjectTypeId](#) assuming it is an InternalStruct type.
- [NetworkPrefabId](#) [AsPrefabId](#) [get]
Gets the [NetworkPrefabId](#) representation of the [NetworkObjectTypeId](#) assuming it is a Prefab.
- [NetworkSceneObjectId](#) [AsSceneObjectId](#) [get]
Gets the [NetworkSceneObjectId](#) representation of the [NetworkObjectTypeId](#) assuming it is a SceneObject.
- static [EqualityComparer Comparer](#) = new [EqualityComparer](#)() [get]
An instance of the [NetworkObjectTypeId EqualityComparer](#) class.
- bool [IsCustom](#) [get]
Checks if the [NetworkObjectTypeId](#) is a Custom type.

- bool `IsNone` [get]
Checks if the `NetworkObjectTypeId` is invalid.
- bool `IsPrefab` [get]
Checks if the `NetworkObjectTypeId` is a Prefab.
- bool `IsSceneObject` [get]
Checks if the `NetworkObjectTypeId` is a SceneObject.
- bool `IsStruct` [get]
Checks if the `NetworkObjectTypeId` is an InternalStruct.
- bool `IsValid` [get]
Checks if the `NetworkObjectTypeId` is valid.
- `NetworkTypeIdKind Kind` [get]
Gets the kind of the `NetworkObjectTypeId`.
- static `NetworkObjectTypeId PlayerData` [get]
Represents a `NetworkObjectTypeId` for the PlayerData.

6.192.1 Detailed Description

ID for a `NetworkObject` Prefab which has been cataloged in a `NetworkProjectConfig.PrefabTable`.

6.192.2 Member Function Documentation

6.192.2.1 Equals() [1/2]

```
bool Equals (
    NetworkObjectId other )
```

Checks if the current `NetworkObjectTypeId` instance is equal to another `NetworkObjectTypeId` instance.

Parameters

<i>other</i>	The other <code>NetworkObjectTypeId</code> instance to compare with the current instance.
--------------	---

6.192.2.2 Equals() [2/2]

```
override bool Equals (
    object obj )
```

Determines whether the specified object is equal to the current `NetworkObjectTypeId` instance.

Parameters

<i>obj</i>	The object to compare with the current <code>NetworkObjectTypeId</code> instance.
------------	---

6.192.2.3 FromCustom()

```
static NetworkObjectId FromCustom (
    uint raw ) [static]
```

Creates a [NetworkObjectId](#) from a raw uint value representing a Custom type.

Parameters

<i>raw</i>	The raw uint value to use.
------------	----------------------------

Returns

A [NetworkObjectId](#) that represents a Custom type with the given raw value.

6.192.2.4 FromPrefabId()

```
static NetworkObjectId FromPrefabId (
    NetworkPrefabId prefabId ) [static]
```

Creates a [NetworkObjectId](#) from a [NetworkPrefabId](#).

Parameters

<i>prefabId</i>	The NetworkPrefabId to use.
-----------------	---

Returns

A [NetworkObjectId](#) that represents a Prefab with the given [NetworkPrefabId](#).

Exceptions

<i>ArgumentException</i>	Thrown when the provided NetworkPrefabId is not valid.
--------------------------	--

6.192.2.5 FromSceneRefAndObjectIndex()

```
static NetworkObjectId FromSceneRefAndObjectIndex (
    SceneRef sceneRef,
    int objIndex,
    NetworkSceneLoadId loadId = default ) [static]
```

Creates a [NetworkObjectId](#) from a [SceneRef](#), an object index, and an optional [NetworkSceneLoadId](#).

Parameters

<i>sceneRef</i>	The SceneRef to use.
<i>objIndex</i>	The object index to use.
<i>loadId</i>	The NetworkSceneLoadId to use. Defaults to default(NetworkSceneLoadId).

Returns

A [NetworkObjectTypeId](#) that represents a SceneObject with the given [SceneRef](#), object index, and [NetworkSceneLoadId](#).

Exceptions

<i>ArgumentException</i>	Thrown when the provided SceneRef is not valid.
<i>ArgumentOutOfRangeException</i>	Thrown when the provided object index is out of range.

6.192.2.6 FromStruct()

```
static NetworkObjectTypeId FromStruct (
    ushort structId ) [static]
```

Creates a [NetworkObjectTypeId](#) from a ushort value representing an InternalStruct type.

Parameters

<i>struct↔ Id</i>	The ushort value to use.
-----------------------	--------------------------

Returns

A [NetworkObjectTypeId](#) that represents an InternalStruct type with the given ushort value.

6.192.2.7 GetHashCode()

```
override int GetHashCode ( )
```

Generates a hash code for the current [NetworkObjectTypeId](#) instance.

6.192.2.8 operator NetworkObjectTypeId()

```
static implicit operator NetworkObjectTypeId (
    NetworkPrefabId prefabId ) [static]
```

Converts a [NetworkPrefabId](#) instance to a [NetworkObjectTypeId](#) instance.

Parameters

<i>prefab</i> ↔ <i>Id</i>	The NetworkPrefabId instance to convert.
------------------------------	--

Returns

A [NetworkObjectTypeId](#) instance that represents a Prefab with the given [NetworkPrefabId](#).

6.192.2.9 operator"!=()

```
static bool operator!= (
    NetworkObjectTypeId a,
    NetworkObjectTypeId b ) [static]
```

Determines whether two [NetworkObjectTypeId](#) instances are not equal.

6.192.2.10 operator==()

```
static bool operator== (
    NetworkObjectTypeId a,
    NetworkObjectTypeId b ) [static]
```

Determines whether two [NetworkObjectTypeId](#) instances are equal.

6.192.2.11 ToString()

```
override string ToString ( )
```

Returns a string that represents the current [NetworkObjectTypeId](#) instance.

6.192.3 Member Data Documentation**6.192.3.1 _value0**

```
uint _value0
```

Represents the first part of the value of a [NetworkObjectTypeId](#).

6.192.3.2 `_value1`

```
uint _value1
```

Represents the second part of the value of a [NetworkObjectTypeId](#).

6.192.3.3 ALIGNMENT

```
const int ALIGNMENT = 4 [static]
```

Represents the alignment of a [NetworkObjectTypeId](#) in memory.

6.192.3.4 MAX_SCENE_OBJECT_INDEX

```
const int MAX_SCENE_OBJECT_INDEX = (1 << SCENE_OBJECT_INDEX_BITS) - 1 [static]
```

Represents the maximum number of SceneObjects that can be represented by a [NetworkObjectTypeId](#).

6.192.3.5 SIZE

```
const int SIZE = 8 [static]
```

Represents the size of a [NetworkObjectTypeId](#) in bytes.

6.192.4 Property Documentation

6.192.4.1 AsCustom

```
uint AsCustom [get]
```

Gets the raw uint value representation of the [NetworkObjectTypeId](#) assuming it is a Custom type.

The raw uint value representation of the [NetworkObjectTypeId](#).

Exceptions

<i>InvalidOperationException</i>	Thrown when the NetworkObjectTypeId is not a Custom type.
----------------------------------	---

6.192.4.2 AsInternalStructId

```
ushort AsInternalStructId [get]
```

Gets the ushort value representation of the [NetworkObjectTypeId](#) assuming it is an InternalStruct type.

The ushort value representation of the [NetworkObjectTypeId](#).

Exceptions

<i>InvalidOperationException</i>	Thrown when the NetworkObjectTypeId is not an InternalStruct type.
----------------------------------	--

6.192.4.3 AsPrefabId

```
NetworkPrefabId AsPrefabId [get]
```

Gets the [NetworkPrefabId](#) representation of the [NetworkObjectTypeId](#) assuming it is a Prefab.

The [NetworkPrefabId](#) representation of the [NetworkObjectTypeId](#).

Exceptions

<i>InvalidOperationException</i>	Thrown when the NetworkObjectTypeId is not a Prefab.
----------------------------------	--

6.192.4.4 AsSceneObjectId

```
NetworkSceneObjectId AsSceneObjectId [get]
```

Gets the [NetworkSceneObjectId](#) representation of the [NetworkObjectTypeId](#) assuming it is a SceneObject.

The [NetworkSceneObjectId](#) representation of the [NetworkObjectTypeId](#).

Exceptions

<i>InvalidOperationException</i>	Thrown when the NetworkObjectTypeId is not a SceneObject.
----------------------------------	---

6.192.4.5 Comparer

```
EqualityComparer Comparer = new EqualityComparer() [static], [get]
```

An instance of the [NetworkObjectTypeId EqualityComparer](#) class.

6.192.4.6 IsCustom

```
bool IsCustom [get]
```

Checks if the [NetworkObjectTypeId](#) is a Custom type.

6.192.4.7 IsNone

```
bool IsNone [get]
```

Checks if the [NetworkObjectTypeId](#) is invalid.

6.192.4.8 IsPrefab

```
bool IsPrefab [get]
```

Checks if the [NetworkObjectTypeId](#) is a Prefab.

6.192.4.9 IsSceneObject

```
bool IsSceneObject [get]
```

Checks if the [NetworkObjectTypeId](#) is a SceneObject.

6.192.4.10 IsStruct

```
bool IsStruct [get]
```

Checks if the [NetworkObjectTypeId](#) is an InternalStruct.

6.192.4.11 IsValid

```
bool IsValid [get]
```

Checks if the [NetworkObjectTypeId](#) is valid.

6.192.4.12 Kind

`NetworkTypeIdKind Kind [get]`

Gets the kind of the [NetworkObjectTypeId](#).

6.192.4.13 PlayerData

`NetworkObjectTypeId PlayerData [static], [get]`

Represents a [NetworkObjectTypeId](#) for the PlayerData.

6.193 NetworkObjectTypeId.EqualityComparer Class Reference

[NetworkObjectTypeId](#) Comparer

Inherits `IEqualityComparer< NetworkObjectTypeId >`.

Public Member Functions

- `bool Equals (NetworkObjectTypeId x, NetworkObjectTypeId y)`
Checks if two [NetworkObjectTypeId](#) instances are equal.
- `int GetHashCode (NetworkObjectTypeId obj)`
Gets the hash code of a [NetworkObjectTypeId](#) instance.

6.193.1 Detailed Description

[NetworkObjectTypeId](#) Comparer

6.193.2 Member Function Documentation

6.193.2.1 Equals()

```
bool Equals (  
    NetworkObjectTypeId x,  
    NetworkObjectTypeId y )
```

Checks if two [NetworkObjectTypeId](#) instances are equal.

6.193.2.2 GetHashCode()

```
int GetHashCode (  
    NetworkObjectTypeId obj )
```

Gets the hash code of a [NetworkObjectTypeId](#) instance.

Parameters

<i>obj</i>	The NetworkObjectTyped instance.
------------	--

6.194 NetworkPhysicsInfo Struct Reference

Network Physics [INetworkStruct](#)

Inherits [INetworkStruct](#).

Public Attributes

- float [TimeScale](#)
NetworkPhysicsInfo Time Scale

Static Public Attributes

- const int [SIZE](#) = 40
NetworkPhysicsInfo Total Size
- const int [WORD_COUNT](#) = 10
NetworkPhysicsInfo Word Count

6.194.1 Detailed Description

Network Physics [INetworkStruct](#)

6.194.2 Member Data Documentation

6.194.2.1 SIZE

```
const int SIZE = 40 [static]
```

[NetworkPhysicsInfo](#) Total Size

6.194.2.2 TimeScale

```
float TimeScale
```

[NetworkPhysicsInfo](#) Time Scale

6.194.2.3 WORD_COUNT

```
const int WORD_COUNT = 10 [static]
```

[NetworkPhysicsInfo](#) Word Count

6.195 NetworkPrefabAcquireContext Struct Reference

Represents the context for acquiring a prefab instance for a network object. This struct is unsafe because it uses pointers.

Public Member Functions

- [NetworkPrefabAcquireContext](#) ([NetworkPrefabId](#) prefabId, [NetworkObjectMeta](#) meta=null, bool isSynchronous=true, bool dontDestroyOnLoad=false)

Initializes a new instance of the [NetworkPrefabAcquireContext](#) struct with the specified parameters.

Public Attributes

- readonly bool [DontDestroyOnLoad](#)
Indicates whether the network object should not be destroyed on load.
- readonly bool [IsSynchronous](#)
Indicates whether the operation is synchronous.
- readonly [NetworkObjectMeta](#) Meta
The metadata of the network object.
- readonly [NetworkPrefabId](#) PrefabId
The identifier of the prefab.

Properties

- int * [Data](#) [get]
Gets the data pointer to the first word of this [NetworkObject](#)'s data block.
- bool [HasHeader](#) [get]
Checks if the Header is not null.

6.195.1 Detailed Description

Represents the context for acquiring a prefab instance for a network object. This struct is unsafe because it uses pointers.

6.195.2 Constructor & Destructor Documentation

6.195.2.1 NetworkPrefabAcquireContext()

```
NetworkPrefabAcquireContext (
    NetworkPrefabId prefabId,
    NetworkObjectMeta meta = null,
    bool isSynchronous = true,
    bool dontDestroyOnLoad = false )
```

Initializes a new instance of the [NetworkPrefabAcquireContext](#) struct with the specified parameters.

Parameters

<i>prefabId</i>	The identifier of the prefab.
<i>meta</i>	The metadata of the network object.
<i>isSynchronous</i>	Indicates whether the operation is synchronous.
<i>dontDestroyOnLoad</i>	Indicates whether the network object should not be destroyed on load.

6.195.3 Member Data Documentation

6.195.3.1 DontDestroyOnLoad

```
readonly bool DontDestroyOnLoad
```

Indicates whether the network object should not be destroyed on load.

6.195.3.2 IsSynchronous

```
readonly bool IsSynchronous
```

Indicates whether the operation is synchronous.

6.195.3.3 Meta

```
readonly NetworkObjectMeta Meta
```

The metadata of the network object.

6.195.3.4 PrefabId

```
readonly NetworkPrefabId PrefabId
```

The identifier of the prefab.

6.195.4 Property Documentation

6.195.4.1 Data

```
int* Data [get]
```

Gets the data pointer to the first word of this [NetworkObject](#)'s data block.

Returns

Data pointer to the first word of this [NetworkObject](#)'s data block.

Exceptions

<i>InvalidOperationException</i>	Thrown when the Header is null.
----------------------------------	---------------------------------

6.195.4.2 HasHeader

```
bool HasHeader [get]
```

Checks if the Header is not null.

Returns

True if the Header is not null; otherwise, false.

6.196 NetworkPrefabAttribute Class Reference

Network Prefab Attribute

Inherits [PropertyAttribute](#).

6.196.1 Detailed Description

Network Prefab Attribute

6.197 NetworkPrefabId Struct Reference

ID for a [NetworkObject](#) Prefab which has been cataloged in a [NetworkProjectConfig.PrefabTable](#).

Inherits [INetworkStruct](#), [IEquatable< NetworkPrefabId >](#), [IComparable](#), and [IComparable< NetworkPrefabId >](#).

Classes

- class [EqualityComparer](#)
Equality comparer for [NetworkPrefabId](#).

Public Member Functions

- int [CompareTo](#) ([NetworkPrefabId](#) other)
Compares the [NetworkPrefabId](#) to another [NetworkPrefabId](#).
- int IComparable. [CompareTo](#) (object obj)
Compares the [NetworkPrefabId](#) to another object.
- bool [Equals](#) ([NetworkPrefabId](#) other)
Checks if the [NetworkPrefabId](#) is equal to another [NetworkPrefabId](#).
- override bool [Equals](#) (object obj)
Checks if the [NetworkPrefabId](#) is equal to another object.
- override int [GetHashCode](#) ()
Gets the hash code of the [NetworkPrefabId](#).
- override string [ToString](#) ()
Converts the [NetworkPrefabId](#) to a string.
- string [ToString](#) (bool brackets, bool prefix)
Converts the [NetworkPrefabId](#) to a string with optional brackets and prefix.

Static Public Member Functions

- static [NetworkPrefabId FromIndex](#) (int index)
Creates a [NetworkPrefabId](#) from an index.
- static [NetworkPrefabId FromRaw](#) (uint value)
Creates a [NetworkPrefabId](#) from a raw value.
- static bool [operator!=](#) ([NetworkPrefabId](#) a, [NetworkPrefabId](#) b)
Checks if two [NetworkPrefabId](#) are not equal.
- static bool [operator==](#) ([NetworkPrefabId](#) a, [NetworkPrefabId](#) b)
Checks if two [NetworkPrefabId](#) are equal.

Public Attributes

- uint [RawValue](#)
The raw value of the [NetworkPrefabId](#).

Static Public Attributes

- const int [ALIGNMENT](#) = 4
The alignment of a [NetworkPrefabId](#).
- const int [MAX_INDEX](#) = int.MaxValue - 1
The maximum index value of a [NetworkPrefabId](#).
- const int [SIZE](#) = 4
The size of a [NetworkPrefabId](#).

Properties

- int [AsIndex](#) [get]
Converts the [NetworkPrefabId](#) to an index.
- bool [IsNone](#) [get]
Checks if the [NetworkPrefabId](#) is none.
- bool [IsValid](#) [get]
Checks if the [NetworkPrefabId](#) is valid.

6.197.1 Detailed Description

ID for a [NetworkObject](#) Prefab which has been cataloged in a [NetworkProjectConfig.PrefabTable](#).

6.197.2 Member Function Documentation

6.197.2.1 CompareTo() [1/2]

```
int CompareTo (  
    NetworkPrefabId other )
```

Compares the [NetworkPrefabId](#) to another [NetworkPrefabId](#).

6.197.2.2 CompareTo() [2/2]

```
int IComparable. CompareTo (  
    object obj )
```

Compares the [NetworkPrefabId](#) to another object.

6.197.2.3 Equals() [1/2]

```
bool Equals (  
    NetworkPrefabId other )
```

Checks if the [NetworkPrefabId](#) is equal to another [NetworkPrefabId](#).

6.197.2.4 Equals() [2/2]

```
override bool Equals (  
    object obj )
```

Checks if the [NetworkPrefabId](#) is equal to another object.

6.197.2.5 FromIndex()

```
static NetworkPrefabId FromIndex (
    int index ) [static]
```

Creates a [NetworkPrefabId](#) from an index.

6.197.2.6 FromRaw()

```
static NetworkPrefabId FromRaw (
    uint value ) [static]
```

Creates a [NetworkPrefabId](#) from a raw value.

6.197.2.7 GetHashCode()

```
override int GetHashCode ( )
```

Gets the hash code of the [NetworkPrefabId](#).

6.197.2.8 operator"!="()

```
static bool operator!= (
    NetworkPrefabId a,
    NetworkPrefabId b ) [static]
```

Checks if two [NetworkPrefabId](#) are not equal.

6.197.2.9 operator==()

```
static bool operator== (
    NetworkPrefabId a,
    NetworkPrefabId b ) [static]
```

Checks if two [NetworkPrefabId](#) are equal.

6.197.2.10 ToString() [1/2]

```
override string ToString ( )
```

Converts the [NetworkPrefabId](#) to a string.

6.197.2.11 ToString() [2/2]

```
string ToString (
    bool brackets,
    bool prefix )
```

Converts the [NetworkPrefabId](#) to a string with optional brackets and prefix.

6.197.3 Member Data Documentation**6.197.3.1 ALIGNMENT**

```
const int ALIGNMENT = 4 [static]
```

The alignment of a [NetworkPrefabId](#).

6.197.3.2 MAX_INDEX

```
const int MAX_INDEX = int.MaxValue - 1 [static]
```

The maximum index value of a [NetworkPrefabId](#).

6.197.3.3 RawValue

```
uint RawValue
```

The raw value of the [NetworkPrefabId](#).

6.197.3.4 SIZE

```
const int SIZE = 4 [static]
```

The size of a [NetworkPrefabId](#).

6.197.4 Property Documentation

6.197.4.1 AsIndex

```
int AsIndex [get]
```

Converts the [NetworkPrefabld](#) to an index.

6.197.4.2 IsNone

```
bool IsNone [get]
```

Checks if the [NetworkPrefabld](#) is none.

6.197.4.3 IsValid

```
bool IsValid [get]
```

Checks if the [NetworkPrefabld](#) is valid.

6.198 NetworkPrefabld.EqualityComparer Class Reference

Equality comparer for [NetworkPrefabld](#).

Inherits `IEqualityComparer< NetworkPrefabld >`.

Public Member Functions

- bool [Equals](#) ([NetworkPrefabld](#) x, [NetworkPrefabld](#) y)
Checks if two [NetworkPrefabld](#) are equal.
- int [GetHashCode](#) ([NetworkPrefabld](#) obj)
Gets the hash code of a [NetworkPrefabld](#).

6.198.1 Detailed Description

Equality comparer for [NetworkPrefabld](#).

6.198.2 Member Function Documentation

6.198.2.1 Equals()

```
bool Equals (
    NetworkPrefabId x,
    NetworkPrefabId y )
```

Checks if two [NetworkPrefabId](#) are equal.

6.198.2.2 GetHashCode()

```
int GetHashCode (
    NetworkPrefabId obj )
```

Gets the hash code of a [NetworkPrefabId](#).

6.199 NetworkPrefabInfo Struct Reference

Meta data for a [NetworkObject](#) prefab which has been cataloged in a [NetworkProjectConfig.PrefabTable](#).

Public Attributes

- readonly [NetworkObjectHeader](#) * [Header](#)
Header data for the [NetworkObject](#) prefab.
- readonly bool [IsSynchronous](#)
Is the prefab supposed to be loaded in a synchronous way. [Fusion](#) will report an error if this field is set to true and no prefab is returned by [INetworkObjectProvider](#).
- readonly [NetworkPrefabId](#) [Prefab](#)
Prefab ID. Use [NetworkPrefabTable.TryAddSource](#) to look up the actual prefab reference in the [NetworkProjectConfig.PrefabTable](#).

Properties

- int * [Data](#) [get]
Data pointer to the first word of this [NetworkObject](#)'s data block.
- bool [HasHeader](#) [get]
If the Header is not null.

6.199.1 Detailed Description

Meta data for a [NetworkObject](#) prefab which has been cataloged in a [NetworkProjectConfig.PrefabTable](#).

6.199.2 Member Data Documentation

6.199.2.1 Header

readonly [NetworkObjectHeader*](#) Header

Header data for the [NetworkObject](#) prefab.

6.199.2.2 IsSynchronous

readonly bool IsSynchronous

Is the prefab supposed to be loaded in a synchronous way. [Fusion](#) will report an error if this field is set to true and no prefab is returned by [INetworkObjectProvider](#).

6.199.2.3 Prefab

readonly [NetworkPrefabId](#) Prefab

Prefab ID. Use [NetworkPrefabTable.TryAddSource](#) to look up the actual prefab reference in the [NetworkProjectConfig.PrefabTable](#).

6.199.3 Property Documentation

6.199.3.1 Data

int* Data [get]

Data pointer to the first word of this [NetworkObject](#)'s data block.

6.199.3.2 HasHeader

bool HasHeader [get]

If the Header is not null.

6.200 NetworkPrefabRef Struct Reference

NetworkPrefabRef

Inherits [INetworkStruct](#), [IEquatable< NetworkPrefabRef >](#), and [IComparable< NetworkPrefabRef >](#).

Classes

- class [EqualityComparer](#)
EqualityComparer for NetworkPrefabRef

Public Member Functions

- int [CompareTo](#) ([NetworkPrefabRef](#) other)
Compare the NetworkPrefabRef to another NetworkPrefabRef
- bool [Equals](#) ([NetworkPrefabRef](#) other)
Check if the NetworkPrefabRef is equal to another NetworkPrefabRef
- override bool [Equals](#) (object obj)
Check if the NetworkPrefabRef is equal to another object
- override int [GetHashCode](#) ()
Get the hashcode for a NetworkPrefabRef
- [NetworkPrefabRef](#) (byte *guid)
*Create a NetworkPrefabRef from a byte**
- [NetworkPrefabRef](#) (byte[] guid)
Create a NetworkPrefabRef from a byte array
- [NetworkPrefabRef](#) (long data0, long data1)
Create a new NetworkPrefabRef
- [NetworkPrefabRef](#) (string guid)
Create a new NetworkPrefabRef
- override string [ToString](#) ()
Returns a string representation of the NetworkPrefabRef.
- string [ToString](#) (string format)
Returns a string representation of the NetworkPrefabRef.
- string [ToUnityGuidString](#) ()
Returns a string representation of the NetworkPrefabRef.

Static Public Member Functions

- static implicit [operator Guid](#) ([NetworkPrefabRef](#) guid)
Implicit conversion from NetworkPrefabRef to Guid
- static [operator NetworkObjectGuid](#) ([NetworkPrefabRef](#) t)
Explicit conversion from NetworkPrefabRef to NetworkObjectGuid
- static implicit [operator NetworkPrefabRef](#) ([Guid](#) guid)
Implicit conversion from Guid to NetworkPrefabRef
- static bool [operator!=](#) ([NetworkPrefabRef](#) a, [NetworkPrefabRef](#) b)
Compare two NetworkPrefabRef
- static bool [operator==](#) ([NetworkPrefabRef](#) a, [NetworkPrefabRef](#) b)
Compare two NetworkPrefabRef
- static [NetworkPrefabRef](#) [Parse](#) (string str)
Parse a NetworkPrefabRef from a string.
- static bool [TryParse](#) (string str, out [NetworkPrefabRef](#) guid)
Try to parse a string into a NetworkPrefabRef

Public Attributes

- fixed long [RawGuidValue](#) [2]

The Raw Guid Value of the [NetworkPrefabRef](#)

Static Public Attributes

- const int [ALIGNMENT](#) = 4

The alignment of the [NetworkPrefabRef](#)

- const int [SIZE](#) = 16

The Size of the [NetworkPrefabRef](#) in bytes

Properties

- static [NetworkPrefabRef Empty](#) [get]

The default value of a [NetworkPrefabRef](#)

- bool [IsValid](#) [get]

Signal if the [NetworkPrefabRef](#) is valid.

6.200.1 Detailed Description

[NetworkPrefabRef](#)

A decoupled [NetworkObject](#) prefab reference. Internally stored as a GUID.

6.200.2 Constructor & Destructor Documentation

6.200.2.1 [NetworkPrefabRef\(\)](#) [1/4]

```
NetworkPrefabRef (
    string guid )
```

Create a new [NetworkPrefabRef](#)

Parameters

<i>guid</i>	The guid to use
-------------	-----------------

6.200.2.2 [NetworkPrefabRef\(\)](#) [2/4]

```
NetworkPrefabRef (
```

```

    long data0,
    long data1 )

```

Create a new [NetworkPrefabRef](#)

Parameters

<i>data0</i>	Data0 of the Guid
<i>data1</i>	Data1 of the Guid

6.200.2.3 NetworkPrefabRef() [3/4]

```

NetworkPrefabRef (
    byte[] guid )

```

Create a [NetworkPrefabRef](#) from a byte array

Parameters

<i>guid</i>	The byte array to create the NetworkPrefabRef from
-------------	--

6.200.2.4 NetworkPrefabRef() [4/4]

```

NetworkPrefabRef (
    byte * guid )

```

Create a [NetworkPrefabRef](#) from a byte*

Parameters

<i>guid</i>	The byte* to create the NetworkPrefabRef from
-------------	---

6.200.3 Member Function Documentation

6.200.3.1 CompareTo()

```

int CompareTo (
    NetworkPrefabRef other )

```

Compare the [NetworkPrefabRef](#) to another [NetworkPrefabRef](#)

Parameters

<i>other</i>	The other NetworkPrefabRef to compare against
--------------	---

Returns

0 if the [NetworkPrefabRef](#) are equal, -1 if this [NetworkPrefabRef](#) is less than the other, 1 if this [NetworkPrefabRef](#) is greater than the other

6.200.3.2 Equals() [1/2]

```
bool Equals (
    NetworkPrefabRef other )
```

Check if the [NetworkPrefabRef](#) is equal to another [NetworkPrefabRef](#)

Parameters

<i>other</i>	The other NetworkPrefabRef to check against
--------------	---

Returns

True if the NetworkPrefabRefs are equal, false otherwise

6.200.3.3 Equals() [2/2]

```
override bool Equals (
    object obj )
```

Check if the [NetworkPrefabRef](#) is equal to another object

Parameters

<i>obj</i>	The other object to check against
------------	-----------------------------------

Returns

True if the objects are equal, false otherwise

6.200.3.4 GetHashCode()

```
override int GetHashCode ( )
```

Get the hashcode for a [NetworkPrefabRef](#)

6.200.3.5 operator Guid()

```
static implicit operator Guid (  
    NetworkPrefabRef guid ) [static]
```

Implicit conversion from [NetworkPrefabRef](#) to Guid

Parameters

<i>guid</i>	NetworkPrefabRef to convert from
-------------	--

Returns

Guid

6.200.3.6 operator NetworkObjectGuid()

```
static operator NetworkObjectGuid (  
    NetworkPrefabRef t ) [explicit], [static]
```

Explicit conversion from [NetworkPrefabRef](#) to [NetworkObjectGuid](#)

Parameters

<i>t</i>	NetworkPrefabRef to convert from
----------	--

Returns

[NetworkObjectGuid](#)

6.200.3.7 operator NetworkPrefabRef()

```
static implicit operator NetworkPrefabRef (  
    Guid guid ) [static]
```

Implicit conversion from Guid to [NetworkPrefabRef](#)

Parameters

<i>guid</i>	Guid to convert from
-------------	----------------------

Returns

[NetworkPrefabRef](#)

6.200.3.8 operator"!=()

```
static bool operator!= (
    NetworkPrefabRef a,
    NetworkPrefabRef b ) [static]
```

Compare two [NetworkPrefabRef](#)

Returns

True if the [NetworkPrefabRef](#) are not equal, false otherwise

6.200.3.9 operator=="()

```
static bool operator== (
    NetworkPrefabRef a,
    NetworkPrefabRef b ) [static]
```

Compare two [NetworkPrefabRef](#)

Returns

True if the [NetworkPrefabRef](#) are equal, false otherwise

6.200.3.10 Parse()

```
static NetworkPrefabRef Parse (
    string str ) [static]
```

Parse a [NetworkPrefabRef](#) from a string.

Parameters

<i>str</i>	The string to parse.
------------	----------------------

Returns

The parsed [NetworkPrefabRef](#).

6.200.3.11 ToString() [1/2]

```
override string ToString ( )
```

Returns a string representation of the [NetworkPrefabRef](#).

6.200.3.12 ToString() [2/2]

```
string ToString (
    string format )
```

Returns a string representation of the [NetworkPrefabRef](#).

6.200.3.13 ToUnityGuidString()

```
string ToUnityGuidString ( )
```

Returns a string representation of the [NetworkPrefabRef](#).

6.200.3.14 TryParse()

```
static bool TryParse (
    string str,
    out NetworkPrefabRef guid ) [static]
```

Try to parse a string into a [NetworkPrefabRef](#)

Parameters

<i>str</i>	String to parse
<i>guid</i>	Parsed NetworkPrefabRef

Returns

True if the string was parsed successfully, false otherwise

6.200.4 Member Data Documentation

6.200.4.1 ALIGNMENT

```
const int ALIGNMENT = 4 [static]
```

The alignment of the [NetworkPrefabRef](#)

6.200.4.2 RawGuidValue

```
fixed long RawGuidValue[2]
```

The Raw Guid Value of the [NetworkPrefabRef](#)

6.200.4.3 SIZE

```
const int SIZE = 16 [static]
```

The Size of the [NetworkPrefabRef](#) in bytes

6.200.5 Property Documentation

6.200.5.1 Empty

```
NetworkPrefabRef Empty [static], [get]
```

The default value of a [NetworkPrefabRef](#)

6.200.5.2 IsValid

```
bool IsValid [get]
```

Signal if the [NetworkPrefabRef](#) is valid.

6.201 NetworkPrefabRef.EqualityComparer Class Reference

[EqualityComparer](#) for [NetworkPrefabRef](#)

Inherits [IEqualityComparer](#)< [NetworkPrefabRef](#) >.

Public Member Functions

- bool [Equals](#) ([NetworkPrefabRef](#) x, [NetworkPrefabRef](#) y)
Check if two [NetworkPrefabRef](#) are equals
- int [GetHashCode](#) ([NetworkPrefabRef](#) obj)
Get the hashcode for a [NetworkPrefabRef](#)

6.201.1 Detailed Description

[EqualityComparer](#) for [NetworkPrefabRef](#)

6.201.2 Member Function Documentation

6.201.2.1 Equals()

```
bool Equals (  
    NetworkPrefabRef x,  
    NetworkPrefabRef y )
```

Check if two [NetworkPrefabRef](#) are equals

6.201.2.2 GetHashCode()

```
int GetHashCode (  
    NetworkPrefabRef obj )
```

Get the hashcode for a [NetworkPrefabRef](#)

6.202 NetworkPrefabTable Class Reference

Class representing a table of network prefabs.

Public Member Functions

- int [AddInstance](#) ([NetworkPrefabId](#) prefabId)
Add an instance of a prefab id.
- void [AddSource](#) ([INetworkPrefabSource](#) source)
Adds a prefab source to the table.
- void [Clear](#) ()
Clear the prefab table.
- bool [Contains](#) ([NetworkPrefabId](#) prefabId)
Returns true if the prefab table contains a prefab with the given id.
- [IEnumerable](#)<([NetworkPrefabId](#), [INetworkPrefabSource](#))> [GetEntries](#) ()
Returns all entries in the table.
- [NetworkObjectGuid](#) [GetGuid](#) ([NetworkPrefabId](#) prefabId)
Gets a prefab guid by id.
- [NetworkPrefabId](#) [GetId](#) ([NetworkObjectGuid](#) guid)
Gets a prefab id by guid.
- int [GetInstanceCount](#) ([NetworkPrefabId](#) prefabId)
Get the instance count of a prefab id.
- [INetworkPrefabSource](#) [GetSource](#) ([NetworkObjectGuid](#) guid)
Gets a prefab source by guid.
- [INetworkPrefabSource](#) [GetSource](#) ([NetworkPrefabId](#) prefabId)
Gets a prefab source by id.
- bool [IsAcquired](#) ([NetworkPrefabId](#) prefabId)
Signal if a prefab id has been acquired.
- [NetworkObject](#) [Load](#) ([NetworkPrefabId](#) prefabId, bool isSynchronous)
Load a prefab by id.
- int [RemoveInstance](#) ([NetworkPrefabId](#) prefabId)
Remove an instance of a prefab id.
- bool [TryAddSource](#) ([INetworkPrefabSource](#) source, out [NetworkPrefabId](#) id)
Tries to add a prefab source to the table.
- bool [Unload](#) ([NetworkPrefabId](#) prefabId)
Unload a prefab by id.
- void [UnloadAll](#) ()
Unload all prefabs.
- int [UnloadUnreferenced](#) (bool includeIncompleteLoads=false)
Unload all unreferenced prefabs.

Public Attributes

- [NetworkPrefabTableOptions](#) [Options](#) = [NetworkPrefabTableOptions.Default](#)
Options for the [NetworkPrefabTable](#).

Properties

- [IReadOnlyList](#)< [INetworkPrefabSource](#) > [Prefabs](#) [get]
All prefab sources.
- int [Version](#) [get]
Prefab table version. Incremented every time a change occurs.

6.202.1 Detailed Description

Class representing a table of network prefabs.

6.202.2 Member Function Documentation

6.202.2.1 AddInstance()

```
int AddInstance (
    NetworkPrefabId prefabId )
```

Add an instance of a prefab id.

Parameters

<i>prefabId</i>	Id of the prefab.
-----------------	-------------------

Returns

The new instance count, or 0 if not found.

6.202.2.2 AddSource()

```
void AddSource (
    INetworkPrefabSource source )
```

Adds a prefab source to the table.

Parameters

<i>source</i>	Prefab source to add.
---------------	-----------------------

Exceptions

<i>ArgumentException</i>	Thrown if a prefab source with the same guid already exists.
--------------------------	--

6.202.2.3 Clear()

```
void Clear ( )
```

Clear the prefab table.

6.202.2.4 Contains()

```
bool Contains (
    NetworkPrefabId prefabId )
```

Returns true if the prefab table contains a prefab with the given id.

Parameters

<i>prefab</i> ↔ <i>Id</i>	Id of the prefab.
------------------------------	-------------------

Returns

True if the prefab table contains a prefab with the given id.

6.202.2.5 GetEntries()

```
IEnumerable<(NetworkPrefabId, INetworkPrefabSource)> GetEntries ( )
```

Returns all entries in the table.

6.202.2.6 GetGuid()

```
NetworkObjectGuid GetGuid (
    NetworkPrefabId prefabId )
```

Gets a prefab guid by id.

Parameters

<i>prefab</i> ↔ <i>Id</i>	Id of the prefab source.
------------------------------	--------------------------

Returns

The prefab guid, or default if not found.

6.202.2.7 GetId()

```
NetworkPrefabId GetId (
    NetworkObjectGuid guid )
```

Gets a prefab id by guid.

Parameters

<i>guid</i>	Guid of the prefab source.
-------------	----------------------------

Returns

The prefab id, or default if not found.

6.202.2.8 GetInstancesCount()

```
int GetInstancesCount (
    NetworkPrefabId prefabId )
```

Get the instance count of a prefab id.

Parameters

<i>prefabId</i>	Id of the prefab.
-----------------	-------------------

Returns

The instance count, or 0 if not found.

6.202.2.9 GetSource() [1/2]

```
INetworkPrefabSource GetSource (
    NetworkObjectGuid guid )
```

Gets a prefab source by guid.

Parameters

<i>guid</i>	Guid of the prefab source.
-------------	----------------------------

Returns

The prefab source, or default if not found.

6.202.2.10 GetSource() [2/2]

```
INetworkPrefabSource GetSource (
    NetworkPrefabId prefabId )
```

Gets a prefab source by id.

Parameters

<i>prefab↔ Id</i>	Id of the prefab source.
-----------------------	--------------------------

Returns

The prefab source, or default if not found.

6.202.2.11 IsAcquired()

```
bool IsAcquired (
    NetworkPrefabId prefabId )
```

Signal if a prefab id has been acquired.

Parameters

<i>prefab↔ Id</i>	Id of the prefab.
-----------------------	-------------------

Returns

True if the prefab id has been acquired.

6.202.2.12 Load()

```
NetworkObject Load (
    NetworkPrefabId prefabId,
    bool isSynchronous )
```

Load a prefab by id.

Parameters

<i>prefabId</i>	Id of the prefab.
<i>isSynchronous</i>	If true, the load will be synchronous.

Returns

The loaded prefab, or null if not found.

6.202.2.13 RemoveInstance()

```
int RemoveInstance (
    NetworkPrefabId prefabId )
```

Remove an instance of a prefab id.

Parameters

<i>prefabId</i>	Id of the prefab.
-----------------	-------------------

Returns

The new instance count, or 0 if not found.

6.202.2.14 TryAddSource()

```
bool TryAddSource (
    INetworkPrefabSource source,
    out NetworkPrefabId id )
```

Tries to add a prefab source to the table.

Parameters

<i>source</i>	Prefab source to add.
<i>id</i>	Id of the prefab source.

Returns

True if the prefab source was added, false otherwise.

Exceptions

<i>ArgumentNullException</i>	Thrown if <i>source</i> is null.
------------------------------	----------------------------------

6.202.2.15 Unload()

```
bool Unload (
    NetworkPrefabId prefabId )
```

Unload a prefab by id.

Parameters

<i>prefabId</i>	Id of the prefab.
-----------------	-------------------

Returns

True if the prefab was unloaded, false otherwise.

6.202.2.16 UnloadAll()

```
void UnloadAll ( )
```

Unload all prefabs.

6.202.2.17 UnloadUnreferenced()

```
int UnloadUnreferenced (
    bool includeIncompleteLoads = false )
```

Unload all unreferenced prefabs.

Parameters

<i>includeIncompleteLoads</i>	If true, incomplete loads will be unloaded as well.
-------------------------------	---

Returns

The number of prefabs unloaded.

6.202.3 Member Data Documentation

6.202.3.1 Options

```
NetworkPrefabTableOptions Options = NetworkPrefabTableOptions.Default
```

Options for the [NetworkPrefabTable](#).

6.202.4 Property Documentation

6.202.4.1 Prefabs

```
ReadOnlyList<INetworkPrefabSource> Prefabs [get]
```

All prefab sources.

6.202.4.2 Version

```
int Version [get]
```

Prefab table version. Incremented every time a change occurs.

6.203 NetworkPrefabTableOptions Struct Reference

Options for the [NetworkPrefabTable](#).

Public Attributes

- bool [UnloadPrefabOnReleasingLastInstance](#)
If true, prefabs will be unloaded when the last instance is released.
- bool [UnloadUnusedPrefabsOnShutdown](#)
If true, all prefabs will be unloaded on shutdown.

Static Public Attributes

- static [NetworkPrefabTableOptions Default](#)
Default options.

6.203.1 Detailed Description

Options for the [NetworkPrefabTable](#).

6.203.2 Member Data Documentation

6.203.2.1 Default

[NetworkPrefabTableOptions](#) Default [static]

Initial value:

```
= new NetworkPrefabTableOptions() {  
    UnloadPrefabOnReleasingLastInstance = false,  
    UnloadUnusedPrefabsOnShutdown = true,  
}
```

Default options.

6.203.2.2 UnloadPrefabOnReleasingLastInstance

bool UnloadPrefabOnReleasingLastInstance

If true, prefabs will be unloaded when the last instance is released.

6.203.2.3 UnloadUnusedPrefabsOnShutdown

bool UnloadUnusedPrefabsOnShutdown

If true, all prefabs will be unloaded on shutdown.

6.204 NetworkProjectConfig Class Reference

The core [Fusion](#) config file that is shared with all peers at startup.

Public Types

- enum class [PeerModes](#)

Options for running one or multiple peers in one Unity instance. Multiple is useful for testing multiple players/clients inside of the Unity editor without needing to build executables. Each peer is assigned its own independent physics scene and [NetworkRunner](#) instance.

- enum class [ReplicationFeatures](#)

Public Member Functions

- `int? GetExecutionOrder (Type type)`
Get the execution order for a given type. If the type is registered, returns null.
- `override string ToString ()`
ToString() implementation.

Static Public Member Functions

- `static NetworkProjectConfig Deserialize (string data)`
De-serialize a [NetworkProjectConfig](#) from a JSON string (typically sent by the Room's Creator).
- `static string Serialize (NetworkProjectConfig config)`
Serialize a [NetworkProjectConfig](#) into a JSON string.
- `static void UnloadGlobal ()`
Unloads [Global](#), if already loaded. If loading [Global](#) has faulted, resets the state and next call to the [Global](#) accessor will attempt to load the config again.

Public Attributes

- `string[] AssembliesToWeave`
Names of assemblies [Fusion](#) is going to weave. Not case sensitive.
- `bool CheckNetworkedPropertiesBeingEmpty = false`
If set, the weaver will check if [NetworkedAttribute](#) properties getters and setters are empty.
- `bool CheckRpcAttributeUsage = false`
If set, the weaver will check if [RpcAttribute](#) is used in types that do not support it. This requires all types to be scanned and can increase weaving duration.
- `bool EnqueueIncompleteSynchronousSpawns`
This flag changes the behaviour of [NetworkRunner.Spawn<T>](#) to return null (instead of throwing an exception) and [NetworkRunner.TrySpawn<T>](#) to return [NetworkSpawnStatus.Queued](#) if [Fusion](#) was unable to load a prefab synchronously (e.g. because it was [Addressable](#)). [Fusion](#) will enqueue the spawn and attempt to perform it the next frame, until successful. Useful for transition from [Fusion](#) 1.x.
- `HeapConfiguration Heap = new HeapConfiguration()`
Heap Settings
- `bool HideNetworkObjectInactivityGuard = false`
Inactive [NetworkObject](#) need special handling in case they get destroyed without ever being activated. This is achieved with adding a nested [GameObject](#) called "NetworkObjectInactivityGuard" that tracks the [OnDestroy](#) message. [HideNetworkObjectInactivityGuard](#) can be used to control whether these guards are visible in the hierarchy or not.
- `HostMigrationConfig HostMigration = new HostMigrationConfig()`
Reference to [HostMigration](#) settings for this [NetworkProjectConfig](#)
- `bool InvokeRenderInBatchMode = true`
Signal if the [SimulationBehaviour.Render](#) callbacks should be invoked in Batch Mode.
- `LagCompensationSettings LagCompensation = new LagCompensationSettings()`
Advanced lag compensation buffer settings.
- `NetworkConfiguration Network = new NetworkConfiguration()`
Reference to [NetworkConfiguration](#) settings for this [NetworkProjectConfig](#).
- `NetworkSimulationConfiguration NetworkConditions = new NetworkSimulationConfiguration()`
Settings for simulating network conditions of latency and loss.
- `bool NetworkIdsObjectName`
Signal if the [NetworkId](#) of the [NetworkObject](#) should be included on the name of the [GameObject](#).
- `bool NullChecksForNetworkedProperties = true`

If set, the weaver will add a check to all [Networked] properties on each [NetworkBehaviour](#) to verify if owing [NetworkObject](#) has been attached to.

- [PeerModes](#) [PeerMode](#)

Setting for whether multiple peers can run per Unity instance (typically to allow easy testing of multiple peers inside of the editor).

- [NetworkPrefabTable](#) [PrefabTable](#) = new [NetworkPrefabTable](#)()

Reference to the [NetworkPrefabTable](#) instance for this [NetworkProjectConfig](#).

- [SimulationConfig](#) [Simulation](#) = new [SimulationConfig](#)()

Reference to [SimulationConfig](#) settings for this [NetworkProjectConfig](#).

- [TimeSyncConfiguration](#) [TimeSynchronizationOverride](#)

this can be used to override the time synchronization from code

- string [TypeId](#) = [CurrentTypeId](#)

Current [NetworkProjectConfig](#) Type ID

- bool [UseSerializableDictionary](#) = true

Use [Fusion.SerializableDictionary](#) to store [Networked] dictionary properties initial value. If unchecked, the weaver will emit `System.Generic.Dictionary` instead - a type that's not Unity-serializable, but custom serializers (e.g. `Odin`) may support it.

- int [Version](#) = [CurrentVersion](#)

Current [NetworkProjectConfig](#) version

Static Public Attributes

- static [NetworkRunner](#). [BuildTypes](#)

Get the version information for the `Fusion.Runtime.dll`.

- const string [CurrentTypeId](#) = `nameof(NetworkProjectConfig)`

Current [NetworkProjectConfig](#) Type ID

- const int [CurrentVersion](#) = 1

Current [NetworkProjectConfig](#) version

- const string [DefaultResourceName](#) = `nameof(NetworkProjectConfig)`

Default file name for the [NetworkProjectConfig](#) asset

Properties

- static [NetworkProjectConfig](#) [Global](#) [get]

Reference for the default [NetworkProjectConfig](#). By default, loads a resource named "NetworkProjectConfig". This behaviour can be changed with an attribute `FusionGlobalScriptableObjectLoaderMethodAttribute`.

6.204.1 Detailed Description

The core [Fusion](#) config file that is shared with all peers at startup.

6.204.2 Member Enumeration Documentation

6.204.2.1 PeerModes

```
enum PeerModes [strong]
```

Options for running one or multiple peers in one Unity instance. Multiple is useful for testing multiple players/clients inside of the Unity editor without needing to build executables. Each peer is assigned its own independent physics scene and [NetworkRunner](#) instance.

Enumerator

Single	This is the normal use case, where every build and the editor run a single server, host or client peer.
Multiple	This is the optional use case, which allows running multiple peers in the Unity editor, or in a build.

6.204.2.2 ReplicationFeatures

```
enum ReplicationFeatures [strong]
```

Eventual Consistency [NetworkObject](#) state replication options.

Scheduling enables automatic prioritization of objects when culling occurs (when Object's are not replicated due to exceeding per tick data limits, they increase in priority on the following [Tick](#)).

Interest Management enables [NetworkObject](#) Area Of Interest and Explicit Interest features.

Enumerator

None	No special replication handling. This setting is ideal if your project never exceeds per tick data limits during gameplay.
Scheduling	When changed Network Objects are not replicated by the server to a client due to culling (data per tick limit was reached) the server increases the priority of that Network Object for the next outgoing Tick update to that client.
SchedulingAndInterestManagement	In addition to scheduling, Interest Management features are also enabled (Area Of Interest and Explicit Interest).

6.204.3 Member Function Documentation

6.204.3.1 Deserialize()

```
static NetworkProjectConfig Deserialize (
    string data ) [static]
```

De-serialize a [NetworkProjectConfig](#) from a JSON string (typically sent by the Room's Creator).

Parameters

<i>data</i>	JSON string of a serialized NetworkProjectConfig
-------------	--

Returns

[NetworkProjectConfig](#) reference de-serialized from JSON string

6.204.3.2 GetExecutionOrder()

```
int? GetExecutionOrder (
    Type type )
```

Get the execution order for a given type. If the type is registered, returns null.

Parameters

<i>type</i>	Type to check for the execution order.
-------------	--

Returns

Execution order for the type, or null if not registered.

6.204.3.3 Serialize()

```
static string Serialize (
    NetworkProjectConfig config ) [static]
```

Serialize a [NetworkProjectConfig](#) into a JSON string.

Parameters

<i>config</i>	NetworkProjectConfig reference
---------------	--

Returns

JSON String

6.204.3.4 ToString()

```
override string ToString ( )
```

[ToString\(\)](#) implementation.

6.204.3.5 UnloadGlobal()

```
static void UnloadGlobal ( ) [static]
```

Unloads [Global](#), if already loaded. If loading [Global](#) has faulted, resets the state and next call to the [Global](#) accessor will attempt to load the config again.

6.204.4 Member Data Documentation

6.204.4.1 AssembliesToWeave

```
string [] AssembliesToWeave
```

Initial value:

```
= new string[] {  
    "Fusion.Unity",  
    "Assembly-CSharp",  
    "Assembly-CSharp-firstpass",  
    "Fusion.Addons.Physics",  
}
```

Names of assemblies [Fusion](#) is going to weave. Not case sensitive.

6.204.4.2 BuildTypes

```
NetworkRunner. BuildTypes [static]
```

Get the version information for the Fusion.Runtime.dll.

6.204.4.3 CheckNetworkedPropertiesBeingEmpty

```
bool CheckNetworkedPropertiesBeingEmpty = false
```

If set, the weaver will check if [NetworkedAttribute](#) properties getters and setters are empty.

6.204.4.4 CheckRpcAttributeUsage

```
bool CheckRpcAttributeUsage = false
```

If set, the weaver will check if [RpcAttribute](#) is used in types that do not support it. This requires all types to be scanned and can increase weaving duration.

6.204.4.5 CurrentTypeId

```
const string CurrentTypeId = nameof(NetworkProjectConfig) [static]
```

Current [NetworkProjectConfig](#) Type ID

6.204.4.6 CurrentVersion

```
const int CurrentVersion = 1 [static]
```

Current [NetworkProjectConfig](#) version

6.204.4.7 DefaultResourceName

```
const string DefaultResourceName = nameof(NetworkProjectConfig) [static]
```

Default file name for the [NetworkProjectConfig](#) asset

6.204.4.8 EnqueueIncompleteSynchronousSpawns

```
bool EnqueueIncompleteSynchronousSpawns
```

This flag changes the behaviour of [NetworkRunner.Spawn<T>](#) to return null (instead of throwing an exception) and [NetworkRunner.TrySpawn<T>](#) to return [NetworkSpawnStatus.Queued](#) if [Fusion](#) was unable to load a prefab synchronously (e.g. because it was Addressable). [Fusion](#) will enqueue the spawn and attempt to perform it the next frame, until successful. Useful for transition from [Fusion](#) 1.x.

6.204.4.9 Heap

```
HeapConfiguration Heap = new HeapConfiguration()
```

Heap Settings

6.204.4.10 HideNetworkObjectInactivityGuard

```
bool HideNetworkObjectInactivityGuard = false
```

Inactive [NetworkObject](#) need special handling in case they get destroyed without ever being activated. This is achieved with adding a nested GameObject called "NetworkObjectInactivityGuard" that tracks the OnDestroy message. [HideNetworkObjectInactivityGuard](#) can be used to control whether these guards are visible in the hierarchy or not.

6.204.4.11 HostMigration

```
HostMigrationConfig HostMigration = new HostMigrationConfig()
```

Reference to [HostMigration](#) settings for this [NetworkProjectConfig](#)

6.204.4.12 InvokeRenderInBatchMode

```
bool InvokeRenderInBatchMode = true
```

Signal if the [SimulationBehaviour.Render](#) callbacks should be invoked in Batch Mode.

6.204.4.13 LagCompensation

```
LagCompensationSettings LagCompensation = new LagCompensationSettings()
```

Advanced lag compensation buffer settings.

6.204.4.14 Network

```
NetworkConfiguration Network = new NetworkConfiguration()
```

Reference to [NetworkConfiguration](#) settings for this [NetworkProjectConfig](#).

6.204.4.15 NetworkConditions

```
NetworkSimulationConfiguration NetworkConditions = new NetworkSimulationConfiguration()
```

Settings for simulating network conditions of latency and loss.

6.204.4.16 NetworkIdIsObjectName

```
bool NetworkIdIsObjectName
```

Signal if the [NetworkId](#) of the [NetworkObject](#) should be included on the name of the GameObject.

6.204.4.17 NullChecksForNetworkedProperties

```
bool NullChecksForNetworkedProperties = true
```

If set, the weaver will add a check to all [Networked] properties on each [NetworkBehaviour](#) to verify if owing [NetworkObject](#) has been attached to.

6.204.4.18 PeerMode

```
PeerModes PeerMode
```

Setting for whether multiple peers can run per Unity instance (typically to allow easy testing of multiple peers inside of the editor).

6.204.4.19 PrefabTable

```
NetworkPrefabTable PrefabTable = new NetworkPrefabTable()
```

Reference to the [NetworkPrefabTable](#) instance for this [NetworkProjectConfig](#).

6.204.4.20 Simulation

```
SimulationConfig Simulation = new SimulationConfig()
```

Reference to [SimulationConfig](#) settings for this [NetworkProjectConfig](#).

6.204.4.21 TimeSynchronizationOverride

```
TimeSyncConfiguration TimeSynchronizationOverride
```

this can be used to override the time synchronization from code

6.204.4.22 TypeId

```
string TypeId = CurrentTypeId
```

Current [NetworkProjectConfig](#) Type ID

6.204.4.23 UseSerializableDictionary

```
bool UseSerializableDictionary = true
```

Use [Fusion.SerializableDictionary](#) to store [Networked] dictionary properties initial value. If unchecked, the weaver will emit System.Generic.Dictionary instead - a type that's not Unity-serializable, but custom serializers (e.g. Odin) may support it.

6.204.4.24 Version

```
int Version = CurrentVersion
```

Current [NetworkProjectConfig](#) version

6.204.5 Property Documentation

6.204.5.1 Global

```
NetworkProjectConfig Global [static], [get]
```

Reference for the default [NetworkProjectConfig](#). By default, loads a resource named "NetworkProjectConfig". This behaviour can be changed with an attribute [FusionGlobalScriptableObjectLoaderMethodAttribute](#).

6.205 NetworkProjectConfigAsset Class Reference

Manages and references the current instance of [NetworkProjectConfig](#)

Inherits [FusionGlobalScriptableObject< T >](#).

Classes

- struct [SerializableSimulationBehaviourMeta](#)

An auto-generated list containing meta information about all the [SimulationBehaviours](#) in the project, e.g. execution order.

Static Public Member Functions

- static bool [TryGetGlobal](#) (out [NetworkProjectConfigAsset](#) global)
Try to get the current [NetworkProjectConfig](#) instance.
- static void [UnloadGlobal](#) ()
Unload the current [NetworkProjectConfig](#) instance.

Public Attributes

- `SerializableSimulationBehaviourMeta[] BehaviourMeta = Array.Empty<SerializableSimulationBehaviourMeta>()`
An auto-generated list containing meta information about all the [SimulationBehaviours](#) in the project, e.g. execution order.
- `NetworkProjectConfig Config = new NetworkProjectConfig()`
The current [NetworkProjectConfig](#) instance.
- `NetworkPrefabTableOptions PrefabOptions = NetworkPrefabTableOptions.Default`
Options for the [NetworkPrefabTable](#).
- `List< INetworkPrefabSource > Prefabs = new List<INetworkPrefabSource>()`
An auto-generated list containing source information (e.g. Resource path, address, static reference) for all the prefabs that can be spawned, i.e. the ones with [NetworkObject](#) component and [NetworkObject.IsSpawnable](#) enabled. Additional prefabs can registered at runtime with [NetworkPrefabTable.TryAddSource](#).

Properties

- static `NetworkProjectConfigAsset Global` [get]
The current [NetworkProjectConfig](#) instance.
- static bool `IsGlobalLoaded` [get]
True if the [NetworkProjectConfig](#) instance exists, otherwise false.

6.205.1 Detailed Description

Manages and references the current instance of [NetworkProjectConfig](#)

6.205.2 Member Function Documentation

6.205.2.1 TryGetGlobal()

```
static bool TryGetGlobal (
    out NetworkProjectConfigAsset global ) [static]
```

Try to get the current [NetworkProjectConfig](#) instance.

Parameters

<i>global</i>	NetworkProjectConfig instance if it exists, otherwise null.
---------------	---

Returns

True if the [NetworkProjectConfig](#) instance exists, otherwise false.

6.205.2.2 UnloadGlobal()

```
static void UnloadGlobal ( ) [static]
```

Unload the current [NetworkProjectConfig](#) instance.

6.205.3 Member Data Documentation

6.205.3.1 BehaviourMeta

```
SerializableSimulationBehaviourMeta [ ] BehaviourMeta = Array.Empty<SerializableSimulationBehaviourMeta>()
```

An auto-generated list containing meta information about all the [SimulationBehaviours](#) in the project, e.g. execution order.

6.205.3.2 Config

```
NetworkProjectConfig Config = new NetworkProjectConfig()
```

The current [NetworkProjectConfig](#) instance.

6.205.3.3 PrefabOptions

```
NetworkPrefabTableOptions PrefabOptions = NetworkPrefabTableOptions.Default
```

Options for the [NetworkPrefabTable](#).

6.205.3.4 Prefabs

```
List<INetworkPrefabSource> Prefabs = new List<INetworkPrefabSource>()
```

An auto-generated list containing source information (e.g. Resource path, address, static reference) for all the prefabs that can be spawned, i.e. the ones with [NetworkObject](#) component and [NetworkObject.IsSpawnable](#) enabled. Additional prefabs can be registered at runtime with [NetworkPrefabTable.TryAddSource](#).

6.205.4 Property Documentation

6.205.4.1 Global

`NetworkProjectConfigAsset` Global [static], [get]

The current `NetworkProjectConfig` instance.

6.205.4.2 IsGlobalLoaded

`bool IsGlobalLoaded` [static], [get]

True if the `NetworkProjectConfig` instance exists, otherwise false.

6.206 NetworkProjectConfigAsset.SerializableSimulationBehaviourMeta Struct Reference

An auto-generated list containing meta information about all the `SimulationBehaviours` in the project, e.g. execution order.

Public Attributes

- int `ExecutionOrder`
The execution order of the `SimulationBehaviour`.
- `SerializableType< SimulationBehaviour > Type`
The type of the `SimulationBehaviour`.

6.206.1 Detailed Description

An auto-generated list containing meta information about all the `SimulationBehaviours` in the project, e.g. execution order.

6.206.2 Member Data Documentation

6.206.2.1 ExecutionOrder

`int ExecutionOrder`

The execution order of the `SimulationBehaviour`.

6.206.2.2 Type

`SerializableType<SimulationBehaviour> Type`

The type of the [SimulationBehaviour](#).

6.207 NetworkRNG Struct Reference

PCG32 random generator, 16 bytes in size. <http://www.pcg-random.org>

Inherits [INetworkStruct](#).

Public Member Functions

- [NetworkRNG](#) (Int32 seed)
Creates a new instance of [NetworkRNG](#) with a random seed.
- double [Next](#) ()
Generates a random double value within the inclusive range [0, 1].
- double [NextExclusive](#) ()
Generates a random double value within the exclusive range [0, 1).
- int [NextInt32](#) ()
Generates a random integer value within the range of `int.MinValue` to `int.MaxValue`.
- float [NextSingle](#) ()
Generates a random float value within the inclusive range [0, 1].
- float [NextSingleExclusive](#) ()
Generates a random float value within the exclusive range [0, 1).
- uint [NextUInt32](#) ()
Generates a random unsigned integer value within the range of 0 to `uint.MaxValue`.
- Int32 [RangeExclusive](#) (Int32 minInclusive, Int32 maxExclusive)
Returns a random Int32 within [minInclusive, maxExclusive) (range is exclusive). If minInclusive and maxExclusive are equal, then the "exclusive rule" is ignored and minInclusive will be returned. If minInclusive is greater than maxExclusive, then the numbers are automatically swapped.
- UInt32 [RangeExclusive](#) (UInt32 minInclusive, UInt32 maxExclusive)
Returns a random UInt32 within [minInclusive, maxExclusive) (range is exclusive). If minInclusive and maxExclusive are equal, then the "exclusive rule" is ignored and minInclusive will be returned. If minInclusive is greater than maxExclusive, then the numbers are automatically swapped.
- Double [RangeInclusive](#) (Double minInclusive, Double maxInclusive)
Returns a random Double within [minInclusive, maxInclusive] (range is inclusive). If minInclusive is greater than maxInclusive, then the numbers are automatically swapped.
- Int32 [RangeInclusive](#) (Int32 minInclusive, Int32 maxInclusive)
Returns a random Int32 within [minInclusive, maxInclusive] (range is inclusive). If minInclusive is greater than maxInclusive, then the numbers are automatically swapped.
- Single [RangeInclusive](#) (Single minInclusive, Single maxInclusive)
Returns a random Single within [minInclusive, maxInclusive] (range is inclusive). If minInclusive is greater than maxInclusive, then the numbers are automatically swapped.
- UInt32 [RangeInclusive](#) (UInt32 minInclusive, UInt32 maxInclusive)
Returns a random UInt32 within [minInclusive, maxInclusive] (range is inclusive). If minInclusive is greater than maxInclusive, then the numbers are automatically swapped.
- override string [ToString](#) ()
String representation of the RNG state.

Static Public Attributes

- const UInt32 `MAX` = UInt32.MaxValue
Maximum allowed value
- const int `SIZE` = 16
Size of the struct in bytes.

Properties

- `NetworkRNG Peek` [get]
Returns the same RNG instance.

6.207.1 Detailed Description

PCG32 random generator, 16 bytes in size. <http://www.pcg-random.org>

6.207.2 Constructor & Destructor Documentation

6.207.2.1 NetworkRNG()

```
NetworkRNG (
    Int32 seed )
```

Creates a new instance of `NetworkRNG` with a random seed.

Parameters

<code>seed</code>	Seed value.
-------------------	-------------

6.207.3 Member Function Documentation

6.207.3.1 Next()

```
double Next ( )
```

Generates a random double value within the inclusive range [0, 1].

Returns

A random double value between 0 and 1, inclusive.

6.207.3.2 NextExclusive()

```
double NextExclusive ( )
```

Generates a random double value within the exclusive range [0, 1).

Returns

A random double value between 0 (inclusive) and 1 (exclusive).

6.207.3.3 NextInt32()

```
int NextInt32 ( )
```

Generates a random integer value within the range of int.MinValue to int.MaxValue.

Returns

A random integer value between int.MinValue and int.MaxValue, inclusive.

6.207.3.4 NextSingle()

```
float NextSingle ( )
```

Generates a random float value within the inclusive range [0, 1].

Returns

A random float value between 0 and 1, inclusive.

6.207.3.5 NextSingleExclusive()

```
float NextSingleExclusive ( )
```

Generates a random float value within the exclusive range [0, 1).

Returns

A random float value between 0 (inclusive) and 1 (exclusive).

6.207.3.6 NextUInt32()

```
uint NextUInt32 ( )
```

Generates a random unsigned integer value within the range of 0 to uint.MaxValue.

Returns

A random unsigned integer value between 0 and uint.MaxValue, inclusive.

6.207.3.7 RangeExclusive() [1/2]

```
Int32 RangeExclusive (
    Int32 minInclusive,
    Int32 maxExclusive )
```

Returns a random Int32 within [minInclusive, maxExclusive) (range is exclusive). If minInclusive and maxExclusive are equal, then the "exclusive rule" is ignored and minInclusive will be returned. If minInclusive is greater than maxExclusive, then the numbers are automatically swapped.

6.207.3.8 RangeExclusive() [2/2]

```
UInt32 RangeExclusive (
    UInt32 minInclusive,
    UInt32 maxExclusive )
```

Returns a random UInt32 within [minInclusive, maxExclusive) (range is exclusive). If minInclusive and maxExclusive are equal, then the "exclusive rule" is ignored and minInclusive will be returned. If minInclusive is greater than maxExclusive, then the numbers are automatically swapped.

6.207.3.9 RangeInclusive() [1/4]

```
Double RangeInclusive (
    Double minInclusive,
    Double maxInclusive )
```

Returns a random Double within [minInclusive, maxInclusive] (range is inclusive). If minInclusive is greater than maxInclusive, then the numbers are automatically swapped.

6.207.3.10 RangeInclusive() [2/4]

```
Int32 RangeInclusive (
    Int32 minInclusive,
    Int32 maxInclusive )
```

Returns a random Int32 within [minInclusive, maxInclusive] (range is inclusive). If minInclusive is greater than maxInclusive, then the numbers are automatically swapped.

6.207.3.11 RangeInclusive() [3/4]

```
Single RangeInclusive (
    Single minInclusive,
    Single maxInclusive )
```

Returns a random Single within [minInclusive, maxInclusive] (range is inclusive). If minInclusive is greater than maxInclusive, then the numbers are automatically swapped.

6.207.3.12 RangeInclusive() [4/4]

```
UInt32 RangeInclusive (
    UInt32 minInclusive,
    UInt32 maxInclusive )
```

Returns a random UInt32 within [minInclusive, maxInclusive] (range is inclusive). If minInclusive is greater than maxInclusive, then the numbers are automatically swapped.

6.207.3.13 ToString()

```
override string ToString ( )
```

String representation of the RNG state.

6.207.4 Member Data Documentation**6.207.4.1 MAX**

```
const UInt32 MAX = UInt32.MaxValue [static]
```

Maximum allowed value

6.207.4.2 SIZE

```
const int SIZE = 16 [static]
```

Size of the struct in bytes.

6.207.5 Property Documentation

6.207.5.1 Peek

```
NetworkRNG Peek [get]
```

Returns the same RNG instance.

6.208 NetworkRpcStaticWeavedInvokerAttribute Class Reference

Network Rpc Static Weaved Invoker Attribute Contains info about a static weaved RPC Method

Inherits Attribute.

Public Member Functions

- [NetworkRpcStaticWeavedInvokerAttribute](#) (string key)
[NetworkRpcStaticWeavedInvokerAttribute](#) Constructor

Properties

- string [Key](#) [get]
RPC Key

6.208.1 Detailed Description

Network Rpc Static Weaved Invoker Attribute Contains info about a static weaved RPC Method

6.208.2 Constructor & Destructor Documentation

6.208.2.1 NetworkRpcStaticWeavedInvokerAttribute()

```
NetworkRpcStaticWeavedInvokerAttribute (  
    string key )
```

[NetworkRpcStaticWeavedInvokerAttribute](#) Constructor

Parameters

<i>key</i>	Key
------------	---------------------

6.208.3 Property Documentation

6.208.3.1 Key

`string Key [get]`

RPC Key

6.209 NetworkRpcWeavedInvokerAttribute Class Reference

Network Rpc Weaved Invoker Attribute Contains info about a weaved RPC Method

Inherits Attribute.

Public Member Functions

- [NetworkRpcWeavedInvokerAttribute](#) (int key, int sources, int targets)
NetworkRpcWeavedInvokerAttribute Constructor

Properties

- int [Key](#) [get]
RPC Key
- int [Sources](#) [get]
RPC Sources
- int [Targets](#) [get]
RPC Targets

6.209.1 Detailed Description

Network Rpc Weaved Invoker Attribute Contains info about a weaved RPC Method

6.209.2 Constructor & Destructor Documentation

6.209.2.1 NetworkRpcWeavedInvokerAttribute()

```
NetworkRpcWeavedInvokerAttribute (  
    int key,  
    int sources,  
    int targets )
```

[NetworkRpcWeavedInvokerAttribute](#) Constructor

Parameters

<i>key</i>	Key
<i>sources</i>	Sources
<i>targets</i>	Targets

6.209.3 Property Documentation

6.209.3.1 Key

```
int Key [get]
```

RPC Key

6.209.3.2 Sources

```
int Sources [get]
```

RPC Sources

6.209.3.3 Targets

```
int Targets [get]
```

RPC Targets

6.210 NetworkRunner Class Reference

Host Migration related code in order to get a copy of the [Simulation](#) State

Inherits [Behaviour](#), and [Simulation.ICallbacks](#).

Public Types

- enum class [BuildTypes](#)
Enumeration of Fusion.Runtime.dll options.
- enum class [States](#)
Initialization stages of [Fusion](#)

Public Member Functions

- void [AddCallbacks](#) (params [INetworkRunnerCallbacks](#)[] callbacks)
Register an [INetworkRunnerCallbacks](#) instance for callbacks from this [NetworkRunner](#).
- void [AddGlobal](#) ([SimulationBehaviour](#) instance)
Add and register a [SimulationBehaviour](#) to this [NetworkRunner](#). Note: It should NOT be a [NetworkBehaviour](#)
- void [AddPlayerAreaOfInterest](#) ([PlayerRef](#) player, [Vector3](#) center, float radius)
Call this every [FixedUpdateNetwork](#) to add an area of interest for a player. Should only be called from the Host/Server in Server client mode. Should only be called for the local player in shared mode.
- void [Attach](#) ([NetworkObject](#) networkObject, [PlayerRef?](#) inputAuthority=null, bool allocate=true, bool? masterClientObjectOverride=null)
- void [Attach](#) ([NetworkObject](#)[] networkObjects, [PlayerRef?](#) inputAuthority=null, bool allocate=true, bool? masterClientObjectOverride=null)
Attach and assign to this [NetworkRunner](#) the [NetworkObject](#) provided. Used internally from the default implementation of [INetworkSceneManager](#) to register scene objects.
- void [ClearPlayerAreaOfInterest](#) ([PlayerRef](#) player)
Clears the area of interest for a player. This can only be called from the server/host
- void [Despawn](#) ([NetworkObject](#) networkObject)
Destroys a [NetworkObject](#).
- void [DestroySingleton](#)< T > ()
Removes a specific [SimulationBehaviour](#) from this [NetworkRunner](#) gameobject, if it exists.
- void [Disconnect](#) ([PlayerRef](#) player, byte[] token=null)
Disconnects a player from the server.
- bool [EnsureRunnerSceneIsActive](#) (out Scene previousActiveScene)
Ensures the scene of this runner is active and returns the previous active scene
- bool [Exists](#) ([NetworkId](#) id)
Returns if the [Fusion.Simulation](#) contains a [NetworkObject](#) with given id in the current State.
- bool [Exists](#) ([NetworkObject](#) obj)
Returns if the [Fusion.Simulation](#) contains a reference to a [NetworkObject](#) in the current State.
- [NetworkObject](#) [FindObject](#) ([NetworkId](#) networkId)
Get the [NetworkObject](#) instance for this [NetworkRunner](#) from a [NetworkId](#).
- [SimulationBehaviour](#)[] [GetAllBehaviours](#) (Type type)
Returns an array of all [SimulationBehaviour](#) instances registered with this [NetworkRunner](#).
- List< T > [GetAllBehaviours](#)< T > ()
Get a list with all behaviours of the desired type that are registered on the [NetworkRunner](#).
- void [GetAllBehaviours](#)< T > (List< T > result)
Add on the list all behaviours of the desired type that are registered on the [NetworkRunner](#). Note: The list will not be cleared before adding the results.
- void [GetAreaOfInterestGizmoData](#) (List<(Vector3 center, Vector3 size, int playerCount, int objectCount)> result)
Populates the provided list with data about the current Area of Interest (AOI) cells. Each element in the list represents one AOI cell.
- T? [GetInputForPlayer](#)< T > ([PlayerRef](#) player)
Returns the [NetworkInput](#) data from player, converted to the indicated [INetworkInput](#).
- [SimulationBehaviourListScope](#) [GetInterfaceListHead](#) (Type type, int index, out [SimulationBehaviour](#) head)
Get the interface list head.
- [SimulationBehaviour](#) [GetInterfaceListNext](#) ([SimulationBehaviour](#) behaviour)
Get the next behaviour
- [SimulationBehaviour](#) [GetInterfaceListPrev](#) ([SimulationBehaviour](#) behaviour)
Get the previous behaviour
- int [GetInterfaceListsCount](#) (Type type)
Get the number of interfaces of the desired type that are registered on the behaviour updater.

- PhysicsScene [GetPhysicsScene](#) ()
Get the 3D Physics scene being used by this Runner.
- PhysicsScene2D [GetPhysicsScene2D](#) ()
Get the 2D Physics scene being used by this Runner.
- int? [GetPlayerActorId](#) (PlayerRef player)
Gets Player's Actor Number (ID).
- byte[] [GetPlayerConnectionToken](#) (PlayerRef player=default)
Returns a copy of the Connection Token used by a Player when connecting to this Server. Only available on Server. It will return null if running on a Client or the Connection token is missing
- ConnectionType [GetPlayerConnectionType](#) (PlayerRef player)
Return the ConnectionType with a Remote PlayerRef. Valid only when invoked from a Server ([NetworkRunner.IsServer](#))
- NetworkObject [GetPlayerObject](#) (PlayerRef player)
Gets the network object associated with a specific player
- double [GetPlayerRtt](#) (PlayerRef playerRef)
Returns the player round trip time (ping) in seconds
- string [GetPlayerUserId](#) (PlayerRef player=default)
Gets Player's UserID.
- NetworkInput? [GetRawInputForPlayer](#) (PlayerRef player)
Returns the unconverted unsafe NetworkInput for the indicated player.
- IEnumerable< NetworkObject > [GetResumeSnapshotNetworkObjects](#) ()
Iterate over the old NetworkObjects from the Resume Snapshot
- IEnumerable<(NetworkObject, NetworkObjectHeaderPtr)> [GetResumeSnapshotNetworkSceneObjects](#) ()
Iterate over the Scene NetworkObjects from the Resume Snapshot while giving the reference of the old Snapshot data associated with that particular Scene Object
- RpcTargetStatus [GetRpcTargetStatus](#) (PlayerRef target)
Return the RpcTargetStatus for a specific player.
- SceneRef [GetSceneRef](#) (GameObject gameObj)
- SceneRef [GetSceneRef](#) (string sceneNameOrPath)
- T [GetSingleton](#)< T > ()
Ensures that a specific SimulationBehaviour component exists on this NetworkRunner gameobject.
- bool [HasAnyActiveConnections](#) ()
- bool [HasSingleton](#)< T > ()
Returns if a given SimulationBehaviour is present in this NetworkRunner gameobject.
- GameObject [InstantiateInRunnerScene](#) (GameObject original)
Instantiates an object in the scene of this runner
- GameObject [InstantiateInRunnerScene](#) (GameObject original, Vector3 position, Quaternion rotation)
Instantiates an object in the scene of this runner
- T [InstantiateInRunnerScene](#)< T > (T original)
Instantiates an object in the scene of this runner
- T [InstantiateInRunnerScene](#)< T > (T original, Vector3 position, Quaternion rotation)
Instantiates an object in the scene of this runner
- void [InvokeSceneLoadDone](#) (in SceneLoadDoneArgs info)
Invoke INetworkRunnerCallbacks.OnSceneLoadDone(NetworkRunner) on all implementations
- void [InvokeSceneLoadStart](#) (SceneRef sceneRef)
Invoke INetworkRunnerCallbacks.OnSceneLoadStart(NetworkRunner) on all implementations
- bool? [IsInterestedIn](#) (NetworkObject obj, PlayerRef player)
Test if a player has Interest in a NetworkObject.
- bool [IsPlayerValid](#) (PlayerRef player)
Checks if the provided player is valid in the current simulation.
- async Task< StartGameResult > [JoinSessionLobby](#) (SessionLobby sessionLobby, string lobbyID=null, AuthenticationValues authentication=null, FusionAppSettings customAppSettings=null, bool? useDefault↵ CloudPorts=false, CancellationToken cancellationToken=default, bool useCachedRegions=false)

Join the Peer to a specific Lobby, either a prebuild or a custom one.

- [NetworkSceneAsyncOp LoadScene](#) ([SceneRef](#) sceneRef, [LoadSceneMode](#) loadSceneMode=[LoadSceneMode.Single](#), [LocalPhysicsMode](#) localPhysicsMode=[LocalPhysicsMode.None](#), [bool](#) setActiveOnLoad=[DefaultSetActiveOnLoad](#))

Loads a scene

- [NetworkSceneAsyncOp LoadScene](#) ([SceneRef](#) sceneRef, [LoadSceneParameters](#) parameters, [bool](#) setActiveOnLoad=[DefaultSetActiveOnLoad](#))
- [NetworkSceneAsyncOp LoadScene](#) ([string](#) sceneName, [LoadSceneMode](#) loadSceneMode=[LoadSceneMode.Single](#), [LocalPhysicsMode](#) localPhysicsMode=[LocalPhysicsMode.None](#), [bool](#) setActiveOnLoad=[DefaultSetActiveOnLoad](#))

Loads a scene

- [NetworkSceneAsyncOp LoadScene](#) ([string](#) sceneName, [LoadSceneParameters](#) parameters, [bool](#) setActiveOnLoad=[DefaultSetActiveOnLoad](#))

Loads a scene

- [void MakeDontDestroyOnLoad](#) ([GameObject](#) obj)

Mark an object as DontDestroyOnLoad.

- [bool MoveGameObjectToSameScene](#) ([GameObject](#) gameObj, [GameObject](#) other)

Moves a GameObject to the same scene as another GameObject

- [bool MoveGameObjectToScene](#) ([GameObject](#) gameObj, [SceneRef](#) sceneRef)

Moves a GameObject to a specific scene

- [void MoveToRunnerScene](#) ([GameObject](#) instance, [SceneRef?](#) targetSceneRef=null)

Moves an object to the scene of this runner

- [void MoveToRunnerScene< T >](#) ([T](#) component)

Moves an object to the scene of this runner

- [delegate void ObjectDelegate](#) ([NetworkRunner](#) runner, [NetworkObject](#) obj)

Delegate type for object callback

- [delegate void OnBeforeSpawned](#) ([NetworkRunner](#) runner, [NetworkObject](#) obj)

Delegate type for on before spawned callback

- [async Task< bool > PushHostMigrationSnapshot](#) ()

Compute and send a Host Migration Snapshot to the Photon Cloud

- [int RegisterSceneObjects](#) ([SceneRef](#) scene, [NetworkObject\[\]](#) objects, [NetworkSceneLoadId](#) loadId=default)

Registers scene objects to the network.

- [void RemoveCallbacks](#) ([params INetworkRunnerCallbacks\[\]](#) callbacks)

Unregister an [INetworkRunnerCallbacks](#) instance for callbacks from this [NetworkRunner](#).

- [void RemoveGlobal](#) ([SimulationBehaviour](#) instance)

Removes a specific [SimulationBehaviour](#) from this [NetworkObject](#) gameobject, if it exists.

- [void RemoveSimulationBehavior](#) ([SimulationBehaviour](#) behaviour)

Unregister a [SimulationBehaviour](#) instance from the [SimulationBehaviourUpdater](#) callbacks. Invalid if [NetworkRunner](#) has not been started and initialized.

- [void RenderInternal](#) ()

This method is meant to be called by [INetworkRunnerUpdater](#).

- [void SendReliableDataToPlayer](#) ([PlayerRef](#) player, [ReliableKey](#) key, [byte\[\]](#) data)

Sends a reliable data buffer to a target player.

- [void SendReliableDataToServer](#) ([ReliableKey](#) key, [byte\[\]](#) data)

Sends a reliable data buffer to the server.

- [void SendRpc](#) ([SimulationMessage](#) *message)

Sends RPC message. Not meant to be used directly, ILWeaver calls this.

- [void SendRpc](#) ([SimulationMessage](#) *message, [out RpcSendResult](#) info)

Sends RPC message. Not meant to be used directly, ILWeaver calls this.

- [void SetAreaOfInterestCellSize](#) ([int](#) size)

Set the area of interest cell size

- [void SetAreaOfInterestGrid](#) ([int](#) x, [int](#) y, [int](#) z)

- Set the area of interest grid dimensions*

 - bool [SetIsSimulated](#) ([NetworkObject](#) obj, bool simulate)

Sets the simulation state for this object, if it takes part in the [NetworkFixedUpdate](#), etc.
- void [SetMasterClient](#) ([PlayerRef](#) player)

Promote a player to be the new master client. Only the master client is able to call this method
- void [SetPlayerAlwaysInterested](#) ([PlayerRef](#) player, [NetworkObject](#) networkObject, bool alwaysInterested)

Flags this player as always interested in this object. Means it does not have to be in a players area of interest to be replicated. Only the [NetworkObject](#) State Authority can set interest.
- void [SetPlayerObject](#) ([PlayerRef](#) player, [NetworkObject](#) networkObject)

Sets the network object associated with this player
- Task [Shutdown](#) (bool destroyGameObject=true, [ShutdownReason](#) shutdownReason=[ShutdownReason.Ok](#), bool forceShutdownProcedure=false)

Initiates a [Simulation.Dispose](#).
- void [SinglePlayerContinue](#) ()

Continues a paused game in single player
- void [SinglePlayerPause](#) ()

Pauses the game in single player
- void [SinglePlayerPause](#) (bool paused)

Sets the paused state in a single player
- [NetworkObject](#) [Spawn](#) (GameObject prefab, Vector3? position=null, Quaternion? rotation=null, [PlayerRef](#)? inputAuthority=null, [OnBeforeSpawned](#) onBeforeSpawned=null, [NetworkSpawnFlags](#) flags=default)

Attempts to network instantiate a [NetworkObject](#) using a [GameObject](#). The supplied [GameObject](#) must have a [NetworkObject](#) component.
- [NetworkObject](#) [Spawn](#) ([NetworkObject](#) prefab, Vector3? position=null, Quaternion? rotation=null, [PlayerRef](#)? inputAuthority=null, [OnBeforeSpawned](#) onBeforeSpawned=null, [NetworkSpawnFlags](#) flags=default)

Attempts to network instantiate a [NetworkObject](#) using a [NetworkObject](#) prefab. Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.
- [NetworkObject](#) [Spawn](#) ([NetworkObjectGuid](#) prefabGuid, Vector3? position=null, Quaternion? rotation=null, [PlayerRef](#)? inputAuthority=null, [OnBeforeSpawned](#) onBeforeSpawned=null, [NetworkSpawnFlags](#) flags=default)

Attempts to network instantiate a [NetworkObject](#) using a [NetworkObjectGuid](#) Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.
- [NetworkObject](#) [Spawn](#) ([NetworkPrefabId](#) typeId, Vector3? position=null, Quaternion? rotation=null, [PlayerRef](#)? inputAuthority=null, [OnBeforeSpawned](#) onBeforeSpawned=null, [NetworkSpawnFlags](#) flags=default)

Attempts to network instantiate a [NetworkObject](#) using a [NetworkPrefabId](#) Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.
- [NetworkObject](#) [Spawn](#) ([NetworkPrefabRef](#) prefabRef, Vector3? position=null, Quaternion? rotation=null, [PlayerRef](#)? inputAuthority=null, [OnBeforeSpawned](#) onBeforeSpawned=null, [NetworkSpawnFlags](#) flags=default)

Attempts to network instantiate a [NetworkObject](#) using a [NetworkPrefabRef](#). Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.
- T [Spawn](#)< T > (T prefab, Vector3? position=null, Quaternion? rotation=null, [PlayerRef](#)? inputAuthority=null, [OnBeforeSpawned](#) onBeforeSpawned=null, [NetworkSpawnFlags](#) flags=default)

Attempts to network instantiate a [NetworkObject](#) using a [Component](#) type that is part of a [NetworkObject](#)
- [NetworkSpawnOp](#) [SpawnAsync](#) (GameObject prefab, Vector3? position=null, Quaternion? rotation=null, [PlayerRef](#)? inputAuthority=null, [OnBeforeSpawned](#) onBeforeSpawned=null, [NetworkSpawnFlags](#) flags=default, [NetworkObjectSpawnDelegate](#) onCompleted=null)

Attempts to network instantiate a [NetworkObject](#) using a [GameObject](#). The supplied [GameObject](#) must have a [NetworkObject](#) component.

- [NetworkSpawnOp SpawnAsync](#) ([NetworkObject](#) prefab, [Vector3?](#) position=null, [Quaternion?](#) rotation=null, [PlayerRef?](#) inputAuthority=null, [OnBeforeSpawned](#) onBeforeSpawned=null, [NetworkSpawnFlags](#) flags=default, [NetworkObjectSpawnDelegate](#) onCompleted=null)
Attempts to network instantiate a [NetworkObject](#) using a [NetworkObject](#) prefab. Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.
- [NetworkSpawnOp SpawnAsync](#) ([NetworkObjectGuid](#) prefabGuid, [Vector3?](#) position=null, [Quaternion?](#) rotation=null, [PlayerRef?](#) inputAuthority=null, [OnBeforeSpawned](#) onBeforeSpawned=null, [NetworkSpawnFlags](#) flags=default, [NetworkObjectSpawnDelegate](#) onCompleted=null)
Attempts to network instantiate a [NetworkObject](#) using a [NetworkObjectGuid](#) Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.
- [NetworkSpawnOp SpawnAsync](#) ([NetworkPrefabId](#) typeId, [Vector3?](#) position=null, [Quaternion?](#) rotation=null, [PlayerRef?](#) inputAuthority=null, [OnBeforeSpawned](#) onBeforeSpawned=null, [NetworkSpawnFlags](#) flags=default, [NetworkObjectSpawnDelegate](#) onCompleted=null)
Attempts to network instantiate a [NetworkObject](#) using a [NetworkPrefabId](#) Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.
- [NetworkSpawnOp SpawnAsync](#) ([NetworkPrefabRef](#) prefabRef, [Vector3?](#) position=null, [Quaternion?](#) rotation=null, [PlayerRef?](#) inputAuthority=null, [OnBeforeSpawned](#) onBeforeSpawned=null, [NetworkSpawnFlags](#) flags=default, [NetworkObjectSpawnDelegate](#) onCompleted=null)
Attempts to network instantiate a [NetworkObject](#) using a [NetworkPrefabRef](#). Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.
- [NetworkSpawnOp SpawnAsync< T >](#) ([T](#) prefab, [Vector3?](#) position=null, [Quaternion?](#) rotation=null, [PlayerRef?](#) inputAuthority=null, [OnBeforeSpawned](#) onBeforeSpawned=null, [NetworkSpawnFlags](#) flags=default, [NetworkObjectSpawnDelegate](#) onCompleted=null)
Attempts to network instantiate a [NetworkObject](#) using a Component type that is part of a [NetworkObject](#)
- Task< [StartGameResult](#) > [StartGame](#) ([StartGameArgs](#) args)
Starts the local [Fusion](#) Runner and takes care of all major setup necessary
- bool [TryFindBehaviour](#) ([NetworkBehaviourId](#) behaviourId, out [NetworkBehaviour](#) behaviour)
Get the [NetworkBehaviour](#) instance for this [NetworkRunner](#) from a [NetworkBehaviourId](#).
- bool [TryFindBehaviour< T >](#) ([NetworkBehaviourId](#) id, out T behaviour)
Try to find a [NetworkBehaviour](#) with the provided [NetworkBehaviourId](#).
- bool [TryFindObject](#) ([NetworkId](#) objectId, out [NetworkObject](#) networkObject)
Get the [NetworkObject](#) instance for this [NetworkRunner](#) from a [NetworkId](#).
- bool [TryGetBehaviourStats](#) (List<(Type, [BehaviourStats](#))> result)
Populate the provided list with all registered behaviours and their [BehaviourStats](#).
- bool [TryGetInputForPlayer< T >](#) ([PlayerRef](#) player, out T input)
Outputs the [NetworkInput](#) from player, translated to the indicated [INetworkInput](#).
- T [TryGetNetworkedBehaviourFromNetworkedObjectRef< T >](#) ([NetworkId](#) networkId)
Tries to return the first instance of T found on the root of a [NetworkObject](#).
- [NetworkBehaviourId](#) [TryGetNetworkedBehaviourId](#) ([NetworkBehaviour](#) behaviour)
Tries to return a [NetworkBehaviourId](#) for the [NetworkBehaviour](#) provided.
- [NetworkId](#) [TryGetObjectRefFromNetworkedBehaviour](#) ([NetworkBehaviour](#) behaviour)
Tries to return the behaviour [NetworkId](#).
- bool [TryGetObjectStats](#) ([NetworkId](#) id, out [NetworkObjectStats](#) stats)
Try to get [NetworkObjectStats](#) buffer for a [NetworkObject](#) from this [NetworkRunner](#).
- bool [TryGetPhysicsInfo](#) (out [NetworkPhysicsInfo](#) info)
Try to get the physics info.
- bool [TryGetPlayerObject](#) ([PlayerRef](#) player, out [NetworkObject](#) networkObject)
Try to gets the [NetworkObject](#) associated with a specific player
- bool [TryGetPlayerStats](#) ([PlayerRef](#) player, out [SimulationConnectionStats](#) stats)

- Try to get [SimulationConnectionStats](#) buffer for a player reference from this [NetworkRunner](#).
- bool [TryGetSceneInfo](#) (out [NetworkSceneInfo](#) sceneInfo)
 - Trys to get the [NetworkSceneInfo](#) of this [NetworkRunner](#).
- bool [TryGetSimulationStats](#) (out [SimulationStats](#) stats)
 - Try to get [SimulationStats](#) buffer from this [NetworkRunner](#).
- bool [TrySetPhysicsInfo](#) ([NetworkPhysicsInfo](#) info)
 - Try to set the physics info.
- [NetworkSpawnStatus TrySpawn](#) (GameObject prefab, out [NetworkObject](#) obj, Vector3? position=null, Quaternion? rotation=null, [PlayerRef?](#) inputAuthority=null, [OnBeforeSpawned](#) onBeforeSpawned=null, [NetworkSpawnFlags](#) flags=default)
 - Attempts to network instantiate a [NetworkObject](#) using a [GameObject](#). The supplied [GameObject](#) must have a [NetworkObject](#) component.
- [NetworkSpawnStatus TrySpawn](#) ([NetworkObject](#) prefab, out [NetworkObject](#) obj, Vector3? position=null, Quaternion? rotation=null, [PlayerRef?](#) inputAuthority=null, [OnBeforeSpawned](#) onBeforeSpawned=null, [NetworkSpawnFlags](#) flags=default)
 - Attempts to network instantiate a [NetworkObject](#) using a [NetworkObject](#) prefab. Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.
- [NetworkSpawnStatus TrySpawn](#) ([NetworkObjectGuid](#) prefabGuid, out [NetworkObject](#) obj, Vector3? position=null, Quaternion? rotation=null, [PlayerRef?](#) inputAuthority=null, [OnBeforeSpawned](#) onBeforeSpawned=null, [NetworkSpawnFlags](#) flags=default)
 - Attempts to network instantiate a [NetworkObject](#) using a [NetworkObjectGuid](#) Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.
- [NetworkSpawnStatus TrySpawn](#) ([NetworkPrefabId](#) typeId, out [NetworkObject](#) obj, Vector3? position=null, Quaternion? rotation=null, [PlayerRef?](#) inputAuthority=null, [OnBeforeSpawned](#) onBeforeSpawned=null, [NetworkSpawnFlags](#) flags=default)
 - Attempts to network instantiate a [NetworkObject](#) using a [NetworkPrefabId](#) Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.
- [NetworkSpawnStatus TrySpawn](#) ([NetworkPrefabRef](#) prefabRef, out [NetworkObject](#) obj, Vector3? position=null, Quaternion? rotation=null, [PlayerRef?](#) inputAuthority=null, [OnBeforeSpawned](#) onBeforeSpawned=null, [NetworkSpawnFlags](#) flags=default)
 - Attempts to network instantiate a [NetworkObject](#) using a [NetworkPrefabRef](#). Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.
- [NetworkSpawnStatus TrySpawn< T >](#) (T prefab, out T obj, Vector3? position=null, Quaternion? rotation=null, [PlayerRef?](#) inputAuthority=null, [OnBeforeSpawned](#) onBeforeSpawned=null, [NetworkSpawnFlags](#) flags=default)
 - Attempts to network instantiate a [NetworkObject](#) using a [Component](#) type that is part of a [NetworkObject](#)
- [NetworkSceneAsyncOp UnloadScene](#) ([SceneRef](#) sceneRef)
- [NetworkSceneAsyncOp UnloadScene](#) (string sceneName)
 - Unloads a scene
- void [UpdateInternal](#) (double dt)
 - This method is meant to be called by [INetworkRunnerUpdater](#).

Static Public Member Functions

- static List< [NetworkRunner](#) >.Enumerator [GetInstancesEnumerator](#) ()
 - Get enumerator for the collection of all [NetworkRunners](#). Allows to enumerate alloc-free.
- static [NetworkRunner GetRunnerForGameObject](#) (GameObject gameObject)
 - Get the [NetworkRunner](#) a [GameObject](#) instance belongs to.
- static [NetworkRunner GetRunnerForScene](#) (Scene scene)
 - Get the [NetworkRunner](#) from a specific [Scene](#)

Properties

- `IEnumerable< PlayerRef > ActivePlayers` [get]
Returns the collection of [PlayerRef](#) objects for this [NetworkRunner](#)'s [Fusion.Simulation](#).
- `AuthenticationValues AuthenticationValues` [get]
[AuthenticationValues](#) used by this Runner to Authenticate the local peer.
- `static BuildTypes BuildType` [get]
Get [Fusion.Runtime.dll](#) build type.
- `bool CanSpawn` [get]
Signal if the Network Runner can spawn a [NetworkObject](#)
- `NetworkProjectConfig Config` [get]
Returns the [NetworkProjectConfig](#) reference.
- `ConnectionType CurrentConnectionType` [get]
Check the current Connection Type with the Remote Server
- `float DeltaTime` [get]
Returns the fixed tick time interval. Derived from the [SimulationRuntimeConfig.TickRate](#).
- `GameMode GameMode` [get]
Current Game Mode active on the [Fusion Simulation](#)
- `static IReadOnlyList< NetworkRunner > Instances` [get]
A list of all [NetworkRunners](#).
- `bool IsClient` [get]
Returns if this [Fusion.Simulation](#) represents a Client connection.
- `bool IsCloudReady` [get]
Signal if the Local Peer is connected to Photon Cloud and is able to Create/Join Room but also receive Lobby Updates
- `bool IsConnectedToServer` [get]
Returns if this Client is currently connected to a Remote Server
- `bool IsFirstTick` [get]
If this is the first tick that executes this update or re-simulation
- `bool IsForward` [get]
If this is not a re-simulation but a new forward tick
- `bool IsLastTick` [get]
If this is the last tick that is being executed this update
- `bool IsPlayer` [get]
Returns true if this runner represents a Client or Host. Dedicated servers have no local player and will return false.
- `bool IsResimulation` [get]
If we are currently executing a client side prediction re-simulation.
- `bool IsResume` [get]
if this instance is a resume (host migration)
- `bool IsRunning` [get]
Returns if this [Fusion.Simulation](#) is valid and running.
- `bool IsSceneAuthority` [get]
Is this runner responsible for scene management.
- `bool? IsSceneManagerBusy` [get]
Signals if the [INetworkSceneManager](#) instance assigned to this [NetworkRunner](#) is busy with any scene loading operation.
- `bool IsServer` [get]
Returns if this [Fusion.Simulation](#) represents a Server connection.
- `bool IsSharedModeMasterClient` [get]
Signal if the Local Peer is in a Room and is the Room Master Client
- `bool IsShutdown` [get]
If the runner is shutdown

- bool [IsSinglePlayer](#) [get]
Returns true if this runner was started as single player (Started as [SimulationModes.Host](#) with [SimulationConfig.PlayerCount](#) = 1).
- bool [IsStarting](#) [get]
If the runner is pending to start
- [HitboxManager LagCompensation](#) [get]
Returns the global instance of a lag compensation buffer [Fusion.HitboxManager](#).
- [Tick LatestServerTick](#) [get]
Get the latest confirmed tick of the server we are aware of
- [LobbyInfo LobbyInfo](#) = new [LobbyInfo\(\)](#) [get]
Signal if the local peer is already inside a Lobby
- float [LocalAlpha](#) [get]
Get the local time alpha value
- [PlayerRef LocalPlayer](#) [get]
Returns a [PlayerRef](#) for the local simulation. For a dedicated server [PlayerRef.IsRealPlayer](#) will equal false. Player↔Refs are assigned in order from 0 to MaxPlayers-1 and are re-used as players join and leave. The only caveat is that the server player (if one exists), always gets the last index no matter how many clients are connected.
- float [LocalRenderTime](#) [get]
The current time (current [State.Time](#) + [Simulation.DeltaTime](#)) for predicted objects (objects in the local time frame). Use as an equivalent to Unity's [Time.time](#). Time is relative to [Tick 0](#) (which represents Time 0f).
- [SimulationModes Mode](#) [get]
Returns the [SimulationModes](#) flags for The type of network peer the associated [Fusion.Simulation](#) represents.
- [NATType NATType](#) [get]
Exposes the current NAT Type from the local Peer
- [INetworkObjectProvider ObjectProvider](#) [get]
Returns the [INetworkObjectProvider](#) instance.
- [NetworkPrefabTable Prefabs](#) [get]
Reference to the [NetworkPrefabTable](#).
- bool [ProvideInput](#) [get, set]
Indicates if this [NetworkRunner](#) is collecting [PlayerRef INetworkInput](#).
- float [RemoteRenderTime](#) [get]
The current time (current [State.Time](#) + [Simulation.DeltaTime](#)) for non-predicted objects (objects in a remote time frame). Use as an equivalent to Unity's [Time.time](#). Time is relative to [Tick 0](#) (which represents Time 0f).
- [INetworkSceneManager SceneManager](#) [get]
Returns the [INetworkSceneManager](#) instance.
- [SessionInfo SessionInfo](#) = new [SessionInfo\(\)](#) [get]
Stores information about the current running session
- float [SimulationTime](#) [get]
The time the current [State](#) represents (the most recent [FixedUpdateNetwork](#) simulation). Use as an equivalent to Unity's [Time.fixedTime](#). Time is relative to [Tick 0](#) (which represents Time 0f).
- [Scene??? SimulationUnityScene](#) [get]
The main scene of the [NetworkRunner](#) or default if not running.
- [SimulationStages Stage](#) [get]
Returns the current [SimulationStages](#) stage of this [Fusion.Simulation](#).
- [States State](#) [get]
The current state of the runner, if it's Starting, Running, Shutdown
- [Tick??? Tick](#) [get]
The tick associated with the current state of networked objects, or the current simulation tick being processed (when evaluated during [FixedUpdateNetwork](#)).
- int [TickRate](#) [get]
- int [TicksExecuted](#) [get]
Returns how many ticks we executed last update.

- [Topologies Topology](#) [get]
The current topology used
- string [UserId](#) [get]
Photon Client UserID

Events

- [ObjectDelegate ObjectAcquired](#)
Event for object acquired

6.210.1 Detailed Description

Host Migration related code in order to get a copy of the [Simulation](#) State

All Scene related API and fields

Represents a Server or Client [Simulation](#).

6.210.2 Member Enumeration Documentation

6.210.2.1 BuildTypes

```
enum BuildTypes [strong]
```

Enumeration of Fusion.Runtime.dll options.

Enumerator

Debug	Use the Debug version of the Fusion.Runtime.dll.
Release	Use the Debug version of the Fusion.Runntime.dll.

6.210.2.2 States

```
enum States [strong]
```

Initialization stages of [Fusion](#)

Enumerator

Starting	Runner is about to start
Running	Runner is running
Shutdown	Runner is shutdown

6.210.3 Member Function Documentation

6.210.3.1 AddCallbacks()

```
void AddCallbacks (
    params INetworkRunnerCallbacks[] callbacks )
```

Register an [INetworkRunnerCallbacks](#) instance for callbacks from this [NetworkRunner](#).

Parameters

<i>callbacks</i>	Callbacks to register
------------------	-----------------------

6.210.3.2 AddGlobal()

```
void AddGlobal (
    SimulationBehaviour instance )
```

Add and register a [SimulationBehaviour](#) to this [NetworkRunner](#). Note: It should NOT be a [NetworkBehaviour](#)

6.210.3.3 AddPlayerAreaOfInterest()

```
void AddPlayerAreaOfInterest (
    PlayerRef player,
    Vector3 center,
    float radius )
```

Call this every `FixedUpdateNetwork` to add an area of interest for a player. Should only be called from the Host/↔ Server in Server client mode. Should only be called for the local player in shared mode.

6.210.3.4 Attach() [1/2]

```
void Attach (
    NetworkObject networkObject,
    PlayerRef? inputAuthority = null,
    bool allocate = true,
    bool? masterClientObjectOverride = null )
```

Attaches a user-created network object to the network.

Parameters

<i>networkObject</i>	The network object to attach. Must not be null and must have a valid <code>NetworkType</code> id.
<i>inputAuthority</i>	Optional PlayerRef . If assigned, it will be the default input authority for this object.
<i>allocate</i>	Optional boolean. If true, the object will be allocated in memory and attached to the scene object. Default is true.
<i>masterClientObjectOverride</i>	Optional boolean. If provided, it will override the master client object setting. Default is null.

Exceptions

<i>ArgumentNullException</i>	Thrown when the provided network object is null.
<i>ArgumentException</i>	Thrown when the provided network object has an invalid <code>NetworkType</code> id.

6.210.3.5 Attach() [2/2]

```
void Attach (
    NetworkObject[] networkObjects,
    PlayerRef? inputAuthority = null,
    bool allocate = true,
    bool? masterClientObjectOverride = null )
```

Attach and assign to this [NetworkRunner](#) the [NetworkObject](#) provided. Used internally from the default implementation of [INetworkSceneManager](#) to register scene objects.

6.210.3.6 ClearPlayerAreaOfInterest()

```
void ClearPlayerAreaOfInterest (
    PlayerRef player )
```

Clears the area of interest for a player. This can only be called from the server/host

6.210.3.7 Despawn()

```
void Despawn (
    NetworkObject networkObject )
```

Destroys a [NetworkObject](#).

Parameters

<i>networkObject</i>	The NetworkObject to be destroyed.
----------------------	--

This method checks if the local simulation has state authority over the [NetworkObject](#). If it does, it checks if the [NetworkObject](#) exists and has state authority. If these conditions are met, it destroys the [NetworkObject](#).

Exceptions

<i>InvalidOperationException</i>	Thrown when the NetworkObject does not belong to this runner.
----------------------------------	---

6.210.3.8 DestroySingleton< T >()

```
void DestroySingleton< T > ( )
```

Removes a specific [SimulationBehaviour](#) from this [NetworkRunner](#) gameobject, if it exists.

Type Constraints

***T* : [SimulationBehaviour](#)**

6.210.3.9 Disconnect()

```
void Disconnect (
    PlayerRef player,
    byte[] token = null )
```

Disconnects a player from the server.

Parameters

<i>player</i>	The player to disconnect. Must be a valid PlayerRef .
<i>token</i>	Optional byte array. If provided, it will be used as the disconnection token.

This method can only be called from the server. If called from a client, an error message will be logged.

6.210.3.10 EnsureRunnerSceneIsActive()

```
bool EnsureRunnerSceneIsActive (
    out Scene previousActiveScene )
```

Ensures the scene of this runner is active and returns the previous active scene

Parameters

<i>previousActiveScene</i>	Previous active scene
----------------------------	-----------------------

Returns

True if the scene was changed, false otherwise

6.210.3.11 Exists() [1/2]

```
bool Exists (
    NetworkId id )
```

Returns if the [Fusion.Simulation](#) contains a [NetworkObject](#) with given *id* in the current State.

6.210.3.12 Exists() [2/2]

```
bool Exists (
    NetworkObject obj )
```

Returns if the [Fusion.Simulation](#) contains a reference to a [NetworkObject](#) in the current State.

6.210.3.13 FindObject()

```
NetworkObject FindObject (
    NetworkId networkId )
```

Get the [NetworkObject](#) instance for this [NetworkRunner](#) from a [NetworkId](#).

Parameters

<i>network↔ Id</i>	NetworkID to look forward
------------------------	---------------------------

Returns

null if object cannot be found.

6.210.3.14 GetAllBehaviours()

```
SimulationBehaviour [] GetAllBehaviours (
    Type type )
```

Returns an array of all [SimulationBehaviour](#) instances registered with this [NetworkRunner](#).

Parameters

<i>type</i>	The type of the behaviours to be returned.
-------------	--

Returns

An array of [SimulationBehaviour](#) instances of the specified type.

6.210.3.15 GetAllBehaviours< T >() [1/2]

```
List<T> GetAllBehaviours< T > ( )
```

Get a list with all behaviours of the desired type that are registered on the [NetworkRunner](#).

Template Parameters

<i>T</i>	SimulationBehaviour type
----------	--

Returns

The result list

Type Constraints

***T* : [SimulationBehaviour](#)**

6.210.3.16 GetAllBehaviours< T >() [2/2]

```
void GetAllBehaviours< T > (
    List< T > result )
```

Add on the list all behaviours of the desired type that are registered on the [NetworkRunner](#). Note: The list will not be cleared before adding the results.

Parameters

<i>result</i>	The list to add the behaviours
---------------	--------------------------------

Template Parameters

<i>T</i>	SimulationBehaviour type
----------	--

Type Constraints

T : SimulationBehaviour

6.210.3.17 GetAreaOfInterestGizmoData()

```
void GetAreaOfInterestGizmoData (
    List<(Vector3 center, Vector3 size, int playerCount, int objectCount)> result )
```

Populates the provided list with data about the current Area of Interest (AOI) cells. Each element in the list represents one AOI cell.

Parameters

<i>result</i>	The list to be populated with AOI cell data. Each tuple in the list contains the center of the AOI cell, its size, the count of players in the cell, and the count of objects in the cell.
---------------	--

6.210.3.18 GetInputForPlayer< T >()

```
T? GetInputForPlayer< T > (
    PlayerRef player )
```

Returns the [NetworkInput](#) data from player, converted to the indicated [INetworkInput](#).

Type Constraints

T : unmanaged

T : INetworkInput

6.210.3.19 GetInstancesEnumerator()

```
static List<NetworkRunner>.Enumerator GetInstancesEnumerator ( ) [static]
```

Get enumerator for the collection of all [NetworkRunners](#). Allows to enumerate alloc-free.

6.210.3.20 GetInterfaceListHead()

```
SimulationBehaviourListScope GetInterfaceListHead (
    Type type,
    int index,
    out SimulationBehaviour head )
```

Get the interface list head.

Parameters

<i>type</i>	The interface type
<i>index</i>	The desired index on the list of behaviourList
<i>head</i>	The head reference

Returns

A disposable [SimulationBehaviourListScope](#) to be used on an `using` scope

6.210.3.21 GetInterfaceListNext()

```
SimulationBehaviour GetInterfaceListNext (
    SimulationBehaviour behaviour )
```

Get the next behaviour

Parameters

<i>behaviour</i>	The reference behaviour to get the next one
------------------	---

Returns

Gives the next behaviour

6.210.3.22 GetInterfaceListPrev()

```
SimulationBehaviour GetInterfaceListPrev (
    SimulationBehaviour behaviour )
```

Get the previous behaviour

Parameters

<i>behaviour</i>	The reference behaviour to get the previous one
------------------	---

Returns

Gives the previous behaviour

6.210.3.23 GetInterfaceListsCount()

```
int GetInterfaceListsCount (
    Type type )
```

Get the number of interfaces of the desired type that are registered on the behaviour updater.

Parameters

<i>type</i>	The interface type
-------------	--------------------

Returns

The number of interfaces

6.210.3.24 GetPhysicsScene()

```
PhysicsScene GetPhysicsScene ( )
```

Get the 3D Physics scene being used by this Runner.

6.210.3.25 GetPhysicsScene2D()

```
PhysicsScene2D GetPhysicsScene2D ( )
```

Get the 2D Physics scene being used by this Runner.

6.210.3.26 GetPlayerActorId()

```
int? GetPlayerActorId (
    PlayerRef player )
```

Gets Player's Actor Number (ID).

If used in Shared Mode, every client can get this information. If used in Client Server Mode, only the Server is able to get this information.

Parameters

<i>player</i>	PlayerRef to get the Actor Number (ID)
---------------	--

Returns

Actor Number associated with the [PlayerRef](#), otherwise null.

6.210.3.27 GetPlayerConnectionToken()

```
byte [] GetPlayerConnectionToken (
    PlayerRef player = default )
```

Returns a copy of the Connection Token used by a Player when connecting to this Server. Only available on Server. It will return null if running on a Client or the Connection token is missing

Parameters

<i>player</i>	PlayerRef to check for a Connection Token
---------------	---

Returns

Copy of the Connection Token

6.210.3.28 GetPlayerConnectionType()

```
ConnectionType GetPlayerConnectionType (
    PlayerRef player )
```

Return the [ConnectionType](#) with a Remote [PlayerRef](#). Valid only when invoked from a Server ([NetworkRunner.IsServer](#))

Parameters

<i>player</i>	Remote Player to check the ConnectionType
---------------	---

Returns

[ConnectionType](#) with a [PlayerRef](#)

6.210.3.29 GetPlayerObject()

```
NetworkObject GetPlayerObject (
    PlayerRef player )
```

Gets the network object associated with a specific player

Parameters

<i>player</i>	PlayerRef to get the network object
---------------	---

Returns

Network object if one is associated with the player

6.210.3.30 GetPlayerRtt()

```
double GetPlayerRtt (
    PlayerRef playerRef )
```

Returns the player round trip time (ping) in seconds

Parameters

<i>playerRef</i>	The player you want the round trip time for
------------------	---

6.210.3.31 GetPlayerUserId()

```
string GetPlayerUserId (
    PlayerRef player = default )
```

Gets Player's UserID.

If used in Shared Mode, every client can get this information. If used in Client Server Mode, only the Server is able to get this information.

Parameters

<i>player</i>	PlayerRef to get the UserID. If no PlayerRef is passed, the UserID of the local client is returned instead.
---------------	---

Returns

UserID if valid player found, otherwise null.

6.210.3.32 GetRawInputForPlayer()

```
NetworkInput? GetRawInputForPlayer (
    PlayerRef player )
```

Returns the unconverted unsafe [NetworkInput](#) for the indicated player.

6.210.3.33 GetResumeSnapshotNetworkObjects()

```
IEnumerable<NetworkObject> GetResumeSnapshotNetworkObjects ( )
```

Iterate over the old NetworkObjects from the Resume Snapshot

Returns

Iterable list of [NetworkObject](#)

6.210.3.34 GetResumeSnapshotNetworkSceneObjects()

```
IEnumerable<(NetworkObject, NetworkObjectHeaderPtr)> GetResumeSnapshotNetworkSceneObjects ( )
```

Iterate over the Scene NetworkObjects from the Resume Snapshot while giving the reference of the old Snapshot data associated with that particular Scene Object

Returns

Iterable list of Scene [NetworkObject](#) and Scene Object Header

6.210.3.35 GetRpcTargetStatus()

```
RpcTargetStatus GetRpcTargetStatus (
    PlayerRef target )
```

Return the [RpcTargetStatus](#) for a specific player.

6.210.3.36 GetRunnerForGameObject()

```
static NetworkRunner GetRunnerForGameObject (
    GameObject gameObject ) [static]
```

Get the [NetworkRunner](#) a GameObject instance belongs to.

Parameters

<i>gameObject</i>	GameObject to check for a NetworkRunner
-------------------	---

Returns

[NetworkRunner](#) reference, or null if not found

6.210.3.37 GetRunnerForScene()

```
static NetworkRunner GetRunnerForScene (
    Scene scene ) [static]
```

Get the [NetworkRunner](#) from a specific Scene

Parameters

<i>scene</i>	Scene to check for a NetworkRunner
--------------	--

Returns

[NetworkRunner](#) reference, or null if not found

6.210.3.38 GetSingleton< T >()

```
T GetSingleton< T > ( )
```

Ensures that a specific [SimulationBehaviour](#) component exists on this [NetworkRunner](#) gameobject.

Type Constraints

T : [SimulationBehaviour](#)

6.210.3.39 HasSingleton< T >()

```
bool HasSingleton< T > ( )
```

Returns if a given [SimulationBehaviour](#) is present in this [NetworkRunner](#) gameobject.

Returns

Returns true if the [SimulationBehaviour](#) was found

Type Constraints

T : [SimulationBehaviour](#)

6.210.3.40 InstantiateInRunnerScene() [1/2]

```
GameObject InstantiateInRunnerScene (
    GameObject original )
```

Instantiates an object in the scene of this runner

6.210.3.41 InstantiateInRunnerScene() [2/2]

```
GameObject InstantiateInRunnerScene (
    GameObject original,
    Vector3 position,
    Quaternion rotation )
```

Instantiates an object in the scene of this runner

6.210.3.42 InstantiateInRunnerScene< T >() [1/2]

```
T InstantiateInRunnerScene< T > (
    T original )
```

Instantiates an object in the scene of this runner

Type Constraints

T* : *Component

6.210.3.43 InstantiateInRunnerScene< T >() [2/2]

```
T InstantiateInRunnerScene< T > (
    T original,
    Vector3 position,
    Quaternion rotation )
```

Instantiates an object in the scene of this runner

Type Constraints

T* : *Component

6.210.3.44 InvokeSceneLoadDone()

```
void InvokeSceneLoadDone (
    in SceneLoadDoneArgs info )
```

Invoke [INetworkRunnerCallbacks.OnSceneLoadDone\(NetworkRunner\)](#) on all implementations

6.210.3.45 InvokeSceneLoadStart()

```
void InvokeSceneLoadStart (
    SceneRef sceneRef )
```

Invoke [INetworkRunnerCallbacks.OnSceneLoadStart\(NetworkRunner\)](#) on all implementations

6.210.3.46 IsInterestedIn()

```
bool? IsInterestedIn (
    NetworkObject obj,
    PlayerRef player )
```

Test if a player has Interest in a [NetworkObject](#).

Returns

Returns null if interest cannot be determined (clients without State Authority are not aware of other client's Object Interest)

6.210.3.47 IsPlayerValid()

```
bool IsPlayerValid (
    PlayerRef player )
```

Checks if the provided player is valid in the current simulation.

Parameters

<i>player</i>	The player reference to be validated.
---------------	---------------------------------------

Returns

Returns true if the player is valid, false otherwise.

6.210.3.48 JoinSessionLobby()

```
async Task<StartGameResult> JoinSessionLobby (
    SessionLobby sessionLobby,
    string lobbyID = null,
    AuthenticationValues authentication = null,
    FusionAppSettings customAppSettings = null,
    bool? useDefaultCloudPorts = false,
    CancellationToken cancellationToken = default,
    bool useCachedRegions = false )
```

Join the Peer to a specific Lobby, either a prebuild or a custom one.

More about matchmaking: <https://doc.photonengine.com/en-us/fusion/current/manual/matchmaking>

Parameters

<i>sessionLobby</i>	Lobby Type to Join
<i>lobbyID</i>	Lobby ID
<i>authentication</i>	Authentication Values used to authenticate this peer
<i>customAppSettings</i>	Custom Photon Application Settings
<i>useDefaultCloudPorts</i>	Signal if the LoadBalancingClient should use the Default or Alternative Ports
<i>cancellationToken</i>	Optional Cancellation Token
<i>useCachedRegions</i>	Signal if the cached regions ping should be used to speed up connection

Returns

Async Task to Join a Session Lobby. Can be used to wait for the process to be finished.

6.210.3.49 LoadScene() [1/3]

```
NetworkSceneAsyncOp LoadScene (
    SceneRef sceneRef,
    LoadSceneMode loadSceneMode = LoadSceneMode.Single,
    LocalPhysicsMode localPhysicsMode = LocalPhysicsMode.None,
    bool setActiveOnLoad = DefaultSetActiveOnLoad )
```

Loads a scene

Parameters

<i>sceneRef</i>	Reference to the scene to load
<i>loadSceneMode</i>	Scene load mode
<i>localPhysicsMode</i>	Scene physics mode
<i>setActiveOnLoad</i>	Should the scene be set as active when loaded

Returns

Scene Load operation

6.210.3.50 LoadScene() [2/3]

```
NetworkSceneAsyncOp LoadScene (
    string sceneName,
    LoadSceneMode loadSceneMode = LoadSceneMode.Single,
    LocalPhysicsMode localPhysicsMode = LocalPhysicsMode.None,
    bool setActiveOnLoad = DefaultSetActiveOnLoad )
```

Loads a scene

Parameters

<i>sceneName</i>	Name of the scene to load
<i>loadSceneMode</i>	Scene load mode
<i>localPhysicsMode</i>	Scene physics mode
<i>setActiveOnLoad</i>	Should the scene be set as active when loaded

Returns

Scene Load operation

6.210.3.51 LoadScene() [3/3]

```
NetworkSceneAsyncOp LoadScene (
    string sceneName,
    LoadSceneParameters parameters,
    bool setActiveOnLoad = DefaultSetActiveOnLoad )
```

Loads a scene

Parameters

<i>sceneName</i>	Name of the scene to load
<i>parameters</i>	Parameters to use when loading the scene
<i>setActiveOnLoad</i>	Should the scene be set as active when loaded

Returns

Scene Load operation

6.210.3.52 MakeDontDestroyOnLoad()

```
void MakeDontDestroyOnLoad (
    GameObject obj )
```

Mark an object as DontDestroyOnLoad.

Parameters

<i>obj</i>	Object to mark
------------	----------------

6.210.3.53 MoveGameObjectToSameScene()

```
bool MoveGameObjectToSameScene (
    GameObject gameObj,
    GameObject other )
```

Moves a GameObject to the same scene as another GameObject

Parameters

<i>gameObj</i>	Game Object to move
<i>other</i>	Game Object to move to the same scene as

Returns

True if the object was moved, false otherwise

6.210.3.54 MoveGameObjectToScene()

```
bool MoveGameObjectToScene (
    GameObject gameObj,
    SceneRef sceneRef )
```

Moves a GameObject to a specific scene

Parameters

<i>gameObj</i>	Game Object to move
<i>sceneRef</i>	Scene to move the object to

Returns

True if the object was moved, false otherwise

6.210.3.55 MoveToRunnerScene()

```
void MoveToRunnerScene (
    GameObject instance,
    SceneRef? targetSceneRef = null )
```

Moves an object to the scene of this runner

Parameters

<i>instance</i>	Object to move
<i>targetSceneRef</i>	Target scene to move the object to

6.210.3.56 MoveToRunnerScene< T >()

```
void MoveToRunnerScene< T > (
    T component )
```

Moves an object to the scene of this runner

Template Parameters

<i>T</i>	
----------	--

Parameters

<i>component</i>	Component of object to move
------------------	-----------------------------

Type Constraints

T* : *Component

6.210.3.57 ObjectDelegate()

```
delegate void ObjectDelegate (
    NetworkRunner runner,
    NetworkObject obj )
```

Delegate type for object callback

6.210.3.58 OnBeforeSpawned()

```
delegate void OnBeforeSpawned (
    NetworkRunner runner,
    NetworkObject obj )
```

Delegate type for on before spawned callback

6.210.3.59 PushHostMigrationSnapshot()

```
async Task<bool> PushHostMigrationSnapshot ( )
```

Compute and send a Host Migration Snapshot to the Photon Cloud

Returns

Task with the result of the operation. True if it was successful, false otherwise.

6.210.3.60 RegisterSceneObjects()

```
int RegisterSceneObjects (
    SceneRef scene,
    NetworkObject[] objects,
    NetworkSceneLoadId loadId = default )
```

Registers scene objects to the network.

Parameters

<i>scene</i>	The scene reference. Must be valid.
<i>objects</i>	Array of NetworkObject instances to be registered. Must not be null.
<i>loadId</i>	Optional NetworkSceneLoadId . Default value is used if not provided.

Returns

The number of objects registered.

Exceptions

<i>ArgumentException</i>	Thrown when the provided scene is not valid.
<i>ArgumentNullException</i>	Thrown when the provided objects array is null.

6.210.3.61 RemoveCallbacks()

```
void RemoveCallbacks (
    params INetworkRunnerCallbacks[] callbacks )
```

Unregister an [INetworkRunnerCallbacks](#) instance for callbacks from this [NetworkRunner](#).

Parameters

<i>callbacks</i>	Callbacks to unregister
------------------	-------------------------

6.210.3.62 RemoveGlobal()

```
void RemoveGlobal (
    SimulationBehaviour instance )
```

Removes a specific [SimulationBehaviour](#) from this [NetworkObject](#) gameobject, if it exists.

6.210.3.63 RemoveSimulationBehavior()

```
void RemoveSimulationBehavior (
    SimulationBehaviour behaviour )
```

Unregister a [SimulationBehaviour](#) instance from the [SimulationBehaviourUpdater](#) callbacks. Invalid if [NetworkRunner](#) has not been started and initialized.

6.210.3.64 RenderInternal()

```
void RenderInternal ( )
```

This method is meant to be called by [INetworkRunnerUpdater](#).

6.210.3.65 SendReliableDataToPlayer()

```
void SendReliableDataToPlayer (
    PlayerRef player,
    ReliableKey key,
    byte[] data )
```

Sends a reliable data buffer to a target player.

Parameters

<i>player</i>	The player who should receive the buffer.
<i>key</i>	The key associated with the reliable data.
<i>data</i>	The data buffer to be sent.

6.210.3.66 SendReliableDataToServer()

```
void SendReliableDataToServer (
    ReliableKey key,
    byte[] data )
```

Sends a reliable data buffer to the server.

Parameters

<i>key</i>	The key associated with the reliable data.
<i>data</i>	The data buffer to be sent.

If the runner is a client, the data is sent to the server (connection index 0) with the player's index. If the runner is a server, the data is sent via the simulation callbacks.

6.210.3.67 SendRpc() [1/2]

```
void SendRpc (
    SimulationMessage * message )
```

Sends RPC message. Not meant to be used directly, ILWeaver calls this.

Parameters

<i>message</i>	SimulationMessage to send
----------------	---

6.210.3.68 SendRpc() [2/2]

```
void SendRpc (
    SimulationMessage * message,
    out RpcSendResult info )
```

Sends RPC message. Not meant to be used directly, ILWeaver calls this.

Parameters

<i>message</i>	SimulationMessage to send
<i>info</i>	RpcSendResult

6.210.3.69 SetAreaOfInterestCellSize()

```
void SetAreaOfInterestCellSize (
    int size )
```

Set the area of interest cell size

Parameters

<i>size</i>	Size of the cell
-------------	------------------

Exceptions

<i>Exception</i>	Can't change cell size in shared mode
------------------	---------------------------------------

6.210.3.70 SetAreaOfInterestGrid()

```
void SetAreaOfInterestGrid (
    int x,
    int y,
    int z )
```

Set the area of interest grid dimensions

Parameters

<i>x</i>	X dimension
<i>y</i>	Y dimension
<i>z</i>	Z dimension

Exceptions

<i>Exception</i>	Can't change grid size in shared mode
------------------	---------------------------------------

6.210.3.71 SetIsSimulated()

```
bool SetIsSimulated (
    NetworkObject obj,
    bool simulate )
```

Sets the simulation state for this object, if it takes part in the NetworkFixedUpdate, etc.

Parameters

<i>obj</i>	the object to change state for
<i>simulate</i>	true if it should be simulated, false if otherwise

Returns

true if the state of the object changed, false otherwise

6.210.3.72 SetMasterClient()

```
void SetMasterClient (
    PlayerRef player )
```

Promote a player to be the new master client. Only the master client is able to call this method

Parameters

<i>player</i>	The player to be promoted to master client
---------------	--

6.210.3.73 SetPlayerAlwaysInterested()

```
void SetPlayerAlwaysInterested (
    PlayerRef player,
    NetworkObject networkObject,
    bool alwaysInterested )
```

Flags this player as always interested in this object. Means it does not have to be in a players area of interest to be replicated. Only the [NetworkObject](#) State Authority can set interest.

Parameters

<i>player</i>	The player
<i>networkObject</i>	The object
<i>alwaysInterested</i>	If he's always interested, or not.

6.210.3.74 SetPlayerObject()

```
void SetPlayerObject (
    PlayerRef player,
    NetworkObject networkObject )
```

Sets the network object associated with this player

Parameters

<i>player</i>	PlayerRef to set the network object
<i>networkObject</i>	Network object to associate with the player

6.210.3.75 Shutdown()

```
Task Shutdown (
    bool destroyGameObject = true,
    ShutdownReason shutdownReason = ShutdownReason.Ok,
    bool forceShutdownProcedure = false )
```

Initiates a Simulation.Dispose.

6.210.3.76 SinglePlayerContinue()

```
void SinglePlayerContinue ( )
```

Continues a paused game in single player

6.210.3.77 SinglePlayerPause() [1/2]

```
void SinglePlayerPause ( )
```

Pauses the game in single player

6.210.3.78 SinglePlayerPause() [2/2]

```
void SinglePlayerPause (
    bool paused )
```

Sets the paused state in a single player

6.210.3.79 Spawn() [1/5]

```
NetworkObject Spawn (
    GameObject prefab,
    Vector3? position = null,
    Quaternion? rotation = null,
    PlayerRef? inputAuthority = null,
    OnBeforeSpawned onBeforeSpawned = null,
    NetworkSpawnFlags flags = default )
```

Attempts to network instantiate a [NetworkObject](#) using a [GameObject](#). The supplied [GameObject](#) must have a [NetworkObject](#) component.

Parameters

<i>prefab</i>	A GameObject with a NetworkObject
<i>position</i>	Spawn Position
<i>rotation</i>	Spawn Rotation
<i>inputAuthority</i>	Player Input Authority
<i>onBeforeSpawned</i>	OnBeforeSpawned reference
<i>flags</i>	Spawn flags

Returns

[NetworkObject](#) reference, or null if it was not able to spawn the object

6.210.3.80 **Spawn()** [2/5]

```
NetworkObject Spawn (
    NetworkObject prefab,
    Vector3? position = null,
    Quaternion? rotation = null,
    PlayerRef? inputAuthority = null,
    OnBeforeSpawned onBeforeSpawned = null,
    NetworkSpawnFlags flags = default )
```

Attempts to network instantiate a [NetworkObject](#) using a [NetworkObject](#) prefab. Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.

Parameters

<i>prefab</i>	Prefab used to spawn the NetworkObject
<i>position</i>	Spawn Position
<i>rotation</i>	Spawn Rotation
<i>inputAuthority</i>	Player Input Authority
<i>onBeforeSpawned</i>	OnBeforeSpawned reference
<i>flags</i>	Spawn flags

Returns

[NetworkObject](#) reference, or null if it was not able to spawn the object

6.210.3.81 **Spawn()** [3/5]

```
NetworkObject Spawn (
    NetworkObjectGuid prefabGuid,
```

```

Vector3? position = null,
Quaternion? rotation = null,
PlayerRef? inputAuthority = null,
OnBeforeSpawned onBeforeSpawned = null,
NetworkSpawnFlags flags = default )

```

Attempts to network instantiate a [NetworkObject](#) using a [NetworkObjectGuid](#) Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.

Parameters

<i>prefabGuid</i>	Object Guid used to spawn the NetworkObject
<i>position</i>	Spawn Position
<i>rotation</i>	Spawn Rotation
<i>inputAuthority</i>	Player Input Authority
<i>onBeforeSpawned</i>	OnBeforeSpawned reference
<i>flags</i>	Spawn flags

Returns

[NetworkObject](#) reference, or null if it was not able to spawn the object

6.210.3.82 Spawn() [4/5]

```

NetworkObject Spawn (
    NetworkPrefabId typeId,
    Vector3? position = null,
    Quaternion? rotation = null,
    PlayerRef? inputAuthority = null,
    OnBeforeSpawned onBeforeSpawned = null,
    NetworkSpawnFlags flags = default )

```

Attempts to network instantiate a [NetworkObject](#) using a [NetworkPrefabId](#) Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.

Parameters

<i>typeId</i>	Prefab ID used to spawn the NetworkObject
<i>position</i>	Spawn Position
<i>rotation</i>	Spawn Rotation
<i>inputAuthority</i>	Player Input Authority
<i>onBeforeSpawned</i>	OnBeforeSpawned reference
<i>flags</i>	Spawn flags

Returns

[NetworkObject](#) reference, or null if it was not able to spawn the object

6.210.3.83 Spawn() [5/5]

```
NetworkObject Spawn (
    NetworkPrefabRef prefabRef,
    Vector3? position = null,
    Quaternion? rotation = null,
    PlayerRef? inputAuthority = null,
    OnBeforeSpawned onBeforeSpawned = null,
    NetworkSpawnFlags flags = default )
```

Attempts to network instantiate a [NetworkObject](#) using a [NetworkPrefabRef](#). Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.

Parameters

<i>prefabRef</i>	Prefab Ref used to spawn the NetworkObject
<i>position</i>	Spawn Position
<i>rotation</i>	Spawn Rotation
<i>inputAuthority</i>	Player Input Authority
<i>onBeforeSpawned</i>	OnBeforeSpawned reference
<i>flags</i>	Spawn flags

Returns

[NetworkObject](#) reference, or null if it was not able to spawn the object

6.210.3.84 Spawn< T >()

```
T Spawn< T > (
    T prefab,
    Vector3? position = null,
    Quaternion? rotation = null,
    PlayerRef? inputAuthority = null,
    OnBeforeSpawned onBeforeSpawned = null,
    NetworkSpawnFlags flags = default )
```

Attempts to network instantiate a [NetworkObject](#) using a Component type that is part of a [NetworkObject](#)

Template Parameters

<i>T</i>	Must be a Type derived from SimulationBehaviour
----------	---

Parameters

<i>prefab</i>	SimulationBehaviour used to spawn the NetworkObject
---------------	---

Returns

T reference, or null if it was not able to spawn the object

Parameters

<i>position</i>	Spawn Position
<i>rotation</i>	Spawn Rotation
<i>inputAuthority</i>	Player Input Authority
<i>onBeforeSpawned</i>	OnBeforeSpawned reference
<i>flags</i>	Spawn flags

Type Constraints

***T* : [SimulationBehaviour](#)**

6.210.3.85 SpawnAsync() [1/5]

```
NetworkSpawnOp SpawnAsync (
    GameObject prefab,
    Vector3? position = null,
    Quaternion? rotation = null,
    PlayerRef? inputAuthority = null,
    OnBeforeSpawned onBeforeSpawned = null,
    NetworkSpawnFlags flags = default,
    NetworkObjectSpawnDelegate onCompleted = null )
```

Attempts to network instantiate a [NetworkObject](#) using a `GameObject`. The supplied `GameObject` must have a [NetworkObject](#) component.

Parameters

<i>prefab</i>	A <code>GameObject</code> with a NetworkObject
<i>position</i>	Spawn Position
<i>rotation</i>	Spawn Rotation
<i>inputAuthority</i>	Player Input Authority
<i>onBeforeSpawned</i>	OnBeforeSpawned reference
<i>flags</i>	Spawn flags

,

Parameters

<i>onCompleted</i>	A callback to fire once the spawn is done.
--------------------	--

6.210.3.86 SpawnAsync() [2/5]

```
NetworkSpawnOp SpawnAsync (
    NetworkObject prefab,
    Vector3? position = null,
    Quaternion? rotation = null,
    PlayerRef? inputAuthority = null,
    OnBeforeSpawned onBeforeSpawned = null,
    NetworkSpawnFlags flags = default,
    NetworkObjectSpawnDelegate onCompleted = null )
```

Attempts to network instantiate a [NetworkObject](#) using a [NetworkObject](#) prefab. Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.

Parameters

<i>prefab</i>	Prefab used to spawn the NetworkObject
<i>position</i>	Spawn Position
<i>rotation</i>	Spawn Rotation
<i>inputAuthority</i>	Player Input Authority
<i>onBeforeSpawned</i>	OnBeforeSpawned reference
<i>flags</i>	Spawn flags

,

Parameters

<i>onCompleted</i>	A callback to fire once the spawn is done.
--------------------	--

6.210.3.87 SpawnAsync() [3/5]

```
NetworkSpawnOp SpawnAsync (
    NetworkObjectGuid prefabGuid,
    Vector3? position = null,
    Quaternion? rotation = null,
    PlayerRef? inputAuthority = null,
    OnBeforeSpawned onBeforeSpawned = null,
    NetworkSpawnFlags flags = default,
    NetworkObjectSpawnDelegate onCompleted = null )
```

Attempts to network instantiate a [NetworkObject](#) using a [NetworkObjectGuid](#) Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.

Parameters

<i>prefabGuid</i>	Object Guid used to spawn the NetworkObject
<i>position</i>	Spawn Position
<i>rotation</i>	Spawn Rotation

Parameters

<i>inputAuthority</i>	Player Input Authority
<i>onBeforeSpawned</i>	OnBeforeSpawned reference
<i>flags</i>	Spawn flags

,

Parameters

<i>onCompleted</i>	A callback to fire once the spawn is done.
--------------------	--

6.210.3.88 SpawnAsync() [4/5]

```
NetworkSpawnOp SpawnAsync (
    NetworkPrefabId typeId,
    Vector3? position = null,
    Quaternion? rotation = null,
    PlayerRef? inputAuthority = null,
    OnBeforeSpawned onBeforeSpawned = null,
    NetworkSpawnFlags flags = default,
    NetworkObjectSpawnDelegate onCompleted = null )
```

Attempts to network instantiate a [NetworkObject](#) using a [NetworkPrefabId](#) Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.

Parameters

<i>typeId</i>	Prefab ID used to spawn the NetworkObject
<i>position</i>	Spawn Position
<i>rotation</i>	Spawn Rotation
<i>inputAuthority</i>	Player Input Authority
<i>onBeforeSpawned</i>	OnBeforeSpawned reference
<i>flags</i>	Spawn flags

,

Parameters

<i>onCompleted</i>	A callback to fire once the spawn is done.
--------------------	--

6.210.3.89 SpawnAsync() [5/5]

```
NetworkSpawnOp SpawnAsync (
```



```

NetworkPrefabRef prefabRef,
Vector3? position = null,
Quaternion? rotation = null,
PlayerRef? inputAuthority = null,
OnBeforeSpawned onBeforeSpawned = null,
NetworkSpawnFlags flags = default,
NetworkObjectSpawnDelegate onCompleted = null )

```

Attempts to network instantiate a [NetworkObject](#) using a [NetworkPrefabRef](#). Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.

Parameters

<i>prefabRef</i>	Prefab Ref used to spawn the NetworkObject
<i>position</i>	Spawn Position
<i>rotation</i>	Spawn Rotation
<i>inputAuthority</i>	Player Input Authority
<i>onBeforeSpawned</i>	OnBeforeSpawned reference
<i>flags</i>	Spawn flags

Parameters

<i>onCompleted</i>	A callback to fire once the spawn is done.
--------------------	--

6.210.3.90 SpawnAsync< T >()

```

NetworkSpawnOp SpawnAsync< T > (
    T prefab,
    Vector3? position = null,
    Quaternion? rotation = null,
    PlayerRef? inputAuthority = null,
    OnBeforeSpawned onBeforeSpawned = null,
    NetworkSpawnFlags flags = default,
    NetworkObjectSpawnDelegate onCompleted = null )

```

Attempts to network instantiate a [NetworkObject](#) using a Component type that is part of a [NetworkObject](#)

Template Parameters

<i>T</i>	Must be a Type derived from SimulationBehaviour
----------	---

Parameters

<i>prefab</i>	SimulationBehaviour used to spawn the NetworkObject
---------------	---

Returns

T reference, or null if it was not able to spawn the object

Parameters

<i>onCompleted</i>	A callback to fire once the spawn is done.
<i>position</i>	Spawn Position
<i>rotation</i>	Spawn Rotation
<i>inputAuthority</i>	Player Input Authority
<i>onBeforeSpawned</i>	OnBeforeSpawned reference
<i>flags</i>	Spawn flags

Type Constraints

***T* : [SimulationBehaviour](#)**

6.210.3.91 StartGame()

```
Task<StartGameResult> StartGame (
    StartGameArgs args )
```

Starts the local [Fusion](#) Runner and takes care of all major setup necessary

More about matchmaking: <https://doc.photonengine.com/en-us/fusion/current/manual/matchmaking>

Parameters

<i>args</i>	Custom arguments used to setup the Fusion Simulation
-------------	--

Returns

Task that can be awaited to chain actions

6.210.3.92 TryFindBehaviour()

```
bool TryFindBehaviour (
    NetworkBehaviourId behaviourId,
    out NetworkBehaviour behaviour )
```

Get the [NetworkBehaviour](#) instance for this [NetworkRunner](#) from a [NetworkBehaviourId](#).

Parameters

<i>behaviour↔ Id</i>	NetworkBehaviourId to look forward
<i>behaviour</i>	NetworkBehaviour reference, if found

Returns

True if object was found.

6.210.3.93 TryFindBehaviour< T >()

```
bool TryFindBehaviour< T > (
    NetworkBehaviourId id,
    out T behaviour )
```

Try to find a [NetworkBehaviour](#) with the provided [NetworkBehaviourId](#).

Parameters

<i>id</i>	The NetworkBehaviourId to search for
<i>behaviour</i>	The behaviour found

Template Parameters

<i>T</i>	A NetworkBehaviour type
----------	---

Returns

Returns true if the behaviour was found and it is alive. False otherwise

Type Constraints

***T* : [NetworkBehaviour](#)**

6.210.3.94 TryFindObject()

```
bool TryFindObject (
    NetworkId objectId,
    out NetworkObject networkObject )
```

Get the [NetworkObject](#) instance for this [NetworkRunner](#) from a [NetworkId](#).

Parameters

<i>objectId</i>	Object NetworkID to look forward
<i>networkObject</i>	NetworkObject reference, if found

Returns

True if object was found.

6.210.3.95 TryGetBehaviourStats()

```
bool TryGetBehaviourStats (
    List<(Type, BehaviourStats)> result )
```

Populate the provided list with all registered behaviours and their [BehaviourStats](#).

Parameters

<i>result</i>	The list to be populated
---------------	--------------------------

Returns

Returns true if at least one item is added to the list

6.210.3.96 TryGetInputForPlayer< T >()

```
bool TryGetInputForPlayer< T > (
    PlayerRef player,
    out T input )
```

Outputs the [NetworkInput](#) from player, translated to the indicated [INetworkInput](#).

Type Constraints

***T* : [unmanaged](#)**
***T* : [INetworkInput](#)**

6.210.3.97 TryGetNetworkedBehaviourFromNetworkedObjectRef< T >()

```
T TryGetNetworkedBehaviourFromNetworkedObjectRef< T > (
    NetworkId networkId )
```

Tries to return the first instance of T found on the root of a [NetworkObject](#).

Template Parameters

<i>T</i>	The type of the component to search for
----------	---

Parameters

<i>networkId</i>	NetworkId of the NetworkObject to search for
------------------	--

Returns

Returns the found component. Null if the [NetworkObject](#) cannot be found, or if *T* cannot be found on the [GameObject](#).

Type Constraints

***T* : [NetworkBehaviour](#)**

6.210.3.98 TryGetNetworkedBehaviourId()

```
NetworkBehaviourId TryGetNetworkedBehaviourId (  
    NetworkBehaviour behaviour )
```

Tries to return a [NetworkBehaviourId](#) for the [NetworkBehaviour](#) provided.

Parameters

<i>behaviour</i>	NetworkBehaviour to get the NetworkBehaviourId from
------------------	---

Returns

Returns a [NetworkBehaviourId](#) to the provided behaviour. Returns default if the behaviour is not alive or the [NetworkObject](#) that has this behaviour is not valid.

6.210.3.99 TryGetObjectRefFromNetworkedBehaviour()

```
NetworkId TryGetObjectRefFromNetworkedBehaviour (  
    NetworkBehaviour behaviour )
```

Tries to return the behaviour [NetworkId](#).

Parameters

<i>behaviour</i>	NetworkBehaviour to get the NetworkId from
------------------	--

Returns

Returns the [NetworkId](#) of the provided behaviour. Returns default if the behaviour is not alive or the [NetworkObject](#) that has this behaviour is not valid.

6.210.3.100 TryGetObjectStats()

```
bool TryGetObjectStats (
    NetworkId id,
    out NetworkObjectStats stats )
```

Try to get [NetworkObjectStats](#) buffer for a [NetworkObject](#) from this [NetworkRunner](#).

Returns

Returns false if stats were not available.

6.210.3.101 TryGetPhysicsInfo()

```
bool TryGetPhysicsInfo (
    out NetworkPhysicsInfo info )
```

Try to get the physics info.

Parameters

<i>info</i>	Network physics info
-------------	----------------------

Returns

True if the physics info exists, otherwise false.

6.210.3.102 TryGetPlayerObject()

```
bool TryGetPlayerObject (
    PlayerRef player,
    out NetworkObject networkObject )
```

Try to gets the [NetworkObject](#) associated with a specific player

Parameters

<i>player</i>	PlayerRef to get the network object
<i>networkObject</i>	Network object if one is associated with the player

Returns

Signals if it was able to get a [NetworkObject](#) for the player provided

6.210.3.103 TryGetPlayerStats()

```
bool TryGetPlayerStats (
    PlayerRef player,
    out SimulationConnectionStats stats )
```

Try to get [SimulationConnectionStats](#) buffer for a player reference from this [NetworkRunner](#).

Returns

Returns false if stats were not available.

6.210.3.104 TryGetSceneInfo()

```
bool TryGetSceneInfo (
    out NetworkSceneInfo sceneInfo )
```

Tries to get the [NetworkSceneInfo](#) of this [NetworkRunner](#).

Parameters

<i>sceneInfo</i>	The result NetworkSceneInfo
------------------	---

Returns

Returns true if it was able to get the scene info

6.210.3.105 TryGetSimulationStats()

```
bool TryGetSimulationStats (
    out SimulationStats stats )
```

Try to get [SimulationStats](#) buffer from this [NetworkRunner](#).

Returns

Returns false if stats were not available.

6.210.3.106 TrySetPhysicsInfo()

```
bool TrySetPhysicsInfo (
    NetworkPhysicsInfo info )
```

Try to set the physics info.

Parameters

<i>info</i>	Network physics info
-------------	----------------------

Returns

True if the physics info was set, otherwise false.

Exceptions

<i>InvalidOperationException</i>	Thrown if the runner does not have the scene authority.
----------------------------------	---

6.210.3.107 TrySpawn() [1/5]

```
NetworkSpawnStatus TrySpawn (
    GameObject prefab,
    out NetworkObject obj,
    Vector3? position = null,
    Quaternion? rotation = null,
    PlayerRef? inputAuthority = null,
    OnBeforeSpawned onBeforeSpawned = null,
    NetworkSpawnFlags flags = default )
```

Attempts to network instantiate a [NetworkObject](#) using a `GameObject`. The supplied `GameObject` must have a [NetworkObject](#) component.

Parameters

<i>prefab</i>	A <code>GameObject</code> with a NetworkObject
<i>position</i>	Spawn Position
<i>rotation</i>	Spawn Rotation
<i>inputAuthority</i>	Player Input Authority
<i>onBeforeSpawned</i>	OnBeforeSpawned reference
<i>flags</i>	Spawn flags
<i>obj</i>	Spawned NetworkObject reference

Returns

[NetworkSpawnStatus](#) reference, or null if it was not able to spawn the object

6.210.3.108 TrySpawn() [2/5]

```
NetworkSpawnStatus TrySpawn (
    NetworkObject prefab,
    out NetworkObject obj,
    Vector3? position = null,
    Quaternion? rotation = null,
    PlayerRef? inputAuthority = null,
    OnBeforeSpawned onBeforeSpawned = null,
    NetworkSpawnFlags flags = default )
```

Attempts to network instantiate a [NetworkObject](#) using a [NetworkObject](#) prefab. Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.

Parameters

<i>prefab</i>	Prefab used to spawn the NetworkObject
<i>position</i>	Spawn Position
<i>rotation</i>	Spawn Rotation
<i>inputAuthority</i>	Player Input Authority
<i>onBeforeSpawned</i>	OnBeforeSpawned reference
<i>flags</i>	Spawn flags
<i>obj</i>	Spawned NetworkObject reference

Returns

[NetworkSpawnStatus](#) reference, or null if it was not able to spawn the object

6.210.3.109 TrySpawn() [3/5]

```
NetworkSpawnStatus TrySpawn (
    NetworkObjectGuid prefabGuid,
    out NetworkObject obj,
    Vector3? position = null,
    Quaternion? rotation = null,
    PlayerRef? inputAuthority = null,
    OnBeforeSpawned onBeforeSpawned = null,
    NetworkSpawnFlags flags = default )
```

Attempts to network instantiate a [NetworkObject](#) using a [NetworkObjectGuid](#) Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.

Parameters

<i>prefabGuid</i>	Object Guid used to spawn the NetworkObject
<i>position</i>	Spawn Position
<i>rotation</i>	Spawn Rotation
<i>inputAuthority</i>	Player Input Authority
<i>onBeforeSpawned</i>	OnBeforeSpawned reference
<i>flags</i>	Spawn flags
<i>obj</i>	Spawned NetworkObject reference

Returns

[NetworkSpawnStatus](#) reference, or null if it was not able to spawn the object

6.210.3.110 TrySpawn() [4/5]

```
NetworkSpawnStatus TrySpawn (
    NetworkPrefabId typeId,
    out NetworkObject obj,
    Vector3? position = null,
    Quaternion? rotation = null,
    PlayerRef? inputAuthority = null,
    OnBeforeSpawned onBeforeSpawned = null,
    NetworkSpawnFlags flags = default )
```

Attempts to network instantiate a [NetworkObject](#) using a [NetworkPrefabId](#) Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.

Parameters

<i>typeId</i>	Prefab ID used to spawn the NetworkObject
<i>position</i>	Spawn Position
<i>rotation</i>	Spawn Rotation
<i>inputAuthority</i>	Player Input Authority
<i>onBeforeSpawned</i>	OnBeforeSpawned reference
<i>flags</i>	Spawn flags
<i>obj</i>	Spawned NetworkObject reference

Returns

[NetworkSpawnStatus](#) reference, or null if it was not able to spawn the object

6.210.3.111 TrySpawn() [5/5]

```
NetworkSpawnStatus TrySpawn (
    NetworkPrefabRef prefabRef,
    out NetworkObject obj,
    Vector3? position = null,
    Quaternion? rotation = null,
    PlayerRef? inputAuthority = null,
    OnBeforeSpawned onBeforeSpawned = null,
    NetworkSpawnFlags flags = default )
```

Attempts to network instantiate a [NetworkObject](#) using a [NetworkPrefabRef](#). Note: position and rotation values are only used locally for the instantiation of the object, and are not inherently networked. Use [NetworkTransform](#) (or any custom class derived from [NetworkTRSP](#)) to replicate the initial transform state.

Parameters

<i>prefabRef</i>	Prefab Ref used to spawn the NetworkObject
<i>position</i>	Spawn Position
<i>rotation</i>	Spawn Rotation
<i>inputAuthority</i>	Player Input Authority
<i>onBeforeSpawned</i>	OnBeforeSpawned reference
<i>flags</i>	Spawn flags
<i>obj</i>	Spawned NetworkObject reference

Returns

[NetworkSpawnStatus](#) reference, or null if it was not able to spawn the object

6.210.3.112 TrySpawn< T >()

```
NetworkSpawnStatus TrySpawn< T > (
    T prefab,
    out T obj,
    Vector3? position = null,
    Quaternion? rotation = null,
    PlayerRef? inputAuthority = null,
    OnBeforeSpawned onBeforeSpawned = null,
    NetworkSpawnFlags flags = default )
```

Attempts to network instantiate a [NetworkObject](#) using a Component type that is part of a [NetworkObject](#)

Template Parameters

<i>T</i>	Must be a Type derived from SimulationBehaviour
----------	---

Parameters

<i>prefab</i>	SimulationBehaviour used to spawn the NetworkObject
---------------	---

Returns

T reference, or null if it was not able to spawn the object

Parameters

<i>obj</i>	Spawned NetworkObject reference
<i>position</i>	Spawn Position
<i>rotation</i>	Spawn Rotation
<i>inputAuthority</i>	Player Input Authority
<i>onBeforeSpawned</i>	OnBeforeSpawned reference
<i>flags</i>	Spawn flags

Type Constraints

T : [SimulationBehaviour](#)

6.210.3.113 [UnloadScene\(\)](#)

```
NetworkSceneAsyncOp UnloadScene (
    string sceneName )
```

Unloads a scene

Parameters

<i>sceneName</i>	Name of the scene to unload
------------------	-----------------------------

Returns

Scene Unload operation

6.210.3.114 [UpdateInternal\(\)](#)

```
void UpdateInternal (
    double dt )
```

This method is meant to be called by [INetworkRunnerUpdater](#).

6.210.4 Property Documentation

6.210.4.1 [ActivePlayers](#)

```
IEnumerable<PlayerRef> ActivePlayers [get]
```

Returns the collection of [PlayerRef](#) objects for this [NetworkRunner](#)'s [Fusion.Simulation](#).

6.210.4.2 [AuthenticationValues](#)

```
AuthenticationValues AuthenticationValues [get]
```

[AuthenticationValues](#) used by this Runner to Authenticate the local peer.

6.210.4.3 BuildType

[BuildTypes](#) BuildType [static], [get]

Get Fusion.Runtime.dll build type.

6.210.4.4 CanSpawn

bool CanSpawn [get]

Signal if the Network Runner can spawn a [NetworkObject](#)

6.210.4.5 Config

[NetworkProjectConfig](#) Config [get]

Returns the [NetworkProjectConfig](#) reference.

6.210.4.6 CurrentConnectionType

[ConnectionType](#) CurrentConnectionType [get]

Check the current Connection Type with the Remote Server

6.210.4.7 DeltaTime

float DeltaTime [get]

Returns the fixed tick time interval. Derived from the [SimulationRuntimeConfig.TickRate](#).

6.210.4.8 GameMode

[GameMode](#) GameMode [get]

Current Game Mode active on the [Fusion Simulation](#)

6.210.4.9 Instances

```
ICollection<NetworkRunner> Instances [static], [get]
```

A list of all [NetworkRunners](#).

6.210.4.10 IsClient

```
bool IsClient [get]
```

Returns if this [Fusion.Simulation](#) represents a Client connection.

6.210.4.11 IsCloudReady

```
bool IsCloudReady [get]
```

Signal if the Local Peer is connected to Photon Cloud and is able to Create/Join Room but also receive Lobby Updates

6.210.4.12 IsConnectedToServer

```
bool IsConnectedToServer [get]
```

Returns if this Client is currently connected to a Remote Server

6.210.4.13 IsFirstTick

```
bool IsFirstTick [get]
```

If this is the first tick that executes this update or re-simulation

6.210.4.14 IsForward

```
bool IsForward [get]
```

If this is not a re-simulation but a new forward tick

6.210.4.15 IsLastTick

```
bool IsLastTick [get]
```

If this is the last tick that is being executed this update

6.210.4.16 IsPlayer

```
bool IsPlayer [get]
```

Returns true if this runner represents a Client or Host. Dedicated servers have no local player and will return false.

6.210.4.17 IsResimulation

```
bool IsResimulation [get]
```

If we are currently executing a client side prediction re-simulation.

6.210.4.18 IsResume

```
bool IsResume [get]
```

if this instance is a resume (host migration)

6.210.4.19 IsRunning

```
bool IsRunning [get]
```

Returns if this [Fusion.Simulation](#) is valid and running.

6.210.4.20 IsSceneAuthority

```
bool IsSceneAuthority [get]
```

Is this runner responsible for scene management.

6.210.4.21 IsSceneManagerBusy

```
bool? IsSceneManagerBusy [get]
```

Signals if the [INetworkSceneManager](#) instance assigned to this [NetworkRunner](#) is busy with any scene loading operation.

6.210.4.22 IsServer

```
bool IsServer [get]
```

Returns if this [Fusion.Simulation](#) represents a Server connection.

6.210.4.23 IsSharedModeMasterClient

```
bool IsSharedModeMasterClient [get]
```

Signal if the Local Peer is in a Room and is the Room Master Client

6.210.4.24 IsShutdown

```
bool IsShutdown [get]
```

If the runner is shutdown

6.210.4.25 IsSinglePlayer

```
bool IsSinglePlayer [get]
```

Returns true if this runner was started as single player (Started as [SimulationModes.Host](#) with [SimulationConfig.PlayerCount](#) = 1).

6.210.4.26 IsStarting

```
bool IsStarting [get]
```

If the runner is pending to start

6.210.4.27 LagCompensation

`HitboxManager LagCompensation [get]`

Returns the global instance of a lag compensation buffer [Fusion.HitboxManager](#).

6.210.4.28 LatestServerTick

`Tick LatestServerTick [get]`

Get the latest confirmed tick of the server we are aware of

6.210.4.29 LobbyInfo

`LobbyInfo LobbyInfo = new LobbyInfo() [get]`

Signal if the local peer is already inside a Lobby

6.210.4.30 LocalAlpha

`float LocalAlpha [get]`

Get the local time alpha value

6.210.4.31 LocalPlayer

`PlayerRef LocalPlayer [get]`

Returns a [PlayerRef](#) for the local simulation. For a dedicated server [PlayerRef.IsRealPlayer](#) will equal false. Player↔Refs are assigned in order from 0 to MaxPlayers-1 and are re-used as players join and leave. The only caveat is that the server player (if one exists), always gets the last index no matter how many clients are connected.

6.210.4.32 LocalRenderTime

`float LocalRenderTime [get]`

The current time (current [State.Time](#) + [Simulation.DeltaTime](#)) for predicted objects (objects in the local time frame). Use as an equivalent to Unity's [Time.time](#). Time is relative to [Tick 0](#) (which represents Time 0f).

6.210.4.33 Mode

`SimulationModes Mode [get]`

Returns the [SimulationModes](#) flags for The type of network peer the associated [Fusion.Simulation](#) represents.

6.210.4.34 NATType

`NATType NATType [get]`

Exposes the current NAT Type from the local Peer

6.210.4.35 ObjectProvider

`INetworkObjectProvider ObjectProvider [get]`

Returns the [INetworkObjectProvider](#) instance.

6.210.4.36 Prefabs

`NetworkPrefabTable Prefabs [get]`

Reference to the [NetworkPrefabTable](#).

6.210.4.37 ProvideInput

`bool ProvideInput [get], [set]`

Indicates if this [NetworkRunner](#) is collecting [PlayerRef INetworkInput](#).

6.210.4.38 RemoteRenderTime

`float RemoteRenderTime [get]`

The current time (current `State.Time` + [Simulation.DeltaTime](#)) for non-predicted objects (objects in a remote time frame). Use as an equivalent to Unity's `Time.time`. Time is relative to [Tick 0](#) (which represents Time 0f).

6.210.4.39 SceneManager

`INetworkSceneManager SceneManager [get]`

Returns the [INetworkSceneManager](#) instance.

6.210.4.40 SessionInfo

`SessionInfo SessionInfo = new SessionInfo() [get]`

Stores information about the current running session

6.210.4.41 SimulationTime

`float SimulationTime [get]`

The time the current State represents (the most recent FixedUpdateNetwork simulation). Use as an equivalent to Unity's Time.fixedTime. Time is relative to [Tick 0](#) (which represents Time 0f).

6.210.4.42 SimulationUnityScene

`Scene??? SimulationUnityScene [get]`

The main scene of the [NetworkRunner](#) or default if not running.

6.210.4.43 Stage

`SimulationStages Stage [get]`

Returns the current [SimulationStages](#) stage of this [Fusion.Simulation](#).

6.210.4.44 State

`States State [get]`

The current state of the runner, if it's Starting, Running, Shutdown

6.210.4.45 Tick

`Tick??? Tick [get]`

The tick associated with the current state of networked objects, or the current simulation tick being processed (when evaluated during `FixedUpdateNetwork`).

6.210.4.46 TickRate

`int TickRate [get]`

6.210.4.47 TicksExecuted

`int TicksExecuted [get]`

Returns how many ticks we executed last update.

6.210.4.48 Topology

`Topologies Topology [get]`

The current topology used

6.210.4.49 UserId

`string UserId [get]`

Photon Client UserID

Returns null if Peer is not connected to Photon Cloud

6.210.5 Event Documentation

6.210.5.1 ObjectAcquired

`ObjectDelegate ObjectAcquired`

Event for object acquired

6.211 NetworkRunnerCallbackArgs Class Reference

Stores data types used on the [INetworkRunnerCallbacks](#) interface

Classes

- class [ConnectRequest](#)
Data holder of a Connection Request from a remote client

6.211.1 Detailed Description

Stores data types used on the [INetworkRunnerCallbacks](#) interface

6.212 NetworkRunnerCallbackArgs.ConnectRequest Class Reference

Data holder of a Connection Request from a remote client

Public Member Functions

- void [Accept](#) ()
Accepts the Request
- void [Refuse](#) ()
Refuses the Request
- void [Waiting](#) ()
Refuses the Request

Properties

- [NetAddress RemoteAddress](#) [get, set]
Address of the remote client

6.212.1 Detailed Description

Data holder of a Connection Request from a remote client

6.212.2 Member Function Documentation

6.212.2.1 Accept()

```
void Accept ( )
```

Accepts the Request

6.212.2.2 Refuse()

```
void Refuse ( )
```

Refuses the Request

6.212.2.3 Waiting()

```
void Waiting ( )
```

Refuses the Request

6.212.3 Property Documentation

6.212.3.1 RemoteAddress

```
NetAddress RemoteAddress [get], [set]
```

Address of the remote client

6.213 NetworkRunnerUpdaterDefault Class Reference

Default implementation of [INetworkRunnerUpdater](#) that uses the Unity PlayerLoop.

Inherits [INetworkRunnerUpdater](#).

Classes

- struct [NetworkRunnerRender](#)
Used to invoke [NetworkRunner.RenderInternal](#) in the PlayerLoop.
- struct [NetworkRunnerUpdate](#)
Used to invoke [NetworkRunner.UpdateInternal\(double\)](#) in the PlayerLoop.

Static Public Member Functions

- static bool [RegisterInPlayerLoop](#) ([NetworkRunnerUpdaterDefaultInvokeSettings](#) updateSettings, [NetworkRunnerUpdaterDefaultInvokeSettings](#) renderSettings)
Registers in the PlayerLoop.
- static bool [UnregisterFromPlayerLoop](#) ()
Unregisters from the PlayerLoop.

Public Attributes

- [NetworkRunnerUpdaterDefaultInvokeSettings](#) [RenderSettings](#)
Default settings for the [NetworkRunner](#) Render Loop.
- [NetworkRunnerUpdaterDefaultInvokeSettings](#) [UpdateSettings](#)
Default settings for the [NetworkRunner](#) Update Loop.

Additional Inherited Members

6.213.1 Detailed Description

Default implementation of [INetworkRunnerUpdater](#) that uses the Unity PlayerLoop.

6.213.2 Member Function Documentation

6.213.2.1 RegisterInPlayerLoop()

```
static bool RegisterInPlayerLoop (  
    NetworkRunnerUpdaterDefaultInvokeSettings updateSettings,  
    NetworkRunnerUpdaterDefaultInvokeSettings renderSettings ) [static]
```

Registers in the PlayerLoop.

Parameters

updateSettings	Update settings.
renderSettings	Render settings.

Returns

True if registered, false if already registered with the same settings.

6.213.2.2 UnregisterFromPlayerLoop()

```
static bool UnregisterFromPlayerLoop ( ) [static]
```

Unregisters from the PlayerLoop.

Returns

True if unregistered, false if not registered.

6.213.3 Member Data Documentation

6.213.3.1 RenderSettings

[NetworkRunnerUpdaterDefaultInvokeSettings](#) RenderSettings

Initial value:

```
= new NetworkRunnerUpdaterDefaultInvokeSettings {
    ReferencePlayerLoopSystem = typeof(Update.ScriptRunBehaviourUpdate),
    AddMode                   = UnityPlayerLoopSystemAddMode.After
}
```

Default settings for the [NetworkRunner](#) Render Loop.

6.213.3.2 UpdateSettings

[NetworkRunnerUpdaterDefaultInvokeSettings](#) UpdateSettings

Initial value:

```
= new NetworkRunnerUpdaterDefaultInvokeSettings {
    ReferencePlayerLoopSystem = typeof(Update.ScriptRunBehaviourUpdate),
    AddMode                   = UnityPlayerLoopSystemAddMode.Before
}
```

Default settings for the [NetworkRunner](#) Update Loop.

6.214 NetworkRunnerUpdaterDefault.NetworkRunnerRender Struct Reference

Used to invoke [NetworkRunner.RenderInternal](#) in the PlayerLoop.

6.214.1 Detailed Description

Used to invoke [NetworkRunner.RenderInternal](#) in the PlayerLoop.

6.215 NetworkRunnerUpdaterDefault.NetworkRunnerUpdate Struct Reference

Used to invoke [NetworkRunner.UpdateInternal\(double\)](#) in the PlayerLoop.

6.215.1 Detailed Description

Used to invoke [NetworkRunner.UpdateInternal\(double\)](#) in the PlayerLoop.

6.216 NetworkRunnerUpdaterDefaultInvokeSettings Struct Reference

Settings for the [NetworkRunnerUpdaterDefault](#).

Inherits `IEquatable< NetworkRunnerUpdaterDefaultInvokeSettings >`.

Public Member Functions

- bool [Equals](#) ([NetworkRunnerUpdaterDefaultInvokeSettings](#) other)
Checks if the settings are equal.
- override bool [Equals](#) (object obj)
Checks if the settings are equal.
- override int [GetHashCode](#) ()
Gets the hash code of the settings.
- override string [ToString](#) ()
Returns a string representation of the settings.

Static Public Member Functions

- static bool [operator!=](#) ([NetworkRunnerUpdaterDefaultInvokeSettings](#) left, [NetworkRunnerUpdaterDefaultInvokeSettings](#) right)
Checks if the settings are not equal.
- static bool [operator==](#) ([NetworkRunnerUpdaterDefaultInvokeSettings](#) left, [NetworkRunnerUpdaterDefaultInvokeSettings](#) right)
Checks if the settings are equal.

Public Attributes

- [UnityPlayerLoopSystemAddMode](#) AddMode
Add mode for the PlayerLoopSystem.
- Type [ReferencePlayerLoopSystem](#)
Reference to the PlayerLoopSystem to add the [NetworkRunner](#) to.

6.216.1 Detailed Description

Settings for the [NetworkRunnerUpdaterDefault](#).

6.216.2 Member Function Documentation

6.216.2.1 Equals() [1/2]

```
bool Equals (
    NetworkRunnerUpdaterDefaultInvokeSettings other )
```

Checks if the settings are equal.

Parameters

<i>other</i>	Settings to check for equality.
--------------	---------------------------------

Returns

True if equal, false otherwise.

6.216.2.2 Equals() [2/2]

```
override bool Equals (
    object obj )
```

Checks if the settings are equal.

Parameters

<i>obj</i>	Settings to check for equality.
------------	---------------------------------

Returns

True if equal, false otherwise.

6.216.2.3 GetHashCode()

```
override int GetHashCode ( )
```

Gets the hash code of the settings.

Returns

Hash code.

6.216.2.4 operator!=(())

```
static bool operator!=(  
    NetworkRunnerUpdaterDefaultInvokeSettings left,  
    NetworkRunnerUpdaterDefaultInvokeSettings right ) [static]
```

Checks if the settings are not equal.

Parameters

<i>left</i>	Settings to check for equality.
<i>right</i>	Settings to check for equality.

Returns

True if not equal, false otherwise.

6.216.2.5 operator==(())

```
static bool operator==(  
    NetworkRunnerUpdaterDefaultInvokeSettings left,  
    NetworkRunnerUpdaterDefaultInvokeSettings right ) [static]
```

Checks if the settings are equal.

Parameters

<i>left</i>	Settings to check for equality.
<i>right</i>	Settings to check for equality.

Returns

True if equal, false otherwise.

6.216.2.6 ToString()

```
override string ToString ( )
```

Returns a string representation of the settings.

Returns

String representation.

6.216.3 Member Data Documentation

6.216.3.1 AddMode

`UnityPlayerLoopSystemAddMode` AddMode

Add mode for the PlayerLoopSystem.

6.216.3.2 ReferencePlayerLoopSystem

Type `ReferencePlayerLoopSystem`

Reference to the PlayerLoopSystem to add the [NetworkRunner](#) to.

6.217 NetworkSceneAsyncOp Struct Reference

A wrapper for async scene operations.

Inherits `IEnumerator`.

Classes

- struct [Awaiter](#)
Awaiter for [NetworkSceneAsyncOp](#)

Public Member Functions

- void [AddOnCompleted](#) (Action< [NetworkSceneAsyncOp](#) > action)
Adds a callback to be called when the operation is completed
- [Awaiter](#) [GetAwaiter](#) ()
Gets the awaiter for the operation
- bool `IEnumerator`. **MoveNext** ()
- void `IEnumerator`. **Reset** ()

Static Public Member Functions

- static [NetworkSceneAsyncOp](#) [FromAsyncOperation](#) ([SceneRef](#) sceneRef, `UnityEngine.AsyncOperation` asyncOp)
Creates a [NetworkSceneAsyncOp](#) from a `UnityEngine.AsyncOperation`
- static [NetworkSceneAsyncOp](#) [FromCompleted](#) ([SceneRef](#) sceneRef)
Creates a completed [NetworkSceneAsyncOp](#)
- static [NetworkSceneAsyncOp](#) [FromCoroutine](#) ([SceneRef](#) sceneRef, [ICoroutine](#) coroutine)
Creates a [NetworkSceneAsyncOp](#) from a [ICoroutine](#)
- static [NetworkSceneAsyncOp](#) [FromError](#) ([SceneRef](#) sceneRef, Exception error)
Creates a [NetworkSceneAsyncOp](#) from a `Exception`
- static [NetworkSceneAsyncOp](#) [FromTask](#) ([SceneRef](#) sceneRef, Task task)
Creates a [NetworkSceneAsyncOp](#) from a `Task`

Public Attributes

- readonly [SceneRef](#) [SceneRef](#)
The scene reference of the operation

Properties

- object IEnumerator. **Current** [get]
- Exception? [Error](#) [get]
Attached error to the operation
- bool [IsDone](#) [get]
Signals if the operation is done
- bool [IsValid](#) [get]
Signals if the operation is valid

6.217.1 Detailed Description

A wrapper for async scene operations.

6.217.2 Member Function Documentation

6.217.2.1 AddOnCompleted()

```
void AddOnCompleted (
    Action< NetworkSceneAsyncOp > action )
```

Adds a callback to be called when the operation is completed

Parameters

<i>action</i>	The callback to be called
---------------	---------------------------

6.217.2.2 FromAsyncOperation()

```
static NetworkSceneAsyncOp FromAsyncOperation (
    SceneRef sceneRef,
    UnityEngine.AsyncOperation asyncOp ) [static]
```

Creates a [NetworkSceneAsyncOp](#) from a UnityEngine.AsyncOperation

Parameters

<i>sceneRef</i>	Scene reference
<i>asyncOp</i>	Async operation reference

Returns

Returns a [NetworkSceneAsyncOp](#) instance

Exceptions

<i>ArgumentNullException</i>	Thrown if <i>asyncOp</i> is null
------------------------------	----------------------------------

6.217.2.3 FromCompleted()

```
static NetworkSceneAsyncOp FromCompleted (
    SceneRef sceneRef ) [static]
```

Creates a completed [NetworkSceneAsyncOp](#)

Parameters

<i>sceneRef</i>	Scene reference
-----------------	-----------------

Returns

Returns a [NetworkSceneAsyncOp](#) instance

6.217.2.4 FromCoroutine()

```
static NetworkSceneAsyncOp FromCoroutine (
    SceneRef sceneRef,
    ICoroutine coroutine ) [static]
```

Creates a [NetworkSceneAsyncOp](#) from a [ICoroutine](#)

Parameters

<i>sceneRef</i>	Scene reference
<i>coroutine</i>	Coroutine reference

Returns

Returns a [NetworkSceneAsyncOp](#) instance

Exceptions

<i>ArgumentNullException</i>	Thrown if <i>coroutine</i> is null
------------------------------	------------------------------------

6.217.2.5 FromError()

```
static NetworkSceneAsyncOp FromError (
    SceneRef sceneRef,
    Exception error ) [static]
```

Creates a [NetworkSceneAsyncOp](#) from a Exception

Parameters

<i>sceneRef</i>	Scene reference
<i>error</i>	Exception reference

Returns

Returns a [NetworkSceneAsyncOp](#) instance

Exceptions

<i>ArgumentNullException</i>	Thrown if <i>error</i> is null
------------------------------	--------------------------------

6.217.2.6 FromTask()

```
static NetworkSceneAsyncOp FromTask (
    SceneRef sceneRef,
    Task task ) [static]
```

Creates a [NetworkSceneAsyncOp](#) from a Task

Parameters

<i>sceneRef</i>	Scene reference
<i>task</i>	Task reference

Returns

Returns a [NetworkSceneAsyncOp](#) instance

Exceptions

<i>ArgumentNullException</i>	Thrown if <i>task</i> is null
------------------------------	-------------------------------

6.217.2.7 GetAwaiter()

```
Awaiter GetAwaiter ( )
```

Gets the awaiter for the operation

6.217.3 Member Data Documentation

6.217.3.1 SceneRef

```
readonly SceneRef SceneRef
```

The scene reference of the operation

6.217.4 Property Documentation

6.217.4.1 Error

```
Exception? Error [get]
```

Attached error to the operation

6.217.4.2 IsDone

```
bool IsDone [get]
```

Signals if the operation is done

6.217.4.3 IsValid

```
bool IsValid [get]
```

Signals if the operation is valid

6.218 NetworkSceneAsyncOp.Awaiter Struct Reference

[Awaiter](#) for [NetworkSceneAsyncOp](#)

Inherits [INotifyCompletion](#).

Public Member Functions

- [Awaiter](#) (in [NetworkSceneAsyncOp](#) op)
Creates a new [Awaiter](#) instance
- void [GetResult](#) ()
Gets the result of the operation
- void [OnCompleted](#) (Action continuation)
Adds a callback to be called when the operation is completed

Public Attributes

- [NetworkSceneAsyncOp_op](#)

Properties

- bool [IsCompleted](#) [get]
Signals if the operation is completed

6.218.1 Detailed Description

[Awaiter](#) for [NetworkSceneAsyncOp](#)

6.218.2 Constructor & Destructor Documentation

6.218.2.1 Awaiter()

```
Awaiter (  
    in NetworkSceneAsyncOp op )
```

Creates a new [Awaiter](#) instance

Parameters

<i>op</i>	The operation to await
-----------	------------------------

6.218.3 Member Function Documentation

6.218.3.1 GetResult()

```
void GetResult ( )
```

Gets the result of the operation

6.218.3.2 OnCompleted()

```
void OnCompleted (
    Action continuation )
```

Adds a callback to be called when the operation is completed

Parameters

<i>continuation</i>	The callback to be called
---------------------	---------------------------

6.218.4 Property Documentation

6.218.4.1 IsCompleted

```
bool IsCompleted [get]
```

Signals if the operation is completed

6.219 NetworkSceneInfo Struct Reference

Can store up to 8 active scenes and allows for duplicates. Each write increases [Version](#) which can be used to generate unique scene objects ids for when a scene is supposed to be reloaded.

Inherits [INetworkStruct](#), and `IEquatable< NetworkSceneInfo >`.

Public Member Functions

- int [AddSceneRef](#) ([SceneRef](#) sceneRef, LoadSceneMode loadSceneMode=LoadSceneMode.Single, Local↔PhysicsMode localPhysicsMode=LocalPhysicsMode.None, bool activeOnLoad=false)
Adds a scene to the list
- bool [Equals](#) ([NetworkSceneInfo](#) other)
Compares two [NetworkSceneInfo](#) for equality
- override bool [Equals](#) (object obj)
Compares two [NetworkSceneInfo](#) for equality
- override int [GetHashCode](#) ()
Get the hash code of the [NetworkSceneInfo](#)
- int [IndexOf](#) (([SceneRef](#) sceneRef, [NetworkLoadSceneParameters](#) sceneParams) scene)
- int [IndexOf](#) ([SceneRef](#) sceneRef, [NetworkLoadSceneParameters](#) sceneParams)
Gets the index of the given scene
- bool [RemoveSceneRef](#) ([SceneRef](#) sceneRef)
Removes a scene from the list
- override string [ToString](#) ()
String representation of the [NetworkSceneInfo](#)

Static Public Member Functions

- static implicit [operator \[NetworkSceneInfo\]\(#\)](#) ([SceneRef](#) sceneRef)
Implicit conversion to [NetworkSceneInfo](#)

Static Public Attributes

- const int [MaxScenes](#) = 8
Max number of scenes that can be stored
- const int [SIZE](#) = 52
The size of the struct in bytes
- const int [WORD_COUNT](#) = 13
The size of the struct in words

Properties

- int [SceneCount](#) [get]
Total Scene Count
- [FixedArray](#)< [NetworkLoadSceneParameters](#) > [SceneParams](#) [get]
The scenes load parameters list
- [FixedArray](#)< [SceneRef](#) > [Scenes](#) [get]
The scenes list
- int [Version](#) [get]
Version number

6.219.1 Detailed Description

Can store up to 8 active scenes and allows for duplicates. Each write increases [Version](#) which can be used to generate unique scene objects ids for when a scene is supposed to be reloaded.

6.219.2 Member Function Documentation

6.219.2.1 AddSceneRef()

```
int AddSceneRef (
    SceneRef sceneRef,
    LoadSceneMode loadSceneMode = LoadSceneMode.Single,
    LocalPhysicsMode localPhysicsMode = LocalPhysicsMode.None,
    bool activeOnLoad = false )
```

Adds a scene to the list

Parameters

<i>sceneRef</i>	Scene to add
<i>loadSceneMode</i>	Load scene mode
<i>localPhysicsMode</i>	Local physics mode
<i>activeOnLoad</i>	Signals if the scene should be active on load

Returns

Returns the index of the scene or -1 if the scene could not be added

6.219.2.2 Equals() [1/2]

```
bool Equals (
    NetworkSceneInfo other )
```

Compares two [NetworkSceneInfo](#) for equality

Parameters

<i>other</i>	The other NetworkSceneInfo
--------------	--

Returns

Returns true if the two [NetworkSceneInfo](#) are equal

6.219.2.3 Equals() [2/2]

```
override bool Equals (
    object obj )
```

Compares two [NetworkSceneInfo](#) for equality

Parameters

<i>obj</i>	The other NetworkSceneInfo
------------	--

Returns

Returns true if the two [NetworkSceneInfo](#) are equal

6.219.2.4 GetHashCode()

```
override int GetHashCode ( )
```

Get the hash code of the [NetworkSceneInfo](#)

Returns

Hasht code of the [NetworkSceneInfo](#)

6.219.2.5 IndexOf()

```
int IndexOf (
    SceneRef sceneRef,
    NetworkLoadSceneParameters sceneParams )
```

Gets the index of the given scene

Parameters

<i>sceneRef</i>	SceneRef to look for
<i>sceneParams</i>	Scene parameters to look for

Returns

Returns the index of the scene or -1 if not found

6.219.2.6 operator NetworkSceneInfo()

```
static implicit operator NetworkSceneInfo (
    SceneRef sceneRef ) [static]
```

Implicit conversion to [NetworkSceneInfo](#)

Parameters

<i>sceneRef</i>	SceneRef to convert
-----------------	-------------------------------------

Returns

Returns a [NetworkSceneInfo](#) instance

6.219.2.7 RemoveSceneRef()

```
bool RemoveSceneRef (
    SceneRef sceneRef )
```

Removes a scene from the list

Parameters

<i>sceneRef</i>	Scene to remove
-----------------	-----------------

Returns

Returns true if the scene was removed

6.219.2.8 ToString()

```
override string ToString ( )
```

String representation of the [NetworkSceneInfo](#)

6.219.3 Member Data Documentation**6.219.3.1 MaxScenes**

```
const int MaxScenes = 8 [static]
```

Max number of scenes that can be stored

6.219.3.2 SIZE

```
const int SIZE = 52 [static]
```

The size of the struct in bytes

6.219.3.3 WORD_COUNT

```
const int WORD_COUNT = 13 [static]
```

The size of the struct in words

6.219.4 Property Documentation

6.219.4.1 SceneCount

```
int SceneCount [get]
```

Total Scene Count

6.219.4.2 SceneParams

```
FixedArray<NetworkLoadSceneParameters> SceneParams [get]
```

The scenes load parameters list

6.219.4.3 Scenes

```
FixedArray<SceneRef> Scenes [get]
```

The scenes list

6.219.4.4 Version

```
int Version [get]
```

Version number

6.220 NetworkSceneLoadId Struct Reference

A unique identifier for a scene load operation.

Inherits IEquatable< NetworkSceneLoadId >.

Public Member Functions

- bool [Equals](#) ([NetworkSceneLoadId](#) other)
Compares two [NetworkSceneLoadId](#) for equality
- override bool [Equals](#) (object obj)
Compares two [NetworkSceneLoadId](#) for equality
- override int [GetHashCode](#) ()
Returns the hash code of the [NetworkSceneLoadId](#)
- [NetworkSceneLoadId](#) (byte value)
Creates a new [NetworkSceneLoadId](#) with the given value

Public Attributes

- readonly byte [Value](#)
The value of the id

6.220.1 Detailed Description

A unique identifier for a scene load operation.

6.220.2 Constructor & Destructor Documentation

6.220.2.1 NetworkSceneLoadId()

```
NetworkSceneLoadId (  
    byte value )
```

Creates a new [NetworkSceneLoadId](#) with the given value

Parameters

<i>value</i>	The value of the id
--------------	---------------------

6.220.3 Member Function Documentation

6.220.3.1 Equals() [1/2]

```
bool Equals (
    NetworkSceneLoadId other )
```

Compares two [NetworkSceneLoadId](#) for equality

Parameters

<i>other</i>	The other NetworkSceneLoadId
--------------	--

Returns

Returns true if the two [NetworkSceneLoadId](#) are equal

6.220.3.2 Equals() [2/2]

```
override bool Equals (
    object obj )
```

Compares two [NetworkSceneLoadId](#) for equality

Parameters

<i>obj</i>	The other object to check
------------	---------------------------

Returns

Returns true if the two [NetworkSceneLoadId](#) are equal

6.220.3.3 GetHashCode()

```
override int GetHashCode ( )
```

Returns the hash code of the [NetworkSceneLoadId](#)

6.220.4 Member Data Documentation

6.220.4.1 Value

```
readonly byte Value
```

The value of the id

6.221 NetworkSceneObjectId Struct Reference

A unique identifier for a scene object.

Inherits `IEquatable< NetworkSceneObjectId >`.

Public Member Functions

- `bool Equals (NetworkSceneObjectId other)`
Check if two [NetworkSceneObjectId](#) are equal.
- `override bool Equals (object obj)`
Check if two [NetworkSceneObjectId](#) are equal.
- `override int GetHashCode ()`
Get the hash code of the [NetworkSceneObjectId](#).
- `override string ToString ()`
String representation of the [NetworkSceneObjectId](#).

Public Attributes

- `int ObjectId`
Index of the object in the scene or any other form of unique identifier.
- `SceneRef Scene`
Identifies the scene in which the object is located.
- `int SceneLoadId`
Unique identifier of a specific scene load. Needs to be used when loading multiple scenes with the same [SceneRef](#) or reloading a scene. For example, [NetworkSceneInfo](#) increments its internal `LoadId` every time a new scene is added.

Properties

- `bool IsValid [get]`
Signal if the [NetworkSceneObjectId](#) is valid.

6.221.1 Detailed Description

A unique identifier for a scene object.

6.221.2 Member Function Documentation

6.221.2.1 Equals() [1/2]

```
bool Equals (
    NetworkSceneObjectId other )
```

Check if two [NetworkSceneObjectId](#) are equal.

Parameters

<i>other</i>	Another NetworkSceneObjectId to check for equality
--------------	--

Returns

Returns true if the two [NetworkSceneObjectId](#) are equal

6.221.2.2 Equals() [2/2]

```
override bool Equals (  
    object obj )
```

Check if two [NetworkSceneObjectId](#) are equal.

Parameters

<i>obj</i>	Another NetworkSceneObjectId to check for equality
------------	--

Returns

Returns true if the two [NetworkSceneObjectId](#) are equal

6.221.2.3 GetHashCode()

```
override int GetHashCode ( )
```

Get the hash code of the [NetworkSceneObjectId](#).

6.221.2.4 ToString()

```
override string ToString ( )
```

String representation of the [NetworkSceneObjectId](#).

6.221.3 Member Data Documentation

6.221.3.1 ObjectId

`int ObjectId`

Index of the object in the scene or any other form of unique identifier.

6.221.3.2 Scene

[SceneRef](#) Scene

Identifies the scene in which the object is located.

6.221.3.3 SceneLoadId

`int SceneLoadId`

Unique identifier of a specific scene load. Needs to be used when loading multiple scenes with the same [SceneRef](#) or reloading a scene. For example, [NetworkSceneInfo](#) increments its internal LoadId every time a new scene is added.

6.221.4 Property Documentation

6.221.4.1 IsValid

`bool IsValid [get]`

Signal if the [NetworkSceneObjectId](#) is valid.

6.222 NetworkSerializeMethodAttribute Class Reference

Network Serialize Method Attribute

Inherits Attribute.

Properties

- `int MaxSize [get, set]`

If set, this changes expected Wrap method signature to `int Name(NetworkRunner, T, byte*)` and Unwrap to `int Name(NetworkRunner, byte*, ref T)`. In both cases, the result is the number of bytes written/read and can not be greater than what's declared here.

6.222.1 Detailed Description

Network Serialize Method Attribute

6.222.2 Property Documentation

6.222.2.1 MaxSize

```
int MaxSize [get], [set]
```

If set, this changes expected Wrap method signature to `int Name(NetworkRunner, T, byte*)` and Unwrap to `int Name(NetworkRunner, byte*, ref T)`. In both cases, the result is the number of bytes written/read and can not be greater than what's declared here.

6.223 NetworkSimulationConfiguration Class Reference

Configuration for network conditions simulation (induced latency and loss).

Public Member Functions

- [NetworkSimulationConfiguration Clone](#) ()
Creates a copy of this [NetworkSimulationConfiguration](#).
- `NetConfigSimulation Create` ()
Creates a new `NetConfigSimulation` based on the current configuration.

Public Attributes

- double [AdditionalJitter](#) = 0.05
After the delay value from the [DelayShape](#) oscillator is determined, random 0 to this value of additional seconds be added to the packet latency.
- double [AdditionalLoss](#) = 0
After the [LossChanceShape](#) oscillation loss chance is calculated, an additional random value of 0 to this (normalized) percentage of loss chance is added.
- double [DelayMax](#) = 0.15
The highest packet delay value returned from the [DelayShape](#) oscillator.
- double [DelayMin](#) = 0.15
The lowest packet delay value returned from the [DelayShape](#) oscillator.
- double [DelayPeriod](#) = 0
The period of the [DelayShape](#) oscillator (the rate at which delay oscillates in seconds).
- `NetConfigSimulationOscillator.WaveShape` [DelayShape](#) = `NetConfigSimulationOscillator.WaveShape.Noise`
The pattern used to oscillate between [DelayMin](#) and [DelayMax](#) values.
- double [DelayThreshold](#) = 0
The [DelayShape](#) oscillates between 0 and 1. Values below this threshold are reduced to zero, resulting in a value equal to [DelayMin](#).

- bool [Enabled](#)
If adverse network conditions are being simulated.
- double [LossChanceMax](#) = 0.05
The highest loss chance value the [LossChanceShape](#) oscillator will produce. 0 = 0% chance of being lost. 1 = 100% chance of being lost.
- double [LossChanceMin](#) = 0.05
The lowest loss chance value the [LossChanceShape](#) oscillator will produce. 0 = 0% chance of being lost. 1 = 100% chance of being lost.
- double [LossChancePeriod](#) = 0
The period of the [LossChanceShape](#) oscillator (the rate at which delay oscillates between [LossChanceMin](#) and [LossChanceMax](#)).
- NetConfigSimulationOscillator.WaveShape [LossChanceShape](#) = NetConfigSimulationOscillator.Wave↔Shape.Noise
The pattern used to oscillate between [LossChanceMin](#) and [LossChanceMax](#) values.
- double [LossChanceThreshold](#) = 0
The [LossChanceShape](#) wave oscillates between 0 and 1. Values below this threshold are reduced to zero, resulting in a value equal to [LossChanceMin](#).

6.223.1 Detailed Description

Configuration for network conditions simulation (induced latency and loss).

6.223.2 Member Function Documentation

6.223.2.1 Clone()

```
NetworkSimulationConfiguration Clone ( )
```

Creates a copy of this [NetworkSimulationConfiguration](#).

6.223.2.2 Create()

```
NetConfigSimulation Create ( )
```

Creates a new NetConfigSimulation based on the current configuration.

Returns

A new NetConfigSimulation based on the current configuration.

6.223.3 Member Data Documentation

6.223.3.1 AdditionalJitter

```
double AdditionalJitter = 0.05
```

After the delay value from the [DelayShape](#) oscillator is determined, random 0 to this value of additional seconds be added to the packet latency.

6.223.3.2 AdditionalLoss

```
double AdditionalLoss = 0
```

After the [LossChanceShape](#) oscillation loss chance is calculated, an additional random value of 0 to this (normalized) percentage of loss chance is added.

6.223.3.3 DelayMax

```
double DelayMax = 0.15
```

The highest packet delay value returned from the [DelayShape](#) oscillator.

6.223.3.4 DelayMin

```
double DelayMin = 0.15
```

The lowest packet delay value returned from the [DelayShape](#) oscillator.

6.223.3.5 DelayPeriod

```
double DelayPeriod = 0
```

The period of the [DelayShape](#) oscillator (the rate at which delay oscillates in seconds).

6.223.3.6 DelayShape

```
NetConfigSimulationOscillator.WaveShape DelayShape = NetConfigSimulationOscillator.WaveShape.Noise
```

The pattern used to oscillate between [DelayMin](#) and [DelayMax](#) values.

6.223.3.7 DelayThreshold

```
double DelayThreshold = 0
```

The [DelayShape](#) oscillates between 0 and 1. Values below this threshold are reduced to zero, resulting in a value equal to [DelayMin](#).

6.223.3.8 Enabled

```
bool Enabled
```

If adverse network conditions are being simulated.

6.223.3.9 LossChanceMax

```
double LossChanceMax = 0.05
```

The highest loss chance value the [LossChanceShape](#) oscillator will produce. 0 = 0% chance of being lost. 1 = 100% chance of being lost.

6.223.3.10 LossChanceMin

```
double LossChanceMin = 0.05
```

The lowest loss chance value the [LossChanceShape](#) oscillator will produce. 0 = 0% chance of being lost. 1 = 100% chance of being lost.

6.223.3.11 LossChancePeriod

```
double LossChancePeriod = 0
```

The period of the [LossChanceShape](#) oscillator (the rate at which delay oscillates between [LossChanceMin](#) and [LossChanceMax](#)).

6.223.3.12 LossChanceShape

```
NetConfigSimulationOscillator.WaveShape LossChanceShape = NetConfigSimulationOscillator.Wave↵  
Shape.Noise
```

The pattern used to oscillate between [LossChanceMin](#) and [LossChanceMax](#) values.

6.223.3.13 LossChanceThreshold

```
double LossChanceThreshold = 0
```

The [LossChanceShape](#) wave oscillates between 0 and 1. Values below this threshold are reduced to zero, resulting in a value equal to [LossChanceMin](#).

6.224 NetworkSpawnOp Struct Reference

Spawn Operation

Classes

- struct [Awaiter](#)
[Awaiter](#) for [NetworkSpawnOp](#)

Public Member Functions

- [Awaiter](#) [GetAwaiter](#) ()
Get this Spawn Operation [Awaiter](#)

Public Attributes

- readonly [NetworkRunner](#) [Runner](#)
Network Runner Reference

Properties

- bool [IsFailed](#) [get]
Returns true if the object has failed to spawn.
- bool [IsQueued](#) [get]
Returns true if the object is still queued for spawning.
- bool [IsSpawned](#) [get]
Returns true if the object has been spawned.
- [NetworkObject](#) [Object](#) [get]
Get the spawned Network Object
- [NetworkSpawnStatus](#) [Status](#) [get]
Get the Spawn Operation Status

6.224.1 Detailed Description

Spawn Operation

6.224.2 Member Function Documentation

6.224.2.1 GetAwaiter()

`Awaiter` GetAwaiter ()

Get this Spawn Operation [Awaiter](#)

6.224.3 Member Data Documentation

6.224.3.1 Runner

readonly `NetworkRunner` Runner

Network Runner Reference

6.224.4 Property Documentation

6.224.4.1 IsFailed

`bool` IsFailed [get]

Returns true if the object has failed to spawn.

6.224.4.2 IsQueued

`bool` IsQueued [get]

Returns true if the object is still queued for spawning.

6.224.4.3 IsSpawned

`bool` IsSpawned [get]

Returns true if the object has been spawned.

6.224.4.4 Object

[NetworkObject](#) Object [get]

Get the spawned Network Object

6.224.4.5 Status

[NetworkSpawnStatus](#) Status [get]

Get the Spawn Operation Status

6.225 NetworkSpawnOp.Awaiter Struct Reference

[Awaiter](#) for [NetworkSpawnOp](#)

Inherits [INotifyCompletion](#).

Public Member Functions

- [Awaiter](#) (in [NetworkSpawnOp](#) op)
[Awaiter](#) Constructor
- [NetworkObject](#) [GetResult](#) ()
Get the result of the Spawn Operation
- void [OnCompleted](#) (Action continuation)
[Awaiter](#) OnCompleted Callback

Public Attributes

- [NetworkSpawnOp](#) [_op](#)

Properties

- bool [IsCompleted](#) [get]
Returns true if the Spawn Operation is completed

6.225.1 Detailed Description

[Awaiter](#) for [NetworkSpawnOp](#)

6.225.2 Constructor & Destructor Documentation

6.225.2.1 Awaiter()

```
Awaiter (  
    in NetworkSpawnOp op )
```

[Awaiter](#) Constructor

Parameters

<i>op</i>	Spawn Operation
-----------	-----------------

6.225.3 Member Function Documentation

6.225.3.1 GetResult()

`NetworkObject` GetResult ()

Get the result of the Spawn Operation

Returns

Spawned Network Object

Exceptions

<code>NetworkObjectSpawnException</code>	Thrown if the Spawn Operation failed
--	--------------------------------------

6.225.3.2 OnCompleted()

```
void OnCompleted (
    Action continuation )
```

[`Awaiter`](#) OnCompleted Callback

Parameters

<i>continuation</i>	Continuation Action
---------------------	---------------------

Exceptions

<code>NotSupportedException</code>	Thrown if the Spawn Operation is not supported
--	--

6.225.4 Property Documentation

6.225.4.1 IsCompleted

```
bool IsCompleted [get]
```

Returns true if the Spawn Operation is completed

6.226 NetworkString< TSize > Class Template Reference

Fixed-size UTF32 string. All operations are alloc-free, except for converting to System.String.

Inherits INetworkString, [INetworkStruct](#), [IEquatable< NetworkString< TSize >>](#), and [IEnumerable< char >](#).

Public Member Functions

- void [Assign](#) (string value)
Assign a new value to this [NetworkString](#).
- int [Compare](#) ([NetworkString< TSize >](#) s)
Compares this instance with a specified [NetworkString](#).
- int [Compare](#) (ref [NetworkString< TSize >](#) s)
Compares this instance with a specified [NetworkString](#).
- int [Compare](#) (string s)
Compares this instance with a specified string.
- int [Compare< TOtherSize >](#) ([NetworkString< TOtherSize >](#) other)
Compares this instance with a specified [NetworkString](#) of a different size.
- int [Compare< TOtherSize >](#) (ref [NetworkString< TOtherSize >](#) other)
Compares this instance with a specified [NetworkString](#) of a different size.
- bool [Contains](#) (char c)
Determines whether a specified character is in this instance.
- bool [Contains](#) (string str)
Determines whether a specified string is in this instance.
- bool [Contains](#) (uint codePoint)
Determines whether a specified Unicode code point is in this instance.
- bool [Contains< TOtherSize >](#) ([NetworkString< TOtherSize >](#) str)
Determines whether a specified [NetworkString](#) is in this instance.
- bool [Contains< TOtherSize >](#) (ref [NetworkString< TOtherSize >](#) str)
Determines whether a specified [NetworkString](#) is in this instance.
- bool [EndsWith](#) (string s)
Checks if the current [NetworkString](#) ends with a specified string.
- bool [EndsWith< TOtherSize >](#) (ref [NetworkString< TOtherSize >](#) other)
Checks if the current [NetworkString](#) ends with a specified [NetworkString](#) of a different size.
- bool [Equals](#) ([NetworkString< TSize >](#) other)
Determines whether the current [NetworkString](#) is equal to a specified [NetworkString](#).
- override bool [Equals](#) (object obj)
Determines whether the current [NetworkString](#) is equal to a specified object.
- bool [Equals](#) (ref [NetworkString< TSize >](#) other)
Determines whether the current [NetworkString](#) is equal to a specified [NetworkString](#).
- bool [Equals](#) (string s)
Determines whether the current [NetworkString](#) is equal to a specified string.
- bool [Equals< TOtherSize >](#) ([NetworkString< TOtherSize >](#) other)

- Determines whether the current [NetworkString](#) is equal to a specified [NetworkString](#) of a different size.*

 - bool [Equals< TOtherSize >](#) (ref [NetworkString](#)< TOtherSize > other)
- Determines whether the current [NetworkString](#) is equal to a specified [NetworkString](#) of a different size.*

 - bool [Get](#) (ref string cache)
- Checks if cache is equivalent and if not converts to UTF16 and stores the result in cache .*

 - int [GetCharCount](#) ()
- Calculates the length of the equivalent UTF16 string.*

 - UTF32Tools.CharEnumerator [GetEnumerator](#) ()
- Returns an enumerator that iterates through the [NetworkString](#).*

 - IEnumerator< char > IEnumerable< char >. **[GetEnumerator](#)** ()
 - IEnumerator IEnumerable. **[GetEnumerator](#)** ()
 - override int [GetHashCode](#) ()
- Returns the hash code for this [NetworkString](#).*

 - int [IndexOf](#) (char c, int startIndex, int count)
- Returns the index of the first occurrence of a specified character in this instance.*

 - int [IndexOf](#) (char c, int startIndex=0)
- Returns the index of the first occurrence of a specified character in this instance.*

 - int [IndexOf](#) (string str, int startIndex, int count)
- Returns the index of the first occurrence of a specified string in this instance.*

 - int [IndexOf](#) (string str, int startIndex=0)
- Returns the index of the first occurrence of a specified string in this instance.*

 - int [IndexOf](#) (uint codePoint, int startIndex, int count)
- Returns the index of the first occurrence of a specified Unicode code point in this instance.*

 - int [IndexOf](#) (uint codePoint, int startIndex=0)
- Returns the index of the first occurrence of a specified Unicode code point in this instance.*

 - int [IndexOf< TOtherSize >](#) ([NetworkString](#)< TOtherSize > str, int startIndex, int count)
- Returns the index of the first occurrence of a specified [NetworkString](#) in this instance.*

 - int [IndexOf< TOtherSize >](#) ([NetworkString](#)< TOtherSize > str, int startIndex=0)
- Returns the index of the first occurrence of a specified [NetworkString](#) in this instance.*

 - int [IndexOf< TOtherSize >](#) (ref [NetworkString](#)< TOtherSize > str, int startIndex, int count)
- Returns the index of the first occurrence of a specified [NetworkString](#) in this instance.*

 - int [IndexOf< TOtherSize >](#) (ref [NetworkString](#)< TOtherSize > str, int startIndex=0)
- Returns the index of the first occurrence of a specified [NetworkString](#) in this instance.*

 - [NetworkString](#) (string value)
- Creates a new instance of [NetworkString<Size>](#) with the given value.*

 - bool [Set](#) (string value)
- Converts value to UTF32 string and stores it internally.*

 - bool [StartsWith](#) (string s)
- Checks if the current [NetworkString](#) starts with a specified string.*

 - bool [StartsWith< TOtherSize >](#) (ref [NetworkString](#)< TOtherSize > other)
- Checks if the current [NetworkString](#) starts with a specified [NetworkString](#) of a different size.*

 - [NetworkString](#)< TSize > [Substring](#) (int startIndex)
- Returns a substring from this instance. The substring starts at a specified character position.*

 - [NetworkString](#)< TSize > [Substring](#) (int startIndex, int length)
- Returns a substring from this instance. The substring starts at a specified character position and has a specified length.*

 - [NetworkString](#)< TSize > [ToLower](#) ()
- Converts all the characters in this [NetworkString](#) to lowercase.*

 - override string [ToString](#) ()
- Converts the value of this [NetworkString](#) to its equivalent string representation.*

 - [NetworkString](#)< TSize > [ToUpper](#) ()
- Converts all the characters in this [NetworkString](#) to uppercase.*

Static Public Member Functions

- static int [GetCapacity< TSize > \(\)](#)
Gets the capacity of a [NetworkString](#) of a specified size.
- static implicit [operator NetworkString< TSize > \(string str\)](#)
Defines an implicit conversion of a string to a [NetworkString](#).
- static [operator string \(NetworkString< TSize > str\)](#)
Defines an explicit conversion of a [NetworkString](#) to a string.
- static bool [operator!= \(NetworkString< TSize > a, NetworkString< TSize > b\)](#)
Defines an inequality operator for [NetworkString](#).
- static bool [operator!= \(NetworkString< TSize > a, string b\)](#)
Defines an inequality operator for a [NetworkString](#) and a string.
- static bool [operator!= \(string a, NetworkString< TSize > b\)](#)
Defines an inequality operator for a string and a [NetworkString](#).
- static bool [operator== \(NetworkString< TSize > a, NetworkString< TSize > b\)](#)
Defines an equality operator for [NetworkString](#).
- static bool [operator== \(NetworkString< TSize > a, string b\)](#)
Defines an equality operator for a [NetworkString](#) and a string.
- static bool [operator== \(string a, NetworkString< TSize > b\)](#)
Defines an equality operator for a string and a [NetworkString](#).

Properties

- int [Capacity](#) [get]
Maximum UTF32 string length.
- int [Length](#) [get]
Number of UTF32 scalars. It is equal or less than [GetCharCount](#) or the length of [Value](#), because those use UTF16 encoding, which needs two characters to encode some values.
- ref uint [this\[int index\]](#) [get]
Returns UTF32 scalar at index position. To iterate over characters, use [GetEnumerator](#).
- string [Value](#) [get, set]
Converts to/from regular UTF16 string. Setter is alloc-free. Use [Get](#) to get possibly alloc-free conversion.

6.226.1 Detailed Description

Fixed-size UTF32 string. All operations are alloc-free, except for converting to System.String.

Provides static methods for [NetworkString](#) operations.

Template Parameters

TSize	
-----------------------	--

Type Constraints

TSize : unmanaged

TSize : [IFixedStorage](#)

6.226.2 Constructor & Destructor Documentation

6.226.2.1 NetworkString()

```
NetworkString (
    string value )
```

Creates a new instance of [NetworkString<Size>](#) with the given value.

Parameters

<i>value</i>	String value.
--------------	---------------

6.226.3 Member Function Documentation

6.226.3.1 Assign()

```
void Assign (
    string value )
```

Assign a new value to this [NetworkString](#).

Parameters

<i>value</i>	String value.
--------------	---------------

6.226.3.2 Compare() [1/3]

```
int Compare (
    NetworkString< TSize > s )
```

Compares this instance with a specified [NetworkString](#).

Parameters

<i>s</i>	The NetworkString to compare.
----------	---

Returns

A 32-bit signed integer that indicates the comparison result.

6.226.3.3 Compare() [2/3]

```
int Compare (
    ref NetworkString< TSize > s )
```

Compares this instance with a specified [NetworkString](#).

Parameters

s	The NetworkString to compare.
----------	---

Returns

A 32-bit signed integer that indicates the comparison result.

6.226.3.4 Compare() [3/3]

```
int Compare (
    string s )
```

Compares this instance with a specified string.

Parameters

s	The string to compare.
----------	------------------------

Returns

A 32-bit signed integer that indicates the comparison result.

6.226.3.5 Compare< TOtherSize >() [1/2]

```
int Compare< TOtherSize > (
    NetworkString< TOtherSize > other )
```

Compares this instance with a specified [NetworkString](#) of a different size.

Template Parameters

<i>TOtherSize</i>	The size of the other NetworkString .
-------------------	---

Parameters

<i>other</i>	The NetworkString to compare.
--------------	---

Returns

A 32-bit signed integer that indicates the comparison result.

Type Constraints

TOtherSize : unmanaged

TOtherSize : IFixedStorage

TOtherSize : Compare

TOtherSize : ref

TOtherSize : other

6.226.3.6 Compare< TOtherSize >() [2/2]

```
int Compare< TOtherSize > (  
    ref NetworkString< TOtherSize > other )
```

Compares this instance with a specified [NetworkString](#) of a different size.

Template Parameters

<i>TOtherSize</i>	The size of the other NetworkString .
-------------------	---

Parameters

<i>other</i>	The NetworkString to compare.
--------------	---

Returns

A 32-bit signed integer that indicates the comparison result.

Type Constraints

TOtherSize : unmanaged

TOtherSize : IFixedStorage

6.226.3.7 Contains() [1/3]

```
bool Contains (
    char c )
```

Determines whether a specified character is in this instance.

Parameters

<i>c</i>	The Unicode character to seek.
----------	--------------------------------

Returns

true if the value parameter occurs within this string, or if value is the empty string (""); otherwise, false.

6.226.3.8 Contains() [2/3]

```
bool Contains (
    string str )
```

Determines whether a specified string is in this instance.

Parameters

<i>str</i>	The string to seek.
------------	---------------------

Returns

true if the value parameter occurs within this string, or if value is the empty string (""); otherwise, false.

6.226.3.9 Contains() [3/3]

```
bool Contains (
    uint codePoint )
```

Determines whether a specified Unicode code point is in this instance.

Parameters

<i>codePoint</i>	The Unicode code point to seek.
------------------	---------------------------------

Returns

true if the value parameter occurs within this string, or if value is the empty string (""); otherwise, false.

6.226.3.10 Contains< TOtherSize >() [1/2]

```
bool Contains< TOtherSize > (
    NetworkString< TOtherSize > str )
```

Determines whether a specified [NetworkString](#) is in this instance.

Template Parameters

<i>TOtherSize</i>	The size of the other NetworkString .
-------------------	---

Parameters

<i>str</i>	The NetworkString to seek.
------------	--

Returns

true if the value parameter occurs within this string, or if value is the empty string (""); otherwise, false.

Type Constraints

TOtherSize : unmanaged
TOtherSize : IFixedStorage
TOtherSize : IndexOf
TOtherSize : ref
TOtherSize : str

6.226.3.11 Contains< TOtherSize >() [2/2]

```
bool Contains< TOtherSize > (
    ref NetworkString< TOtherSize > str )
```

Determines whether a specified [NetworkString](#) is in this instance.

Template Parameters

<i>TOtherSize</i>	The size of the other NetworkString .
-------------------	---

Parameters

<i>str</i>	The NetworkString to seek.
------------	--

Returns

true if the value parameter occurs within this string, or if value is the empty string (""); otherwise, false.

Type Constraints

TOtherSize : unmanaged

TOtherSize : IFixedStorage

TOtherSize : IndexOf

TOtherSize : ref

TOtherSize : str

6.226.3.12 EndsWith()

```
bool EndsWith (
    string s )
```

Checks if the current [NetworkString](#) ends with a specified string.

Parameters

s	The string to check.
----------	----------------------

Returns

true if the current [NetworkString](#) ends with the specified string; otherwise, false.

Exceptions

<i>ArgumentNullException</i>	Thrown when the string is null.
-------------------------------------	---------------------------------

6.226.3.13 EndsWith< TOtherSize >()

```
bool EndsWith< TOtherSize > (
    ref NetworkString< TOtherSize > other )
```

Checks if the current [NetworkString](#) ends with a specified [NetworkString](#) of a different size.

Template Parameters

<i>TOtherSize</i>	The size of the other NetworkString .
--------------------------	---

Parameters

<i>other</i>	The NetworkString to check.
--------------	---

Returns

true if the current [NetworkString](#) ends with the specified [NetworkString](#); otherwise, false.

Type Constraints

TOtherSize : unmanaged

TOtherSize : IFixedStorage

6.226.3.14 Equals() [1/4]

```
bool Equals (
    NetworkString< TSize > other )
```

Determines whether the current [NetworkString](#) is equal to a specified [NetworkString](#).

Parameters

<i>other</i>	The NetworkString to compare with the current NetworkString .
--------------	---

Returns

true if the specified [NetworkString](#) is equal to the current [NetworkString](#); otherwise, false.

6.226.3.15 Equals() [2/4]

```
override bool Equals (
    object obj )
```

Determines whether the current [NetworkString](#) is equal to a specified object.

Parameters

<i>obj</i>	The object to compare with the current NetworkString .
------------	--

Returns

true if the specified object is equal to the current [NetworkString](#); otherwise, false.

6.226.3.16 `Equals()` [3/4]

```
bool Equals (
    ref NetworkString< TSize > other )
```

Determines whether the current `NetworkString` is equal to a specified `NetworkString`.

Parameters

<i>other</i>	The <code>NetworkString</code> to compare with the current <code>NetworkString</code> .
--------------	---

Returns

true if the specified `NetworkString` is equal to the current `NetworkString`; otherwise, false.

6.226.3.17 `Equals()` [4/4]

```
bool Equals (
    string s )
```

Determines whether the current `NetworkString` is equal to a specified string.

Parameters

<i>s</i>	The string to compare with the current <code>NetworkString</code> .
----------	---

Returns

true if the specified string is equal to the current `NetworkString`; otherwise, false.

6.226.3.18 `Equals< TOtherSize >()` [1/2]

```
bool Equals< TOtherSize > (
    NetworkString< TOtherSize > other )
```

Determines whether the current `NetworkString` is equal to a specified `NetworkString` of a different size.

Template Parameters

<i>TOtherSize</i>	The size of the other <code>NetworkString</code> .
-------------------	--

Parameters

<i>other</i>	The <code>NetworkString</code> to compare with the current <code>NetworkString</code> .
--------------	---

Returns

true if the specified [NetworkString](#) is equal to the current [NetworkString](#); otherwise, false.

Type Constraints

TOtherSize : unmanaged
TOtherSize : IFixedStorage
TOtherSize : Compare
TOtherSize : ref
TOtherSize : other

6.226.3.19 Equals< TOtherSize >() [2/2]

```
bool Equals< TOtherSize > (
    ref NetworkString< TOtherSize > other )
```

Determines whether the current [NetworkString](#) is equal to a specified [NetworkString](#) of a different size.

Template Parameters

<i>TOtherSize</i>	The size of the other NetworkString .
-------------------	---

Parameters

<i>other</i>	The NetworkString to compare with the current NetworkString .
--------------	---

Returns

true if the specified [NetworkString](#) is equal to the current [NetworkString](#); otherwise, false.

Type Constraints

TOtherSize : unmanaged
TOtherSize : IFixedStorage
TOtherSize : Compare
TOtherSize : ref
TOtherSize : other

6.226.3.20 Get()

```
bool Get (
    ref string cache )
```

Checks if *cache* is equivalent and if not converts to UTF16 and stores the result in *cache* .

Parameters

<i>cache</i>	The string to convert.
--------------	------------------------

Returns

False if no conversion was performed, true otherwise.

6.226.3.21 GetCapacity< TSize >()

```
static int GetCapacity< TSize > ( ) [static]
```

Gets the capacity of a [NetworkString](#) of a specified size.

Template Parameters

<i>TSize</i>	The size of the NetworkString .
--------------	---

Returns

The capacity of a [NetworkString](#) of the specified size.

Type Constraints

TSize : unmanaged

TSize : IFixedStorage

6.226.3.22 GetCharCount()

```
int GetCharCount ( )
```

Calculates the length of the equivalent UTF16 string.

Returns

The length of the equivalent UTF16 string.

6.226.3.23 GetEnumerator()

```
UTF32Tools.CharEnumerator GetEnumerator ( )
```

Returns an enumerator that iterates through the [NetworkString](#).

Returns

A UTF32Tools.CharEnumerator for the [NetworkString](#).

6.226.3.24 GetHashCode()

```
override int GetHashCode ( )
```

Returns the hash code for this [NetworkString](#).

Returns

A 32-bit signed integer hash code.

6.226.3.25 IndexOf() [1/6]

```
int IndexOf (
    char c,
    int startIndex,
    int count )
```

Returns the index of the first occurrence of a specified character in this instance.

Parameters

<i>c</i>	The Unicode character to seek.
<i>startIndex</i>	The search starting position.
<i>count</i>	The number of character positions to examine.

Returns

The zero-based index position of value if that character is found, or -1 if it is not.

6.226.3.26 IndexOf() [2/6]

```
int IndexOf (
    char c,
    int startIndex = 0 )
```

Returns the index of the first occurrence of a specified character in this instance.

Parameters

<i>c</i>	The Unicode character to seek.
<i>startIndex</i>	The search starting position.

Returns

The zero-based index position of value if that character is found, or -1 if it is not.

6.226.3.27 IndexOf() [3/6]

```
int IndexOf (
    string str,
    int startIndex,
    int count )
```

Returns the index of the first occurrence of a specified string in this instance.

Parameters

<i>str</i>	The string to seek.
<i>startIndex</i>	The search starting position.
<i>count</i>	The number of character positions to examine.

Returns

The zero-based index position of value if that string is found, or -1 if it is not.

Exceptions

<i>ArgumentNullException</i>	Thrown when the string is null.
<i>ArgumentOutOfRangeException</i>	Thrown when the start index is less than zero or greater than the safe length of the string, or when the count is less than zero or the sum of the start index and count is greater than the safe length of the string.

6.226.3.28 IndexOf() [4/6]

```
int IndexOf (
    string str,
    int startIndex = 0 )
```

Returns the index of the first occurrence of a specified string in this instance.

Parameters

<i>str</i>	The string to seek.
<i>startIndex</i>	The search starting position.

Returns

The zero-based index position of value if that string is found, or -1 if it is not.

6.226.3.29 IndexOf() [5/6]

```
int IndexOf (
    uint codePoint,
    int startIndex,
    int count )
```

Returns the index of the first occurrence of a specified Unicode code point in this instance.

Parameters

<i>codePoint</i>	The Unicode code point to seek.
<i>startIndex</i>	The search starting position.
<i>count</i>	The number of character positions to examine.

Returns

The zero-based index position of value if that Unicode code point is found, or -1 if it is not.

Exceptions

<i>ArgumentOutOfRangeException</i>	Thrown when the start index is less than zero or greater than the safe length of the string, or when the count is less than zero or the sum of the start index and count is greater than the safe length of the string.
------------------------------------	---

6.226.3.30 IndexOf() [6/6]

```
int IndexOf (
    uint codePoint,
    int startIndex = 0 )
```

Returns the index of the first occurrence of a specified Unicode code point in this instance.

Parameters

<i>codePoint</i>	The Unicode code point to seek.
<i>startIndex</i>	The search starting position.

Returns

The zero-based index position of value if that Unicode code point is found, or -1 if it is not.

6.226.3.31 IndexOf< TOtherSize >() [1/4]

```
int IndexOf< TOtherSize > (
    NetworkString< TOtherSize > str,
    int startIndex,
    int count )
```

Returns the index of the first occurrence of a specified [NetworkString](#) in this instance.

Template Parameters

<i>TOtherSize</i>	The size of the other NetworkString .
-------------------	---

Parameters

<i>str</i>	The NetworkString to seek.
<i>startIndex</i>	The search starting position.
<i>count</i>	The number of character positions to examine.

Returns

The zero-based index position of value if that [NetworkString](#) is found, or -1 if it is not.

Type Constraints

TOtherSize : unmanaged
TOtherSize : IFixedStorage
TOtherSize : IndexOf
TOtherSize : ref
TOtherSize : str
TOtherSize : startIndex
TOtherSize : count

6.226.3.32 IndexOf< TOtherSize >() [2/4]

```
int IndexOf< TOtherSize > (
    NetworkString< TOtherSize > str,
    int startIndex = 0 )
```

Returns the index of the first occurrence of a specified [NetworkString](#) in this instance.

Template Parameters

<i>TOtherSize</i>	The size of the other NetworkString .
-------------------	---

Parameters

<i>str</i>	The NetworkString to seek.
<i>startIndex</i>	The search starting position.

Returns

The zero-based index position of value if that [NetworkString](#) is found, or -1 if it is not.

Type Constraints

TOtherSize : unmanaged
TOtherSize : IFixedStorage
TOtherSize : IndexOf
TOtherSize : ref
TOtherSize : str
TOtherSize : startIndex
TOtherSize : SafeLength
TOtherSize : startIndex

6.226.3.33 IndexOf< TOtherSize >() [3/4]

```
int IndexOf< TOtherSize > (
    ref NetworkString< TOtherSize > str,
    int startIndex,
    int count )
```

Returns the index of the first occurrence of a specified [NetworkString](#) in this instance.

Template Parameters

<i>TOtherSize</i>	The size of the other NetworkString .
-------------------	---

Parameters

<i>str</i>	The NetworkString to seek.
<i>startIndex</i>	The search starting position.
<i>count</i>	The number of character positions to examine.

Returns

The zero-based index position of value if that [NetworkString](#) is found, or -1 if it is not.

Exceptions

<i>ArgumentOutOfRangeException</i>	Thrown when the start index is less than zero or greater than the safe length of the string, or when the count is less than zero or the sum of the start index and count is greater than the safe length of the string.
------------------------------------	---

Type Constraints

TOtherSize : unmanaged

TOtherSize : IFixedStorage

6.226.3.34 IndexOf< TOtherSize >() [4/4]

```
int IndexOf< TOtherSize > (
    ref NetworkString< TOtherSize > str,
    int startIndex = 0 )
```

Returns the index of the first occurrence of a specified [NetworkString](#) in this instance.

Template Parameters

<i>TOtherSize</i>	The size of the other NetworkString .
-------------------	---

Parameters

<i>str</i>	The NetworkString to seek.
<i>startIndex</i>	The search starting position.

Returns

The zero-based index position of value if that [NetworkString](#) is found, or -1 if it is not.

Type Constraints

TOtherSize : unmanaged

TOtherSize : IFixedStorage

TOtherSize : IndexOf

TOtherSize : ref

TOtherSize : str

TOtherSize : startIndex

TOtherSize : SafeLength

TOtherSize : startIndex

6.226.3.35 operator NetworkString< TSize >()

```
static implicit operator NetworkString< TSize > (
    string str ) [static]
```

Defines an implicit conversion of a string to a [NetworkString](#).

Parameters

<i>str</i>	The string to convert.
------------	------------------------

Returns

A new instance of [NetworkString](#) with the same value as the string.

6.226.3.36 operator string()

```
static operator string (
    NetworkString< TSize > str ) [explicit], [static]
```

Defines an explicit conversion of a [NetworkString](#) to a string.

Parameters

<i>str</i>	The NetworkString to convert.
------------	---

Returns

The string value of the [NetworkString](#).

6.226.3.37 operator"!=()" [1/3]

```
static bool operator!= (
    NetworkString< TSize > a,
    NetworkString< TSize > b ) [static]
```

Defines an inequality operator for [NetworkString](#).

Parameters

<i>a</i>	The first NetworkString to compare.
<i>b</i>	The second NetworkString to compare.

Returns

true if the NetworkStrings are not equal; otherwise, false.

6.226.3.38 operator"!="() [2/3]

```
static bool operator!= (
    NetworkString< TSize > a,
    string b ) [static]
```

Defines an inequality operator for a [NetworkString](#) and a string.

Parameters

<i>a</i>	The NetworkString to compare.
<i>b</i>	The string to compare.

Returns

true if the [NetworkString](#) and the string are not equal; otherwise, false.

6.226.3.39 operator"!="() [3/3]

```
static bool operator!= (
    string a,
    NetworkString< TSize > b ) [static]
```

Defines an inequality operator for a string and a [NetworkString](#).

Parameters

<i>a</i>	The string to compare.
<i>b</i>	The NetworkString to compare.

Returns

true if the string and the [NetworkString](#) are not equal; otherwise, false.

6.226.3.40 operator==() [1/3]

```
static bool operator== (
    NetworkString< TSize > a,
    NetworkString< TSize > b ) [static]
```

Defines an equality operator for [NetworkString](#).

Parameters

<i>a</i>	The first NetworkString to compare.
<i>b</i>	The second NetworkString to compare.

Returns

true if the [NetworkStrings](#) are equal; otherwise, false.

6.226.3.41 operator==() [2/3]

```
static bool operator==(
    NetworkString< TSize > a,
    string b ) [static]
```

Defines an equality operator for a [NetworkString](#) and a string.

Parameters

<i>a</i>	The NetworkString to compare.
<i>b</i>	The string to compare.

Returns

true if the [NetworkString](#) and the string are equal; otherwise, false.

6.226.3.42 operator==() [3/3]

```
static bool operator==(
    string a,
    NetworkString< TSize > b ) [static]
```

Defines an equality operator for a string and a [NetworkString](#).

Parameters

<i>a</i>	The string to compare.
<i>b</i>	The NetworkString to compare.

Returns

true if the string and the [NetworkString](#) are equal; otherwise, false.

6.226.3.43 Set()

```
bool Set (
    string value )
```

Converts *value* to UTF32 string and stores it internally.

Parameters

<i>value</i>	The string to set.
--------------	--------------------

Returns

False if *value* was too long to fit and had to be trimmed.

6.226.3.44 StartsWith()

```
bool StartsWith (
    string s )
```

Checks if the current [NetworkString](#) starts with a specified string.

Parameters

<i>s</i>	The string to check.
----------	----------------------

Returns

true if the current [NetworkString](#) starts with the specified string; otherwise, false.

Exceptions

<i>ArgumentNullException</i>	Thrown when the string is null.
------------------------------	---------------------------------

6.226.3.45 StartsWith< TOtherSize >()

```
bool StartsWith< TOtherSize > (
    ref NetworkString< TOtherSize > other )
```

Checks if the current [NetworkString](#) starts with a specified [NetworkString](#) of a different size.

Template Parameters

<i>TOtherSize</i>	The size of the other NetworkString .
-------------------	---

Parameters

<i>other</i>	The NetworkString to check.
--------------	---

Returns

true if the current [NetworkString](#) starts with the specified [NetworkString](#); otherwise, false.

Type Constraints

TOtherSize : unmanaged

TOtherSize : IFixedStorage

6.226.3.46 Substring() [1/2]

```
NetworkString<TSize> Substring (
    int startIndex )
```

Returns a substring from this instance. The substring starts at a specified character position.

Parameters

<i>startIndex</i>	The zero-based starting character position of a substring in this instance.
-------------------	---

Returns

A new [NetworkString](#) that is equivalent to the substring that begins at *startIndex* in this instance, or [NetworkString.Empty](#) if *startIndex* is equal to the length of this instance.

Exceptions

<i>ArgumentOutOfRangeException</i>	<i>startIndex</i> is less than zero or greater than the length of this instance.
------------------------------------	--

6.226.3.47 Substring() [2/2]

```
NetworkString<TSize> Substring (
    int startIndex,
    int length )
```

Returns a substring from this instance. The substring starts at a specified character position and has a specified length.

Parameters

<i>startIndex</i>	The zero-based starting character position of a substring in this instance.
<i>length</i>	The number of characters in the substring.

Returns

A new `NetworkString` that is equivalent to the substring of length `length` that begins at `startIndex` in this instance, or `NetworkString.Empty` if `startIndex` is equal to the length of this instance and `length` is zero.

Exceptions

<i>ArgumentOutOfRangeException</i>	<code>startIndex</code> plus <code>length</code> indicates a position not within this instance, or <code>startIndex</code> or <code>length</code> is less than zero.
------------------------------------	--

6.226.3.48 ToLower()

```
NetworkString<TSize> ToLower ( )
```

Converts all the characters in this `NetworkString` to lowercase.

Returns

A new `NetworkString` in which all characters in this `NetworkString` are converted to lowercase.

6.226.3.49 ToString()

```
override string ToString ( )
```

Converts the value of this `NetworkString` to its equivalent string representation.

Returns

A string representation of the value of this `NetworkString`.

6.226.3.50 ToUpper()

```
NetworkString<TSize> ToUpper ( )
```

Converts all the characters in this `NetworkString` to uppercase.

Returns

A new `NetworkString` in which all characters in this `NetworkString` are converted to uppercase.

6.226.4 Property Documentation

6.226.4.1 Capacity

```
int Capacity [get]
```

Maximum UTF32 string length.

6.226.4.2 Length

```
int Length [get]
```

Number of UTF32 scalars. It is equal or less than [GetCharCount](#) or the length of [Value](#), because those use UTF16 encoding, which needs two characters to encode some values.

6.226.4.3 this[int index]

```
ref uint this[int index] [get]
```

Returns UTF32 scalar at *index* position. To iterate over characters, use [GetEnumerator](#).

Parameters

<i>index</i>	Index to get.
--------------	---------------

Returns

UTF32 scalar at *index* position.

6.226.4.4 Value

```
string Value [get], [set]
```

Converts to/from regular UTF16 string. Setter is alloc-free. Use [Get](#) to get possibly alloc-free conversion.

6.227 NetworkStructUtils Class Reference

Utility methods for [INetworkStruct](#)

Static Public Member Functions

- static int [GetWordCount](#) (Type type)
- static int [GetWordCount](#)< T > ()
Get [INetworkStruct](#) Word Count

6.227.1 Detailed Description

Utility methods for [INetworkStruct](#)

6.227.2 Member Function Documentation

6.227.2.1 [GetWordCount](#)< T >()

```
static int GetWordCount< T > ( ) [static]
```

Get [INetworkStruct](#) Word Count

Template Parameters

<i>T</i>	INetworkStruct type reference
----------	---

Returns

Number of Words necessary for this specific [INetworkStruct](#)

Type Constraints

T : *unmanaged*

T : *INetworkStruct*

6.228 NetworkStructWeavedAttribute Class Reference

Describes the total number of WORDs a [INetworkStruct](#) uses.

Inherits Attribute.

Public Member Functions

- [NetworkStructWeavedAttribute](#) (int wordCount)
NetworkStructWeavedAttribute Constructor

Properties

- int [WordCount](#) [get]
[INetworkStruct](#) Word Count

6.228.1 Detailed Description

Describes the total number of WORDs a [INetworkStruct](#) uses.

6.228.2 Constructor & Destructor Documentation

6.228.2.1 NetworkStructWeavedAttribute()

```
NetworkStructWeavedAttribute (
    int wordCount )
```

[NetworkStructWeavedAttribute](#) Constructor

Parameters

<i>wordCount</i>	INetworkStruct word count
------------------	---

6.228.3 Property Documentation

6.228.3.1 WordCount

```
int WordCount [get]
```

[INetworkStruct](#) Word Count

6.229 NetworkTransform Class Reference

Add to any [NetworkObject](#) Transform, or its associated child Transforms to automatically synchronize TRSP (Position/Rotation/Scale/Parent).

Inherits [NetworkTRSP](#), [INetworkTRSPTeleport](#), [IBeforeAllTicks](#), [IAfterAllTicks](#), and [IBeforeCopyPreviousState](#).

Public Member Functions

- override void [Render](#) ()
Post simulation frame rendering callback. Runs after all simulations have finished. Use in place of Unity's Update when [Fusion](#) is handling Physics.
- override void [SetAreaOfInterestOverride](#) ([NetworkObject](#) obj)
Manually set the [NetworkObject](#) used as the AreaOfInterestOverride.
- override void [Spawned](#) ()
Post spawn callback.
- void [Teleport](#) (Vector3? position=null, Quaternion? rotation=null)
Set the transform position and rotation to the indicated values, and network the Teleport event. This will suspend interpolation between the previous tick state and the current tick state in [Render\(\)](#), on this peer and all remote peers.

Public Attributes

- bool [DisableSharedModelInterpolation](#) = false
Disable interpolation on State Authority in Shared Mode. You should disable interpolation if your controller code moves an object inside of Update() rather than [FixedUpdateNetwork\(\)](#).
- bool [SyncParent](#) = false
Enables synchronization of transform.parent. NOTE: Parent GameObjects must have a [NetworkBehaviour](#) derived component to be a valid parent, parent must belong to a different [NetworkObject](#) than this Object.
- bool [SyncScale](#) = false
Enables synchronization of LocalScale.

Properties

- bool [AutoUpdateAreaOfInterestOverride](#) [get, set]
Determines if parent changes should automatically call [SetAreaOfInterestOverride\(NetworkObject\)](#), and assign the parent [NetworkObject](#) as the override. Default is true, as you typically will want player interest in this object to reflect player interest in the nested parent object. For example, if a player is carrying an nested Object, players should only see that carried Object if they see the player. Additionally, AOI works in world space, and [NetworkTransform](#) operates in local space, so any AOI position values of nested Objects will ALWAYS be invalid, so nested Objects should always have their AOI Override set to a non-nested Object.

Additional Inherited Members

6.229.1 Detailed Description

Add to any [NetworkObject](#) Transform, or its associated child Transforms to automatically synchronize TRSP (Position/Rotation/Scale/Parent).

6.229.2 Member Function Documentation

6.229.2.1 SetAreaOfInterestOverride()

```
override void SetAreaOfInterestOverride (
    NetworkObject obj ) [virtual]
```

Manually set the [NetworkObject](#) used as the AreaOfInterestOverride.

Parameters

<i>obj</i>	NetworkObject to use as the AreaOfInterestOverride.
------------	---

Reimplemented from [NetworkTRSP](#).

6.229.2.2 Teleport()

```
void Teleport (
    Vector3? position = null,
    Quaternion? rotation = null )
```

Set the transform position and rotation to the indicated values, and network the Teleport event. This will suspend interpolation between the previous tick state and the current tick state in [Render\(\)](#), on this peer and all remote peers.

Implements [INetworkTRSPTeleport](#).

6.229.3 Member Data Documentation

6.229.3.1 DisableSharedModeInterpolation

```
bool DisableSharedModeInterpolation = false
```

Disable interpolation on State Authority in Shared Mode. You should disable interpolation if your controller code moves an object inside of Update() rather than [FixedUpdateNetwork\(\)](#).

6.229.3.2 SyncParent

```
bool SyncParent = false
```

Enables synchronization of transform.parent. NOTE: Parent GameObjects must have a [NetworkBehaviour](#) derived component to be a valid parent, parent must belong to a different [NetworkObject](#) than this Object.

6.229.3.3 SyncScale

```
bool SyncScale = false
```

Enables synchronization of LocalScale.

6.229.4 Property Documentation

6.229.4.1 AutoUpdateAreaOfInterestOverride

```
bool AutoUpdateAreaOfInterestOverride [get], [set]
```

Determines if parent changes should automatically call [SetAreaOfInterestOverride\(NetworkObject\)](#), and assign the parent [NetworkObject](#) as the override. Default is true, as you typically will want player interest in this object to reflect player interest in the nested parent object. For example, if a player is carrying an nested Object, players should only see that carried Object if they see the player. Additionally, AOI works in world space, and [NetworkTransform](#) operates in local space, so any AOI position values of nested Objects will ALWAYS be invalid, so nested Objects should always have their AOI Override set to a non-nested Object.

6.230 NetworkTRSP Class Reference

Base class for spatial (Position/Rotation/Scale/Parent) synchronization component, such as [NetworkTransform](#). Provides the base logic for render interpolation, parenting synchronization, and teleport, that can be used in components derived from this class.

Inherits [NetworkBehaviour](#).

Inherited by [NetworkTransform](#).

Public Member Functions

- virtual void [SetAreaOfInterestOverride](#) ([NetworkObject](#) obj)
Manually set the [NetworkObject](#) used as the AreaOfInterestOverride.

Static Protected Member Functions

- static void [Render](#) ([NetworkTRSP](#) behaviour, Transform transform, bool syncScale, bool syncParent, bool local, ref [Tick](#) initial)
Default Render handling for [NetworkTRSP](#) derived classes.
- static void [ResolveAOIOVERRIDE](#) ([NetworkTRSP](#) behaviour, Transform parent)
Recursively attempts to find nested parent [NetworkObject](#), and if found assigns that [NetworkObject](#) as the AreaOfInterestOverride.
- static void [SetParentTransform](#) ([NetworkTRSP](#) behaviour, Transform transform, [NetworkBehaviourId](#) parentId)
Default handling for setting a [NetworkTRSP](#)'s parent using a [NetworkBehaviourId](#) value.
- static void [Teleport](#) ([NetworkTRSP](#) behaviour, Transform transform, Vector3? position=null, Quaternion? rotation=null)
The default Teleport implementation for [NetworkTRSP](#) derived classes.

Properties

- [NetworkTRSPData Data](#) [get]
The networked data of this [NetworkTRSP](#).
- bool [IsMainTRSP](#) [get]
The main [NetworkTRSP](#) is at the root of the [NetworkObject](#) and it will be used for area of interest operations and parenting of the [NetworkObject](#).
- ref [NetworkTRSPData State](#) [get]
A reference to the networked data of this [NetworkTRSP](#).

Additional Inherited Members

6.230.1 Detailed Description

Base class for spatial (Position/Rotation/Scale/Parent) synchronization component, such as [NetworkTransform](#). Provides the base logic for render interpolation, parenting synchronization, and teleport, that can be used in components derived from this class.

6.230.2 Member Function Documentation

6.230.2.1 Render()

```
static void Render (
    NetworkTRSP behaviour,
    Transform transform,
    bool syncScale,
    bool syncParent,
    bool local,
    ref Tick initial ) [static], [protected]
```

Default Render handling for [NetworkTRSP](#) derived classes.

6.230.2.2 ResolveAOIOVERRIDE()

```
static void ResolveAOIOVERRIDE (
    NetworkTRSP behaviour,
    Transform parent ) [static], [protected]
```

Recursively attempts to find nested parent [NetworkObject](#), and if found assigns that [NetworkObject](#) as the [AreaOfInterestOverride](#).

Parameters

<i>behaviour</i>	Only pass a NetworkTRSP derived class that is on the same Transform as its associated NetworkObject , as AreaOfInterestOverride is only applicable when IsMainTRSP is true.
------------------	---

Parameters

<i>parent</i>	The direct parent of the
---------------	--------------------------

6.230.2.3 SetAreaOfInterestOverride()

```
virtual void SetAreaOfInterestOverride (
    NetworkObject obj ) [virtual]
```

Manually set the [NetworkObject](#) used as the AreaOfInterestOverride.

Parameters

<i>obj</i>	NetworkObject to use as the AreaOfInterestOverride.
------------	---

Reimplemented in [NetworkTransform](#).

6.230.2.4 SetParentTransform()

```
static void SetParentTransform (
    NetworkTRSP behaviour,
    Transform transform,
    NetworkBehaviourId parentId ) [static], [protected]
```

Default handling for setting a [NetworkTRSP](#)'s parent using a [NetworkBehaviourId](#) value.

6.230.2.5 Teleport()

```
static void Teleport (
    NetworkTRSP behaviour,
    Transform transform,
    Vector3? position = null,
    Quaternion? rotation = null ) [static], [protected]
```

The default Teleport implementation for [NetworkTRSP](#) derived classes.

6.230.3 Property Documentation

6.230.3.1 Data

`NetworkTRSPData` Data [get]

The networked data of this [NetworkTRSP](#).

6.230.3.2 IsMainTRSP

`bool` IsMainTRSP [get]

The main [NetworkTRSP](#) is at the root of the [NetworkObject](#) and it will be used for area of interest operations and parenting of the [NetworkObject](#).

6.230.3.3 State

`ref` [NetworkTRSPData](#) State [get], [protected]

A reference to the networked data of this [NetworkTRSP](#).

6.231 NetworkTRSPData Struct Reference

Data structure storing spatial (Position/Rotation/Scale/Parent) synchronization data for spatial synchronization components, [NetworkTRSP](#) and its subclass [NetworkTransform](#).

Inherits [INetworkStruct](#).

Public Attributes

- [NetworkId](#) [AreaOfInterestOverride](#)
Id of a behaviour used as the reference point for this component during area of interest operations The behaviour should be a [NetworkTRSP](#) derived class, that is on the same Transform as its associated [NetworkObject](#)
- [NetworkBehaviourId](#) [Parent](#)
Id of a [NetworkBehaviour](#) on the parent of the component's transform.
- `Vector3` [Position](#)
Position relevant for the spatial synchronization component (can be used to either store a local position or a world position, depending on the component)
- `Quaternion` [Rotation](#)
Rotation relevant for the spatial synchronization component (can be used to either store a local rotation or a world rotation, depending on the component)
- `Vector3Compressed` [Scale](#)
Scale relevant for the spatial synchronization component
- `int` [TeleportKey](#)
Key used to differentiate between several teleports

Static Public Attributes

- const int `POSITION_OFFSET` = 2
Offset to point at the position values on the data buffer
- const int `SIZE` = `WORDS * Allocator.REPLICATE_WORD_SIZE`
The actual size for the networked properties in bytes
- const int `WORDS` = 14
Networked properties word count for the base [NetworkTRSPData](#)

Properties

- static `NetworkBehaviourId NonNetworkedParent` [get]
Special [NetworkBehaviourId](#) value, used as a flag to tell the parent is a non-networked object

6.231.1 Detailed Description

Data structure storing spatial (Position/Rotation/Scale/Parent) synchronization data for spatial synchronization components, [NetworkTRSP](#) and its subclass [NetworkTransform](#).

6.231.2 Member Data Documentation

6.231.2.1 AreaOfInterestOverride

`NetworkId` `AreaOfInterestOverride`

Id of a behaviour used as the reference point for this component during area of interest operations The behaviour should be a [NetworkTRSP](#) derived class, that is on the same Transform as its associated [NetworkObject](#)

6.231.2.2 Parent

`NetworkBehaviourId` `Parent`

Id of a [NetworkBehaviour](#) on the parent of the component's transform.

6.231.2.3 Position

`Vector3` `Position`

Position relevant for the spatial synchronization component (can be used to either store a local position or a world position, depending on the component)

6.231.2.4 POSITION_OFFSET

```
const int POSITION_OFFSET = 2 [static]
```

Offset to point at the position values on the data buffer

6.231.2.5 Rotation

```
Quaternion Rotation
```

Rotation relevant for the spatial synchronization component (can be used to either store a local rotation or a world rotation, depending on the component)

6.231.2.6 Scale

```
Vector3Compressed Scale
```

Scale relevant for the spatial synchronization component

6.231.2.7 SIZE

```
const int SIZE = WORDS * Allocator.REPLICATE_WORD_SIZE [static]
```

The actual size for the networked properties in bytes

6.231.2.8 TeleportKey

```
int TeleportKey
```

Key used to differentiate between several teleports

6.231.2.9 WORDS

```
const int WORDS = 14 [static]
```

Networked properties word count for the base [NetworkTRSPData](#)

6.231.3 Property Documentation

6.231.3.1 NonNetworkedParent

`NetworkBehaviourId` NonNetworkedParent [static], [get]

Special `NetworkBehaviourId` value, used as a flag to tell the parent is a non-networked object

6.232 NormalizedRectAttribute Class Reference

Enables a special inspector drawer for Unity Rect type, specially designed for editing RectTransforms using normalized values.

Inherits PropertyAttribute.

Public Member Functions

- `NormalizedRectAttribute` (bool invertY=true, float aspectRatio=0)
Constructor for `NormalizedRectAttribute`. InvertY inverts Y handling, for RectTransforms which treat lowerRight as origin, rather than upper left.

Public Attributes

- float `AspectRatio`
Set the Aspect Ratio
- bool `InvertY`
Signal if Y should be inverted

6.232.1 Detailed Description

Enables a special inspector drawer for Unity Rect type, specially designed for editing RectTransforms using normalized values.

6.232.2 Constructor & Destructor Documentation

6.232.2.1 NormalizedRectAttribute()

```
NormalizedRectAttribute (
    bool invertY = true,
    float aspectRatio = 0 )
```

Constructor for `NormalizedRectAttribute`. InvertY inverts Y handling, for RectTransforms which treat lowerRight as origin, rather than upper left.

Parameters

<i>invertY</i>	Invert Y handling
<i>aspectRatio</i>	Expressed as Width/Height, this defines the ratio of the box shown in the inspector. Value of 0 indicates game window resolution will be used.

6.232.3 Member Data Documentation

6.232.3.1 AspectRatio

`float AspectRatio`

Set the Aspect Ratio

6.232.3.2 InvertY

`bool InvertY`

Signal if Y should be inverted

6.233 PlayerRef Struct Reference

Represents a [Fusion](#) player.

Inherits [INetworkStruct](#), and `IEquatable< PlayerRef >`.

Public Member Functions

- override `bool Equals (object obj)`
Determines whether the specified object is equal to the current object.
- `bool Equals (PlayerRef other)`
Determines whether the specified PlayerRef is equal to the current PlayerRef.
- override `int GetHashCode ()`
Serves as the default hash function.
- override `string ToString ()`
Returns a string that represents the current object.

Static Public Member Functions

- static [PlayerRef FromEncoded](#) (int encoded)
Creates a new [PlayerRef](#) from the given encoded value.
- static [PlayerRef FromIndex](#) (int index)
Creates a new [PlayerRef](#) from the given index.
- static bool [operator!=](#) ([PlayerRef](#) a, [PlayerRef](#) b)
Determines whether two [PlayerRef](#) instances are not equal.
- static bool [operator==](#) ([PlayerRef](#) a, [PlayerRef](#) b)
Determines whether two [PlayerRef](#) instances are equal.
- static unsafe [PlayerRef Read](#) (NetBitBuffer *buffer)
Reads a [PlayerRef](#) from the provided NetBitBuffer.
- static unsafe void [Write](#) (NetBitBuffer *buffer, [PlayerRef](#) playerRef)
Writes the [PlayerRef](#) to the provided NetBitBuffer.
- static unsafe void [Write< T >](#) (T *buffer, [PlayerRef](#) playerRef)
Writes the [PlayerRef](#) to the provided buffer.

Public Attributes

- int [_index](#)

Static Public Attributes

- const int [MASTER_CLIENT_RAW](#) = -1
A constant representing the raw index value for the master client.
- const int [SIZE](#) = 4
The size of the [PlayerRef](#) structure in bytes.

Properties

- int [AsIndex](#) [get]
Returns the [PlayerRef](#) int as an integer Id value.
- static IEqualityComparer< [PlayerRef](#) > [Comparer](#) = new IndexEqualityComparer() [get]
Gets an equality comparer that can be used to compare two [PlayerRef](#) instances.
- bool [IsMasterClient](#) [get]
Returns true if this [PlayerRef](#) indicates the MasterClient rather than a specific Player by Index, This is a special flag value which has the encoded index value of -2 (internal raw backing value of -1). This is not a valid [PlayerRef](#) value in itself, and no Runner will ever be assigned this value as its LocalPlayer. It is used by properties like Object.State↔ Authority to indicate that the MasterClient has authority (which ever player that currently is), rather than a specific Player.
- bool [IsNone](#) [get]
Returns true if the index value equals -1 (internal raw value of 0), indicating no player.
- bool [IsRealPlayer](#) [get]
If this player ref is a valid unique player index
- static [PlayerRef MasterClient](#) [get]
Special master client player ref value of -1
- static [PlayerRef None](#) [get]
None player
- int [PlayerId](#) [get]
Returns the [PlayerRef](#) as an integer Id value.
- int [RawEncoded](#) [get]
Returns the index backing value without modification. Unlike [AsIndex](#) which returns the backing value - 1.

6.233.1 Detailed Description

Represents a [Fusion](#) player.

The [PlayerRef](#), in contrast to the player index, is 1-based. The reason is that `default(PlayerRef)` will return a "null/invalid" player ref struct for convenience. There are automatic cast operators that can cast an int into a [PlayerRef](#).

```
default(PlayerRef), internally a 0, means NOBODY  
PlayerRef, internally 1, is the same as player index 0  
PlayerRef, internally 2, is the same as player index 1
```

6.233.2 Member Function Documentation

6.233.2.1 Equals() [1/2]

```
override bool Equals (  
    object obj )
```

Determines whether the specified object is equal to the current object.

Parameters

<i>obj</i>	The object to compare with the current object.
------------	--

Returns

true if the specified object is equal to the current object; otherwise, false.

6.233.2.2 Equals() [2/2]

```
bool Equals (  
    PlayerRef other )
```

Determines whether the specified [PlayerRef](#) is equal to the current [PlayerRef](#).

Parameters

<i>other</i>	The PlayerRef to compare with the current PlayerRef .
--------------	---

Returns

true if the specified [PlayerRef](#) is equal to the current [PlayerRef](#); otherwise, false.

6.233.2.3 FromEncoded()

```
static PlayerRef FromEncoded (
    int encoded ) [static]
```

Creates a new [PlayerRef](#) from the given encoded value.

Parameters

<i>encoded</i>	The encoded value to create the PlayerRef from.
----------------	---

Returns

A new [PlayerRef](#) that represents the encoded value.

6.233.2.4 FromIndex()

```
static PlayerRef FromIndex (
    int index ) [static]
```

Creates a new [PlayerRef](#) from the given index.

Parameters

<i>index</i>	The index to create the PlayerRef from.
--------------	---

Returns

A new [PlayerRef](#) that represents the index.

6.233.2.5 GetHashCode()

```
override int GetHashCode ( )
```

Serves as the default hash function.

6.233.2.6 operator"!="()

```
static bool operator!= (
    PlayerRef a,
    PlayerRef b ) [static]
```

Determines whether two [PlayerRef](#) instances are not equal.

Parameters

<i>a</i>	The first PlayerRef to compare.
<i>b</i>	The second PlayerRef to compare.

Returns

true if the [PlayerRefs](#) are not equal; otherwise, false.

6.233.2.7 operator==()

```
static bool operator== (  
    PlayerRef a,  
    PlayerRef b ) [static]
```

Determines whether two [PlayerRef](#) instances are equal.

Parameters

<i>a</i>	The first PlayerRef to compare.
<i>b</i>	The second PlayerRef to compare.

Returns

true if the [PlayerRefs](#) are equal; otherwise, false.

6.233.2.8 Read()

```
static unsafe PlayerRef Read (  
    NetBitBuffer * buffer ) [static]
```

Reads a [PlayerRef](#) from the provided [NetBitBuffer](#).

Parameters

<i>buffer</i>	The buffer to read from.
---------------	--------------------------

Returns

The [PlayerRef](#) read from the buffer.

6.233.2.9 ToString()

```
override string ToString ( )
```

Returns a string that represents the current object.

6.233.2.10 Write()

```
static unsafe void Write (
    NetBitBuffer * buffer,
    PlayerRef playerRef ) [static]
```

Writes the [PlayerRef](#) to the provided NetBitBuffer.

Parameters

<i>buffer</i>	The buffer to write to.
<i>playerRef</i>	The PlayerRef to write.

6.233.2.11 Write< T >()

```
static unsafe void Write< T > (
    T * buffer,
    PlayerRef playerRef ) [static]
```

Writes the [PlayerRef](#) to the provided buffer.

Template Parameters

<i>T</i>	The type of the buffer. Must be unmanaged and implement INetBitWriteStream.
----------	---

Parameters

<i>buffer</i>	The buffer to write to.
<i>playerRef</i>	The PlayerRef to write.

Type Constraints

T* : *unmanaged

T* : *INetBitWriteStream

6.233.3 Member Data Documentation

6.233.3.1 MASTER_CLIENT_RAW

```
const int MASTER_CLIENT_RAW = -1 [static]
```

A constant representing the raw index value for the master client.

6.233.3.2 SIZE

```
const int SIZE = 4 [static]
```

The size of the [PlayerRef](#) structure in bytes.

6.233.4 Property Documentation

6.233.4.1 AsIndex

```
int AsIndex [get]
```

Returns the [PlayerRef](#) int as an integer Id value.

-1=None -2=MasterClient >=0=PlayerId

6.233.4.2 Comparer

```
IEqualityComparer<PlayerRef> Comparer = new IndexEqualityComparer() [static], [get]
```

Gets an equality comparer that can be used to compare two [PlayerRef](#) instances.

6.233.4.3 IsMasterClient

```
bool IsMasterClient [get]
```

Returns true if this [PlayerRef](#) indicates the MasterClient rather than a specific Player by Index, This is a special flag value which has the encoded index value of -2 (internal raw backing value of -1). This is not a valid [PlayerRef](#) value in itself, and no Runner will ever be assigned this value as its LocalPlayer. It is used by properties like `Object.StateAuthority` to indicate that the MasterClient has authority (which ever player that currently is), rather than a specific Player.

6.233.4.4 IsNone

```
bool IsNone [get]
```

Returns true if the index value equals -1 (internal raw value of 0), indicating no player.

6.233.4.5 IsRealPlayer

```
bool IsRealPlayer [get]
```

If this player ref is a valid unique player index

6.233.4.6 MasterClient

```
PlayerRef MasterClient [static], [get]
```

Special master client player ref value of -1

6.233.4.7 None

```
PlayerRef None [static], [get]
```

None player

6.233.4.8 PlayerId

```
int PlayerId [get]
```

Returns the [PlayerRef](#) as an integer Id value.

-1=None -2=MasterClient

6.233.4.9 RawEncoded

```
int RawEncoded [get]
```

Returns the index backing value without modification. Unlike [AsIndex](#) which returns the backing value - 1.

0=None -1=MasterClient >0=PlayerId

6.234 PreserveInPluginAttribute Class Reference

Preserve In Plugin Attribute

Inherits Attribute.

Public Member Functions

- [PreserveInPluginAttribute](#) ()
[PreserveInPluginAttribute](#) Constructor

6.234.1 Detailed Description

Preserve In Plugin Attribute

6.234.2 Constructor & Destructor Documentation

6.234.2.1 PreserveInPluginAttribute()

[PreserveInPluginAttribute](#) ()

[PreserveInPluginAttribute](#) Constructor

6.235 IMessage Interface Reference

Represents a [Protocol](#) Message

6.235.1 Detailed Description

Represents a [Protocol](#) Message

Used to tag the Messages in ICommunicator.

6.236 Ptr Struct Reference

[Ptr](#)

Inherits IEquatable< [Ptr](#) >, and [INetworkStruct](#).

Classes

- class [EqualityComparer](#)
Ptr Equality Comparer

Public Member Functions

- override bool [Equals](#) (object obj)
Check Ptr equality
- bool [Equals](#) (Ptr other)
Check Ptr equality
- override int [GetHashCode](#) ()
Ptr Hash Code, same as Address
- override string [ToString](#) ()
Ptr to String

Static Public Member Functions

- static implicit [operator bool](#) (Ptr a)
Implicit Bool Operator Check if Address is not 0
- static bool [operator!=](#) (Ptr a, Ptr b)
Implicit Ptr Not Equals Operator
- static [Ptr operator+](#) (Ptr p, int v)
Implicit Ptr Sum Operator
- static [Ptr operator-](#) (Ptr p, int v)
Implicit Ptr Subtraction Operator
- static bool [operator==](#) (Ptr a, Ptr b)
Implicit Ptr Equals Operator

Public Attributes

- int [Address](#)
Ptr Address

Static Public Attributes

- const int [SIZE](#) = 4
Ptr Size

Properties

- static [Ptr Null](#) [get]
Null Ptr

6.236.1 Detailed Description

[Ptr](#)

6.236.2 Member Function Documentation

6.236.2.1 Equals() [1/2]

```
override bool Equals (  
    object obj )
```

Check [Ptr](#) equality

Parameters

<i>obj</i>	Any object reference
------------	----------------------

Returns

True if *obj* is a [Ptr](#) and points to the same Address

6.236.2.2 Equals() [2/2]

```
bool Equals (  
    Ptr other )
```

Check [Ptr](#) equality

Parameters

<i>other</i>	Ptr Ref
--------------	-------------------------

Returns

True if points to the same Address

6.236.2.3 GetHashCode()

```
override int GetHashCode ( )
```

[Ptr](#) Hash Code, same as [Address](#)

Returns

[Address](#)

6.236.2.4 operator bool()

```
static implicit operator bool (  
    Ptr a ) [static]
```

Implicit Bool Operator Check if Address is not 0

Parameters

<i>a</i>	Ptr to check
----------	--------------

Returns

True if Address is not 0

6.236.2.5 operator"!=()"

```
static bool operator!= (  
    Ptr a,  
    Ptr b ) [static]
```

Implicit Ptr Not Equals Operator

Parameters

<i>a</i>	Ptr A
<i>b</i>	Ptr B

Returns

True if Address is not the same

6.236.2.6 operator+()

```
static Ptr operator+ (  
    Ptr p,  
    int v ) [static]
```

Implicit Ptr Sum Operator

Parameters

<i>p</i>	Ptr to add to
<i>v</i>	Value to add

Returns

[Ptr](#) with [Address](#) increased by v

6.236.2.7 operator-()

```
static Ptr operator- (
    Ptr  $p$ ,
    int  $v$  ) [static]
```

Implicit [Ptr](#) Subtraction Operator

Parameters

p	Ptr to subtract from
v	Value to subtract

Returns

[Ptr](#) with [Address](#) decreased by v

6.236.2.8 operator==()

```
static bool operator== (
    Ptr  $a$ ,
    Ptr  $b$  ) [static]
```

Implicit [Ptr](#) Equals Operator

Parameters

a	Ptr A
b	Ptr B

Returns

True if [Address](#) is the same

6.236.2.9 ToString()

```
override string ToString ( )
```

[Ptr](#) to String

Returns

[Address](#) in Hexadecimal format

6.236.3 Member Data Documentation

6.236.3.1 Address

```
int Address
```

[Ptr](#) Address

6.236.3.2 SIZE

```
const int SIZE = 4 [static]
```

[Ptr](#) Size

6.236.4 Property Documentation

6.236.4.1 Null

```
Ptr Null [static], [get]
```

Null [Ptr](#)

6.237 Ptr.EqualityComparer Class Reference

[Ptr](#) Equality Comparer

Inherits `IEqualityComparer< Ptr >`.

Public Member Functions

- bool [Equals](#) ([Ptr](#) x, [Ptr](#) y)
[Ptr](#) Equality Comparer
- int [GetHashCode](#) ([Ptr](#) obj)
Get Hash Code

6.237.1 Detailed Description

[Ptr](#) Equality Comparer

6.237.2 Member Function Documentation

6.237.2.1 Equals()

```
bool Equals (
    Ptr x,
    Ptr y )
```

[Ptr](#) Equality Comparer

Parameters

<i>x</i>	Ptr X
<i>y</i>	Ptr Y

Returns

True if point to the same Address

6.237.2.2 GetHashCode()

```
int GetHashCode (
    Ptr obj )
```

Get Hash Code

Parameters

<i>obj</i>	Ptr
------------	---------------------

Returns

[Ptr](#) Address

6.238 QuaternionCompressed Struct Reference

Represents a compressed Quaternion value for network transmission.

Inherits [INetworkStruct](#), and [IEquatable< QuaternionCompressed >](#).

Public Member Functions

- override bool [Equals](#) (object obj)
Checks if the provided object is a [QuaternionCompressed](#) instance and if it's equal to the current [QuaternionCompressed](#) instance.
- bool [Equals](#) ([QuaternionCompressed](#) other)
Checks if the current [QuaternionCompressed](#) instance is equal to the other [QuaternionCompressed](#) instance.
- override int [GetHashCode](#) ()
Returns the hash code for the current [QuaternionCompressed](#) instance.

Static Public Member Functions

- static implicit [operator Quaternion](#) ([QuaternionCompressed](#) q)
Implicit conversion from [QuaternionCompressed](#) to Quaternion.
- static implicit [operator QuaternionCompressed](#) (Quaternion v)
Implicit conversion from Quaternion to [QuaternionCompressed](#).
- static bool [operator!=](#) ([QuaternionCompressed](#) left, [QuaternionCompressed](#) right)
Inequality operator for [QuaternionCompressed](#) struct.
- static bool [operator==](#) ([QuaternionCompressed](#) left, [QuaternionCompressed](#) right)
Equality operator for [QuaternionCompressed](#) struct.

Public Attributes

- int [wEncoded](#)
Encoded value of the w component.
- int [xEncoded](#)
Encoded value of the x component.
- int [yEncoded](#)
Encoded value of the y component.
- int [zEncoded](#)
Encoded value of the z component.

Properties

- float [W](#) [get, set]
Gets or sets the w component.
- float [X](#) [get, set]
Gets or sets the x component.
- float [Y](#) [get, set]
Gets or sets the y component.
- float [Z](#) [get, set]
Gets or sets the z component.

6.238.1 Detailed Description

Represents a compressed Quaternion value for network transmission.

6.238.2 Member Function Documentation

6.238.2.1 Equals() [1/2]

```
override bool Equals (  
    object obj )
```

Checks if the provided object is a [QuaternionCompressed](#) instance and if it's equal to the current [QuaternionCompressed](#) instance.

Parameters

<i>obj</i>	The object to compare with the current QuaternionCompressed instance.
------------	---

Returns

True if the provided object is a [QuaternionCompressed](#) instance and it's equal to the current [QuaternionCompressed](#) instance, otherwise false.

6.238.2.2 Equals() [2/2]

```
bool Equals (  
    QuaternionCompressed other )
```

Checks if the current [QuaternionCompressed](#) instance is equal to the other [QuaternionCompressed](#) instance.

Parameters

<i>other</i>	The other QuaternionCompressed instance to compare with the current QuaternionCompressed instance.
--------------	--

Returns

True if the values of both [QuaternionCompressed](#) instances are equal, otherwise false.

6.238.2.3 GetHashCode()

```
override int GetHashCode ( )
```

Returns the hash code for the current [QuaternionCompressed](#) instance.

Returns

A hash code for the current [QuaternionCompressed](#) instance.

6.238.2.4 operator Quaternion()

```
static implicit operator Quaternion (  
    QuaternionCompressed q ) [static]
```

Implicit conversion from [QuaternionCompressed](#) to Quaternion.

Parameters

<i>q</i>	The QuaternionCompressed instance to convert.
----------	---

Returns

The decompressed Quaternion value of the [QuaternionCompressed](#) instance.

6.238.2.5 operator QuaternionCompressed()

```
static implicit operator QuaternionCompressed (  
    Quaternion v ) [static]
```

Implicit conversion from Quaternion to [QuaternionCompressed](#).

Parameters

<i>v</i>	The Quaternion value to convert.
----------	----------------------------------

Returns

A new [QuaternionCompressed](#) instance with the compressed value of the Quaternion.

6.238.2.6 operator "!="()

```
static bool operator!= (  
    QuaternionCompressed left,  
    QuaternionCompressed right ) [static]
```

Inequality operator for [QuaternionCompressed](#) struct.

Parameters

<i>left</i>	First QuaternionCompressed instance.
<i>right</i>	Second QuaternionCompressed instance.

Returns

True if the value of the first [QuaternionCompressed](#) instance is not equal to the value of the second [QuaternionCompressed](#) instance, otherwise false.

6.238.2.7 operator==()

```
static bool operator== (
    QuaternionCompressed left,
    QuaternionCompressed right ) [static]
```

Equality operator for [QuaternionCompressed](#) struct.

Parameters

<i>left</i>	First QuaternionCompressed instance.
<i>right</i>	Second QuaternionCompressed instance.

Returns

True if the value of the first [QuaternionCompressed](#) instance is equal to the value of the second [QuaternionCompressed](#) instance, otherwise false.

6.238.3 Member Data Documentation

6.238.3.1 wEncoded

```
int wEncoded
```

Encoded value of the w component.

6.238.3.2 xEncoded

```
int xEncoded
```

Encoded value of the x component.

6.238.3.3 yEncoded

```
int yEncoded
```

Encoded value of the y component.

6.238.3.4 zEncoded

```
int zEncoded
```

Encoded value of the z component.

6.238.4 Property Documentation

6.238.4.1 W

```
float W [get], [set]
```

Gets or sets the w component.

6.238.4.2 X

```
float X [get], [set]
```

Gets or sets the x component.

6.238.4.3 Y

```
float Y [get], [set]
```

Gets or sets the y component.

6.238.4.4 Z

```
float Z [get], [set]
```

Gets or sets the z component.

6.239 ReadWriteUtils Class Reference

Provides utility methods for reading and writing data.

Static Public Member Functions

- static float [ReadFloat](#) (int *data)
Reads a float value from the provided memory location.
- static [NetworkBehaviour ReadNetworkBehaviourRef](#) (int *data, [NetworkRunner](#) runner, out bool isValid)
Reads a [NetworkBehaviour](#) reference from the provided memory location. Null is considered valid (0, 1).
- static Quaternion [ReadQuaternion](#) (int *data)
Reads a Quaternion value from the provided memory location.
- static Vector2 [ReadVector2](#) (int *data)
Reads a Vector2 value from the provided memory location.
- static Vector3 [ReadVector3](#) (int *data)
Reads a Vector3 value from the provided memory location.
- static Vector4 [ReadVector4](#) (int *data)
Reads a Vector4 value from the provided memory location.
- static void [WriteEmptyNetworkBehaviourRef](#) (int *data)
Writes an empty [NetworkBehaviour](#) reference to the provided memory location.
- static void [WriteFloat](#) (int *data, float f)
Writes a float value to the provided memory location.
- static void [WriteNetworkBehaviourRef](#) (int *data, [NetworkRunner](#) runner, [NetworkBehaviour](#) reference)
Writes a [NetworkBehaviour](#) reference to the provided memory location.
- static void [WriteNullBehaviourRef](#) (int *data)
Writes a null [NetworkBehaviour](#) reference to the provided memory location.
- static void [WriteQuaternion](#) (int *data, Quaternion value)
Writes a Quaternion value to the provided memory location.
- static void [WriteVector2](#) (int *data, Vector2 value)
Writes a Vector2 value to the provided memory location.
- static void [WriteVector3](#) (int *data, Vector3 value)
Writes a Vector3 value to the provided memory location.
- static void [WriteVector4](#) (int *data, Vector4 value)
Writes a Vector4 value to the provided memory location.

Static Public Attributes

- const float [ACCURACY](#) = 1 << 10
Accuracy of floating point values when serialized.

6.239.1 Detailed Description

Provides utility methods for reading and writing data.

6.239.2 Member Function Documentation

6.239.2.1 ReadFloat()

```
static float ReadFloat (  
    int * data ) [static]
```

Reads a float value from the provided memory location.

Parameters

<i>data</i>	The memory location to read from.
-------------	-----------------------------------

Returns

The float value read from the memory location.

6.239.2.2 ReadNetworkBehaviourRef()

```
static NetworkBehaviour ReadNetworkBehaviourRef (  
    int * data,  
    NetworkRunner runner,  
    out bool isValid ) [static]
```

Reads a [NetworkBehaviour](#) reference from the provided memory location. Null is considered valid (0,1).

Parameters

<i>data</i>	The memory location to read from.
<i>runner</i>	The NetworkRunner associated with the NetworkBehaviour .
<i>isValid</i>	Out parameter indicating whether the read operation was valid.

Returns

The [NetworkBehaviour](#) reference read from the memory location.

6.239.2.3 ReadQuaternion()

```
static Quaternion ReadQuaternion (  
    int * data ) [static]
```

Reads a Quaternion value from the provided memory location.

Parameters

<i>data</i>	The memory location to read from.
-------------	-----------------------------------

Returns

The Quaternion value read from the memory location.

6.239.2.4 ReadVector2()

```
static Vector2 ReadVector2 (  
    int * data ) [static]
```

Reads a Vector2 value from the provided memory location.

Parameters

<i>data</i>	The memory location to read from.
-------------	-----------------------------------

Returns

The Vector2 value read from the memory location.

6.239.2.5 ReadVector3()

```
static Vector3 ReadVector3 (  
    int * data ) [static]
```

Reads a Vector3 value from the provided memory location.

Parameters

<i>data</i>	The memory location to read from.
-------------	-----------------------------------

Returns

The Vector3 value read from the memory location.

6.239.2.6 ReadVector4()

```
static Vector4 ReadVector4 (  
    int * data ) [static]
```

Reads a Vector4 value from the provided memory location.

Parameters

<i>data</i>	The memory location to read from.
-------------	-----------------------------------

Returns

The Vector4 value read from the memory location.

6.239.2.7 WriteEmptyNetworkBehaviourRef()

```
static void WriteEmptyNetworkBehaviourRef (  
    int * data ) [static]
```

Writes an empty [NetworkBehaviour](#) reference to the provided memory location.

Parameters

<i>data</i>	The memory location to write to.
-------------	----------------------------------

6.239.2.8 WriteFloat()

```
static void WriteFloat (  
    int * data,  
    float f ) [static]
```

Writes a float value to the provided memory location.

Parameters

<i>data</i>	The memory location to write to.
<i>f</i>	The float value to write.

6.239.2.9 WriteNetworkBehaviourRef()

```
static void WriteNetworkBehaviourRef (  
    int * data,  
    NetworkRunner runner,  
    NetworkBehaviour reference ) [static]
```

Writes a [NetworkBehaviour](#) reference to the provided memory location.

Parameters

<i>data</i>	The memory location to write to.
<i>runner</i>	The NetworkRunner associated with the NetworkBehaviour .
<i>reference</i>	The NetworkBehaviour reference to write.

6.239.2.10 WriteNullBehaviourRef()

```
static void WriteNullBehaviourRef (
    int * data ) [static]
```

Writes a null [NetworkBehaviour](#) reference to the provided memory location.

Parameters

<i>data</i>	The memory location to write to.
-------------	----------------------------------

6.239.2.11 WriteQuaternion()

```
static void WriteQuaternion (
    int * data,
    Quaternion value ) [static]
```

Writes a Quaternion value to the provided memory location.

Parameters

<i>data</i>	The memory location to write to.
<i>value</i>	The Quaternion value to write.

6.239.2.12 WriteVector2()

```
static void WriteVector2 (
    int * data,
    Vector2 value ) [static]
```

Writes a Vector2 value to the provided memory location.

Parameters

<i>data</i>	The memory location to write to.
<i>value</i>	The Vector2 value to write.

6.239.2.13 WriteVector3()

```
static void WriteVector3 (
    int * data,
    Vector3 value ) [static]
```

Writes a Vector3 value to the provided memory location.

Parameters

<i>data</i>	The memory location to write to.
<i>value</i>	The Vector3 value to write.

6.239.2.14 WriteVector4()

```
static void WriteVector4 (
    int * data,
    Vector4 value ) [static]
```

Writes a Vector4 value to the provided memory location.

Parameters

<i>data</i>	The memory location to write to.
<i>value</i>	The Vector4 value to write.

6.239.3 Member Data Documentation**6.239.3.1 ACCURACY**

```
const float ACCURACY = 1 << 10 [static]
```

Accuracy of floating point values when serialized.

6.240 ReadWriteUtilsForWeaver Class Reference

Provides utility methods for reading and writing data.

Static Public Member Functions

- static int [GetByteCountUtf8NoHash](#) (string value)
Gets the byte count of a string in UTF8 format without a hash.
- static int [GetWordCountString](#) (int capacity, bool withCaching)
Gets the word count of a string with optional caching.
- static bool [ReadBoolean](#) (int *data)
Reads a boolean value from the provided memory location.
- static unsafe int [ReadStringUtf32NoHash](#) (int *ptr, int maxLength, out string result)
Reads a string from the provided memory location in UTF32 format without a hash.

- static unsafe int [ReadStringUtf32WithHash](#) (int *ptr, int maxLength, ref string cache)
Reads a string from the provided memory location in UTF32 format with a hash.
- static int [ReadStringUtf8NoHash](#) (void *source, out string result)
Reads a string from the provided memory location in UTF8 format without a hash.
- static int [VerifyRawNetworkUnwrap< T >](#) (int actual, int maxBytes)
Verifies the byte count of a network unwrapped object. Throws an exception if the actual byte count exceeds the maximum allowed byte count.
- static int [VerifyRawNetworkWrap< T >](#) (int actual, int maxBytes)
Verifies the byte count of a network wrapped object. Throws an exception if the actual byte count exceeds the maximum allowed byte count.
- static void [WriteBoolean](#) (int *data, bool value)
Writes a boolean value to the provided memory location.
- static unsafe int [WriteStringUtf32NoHash](#) (int *ptr, int maxLength, string value)
Writes a string to the provided memory location in UTF32 format without a hash.
- static unsafe int [WriteStringUtf32WithHash](#) (int *ptr, int maxLength, string value, ref string cache)
Writes a string to the provided memory location in UTF32 format with a hash.
- static int [WriteStringUtf8NoHash](#) (void *destination, string str)
Writes a string to the provided memory location in UTF8 format without a hash.

6.240.1 Detailed Description

Provides utility methods for reading and writing data.

6.240.2 Member Function Documentation

6.240.2.1 GetByteCountUtf8NoHash()

```
static int GetByteCountUtf8NoHash (
    string value ) [static]
```

Gets the byte count of a string in UTF8 format without a hash.

Parameters

<i>value</i>	The string to get the byte count of.
--------------	--------------------------------------

Returns

The byte count of the string in UTF8 format.

6.240.2.2 GetWordCountString()

```
static int GetWordCountString (
    int capacity,
    bool withCaching ) [static]
```

Gets the word count of a string with optional caching.

Parameters

<i>capacity</i>	The capacity of the string.
<i>withCaching</i>	Indicates whether caching is used.

Returns

The word count of the string.

6.240.2.3 ReadBoolean()

```
static bool ReadBoolean (  
    int * data ) [static]
```

Reads a boolean value from the provided memory location.

Parameters

<i>data</i>	The memory location to read from.
-------------	-----------------------------------

Returns

The boolean value read from the memory location.

6.240.2.4 ReadStringUtf32NoHash()

```
static unsafe int ReadStringUtf32NoHash (  
    int * ptr,  
    int maxLength,  
    out string result ) [static]
```

Reads a string from the provided memory location in UTF32 format without a hash.

Parameters

<i>ptr</i>	The memory location to read from.
<i>maxLength</i>	The maximum length of the string.
<i>result</i>	The string read from the memory location.

Returns

The number of bytes read.

6.240.2.5 ReadStringUtf32WithHash()

```
static unsafe int ReadStringUtf32WithHash (
    int * ptr,
    int maxLength,
    ref string cache ) [static]
```

Reads a string from the provided memory location in UTF32 format with a hash.

Parameters

<i>ptr</i>	The memory location to read from.
<i>maxLength</i>	The maximum length of the string.
<i>cache</i>	A reference to a cache string. This will be updated with the read string if it matches the cached hashcode.

Returns

The number of bytes read.

6.240.2.6 ReadStringUtf8NoHash()

```
static int ReadStringUtf8NoHash (
    void * source,
    out string result ) [static]
```

Reads a string from the provided memory location in UTF8 format without a hash.

Parameters

<i>source</i>	The memory location to read from.
<i>result</i>	The string read from the memory location.

Returns

The number of bytes read.

6.240.2.7 VerifyRawNetworkUnwrap< T >()

```
static int VerifyRawNetworkUnwrap< T > (
    int actual,
    int maxBytes ) [static]
```

Verifies the byte count of a network unwrapped object. Throws an exception if the actual byte count exceeds the maximum allowed byte count.

Template Parameters

<i>T</i>	The type of the network unwrapped object.
----------	---

Parameters

<i>actual</i>	The actual byte count.
<i>maxBytes</i>	The maximum allowed byte count.

Returns

The actual byte count if it does not exceed the maximum allowed byte count.

6.240.2.8 VerifyRawNetworkWrap< T >()

```
static int VerifyRawNetworkWrap< T > (  
    int actual,  
    int maxBytes ) [static]
```

Verifies the byte count of a network wrapped object. Throws an exception if the actual byte count exceeds the maximum allowed byte count.

Template Parameters

<i>T</i>	The type of the network wrapped object.
----------	---

Parameters

<i>actual</i>	The actual byte count.
<i>maxBytes</i>	The maximum allowed byte count.

Returns

The actual byte count if it does not exceed the maximum allowed byte count.

6.240.2.9 WriteBoolean()

```
static void WriteBoolean (  
    int * data,  
    bool value ) [static]
```

Writes a boolean value to the provided memory location.

Parameters

<i>data</i>	The memory location to write to.
<i>value</i>	The boolean value to write.

6.240.2.10 WriteStringUtf32NoHash()

```
static unsafe int WriteStringUtf32NoHash (  
    int * ptr,  
    int maxLength,  
    string value ) [static]
```

Writes a string to the provided memory location in UTF32 format without a hash.

Parameters

<i>ptr</i>	The memory location to write to.
<i>maxLength</i>	The maximum length of the string.
<i>value</i>	The string to write.

Returns

The number of bytes written.

6.240.2.11 WriteStringUtf32WithHash()

```
static unsafe int WriteStringUtf32WithHash (  
    int * ptr,  
    int maxLength,  
    string value,  
    ref string cache ) [static]
```

Writes a string to the provided memory location in UTF32 format with a hash.

Parameters

<i>ptr</i>	The memory location to write to.
<i>maxLength</i>	The maximum length of the string.
<i>value</i>	The string to write.
<i>cache</i>	A reference to a cache string. This will be updated with the trimmed value of the input string.

Returns

The number of bytes written.

6.240.2.12 WriteStringUtf8NoHash()

```
static int WriteStringUtf8NoHash (
    void * destination,
    string str ) [static]
```

Writes a string to the provided memory location in UTF8 format without a hash.

Parameters

<i>destination</i>	The memory location to write to.
<i>str</i>	The string to write.

Returns

The number of bytes written.

6.241 ReflectionUtils Class Reference

Provides utility methods for reflection.

Static Public Member Functions

- static IEnumerable< Type > [GetAllNetworkBehaviourTypes](#) ()
Gets all types that are assignable from [NetworkBehaviour](#) from all assemblies.
- static IEnumerable< Type > [GetAllSimulationBehaviourTypes](#) ()
Gets all types that are assignable from [SimulationBehaviour](#) from all assemblies.
- static IEnumerable< Assembly > [GetAllWeavedAssemblies](#) ()
Gets all assemblies that have been weaved.
- static IEnumerable< Type > [GetAllWeavedNetworkBehaviourTypes](#) ()
Gets all types that are assignable from [NetworkBehaviour](#) from all weaved assemblies.
- static IEnumerable< Type > [GetAllWeavedSimulationBehaviourTypes](#) ()
Gets all types that are assignable from [SimulationBehaviour](#) from all weaved assemblies.
- static IEnumerable< Type > [GetAllWeaverGeneratedTypes](#) ()
Gets all types that have the [WeaverGeneratedAttribute](#) from all weaved assemblies.
- static T [GetCustomAttributeOrThrow](#)< T > (this MemberInfo member, bool inherit)
Retrieves a custom attribute of type T from the provided member.
- static [NetworkBehaviourWeavedAttribute](#) [GetWeavedAttributeOrThrow](#) (Type type)
Gets the [NetworkBehaviourWeavedAttribute](#) for the specified type. Throws an [InvalidOperationException](#) if the type has not been weaved.

6.241.1 Detailed Description

Provides utility methods for reflection.

6.241.2 Member Function Documentation

6.241.2.1 GetAllNetworkBehaviourTypes()

```
static IEnumerable<Type> GetAllNetworkBehaviourTypes ( ) [static]
```

Gets all types that are assignable from [NetworkBehaviour](#) from all assemblies.

Returns

An IEnumerable of all types that are assignable from [NetworkBehaviour](#).

6.241.2.2 GetAllSimulationBehaviourTypes()

```
static IEnumerable<Type> GetAllSimulationBehaviourTypes ( ) [static]
```

Gets all types that are assignable from [SimulationBehaviour](#) from all assemblies.

Returns

An IEnumerable of all types that are assignable from [SimulationBehaviour](#).

6.241.2.3 GetAllWeavedAssemblies()

```
static IEnumerable<Assembly> GetAllWeavedAssemblies ( ) [static]
```

Gets all assemblies that have been weaved.

Returns

An IEnumerable of all weaved assemblies.

6.241.2.4 GetAllWeavedNetworkBehaviourTypes()

```
static IEnumerable<Type> GetAllWeavedNetworkBehaviourTypes ( ) [static]
```

Gets all types that are assignable from [NetworkBehaviour](#) from all weaved assemblies.

Returns

An IEnumerable of all types that are assignable from [NetworkBehaviour](#) in weaved assemblies.

6.241.2.5 GetAllWeavedSimulationBehaviourTypes()

```
static IEnumerable<Type> GetAllWeavedSimulationBehaviourTypes ( ) [static]
```

Gets all types that are assignable from [SimulationBehaviour](#) from all weaved assemblies.

Returns

An IEnumerable of all types that are assignable from [SimulationBehaviour](#) in weaved assemblies.

6.241.2.6 GetAllWeaverGeneratedTypes()

```
static IEnumerable<Type> GetAllWeaverGeneratedTypes ( ) [static]
```

Gets all types that have the [WeaverGeneratedAttribute](#) from all weaved assemblies.

Returns

An IEnumerable of all types that have the [WeaverGeneratedAttribute](#) in weaved assemblies.

6.241.2.7 GetCustomAttributeOrThrow< T >()

```
static T GetCustomAttributeOrThrow< T > (
    this MemberInfo member,
    bool inherit ) [static]
```

Retrieves a custom attribute of type T from the provided member.

Template Parameters

<i>T</i>	The type of the attribute to retrieve. Must be a subclass of Attribute.
----------	---

Parameters

<i>member</i>	The member to retrieve the attribute from.
<i>inherit</i>	Specifies whether to search this member's inheritance chain to find the attributes.

Returns

The custom attribute of type T.

Exceptions

<i>ArgumentOutOfRangeException</i>	Thrown when the provided member does not have an attribute of type T.
<i>InvalidOperationException</i>	Thrown when the provided member has more than one attribute of type T.

Type Constraints

T : Attribute**6.241.2.8 GetWeavedAttributeOrThrow()**

```
static NetworkBehaviourWeavedAttribute GetWeavedAttributeOrThrow (
    Type type ) [static]
```

Gets the [NetworkBehaviourWeavedAttribute](#) for the specified type. Throws an `InvalidOperationException` if the type has not been weaved.

Parameters

<i>type</i>	The type to get the NetworkBehaviourWeavedAttribute for.
-------------	--

Returns

The [NetworkBehaviourWeavedAttribute](#) for the specified type.

Exceptions

<i>InvalidOperationException</i>	Thrown when the type has not been weaved.
----------------------------------	---

6.242 RenderAttribute Class Reference

Override default render settings for `[Networked]` properties.

Inherits `Attribute`.

Public Member Functions

- [RenderAttribute](#) ()
Default constructor for [RenderAttribute](#)
- [RenderAttribute](#) ([RenderTimeframe](#) timeframe, [RenderSource](#) source)
[RenderAttribute](#) Constructor

Properties

- string [Method](#) [get, set]
- [RenderSource](#) [Source](#) [get, set]
- [RenderTimeframe](#) [Timeframe](#) [get, set]

6.242.1 Detailed Description

Override default render settings for [Networked] properties.

6.242.2 Constructor & Destructor Documentation

6.242.2.1 RenderAttribute() [1/2]

```
RenderAttribute ( )
```

Default constructor for [RenderAttribute](#)

6.242.2.2 RenderAttribute() [2/2]

```
RenderAttribute (
    RenderTimeframe timeframe,
    RenderSource source )
```

[RenderAttribute](#) Constructor

Parameters

<i>timeframe</i>	RenderTimeframe reference
<i>source</i>	RenderSource reference

6.242.3 Property Documentation

6.242.3.1 Method

```
string Method [get], [set]
```

Override the default interpolation method for this property. The method's signature must match:

```
static T MethodName(T from, T to, float alpha) { /* ... */ }
```

6.242.3.2 Source

```
RenderSource Source [get], [set]
```

Force this property to be rendered using this [RenderSource](#) (in the chosen [RenderTimeframe](#)).

This setting is prioritized over [NetworkBehaviour](#) and [NetworkObject](#) overrides.

6.242.3.3 Timeframe

[RenderTimeframe](#) Timeframe [get], [set]

Force this property to be rendered in this [RenderTimeframe](#).

This setting is prioritized over [NetworkBehaviour](#) and [NetworkObject](#) overrides.

6.243 RenderTimeline Struct Reference

Can be used to acquire interpolated data for different points in time.

Static Public Member Functions

- static void [GetRenderBuffers](#) ([NetworkBehaviour](#) behaviour, out [NetworkBehaviourBuffer](#) from, out [NetworkBehaviourBuffer](#) to, out float alpha)

Get the render data for the given [NetworkBehaviour](#).

6.243.1 Detailed Description

Can be used to acquire interpolated data for different points in time.

6.243.2 Member Function Documentation

6.243.2.1 GetRenderBuffers()

```
static void GetRenderBuffers (
    NetworkBehaviour behaviour,
    out NetworkBehaviourBuffer from,
    out NetworkBehaviourBuffer to,
    out float alpha ) [static]
```

Get the render data for the given [NetworkBehaviour](#).

Parameters

<i>behaviour</i>	Network behaviour to get render data for.
<i>from</i>	Render data for the previous point in time.
<i>to</i>	Render data for the next point in time.
<i>alpha</i>	Interpolation alpha.

6.244 RenderWeavedAttribute Class Reference

Render Weaved Attribute

Inherits Attribute.

Public Member Functions

- [RenderWeavedAttribute](#) ()
[RenderWeavedAttribute](#) Constructor

6.244.1 Detailed Description

Render Weaved Attribute

6.244.2 Constructor & Destructor Documentation

6.244.2.1 RenderWeavedAttribute()

[RenderWeavedAttribute](#) ()

[RenderWeavedAttribute](#) Constructor

6.245 ResolveNetworkPrefabSourceAttribute Class Reference

Resolve Network Prefab Source Attribute

Inherits PropertyAttribute.

6.245.1 Detailed Description

Resolve Network Prefab Source Attribute

6.246 RpcAttribute Class Reference

Flags a method as being a networked Remote Procedure Call. Only usable in a [NetworkBehaviour](#). Calls to this method (from the indicated allowed [RpcSources](#)) will generate a network message, which will execute the method remotely on the indicated [RpcTargets](#). The RPC method can include an empty [RpcInfo](#) argument, that will include meta information about the RPC on the receiving peer.

Inherits Attribute.

Public Member Functions

- [RpcAttribute](#) ()
Constructor for RpcAttributes.
- [RpcAttribute](#) ([RpcSources](#) sources, [RpcTargets](#) targets)
Constructor for RpcAttributes.

Properties

- [RpcChannel](#) Channel = [RpcChannel.Reliable](#) [get, set]
Specifies which RpcChannel to use. Default value is [RpcChannel.Reliable](#)
- [RpcHostMode](#) HostMode = [RpcHostMode.SourceIsServer](#) [get, set]
Options for when the game is run in [SimulationModes.Host](#) mode and RPC is invoked by the host.
- bool [InvokeLocal](#) = true [get, set]
Indicates if the method should be called locally (on the RPC caller). This happens immediately. Default value is true.
- int [Sources](#) [get]
The legal [RpcSources](#) types that can trigger this Rpc. Cast to int. Default value is (int)[RpcSources.All](#).
- int [Targets](#) [get]
The [RpcTargets](#) types that will receive and invoke this method. Cast to int. Default value is (int)[RpcTargets.All](#).
- bool [TickAligned](#) = true [get, set]
Indicates if this RPC's execution will be postponed until the local simulation catches up with the sender's [Tick](#) number. Even if set to false, the order of Rpcs is always preserved. Rpcs are deferred until all preceding Rpcs have executed. Default value is true.

6.246.1 Detailed Description

Flags a method as being a networked Remote Procedure Call. Only usable in a [NetworkBehaviour](#). Calls to this method (from the indicated allowed [RpcSources](#)) will generate a network message, which will execute the method remotely on the indicated [RpcTargets](#). The RPC method can include an empty [RpcInfo](#) argument, that will include meta information about the RPC on the receiving peer.

Example:

```
| [Rpc(RpcSources.All, RpcTargets.All, InvokeLocal = false, InvokeResim =
false, Channel = RpcChannel.Reliable, TickAligned = true)]
| public void RPC_Configure(NetworkObject no, string name, Color color, RpcInfo
info = default) { } To target a specific Player, use the RpcTargetAttribute: | [Rpc] | public
void RpcFoo([RpcTarget] PlayerRef targetPlayer) {} Use RpcInvokeInfo as a return value
to access meta information about the RPC send attempt, such as failure to send reasons, message size, etc.
```

Non-static RPCs are only valid on a [NetworkBehaviour](#). Static RPCs can be implemented on [SimulationBehaviours](#), and do not require a [NetworkObject](#) instance. Static RPC require the first argument to be [NetworkRunner](#).

```
Static RPC Example: | [Rpc] | public static void RPC_Configure(NetworkRunner
runner) { }
```

6.246.2 Constructor & Destructor Documentation

6.246.2.1 RpcAttribute() [1/2]

```
RpcAttribute ( )
```

Constructor for RpcAttributes.

6.246.2.2 RpcAttribute() [2/2]

```
RpcAttribute (
    RpcSources sources,
    RpcTargets targets )
```

Constructor for RpcAttributes.

Parameters

<i>sources</i>	The legal RpcSources types that can trigger this Rpc. Default is RpcSources.All
<i>targets</i>	The RpcTargets types that will receive and invoke this method. Default is RpcTargets.All

6.246.3 Property Documentation

6.246.3.1 Channel

```
RpcChannel Channel = RpcChannel.Reliable [get], [set]
```

Specifies which RpcChannel to use. Default value is [RpcChannel.Reliable](#)

6.246.3.2 HostMode

```
RpcHostMode HostMode = RpcHostMode.SourceIsServer [get], [set]
```

Options for when the game is run in [SimulationModes.Host](#) mode and RPC is invoked by the host.

6.246.3.3 InvokeLocal

```
bool InvokeLocal = true [get], [set]
```

Indicates if the method should be called locally (on the RPC caller). This happens immediately. Default value is true.

6.246.3.4 Sources

```
int Sources [get]
```

The legal [RpcSources](#) types that can trigger this Rpc. Cast to int. Default value is (int)[RpcSources.All](#).

6.246.3.5 Targets

```
int Targets [get]
```

The [RpcTargets](#) types that will receive and invoke this method. Cast to int. Default value is (int)[RpcTargets.All](#).

6.246.3.6 TickAligned

```
bool TickAligned = true [get], [set]
```

Indicates if this RPC's execution will be postponed until the local simulation catches up with the sender's [Tick](#) number. Even if set to false, the order of Rpcs is always preserved. Rpcs are deferred until all preceding Rpcs have executed. Default value is true.

6.247 RpcHeader Struct Reference

Header for RPC messages.

Public Member Functions

- override string [ToString](#) ()
Returns a string that represents the current [RpcHeader](#).

Static Public Member Functions

- static [RpcHeader Create](#) (int staticRpcKey)
Creates a new [RpcHeader](#) with the provided staticRpcKey.
- static [RpcHeader Create](#) ([NetworkId](#) id, int behaviour, int method)
Creates a new [RpcHeader](#) with the provided [NetworkId](#), behaviour, and method.
- static [RpcHeader Read](#) (byte *data, out int size)
Reads the [RpcHeader](#) from the provided byte pointer.
- static int [ReadSize](#) (byte *data)
Reads the size of the [RpcHeader](#) from the provided byte pointer.
- static int [Write](#) ([RpcHeader](#) header, byte *data)
Writes the [RpcHeader](#) to the provided byte pointer.

Public Attributes

- ushort [Behaviour](#)
The behaviour associated with the RPC message.
- ushort [Method](#)
The method associated with the RPC message.
- [NetworkId Object](#)
The [NetworkId](#) of the object associated with the RPC message.

Static Public Attributes

- const int [SIZE](#) = NetworkId.SIZE + 2 + 2
The size of the [RpcHeader](#) structure in bytes.

6.247.1 Detailed Description

Header for RPC messages.

6.247.2 Member Function Documentation

6.247.2.1 Create() [1/2]

```
static RpcHeader Create (
    int staticRpcKey ) [static]
```

Creates a new [RpcHeader](#) with the provided staticRpcKey.

Parameters

<i>staticRpcKey</i>	The staticRpcKey associated with the RPC message.
---------------------	---

Returns

Returns a new [RpcHeader](#) with the provided staticRpcKey.

6.247.2.2 Create() [2/2]

```
static RpcHeader Create (
    NetworkId id,
    int behaviour,
    int method ) [static]
```

Creates a new [RpcHeader](#) with the provided [NetworkId](#), behaviour, and method.

Parameters

<i>id</i>	The NetworkId of the object associated with the RPC message.
<i>behaviour</i>	The behaviour associated with the RPC message.
<i>method</i>	The method associated with the RPC message.

Returns

Returns a new [RpcHeader](#) with the provided parameters.

6.247.2.3 Read()

```
static RpcHeader Read (  
    byte * data,  
    out int size ) [static]
```

Reads the [RpcHeader](#) from the provided byte pointer.

Parameters

<i>data</i>	The byte pointer to read the RpcHeader from.
<i>size</i>	The size of the RpcHeader structure in bytes.

Returns

Returns the [RpcHeader](#) read from the byte pointer.

6.247.2.4 ReadSize()

```
static int ReadSize (  
    byte * data ) [static]
```

Reads the size of the [RpcHeader](#) from the provided byte pointer.

Parameters

<i>data</i>	The byte pointer to read the RpcHeader size from.
-------------	---

Returns

Returns the size of the [RpcHeader](#) structure in bytes.

6.247.2.5 ToString()

```
override string ToString ( )
```

Returns a string that represents the current [RpcHeader](#).

Returns

Returns a string that represents the current [RpcHeader](#).

6.247.2.6 Write()

```
static int Write (
    RpcHeader header,
    byte * data ) [static]
```

Writes the [RpcHeader](#) to the provided byte pointer.

Parameters

<i>header</i>	The RpcHeader to write.
<i>data</i>	The byte pointer to write the RpcHeader to.

Returns

Returns the size of the [RpcHeader](#) structure in bytes.

6.247.3 Member Data Documentation

6.247.3.1 Behaviour

```
ushort Behaviour
```

The behaviour associated with the RPC message.

6.247.3.2 Method

```
ushort Method
```

The method associated with the RPC message.

6.247.3.3 Object

[NetworkId](#) Object

The [NetworkId](#) of the object associated with the RPC message.

6.247.3.4 SIZE

```
const int SIZE = NetworkId.SIZE + 2 + 2 [static]
```

The size of the [RpcHeader](#) structure in bytes.

6.248 RpcInfo Struct Reference

[RpcInfo](#) is a struct that contains information about the RPC message.

Public Member Functions

- override string [ToString](#) ()
Returns a string that represents the current [RpcInfo](#).

Static Public Member Functions

- static [RpcInfo FromLocal](#) ([NetworkRunner](#) runner, [RpcChannel](#) channel, [RpcHostMode](#) hostMode)
Creates a new [RpcInfo](#) instance for a local RPC message.
- static unsafe [RpcInfo FromMessage](#) ([NetworkRunner](#) runner, [SimulationMessage](#) *message, [RpcHostMode](#) hostMode)
Creates a new [RpcInfo](#) instance from a [SimulationMessage](#).

Public Attributes

- [RpcChannel Channel](#)
Represents the channel through which the RPC message was sent.
- bool [IsInvokeLocal](#)
Indicates whether the RPC message is invoked locally.
- [PlayerRef Source](#)
Represents the player who sent the RPC message.
- [Tick Tick](#)
Represents the tick at which the RPC message was sent.

6.248.1 Detailed Description

[RpcInfo](#) is a struct that contains information about the RPC message.

6.248.2 Member Function Documentation

6.248.2.1 FromLocal()

```
static RpcInfo FromLocal (
    NetworkRunner runner,
    RpcChannel channel,
    RpcHostMode hostMode ) [static]
```

Creates a new [RpcInfo](#) instance for a local RPC message.

Parameters

<i>runner</i>	The NetworkRunner associated with the RPC message.
<i>channel</i>	The RpcChannel through which the RPC message was sent.
<i>hostMode</i>	The RpcHostMode of the RPC message.

Returns

Returns a new [RpcInfo](#) instance with the provided parameters.

6.248.2.2 FromMessage()

```
static unsafe RpcInfo FromMessage (
    NetworkRunner runner,
    SimulationMessage * message,
    RpcHostMode hostMode ) [static]
```

Creates a new [RpcInfo](#) instance from a [SimulationMessage](#).

Parameters

<i>runner</i>	The NetworkRunner associated with the RPC message.
<i>message</i>	The SimulationMessage from which to create the RpcInfo instance.
<i>hostMode</i>	The RpcHostMode of the RPC message.

Returns

Returns a new [RpcInfo](#) instance with the provided parameters.

6.248.2.3 ToString()

```
override string ToString ( )
```

Returns a string that represents the current [RpcInfo](#).

Returns

Returns a string that represents the current [RpcInfo](#).

6.248.3 Member Data Documentation

6.248.3.1 Channel

[RpcChannel](#) Channel

Represents the channel through which the RPC message was sent.

6.248.3.2 IsInvokeLocal

bool IsInvokeLocal

Indicates whether the RPC message is invoked locally.

6.248.3.3 Source

[PlayerRef](#) Source

Represents the player who sent the RPC message.

6.248.3.4 Tick

[Tick](#) Tick

Represents the tick at which the RPC message was sent.

6.249 RpcInvokeData Struct Reference

Represents the data required to invoke an RPC message.

Public Member Functions

- override string [ToString](#) ()
Returns a string that represents the current [RpcInvokeData](#).

Public Attributes

- [RpcInvokeDelegate](#) Delegate
Represents the delegate to be invoked for the RPC message.
- int [Key](#)
Represents the key associated with the RPC message.
- int [Sources](#)
Represents the sources of the RPC message.
- int [Targets](#)
Represents the targets of the RPC message.

6.249.1 Detailed Description

Represents the data required to invoke an RPC message.

6.249.2 Member Function Documentation

6.249.2.1 ToString()

```
override string ToString ( )
```

Returns a string that represents the current [RpcInvokeData](#).

Returns

Returns a string that represents the current [RpcInvokeData](#).

6.249.3 Member Data Documentation

6.249.3.1 Delegate

[RpcInvokeDelegate](#) Delegate

Represents the delegate to be invoked for the RPC message.

6.249.3.2 Key

`int Key`

Represents the key associated with the RPC message.

6.249.3.3 Sources

`int Sources`

Represents the sources of the RPC message.

6.249.3.4 Targets

`int Targets`

Represents the targets of the RPC message.

6.250 RpcInvokeInfo Struct Reference

May be used as an optional [RpcAttribute](#) return value. Contains meta data about the RPC send, such as failure to send reasons, culling, message size, etc.

Public Member Functions

- override string [ToString](#) ()
Returns a string that represents the current [RpcInvokeInfo](#).

Public Attributes

- [RpcLocalInvokeResult](#) [LocalInvokeResult](#)
Represents the result of the local RPC invocation.
- [RpcSendCullResult](#) [SendCullResult](#)
Represents the result of the RPC message send operation.
- [RpcSendResult](#) [SendResult](#)
Contains detailed information about the RPC send operation result.

6.250.1 Detailed Description

May be used as an optional [RpcAttribute](#) return value. Contains meta data about the RPC send, such as failure to send reasons, culling, message size, etc.

Example:

```
| [Rpc] | public RpcInvokeInfo RpcFoo(int value) { | return default; | } | |  
public override void FixedUpdateNetwork() { | var info = RpcFoo(); | Debug.  
Log(info); | }
```

6.250.2 Member Function Documentation

6.250.2.1 ToString()

```
override string ToString ( )
```

Returns a string that represents the current [RpcInvokeInfo](#).

6.250.3 Member Data Documentation

6.250.3.1 LocalInvokeResult

```
RpcLocalInvokeResult LocalInvokeResult
```

Represents the result of the local RPC invocation.

6.250.3.2 SendCullResult

```
RpcSendCullResult SendCullResult
```

Represents the result of the RPC message send operation.

6.250.3.3 SendResult

```
RpcSendResult SendResult
```

Contains detailed information about the RPC send operation result.

6.251 RpcSendResult Struct Reference

RPC send operation result information.

Public Member Functions

- override string [ToString](#) ()
Returns a string that represents the current [RpcSendResult](#).

Public Attributes

- int [MessageSize](#)
The size of the RPC message.
- [RpcSendMessageResult](#) Result
Result flags for the RPC send operation.

6.251.1 Detailed Description

RPC send operation result information.

6.251.2 Member Function Documentation

6.251.2.1 ToString()

```
override string ToString ( )
```

Returns a string that represents the current [RpcSendResult](#).

6.251.3 Member Data Documentation

6.251.3.1 MessageSize

```
int MessageSize
```

The size of the RPC message.

6.251.3.2 Result

`RpcSendMessageResult` `Result`

Result flags for the RPC send operation.

6.252 RpcTargetAttribute Class Reference

RPC attribute used to indicate a specific target player for an RPC when sending from one player to another. RPC is sent to the server, and then is forwarded to the specified player. Usage:

Inherits `Attribute`.

Public Member Functions

- `RpcTargetAttribute` ()
RPC Attribute constructor.

6.252.1 Detailed Description

RPC attribute used to indicate a specific target player for an RPC when sending from one player to another. RPC is sent to the server, and then is forwarded to the specified player. Usage:

```
| [Rpc] | public void RpcFoo([RpcTarget] PlayerRef targetPlayer) { }
```

6.252.2 Constructor & Destructor Documentation

6.252.2.1 RpcTargetAttribute()

`RpcTargetAttribute` ()

RPC Attribute constructor.

6.253 SceneLoadDoneArgs Struct Reference

Struct that contains information about a scene after it has been loaded.

Public Member Functions

- `SceneLoadDoneArgs` (`SceneRef` sceneRef, `NetworkObject`[] sceneObjects, `Scene` scene=default, `GameObject`[] rootGameObjects=default)
Constructs a new `SceneLoadDoneArgs` struct.

Public Attributes

- readonly `GameObject[]` [RootGameObjects](#)
Array of root GameObjects present in the loaded Unity scene.
- readonly `Scene` [Scene](#)
The loaded Unity scene.
- readonly `NetworkObject[]` [SceneObjects](#)
Array of NetworkObjects present in the loaded scene.
- readonly [SceneRef](#) `SceneRef`
Reference to the loaded scene.

6.253.1 Detailed Description

Struct that contains information about a scene after it has been loaded.

6.253.2 Constructor & Destructor Documentation

6.253.2.1 SceneLoadDoneArgs()

```
SceneLoadDoneArgs (
    SceneRef sceneRef,
    NetworkObject[] sceneObjects,
    Scene scene = default,
    GameObject[] rootGameObjects = default )
```

Constructs a new [SceneLoadDoneArgs](#) struct.

Parameters

<i>sceneRef</i>	Reference to the loaded scene.
<i>sceneObjects</i>	Array of NetworkObjects present in the loaded scene.
<i>scene</i>	The loaded Unity scene.
<i>rootGameObjects</i>	Array of root GameObjects present in the loaded Unity scene.

6.253.3 Member Data Documentation

6.253.3.1 RootGameObjects

```
readonly GameObject[] RootGameObjects
```

Array of root GameObjects present in the loaded Unity scene.

6.253.3.2 Scene

readonly Scene Scene

The loaded Unity scene.

6.253.3.3 SceneObjects

readonly NetworkObject [] SceneObjects

Array of NetworkObjects present in the loaded scene.

6.253.3.4 SceneRef

readonly SceneRef SceneRef

Reference to the loaded scene.

6.254 SceneRef Struct Reference

Scene reference struct. Can be used to reference a scene by index or by path.

Inherits [INetworkStruct](#), and [IEquatable< SceneRef >](#).

Public Member Functions

- override bool [Equals](#) (object obj)
Determines whether the specified object is equal to the current [SceneRef](#).
- bool [Equals](#) ([SceneRef](#) other)
Determines whether the specified [SceneRef](#) is equal to the current [SceneRef](#).
- override int [GetHashCode](#) ()
Serves as the default hash function.
- bool [IsPath](#) (string path)
Checks if the [SceneRef](#) corresponds to a specific path.
- override string [ToString](#) ()
Returns a string that represents the current [SceneRef](#).
- string [ToString](#) (bool brackets, bool prefix)
Returns a string that represents the current [SceneRef](#), with optional formatting.

Static Public Member Functions

- static [SceneRef FromIndex](#) (int index)
Creates a [SceneRef](#) from an index.
- static [SceneRef FromPath](#) (string path)
Creates a scene ref from a path. The most common use case for this method is when using Unity's addressable scenes. The path is hashed (31 bit), so on rare occasion there may be a hash collision. In such case consider renaming a scene or construct your own hash and use [FromRaw](#). To check if a scene ref is was created for a specific path, use [IsPath](#).
- static [SceneRef FromRaw](#) (uint rawValue)
Creates a [SceneRef](#) from a raw value.
- static bool [operator!=](#) ([SceneRef](#) a, [SceneRef](#) b)
Returns true if the values are not equal.
- static bool [operator==](#) ([SceneRef](#) a, [SceneRef](#) b)
Returns true if the values are equal.

Public Attributes

- uint [RawValue](#)
The raw value of the [SceneRef](#). This can represent either an index or a path hash, depending on the flag.

Static Public Attributes

- const uint [FLAG_ADDRESSABLE](#) = 1u << 31
A constant representing the flag for addressable scenes.
- const int [SIZE](#) = 4
The size of the [SceneRef](#) structure in bytes.

Properties

- int [AsIndex](#) [get]
Returns lower 32 bits as an index.
- uint [AsPathHash](#) [get]
Gets the path hash of the [SceneRef](#).
- bool [IsIndex](#) [get]
Returns true if this scene ref is an index.
- bool [IsValid](#) [get]
If this scene index is valid
- static [SceneRef None](#) [get]
None scene

6.254.1 Detailed Description

Scene reference struct. Can be used to reference a scene by index or by path.

6.254.2 Member Function Documentation

6.254.2.1 Equals() [1/2]

```
override bool Equals (
    object obj )
```

Determines whether the specified object is equal to the current [SceneRef](#).

Parameters

<i>obj</i>	The object to compare with the current SceneRef .
------------	---

Returns

true if the specified object is equal to the current [SceneRef](#); otherwise, false.

6.254.2.2 Equals() [2/2]

```
bool Equals (
    SceneRef other )
```

Determines whether the specified [SceneRef](#) is equal to the current [SceneRef](#).

Parameters

<i>other</i>	The SceneRef to compare with the current SceneRef .
--------------	---

Returns

true if the specified [SceneRef](#) is equal to the current [SceneRef](#); otherwise, false.

6.254.2.3 FromIndex()

```
static SceneRef FromIndex (
    int index ) [static]
```

Creates a [SceneRef](#) from an index.

Parameters

<i>index</i>	The index to create the SceneRef from.
--------------	--

Returns

A [SceneRef](#) that represents the index.

Exceptions

<i>ArgumentOutOfRangeException</i>	Thrown when the index is less than 0 or equal to int.MaxValue.
------------------------------------	--

6.254.2.4 FromPath()

```
static SceneRef FromPath (  
    string path ) [static]
```

Creates a scene ref from a path. The most common use case for this method is when using Unity's addressable scenes. The path is hashed (31 bit), so on rare occasion there may be a hash collision. In such case consider renaming a scene or construct your own hash and use [FromRaw](#). To check if a scene ref is was created for a specific path, use [IsPath](#).

Parameters

<i>path</i>	The path to create the SceneRef from.
-------------	---

Returns

A [SceneRef](#) that represents the path.

6.254.2.5 FromRaw()

```
static SceneRef FromRaw (  
    uint rawValue ) [static]
```

Creates a [SceneRef](#) from a raw value.

Parameters

<i>rawValue</i>	The raw value to create the SceneRef from.
-----------------	--

Returns

A [SceneRef](#) that represents the raw value.

6.254.2.6 GetHashCode()

```
override int GetHashCode ( )
```

Serves as the default hash function.

Returns

A hash code for the current [SceneRef](#).

6.254.2.7 IsPath()

```
bool IsPath (
    string path )
```

Checks if the [SceneRef](#) corresponds to a specific path.

Parameters

<i>path</i>	The path to check.
-------------	--------------------

Returns

true if the [SceneRef](#) corresponds to the path; otherwise, false.

6.254.2.8 operator"!=()"

```
static bool operator!= (
    SceneRef a,
    SceneRef b ) [static]
```

Returns true if the values are not equal.

Parameters

<i>a</i>	SceneRef a
<i>b</i>	SceneRef b

Returns

true if the values are not equal; otherwise, false.

6.254.2.9 operator=="()

```
static bool operator== (
    SceneRef a,
    SceneRef b ) [static]
```

Returns true if the values are equal.

Parameters

<i>a</i>	SceneRef a
<i>b</i>	SceneRef b

Returns

true if the values are equal; otherwise, false.

6.254.2.10 ToString() [1/2]

```
override string ToString ( )
```

Returns a string that represents the current [SceneRef](#).

Returns

A string that represents the current [SceneRef](#).

6.254.2.11 ToString() [2/2]

```
string ToString (
    bool brackets,
    bool prefix )
```

Returns a string that represents the current [SceneRef](#), with optional formatting.

Parameters

<i>brackets</i>	If true, the string will be enclosed in brackets.
<i>prefix</i>	If true, the string will be prefixed with "Scene:".

Returns

A string that represents the current [SceneRef](#), formatted according to the provided parameters.

6.254.3 Member Data Documentation

6.254.3.1 FLAG_ADDRESSABLE

```
const uint FLAG_ADDRESSABLE = 1u << 31 [static]
```

A constant representing the flag for addressable scenes.

6.254.3.2 RawValue

```
uint RawValue
```

The raw value of the [SceneRef](#). This can represent either an index or a path hash, depending on the flag.

6.254.3.3 SIZE

```
const int SIZE = 4 [static]
```

The size of the [SceneRef](#) structure in bytes.

6.254.4 Property Documentation

6.254.4.1 AsIndex

```
int AsIndex [get]
```

Returns lower 32 bits as an index.

6.254.4.2 AsPathHash

```
uint AsPathHash [get]
```

Gets the path hash of the [SceneRef](#).

Exceptions

<i>InvalidOperationException</i>	Thrown when the SceneRef is an index, not a path.
----------------------------------	---

6.254.4.3 IsIndex

```
bool IsIndex [get]
```

Returns true if this scene ref is an index.

6.254.4.4 IsValid

```
bool IsValid [get]
```

If this scene index is valid

6.254.4.5 None

`SceneRef` None [static], [get]

None scene

6.255 SerializableDictionary< TKey, TValue > Class Template Reference

A serializable dictionary.

Inherits `SerializableDictionary`, `IDictionary< TKey, TValue >`, and `ISerializationCallbackReceiver`.

Public Member Functions

- void `Add` (TKey key, TValue value)
Adds the specified key and value to the `SerializableDictionary`.
- virtual void `Clear` ()
Removes all keys and values from the `SerializableDictionary`.
- bool `ContainsKey` (TKey key)
Determines whether the `SerializableDictionary` contains the specified key.
- Dictionary< TKey, TValue >.Enumerator `GetEnumerator` ()
Returns an enumerator that iterates through the `SerializableDictionary`.
- bool `Remove` (TKey key)
Removes the value with the specified key from the `SerializableDictionary`.
- void `Reset` ()
Resets the `SerializableDictionary`, clearing its internal dictionary.
- void `Store` ()
Stores the `SerializableDictionary`'s data into an array for serialization. This includes handling duplicates and null keys.
- bool `TryGetValue` (TKey key, out TValue value)
Gets the value associated with the specified key.

Static Public Member Functions

- static `SerializableDictionary< TKey, TValue > Create< TKey, TValue > ()`
Creates a new serializable dictionary.
- static `SerializableDictionary< TKey, TValue > Wrap` (Dictionary< TKey, TValue > dictionary)
Wraps an existing Dictionary into a `SerializableDictionary`.

Static Public Attributes

- const string `EntryKeyPropertyPath` = nameof(Entry.Key)
The property path for the key in the Entry structure.
- const string `ItemsPropertyPath` = nameof(_items)
The property path for the items in the `SerializableDictionary`.

Properties

- int [Count](#) [get]
Gets the number of key/value pairs contained in the [SerializableDictionary](#).
- bool [IsReadOnly](#) [get]
Gets a value indicating whether the [SerializableDictionary](#) is read-only. This value is always false.
- Dictionary< TKey, TValue >.KeyCollection [Keys](#) [get]
Gets a collection containing the keys in the [SerializableDictionary](#).
- TValue [this\[TKey key\]](#) [get, set]
Gets or sets the value associated with the specified key.
- Dictionary< TKey, TValue >.ValueCollection [Values](#) [get]
Gets a collection containing the values in the [SerializableDictionary](#).

6.255.1 Detailed Description

A serializable dictionary.

Template Parameters

<i>TKey</i>	The type of the dictionary key.
<i>TValue</i>	The type of the dictionary value.

This class is not thread-safe.

6.255.2 Member Function Documentation

6.255.2.1 Add()

```
void Add (
    TKey key,
    TValue value )
```

Adds the specified key and value to the [SerializableDictionary](#).

Parameters

<i>key</i>	The key of the element to add.
<i>value</i>	The value of the element to add.

6.255.2.2 Clear()

```
virtual void Clear ( ) [virtual]
```

Removes all keys and values from the [SerializableDictionary](#).

6.255.2.3 ContainsKey()

```
bool ContainsKey (
    TKey key )
```

Determines whether the [SerializableDictionary](#) contains the specified key.

Parameters

<i>key</i>	The key to locate in the SerializableDictionary .
------------	---

Returns

true if the [SerializableDictionary](#) contains an element with the specified key; otherwise, false.

6.255.2.4 Create< TKey, TValue >()

```
static SerializableDictionary<TKey, TValue> Create< TKey, TValue > ( ) [static]
```

Creates a new serializable dictionary.

Template Parameters

<i>TKey</i>	The type of the dictionary key.
<i>TValue</i>	The type of the dictionary value.

Returns

A new serializable dictionary.

6.255.2.5 GetEnumerator()

```
Dictionary<TKey, TValue>.Enumerator GetEnumerator ( )
```

Returns an enumerator that iterates through the [SerializableDictionary](#).

Returns

A Dictionary{TKey,TValue}.Enumerator structure for the [SerializableDictionary](#).

6.255.2.6 Remove()

```
bool Remove (
    TKey key )
```

Removes the value with the specified key from the [SerializableDictionary](#).

Parameters

<i>key</i>	The key of the element to remove.
------------	-----------------------------------

Returns

true if the element is successfully found and removed; otherwise, false. This method returns false if key is not found in the [SerializableDictionary](#).

6.255.2.7 Reset()

```
void Reset ( )
```

Resets the [SerializableDictionary](#), clearing its internal dictionary.

6.255.2.8 Store()

```
void Store ( )
```

Stores the [SerializableDictionary](#)'s data into an array for serialization. This includes handling duplicates and null keys.

6.255.2.9 TryGetValue()

```
bool TryGetValue (
    TKey key,
    out TValue value )
```

Gets the value associated with the specified key.

Parameters

<i>key</i>	The key of the value to get.
<i>value</i>	When this method returns, contains the value associated with the specified key, if the key is found; otherwise, the default value for the type of the value parameter. This parameter is passed uninitialized.

Returns

true if the [SerializableDictionary](#) contains an element with the specified key; otherwise, false.

6.255.2.10 Wrap()

```
static SerializableDictionary<TKey, TValue> Wrap (  
    Dictionary< TKey, TValue > dictionary ) [static]
```

Wraps an existing Dictionary into a [SerializableDictionary](#).

Parameters

<i>dictionary</i>	The Dictionary to be wrapped.
-------------------	-------------------------------

Returns

A new [SerializableDictionary](#) that wraps the provided Dictionary.

6.255.3 Member Data Documentation**6.255.3.1 EntryKeyPropertyPath**

```
const string EntryKeyPropertyPath = nameof(Entry.Key) [static]
```

The property path for the key in the Entry structure.

6.255.3.2 ItemsPropertyPath

```
const string ItemsPropertyPath = nameof(_items) [static]
```

The property path for the items in the [SerializableDictionary](#).

6.255.4 Property Documentation

6.255.4.1 Count

```
int Count [get]
```

Gets the number of key/value pairs contained in the [SerializableDictionary](#).

6.255.4.2 IsReadOnly

```
bool IsReadOnly [get]
```

Gets a value indicating whether the [SerializableDictionary](#) is read-only. This value is always false.

6.255.4.3 Keys

```
Dictionary<TKey, TValue>.KeyCollection Keys [get]
```

Gets a collection containing the keys in the [SerializableDictionary](#).

6.255.4.4 this[TKey key]

```
TValue this[TKey key] [get], [set]
```

Gets or sets the value associated with the specified key.

Parameters

<i>key</i>	The key of the value to get or set.
------------	-------------------------------------

Returns

The value associated with the specified key. If the specified key is not found, a get operation throws a [KeyNotFoundException](#), and a set operation creates a new element with the specified key.

6.255.4.5 Values

```
Dictionary<TKey, TValue>.ValueCollection Values [get]
```

Gets a collection containing the values in the [SerializableDictionary](#).

6.256 SessionInfo Class Reference

Holds information about the Game Session

Public Member Functions

- override string [ToString](#) ()
String representation of a [SessionInfo](#)
- bool [UpdateCustomProperties](#) (Dictionary< string, SessionProperty > customProperties)
Update or change the Custom Properties of the current joined Room

Static Public Member Functions

- static implicit [operator bool](#) ([SessionInfo](#) sessionInfo)
Check if the [SessionInfo](#) reference is not Null and is Valid.

Properties

- bool?? [IsOpen](#) [get, set]
Signal if the current connected Room is open
- bool [IsValid](#) [get]
Flag to signal if the [SessionInfo](#) is ready for use
- bool?? [IsVisible](#) [get, set]
Signal if the current connected Room is visible
- int [MaxPlayers](#) [get]
Max number of peer that can join this Session, this value always include an extra slot for the Server/Host
- string [Name](#) [get]
Stores the current Room Name
- int [PlayerCount](#) [get]
Current number of peers inside this Session, this includes the Server/Host and Clients
- ReadOnlyDictionary< string, SessionProperty > [Properties](#) [get]
Room Custom Properties
- string [Region](#) [get]
Stores the current connected Region

6.256.1 Detailed Description

Holds information about the Game Session

6.256.2 Member Function Documentation

6.256.2.1 operator bool()

```
static implicit operator bool (
    SessionInfo sessionInfo ) [static]
```

Check if the [SessionInfo](#) reference is not Null and is Valid.

Parameters

<i>sessionInfo</i>	Session Info
--------------------	--------------

6.256.2.2 ToString()

```
override string ToString ( )
```

String representation of a [SessionInfo](#)

Returns

Formatted [SessionInfo](#)

6.256.2.3 UpdateCustomProperties()

```
bool UpdateCustomProperties (
    Dictionary< string, SessionProperty > customProperties )
```

Update or change the Custom Properties of the current joined Room

Parameters

<i>customProperties</i>	New custom properties
-------------------------	-----------------------

6.256.3 Property Documentation**6.256.3.1 IsOpen**

```
bool?? IsOpen [get], [set]
```

Signal if the current connected Room is open

6.256.3.2 IsValid

```
bool IsValid [get]
```

Flag to signal if the [SessionInfo](#) is ready for use

6.256.3.3 IsVisible

```
bool?? IsVisible [get], [set]
```

Signal if the current connected Room is visible

6.256.3.4 MaxPlayers

```
int MaxPlayers [get]
```

Max number of peer that can join this Session, this value always include an extra slot for the Server/Host

6.256.3.5 Name

```
string Name [get]
```

Stores the current Room Name

6.256.3.6 PlayerCount

```
int PlayerCount [get]
```

Current number of peers inside this Session, this includes the Server/Host and Clients

6.256.3.7 Properties

```
ReadOnlyDictionary<string, SessionProperty> Properties [get]
```

Room Custom Properties

6.256.3.8 Region

```
string Region [get]
```

Stores the current connected Region

6.257 Simulation Class Reference

Main simulation class

Inherits ILogSourceProxy, and INetPeerGroupCallbacks.

Classes

- struct [AreaOfInterest](#)
Area of Interest Definition

Public Member Functions

- void [GetAreaOfInterestGizmoData](#) (List<(Vector3 center, Vector3 size, int playerCount, int objectCount)> result)
Clears the provided list and populates it with data about the current Area of Interest (AOI) cells. Each tuple in the list represents one AOI cell, containing its center, size, player count, and object count.
- [PlayerRef](#) [GetInputAuthority](#) ([NetworkObject](#) networkObject)
Get the Input Authority [PlayerRef](#) for a [NetworkObject](#)
- [SimulationInput](#) [GetInputForPlayer](#) ([PlayerRef](#) player)
Get the [Simulation](#) Input for a specific Player
- void [GetObjectsAndPlayersInAreaOfInterestCell](#) (int cellKey, List< [PlayerRef](#) > players, List< [NetworkId](#) > objects)
Used by RunnerAOIGizmos component. Supplies data about current active AOI cells.
- [PlayerRef](#) [GetStateAuthority](#) ([NetworkObject](#) networkObject)
Get the State Authority [PlayerRef](#) for a [NetworkObject](#)
- bool [HasAnyActiveConnections](#) ()
Signal if the Server has any Active Connection with any number of Clients.
- bool [IsInputAuthority](#) ([NetworkObject](#) networkObject, [PlayerRef](#) playerRef)
Check if a Player is the Input Authority over an [NetworkObject](#)
- bool? [IsInterestedIn](#) ([NetworkObject](#) obj, [PlayerRef](#) player)
Check if a [NetworkObject](#) is interested by a specific Player
- bool [IsLocalSimulationInputAuthority](#) ([NetworkObject](#) obj)
Check if the Local Player is the Input Authority over a [NetworkObject](#)
- bool [IsLocalSimulationStateAuthority](#) ([NetworkId](#) id)
Check if a Player is the State Authority over a [NetworkObject](#) by [NetworkId](#)
- bool [IsLocalSimulationStateAuthority](#) ([NetworkObject](#) obj)
Check if the Local Player is the State Authority over a [NetworkObject](#)
- bool [IsLocalSimulationStateOrInputSource](#) ([NetworkObject](#) obj)
Check if the Local Player is the State Authority or Input Authority over a [NetworkObject](#)
- bool [IsStateAuthority](#) ([NetworkObject](#) networkObject, [PlayerRef](#) playerRef)
Check if a Player is the State Authority over a [NetworkObject](#)
- bool [IsStateAuthority](#) ([PlayerRef](#) stateSource, [PlayerRef](#) playerRef)
Check if a Player is the State Authority in relation to another Player
- bool [TryGetHostPlayer](#) (out [PlayerRef](#) player)
Try to get the Host Player
- int [Update](#) (double dt)
Forwards the [Simulation](#) based on the Delta Time

Public Attributes

- [SimulationStats _stats](#) = new [SimulationStats\(\)](#)
Simulation Stats

Protected Member Functions

- virtual void [AfterSimulation](#) ()
Callback invoked after the [Simulation](#) Update
- virtual void [AfterUpdate](#) ()
Callback invoked After the [Simulation](#) Update
- virtual void [BeforeFirstTick](#) ()
Callback invoked before the First [Tick](#)
- virtual int [BeforeSimulation](#) ()
Callback invoked before the [Simulation](#) Loop
- virtual void [BeforeUpdate](#) ()
Callback invoked before the [Simulation](#) Update
- virtual void [NetworkConnected](#) (NetConnection *connection)
Callback invoked on the Connected
- virtual void [NetworkDisconnected](#) (NetConnection *connection, [NetDisconnectReason](#) reason)
Callback invoked on the Disconnected
- virtual void [NetworkReceiveDone](#) ()
Callback invoked when the Network Receive is completed
- virtual void [NoSimulation](#) ()
Callback invoked when there is no simulation

Properties

- virtual IEnumerable< [PlayerRef](#) > [ActivePlayers](#) [get]
List of Active players in the [Simulation](#)
- [SimulationConfig Config](#) [get]
The [SimulationConfig](#) file used by this [Simulation](#).
- float [DeltaTime](#) [get]
Gets the fixed tick time interval. Derived from the [SimulationRuntimeConfig.TickRate](#).
- int [InputCount](#) [get]
The current input collection size
- bool [IsClient](#) [get]
If this peer is a client. True for client peers in Server/Client topologies, and true for all peers in Shared Mode.
- bool [IsFirstTick](#) [get]
Use in conjunction with IsResimulation/IsForward inside of FixedUpdateNetwork to determine if the current tick being simulated is the first tick of the resimulation or forward phase of the simulation loop.
- bool [IsForward](#) [get]
Use inside of FixedUpdateNetwork to determine if the tick currently being simulated has NOT previously been simulated locally.
- bool [IsLastTick](#) [get]
Use in conjunction with IsResimulation/IsForward inside of FixedUpdateNetwork to determine if the current tick being simulated is the last tick of the resimulation or forward phase of the simulation loop.
- bool [IsLocalPlayerFirstExecution](#) [get]
True if the current stage of the simulation loop is Forward. False during resimulations.
- bool [IsMasterClient](#) [get]

Only valid in Shared Mode. Indicates if this peer is flagged as the MasterClient, which means it is default State↔ Authority

- bool [IsPlayer](#) [get]
True for any peer that represents a human player. This is true for all peers except a dedicated server.
- bool [IsResimulation](#) [get]
Use inside of FixedUpdateNetwork to determine if the tick currently being simulated has previously been simulated locally. Resimulation occurs in client prediction when new states arrive from the StateAuthority. Networked objects are set to the most current authority state tick, and simulations are repeated from that tick to the local current tick.
- bool [IsRunning](#) [get]
Signal if the [Simulation](#) is currently running
- bool [IsServer](#) [get]
If this peer is the server. True for the Server or Host peer in Server/Client topologies, and always false for all peers in Shared Mode (the relay is the server).
- bool [IsShutdown](#) [get]
- bool [IsSinglePlayer](#) [get]
Indicates that this simulation is operating in Single Player mode, which is a Host that accepts no connections.
- abstract [Tick LatestServerTick](#) [get]
latest tick on server we are aware of
- [NetAddress LocalAddress](#) [get]
Bound Address of the internal socket
- float [LocalAlpha](#) [get]
- abstract [PlayerRef LocalPlayer](#) [get]
Get LocalPlayer [PlayerRef](#)
- [SimulationModes Mode](#) [get]
Gets the [SimulationModes](#) flags for The type of network peer this simulation represents.
- [NetConfig * NetConfigPointer](#) [get]
Current NetConfig
- int [ObjectCount](#) [get]
Returns the number of objects in the simulation.
- Dictionary< [NetworkId](#), [NetworkObjectMeta](#) > [Objects](#) [get]
Returns a map of all objects in the simulation.
- [NetworkProjectConfig ProjectConfig](#) [get]
The [NetworkProjectConfig](#) file used by this [Simulation](#).
- float [RemoteAlpha](#) [get]
Remote Interpolation Alpha
- [Tick RemoteTick](#) [get]
Remote Tick
- [Tick RemoteTickPrevious](#) [get]
Remote previous Tick
- double [SendDelta](#) [get]
The packet send delta time
- int [SendRate](#) [get]
The packet send rate
- [SimulationStages Stage](#) [get]
Gets the current [SimulationStages](#) value.
- [Tick Tick](#) [get]
The tick associated with the current state of networked objects, or the current simulation tick being processed (when evaluated during FixedUpdateNetwork).
- double [TickDeltaDouble](#) [get]
The delta time of each tick as a double
- float [TickDeltaFloat](#) [get]
The delta time of each tick as a float

- [Tick](#) [TickPrevious](#) [get]
The previous tick
- int [TickRate](#) [get]
The current tick rate of the simulation
- int [TickStride](#) [get]
How large the ticks the current simulation takes are
- double [Time](#) [get]
The current simulation time in seconds
- [Topologies](#) [Topology](#) [get]
Indicates if a Server/Client or Shared Mode (relay server) topology is being used.

6.257.1 Detailed Description

Main simulation class

6.257.2 Member Function Documentation

6.257.2.1 AfterSimulation()

```
virtual void AfterSimulation ( ) [protected], [virtual]
```

Callback invoked after the [Simulation](#) Update

6.257.2.2 AfterUpdate()

```
virtual void AfterUpdate ( ) [protected], [virtual]
```

Callback invoked After the [Simulation](#) Update

6.257.2.3 BeforeFirstTick()

```
virtual void BeforeFirstTick ( ) [protected], [virtual]
```

Callback invoked before the First [Tick](#)

6.257.2.4 BeforeSimulation()

```
virtual int BeforeSimulation ( ) [protected], [virtual]
```

Callback invoked before the [Simulation](#) Loop

Returns

Total number of re-simulations

6.257.2.5 BeforeUpdate()

```
virtual void BeforeUpdate ( ) [protected], [virtual]
```

Callback invoked before the [Simulation](#) Update

6.257.2.6 GetAreaOfInterestGizmoData()

```
void GetAreaOfInterestGizmoData (
    List<(Vector3 center, Vector3 size, int playerCount, int objectCount)> result )
```

Clears the provided list and populates it with data about the current Area of Interest (AOI) cells. Each tuple in the list represents one AOI cell, containing its center, size, player count, and object count.

Parameters

<i>result</i>	The list to be populated with AOI cell data.
---------------	--

6.257.2.7 GetInputAuthority()

```
PlayerRef GetInputAuthority (
    NetworkObject networkObject )
```

Get the Input Authority [PlayerRef](#) for a [NetworkObject](#)

Parameters

<i>networkObject</i>	NetworkObject to check
----------------------	--

Returns

[PlayerRef](#) of the Input Authority for the [NetworkObject](#)

6.257.2.8 GetInputForPlayer()

```
SimulationInput GetInputForPlayer (
    PlayerRef player )
```

Get the [Simulation](#) Input for a specific Player

Parameters

<i>player</i>	Player to check for the Simulation Input
---------------	--

Returns

[Simulation](#) Input for a specific Player

6.257.2.9 GetObjectsAndPlayersInAreaOfInterestCell()

```
void GetObjectsAndPlayersInAreaOfInterestCell (
    int cellKey,
    List< PlayerRef > players,
    List< NetworkId > objects )
```

Used by RunnerAOIGizmos component. Supplies data about current active AOI cells.

6.257.2.10 GetStateAuthority()

```
PlayerRef GetStateAuthority (
    NetworkObject networkObject )
```

Get the State Authority [PlayerRef](#) for a [NetworkObject](#)

Parameters

<i>networkObject</i>	NetworkObject to check
----------------------	--

Returns

[PlayerRef](#) of the State Authority for the [NetworkObject](#)

6.257.2.11 HasAnyActiveConnections()

```
bool HasAnyActiveConnections ( )
```

Signal if the Server has any Active Connection with any number of Clients.

Returns

True, if at least one connection is active, false otherwise.

6.257.2.12 IsInputAuthority()

```
bool IsInputAuthority (
    NetworkObject networkObject,
    PlayerRef playerRef )
```

Check if a Player is the Input Authority over an [NetworkObject](#)

Parameters

<i>networkObject</i>	NetworkObject to check
<i>playerRef</i>	Player to check

Returns

True if the Player is the Input Authority over the [NetworkObject](#), false otherwise

6.257.2.13 IsInterestedIn()

```
bool? IsInterestedIn (
    NetworkObject obj,
    PlayerRef player )
```

Check if a [NetworkObject](#) is interested by a specific Player

Parameters

<i>obj</i>	NetworkObject to check
<i>player</i>	Player to check

Returns

True if the Player is interested in the [NetworkObject](#), false otherwise

6.257.2.14 IsLocalSimulationInputAuthority()

```
bool IsLocalSimulationInputAuthority (
    NetworkObject obj )
```

Check if the Local Player is the Input Authority over a [NetworkObject](#)

Parameters

<i>obj</i>	NetworkObject to check
------------	--

Returns

True if the Player is the Input Authority, false otherwise

6.257.2.15 IsLocalSimulationStateAuthority() [1/2]

```
bool IsLocalSimulationStateAuthority (
    NetworkId id )
```

Check if a Player is the State Authority over a [NetworkObject](#) by [NetworkId](#)

Parameters

<i>id</i>	NetworkId of the NetworkObject to check
-----------	---

Returns

True if the Player is the State Authority, false otherwise

6.257.2.16 IsLocalSimulationStateAuthority() [2/2]

```
bool IsLocalSimulationStateAuthority (
    NetworkObject obj )
```

Check if the Local Player is the State Authority over a [NetworkObject](#)

Parameters

<i>obj</i>	NetworkObject to check
------------	--

Returns

True if the Player is the State Authority, false otherwise

6.257.2.17 IsLocalSimulationStateOrInputSource()

```
bool IsLocalSimulationStateOrInputSource (
    NetworkObject obj )
```

Check if the Local Player is the State Authority or Input Authority over a [NetworkObject](#)

Parameters

<i>obj</i>	NetworkObject to check
------------	--

Returns

True if the Player is the State Authority or Input Authority, false otherwise

6.257.2.18 IsStateAuthority() [1/2]

```
bool IsStateAuthority (
    NetworkObject networkObject,
    PlayerRef playerRef )
```

Check if a Player is the State Authority over a [NetworkObject](#)

Parameters

<i>networkObject</i>	NetworkObject to check
<i>playerRef</i>	Player to check

Returns

True if the Player is the State Authority, false otherwise

6.257.2.19 IsStateAuthority() [2/2]

```
bool IsStateAuthority (
    PlayerRef stateSource,
    PlayerRef playerRef )
```

Check if a Player is the State Authority in relation to another Player

Parameters

<i>stateSource</i>	State Source Player
<i>playerRef</i>	Player to check

Returns

True if the Player is the State Authority, false otherwise

6.257.2.20 NetworkConnected()

```
virtual void NetworkConnected (
    NetConnection * connection ) [protected], [virtual]
```

Callback invoked on the Connected

Parameters

<i>connection</i>	Connection that was connected
-------------------	-------------------------------

6.257.2.21 NetworkDisconnected()

```
virtual void NetworkDisconnected (
    NetConnection * connection,
    NetDisconnectReason reason ) [protected], [virtual]
```

Callback invoked on the Disconnected

Parameters

<i>connection</i>	Connection that was disconnected
<i>reason</i>	Reason for the disconnection

6.257.2.22 NetworkReceiveDone()

```
virtual void NetworkReceiveDone ( ) [protected], [virtual]
```

Callback invoked when the Network Receive is completed

6.257.2.23 NoSimulation()

```
virtual void NoSimulation ( ) [protected], [virtual]
```

Callback invoked when there is no simulation

6.257.2.24 TryGetHostPlayer()

```
bool TryGetHostPlayer (
    out PlayerRef player )
```

Try to get the Host Player

Parameters

<i>player</i>	Host Player
---------------	-------------

Returns

True if the Host Player was found, false otherwise

6.257.2.25 Update()

```
int Update (
    double dt )
```

Forwards the [Simulation](#) based on the Delta Time

Parameters

<i>dt</i>	Delta Time used to forward the simulation
-----------	---

Returns

How many Ticks executed on this Update

6.257.3 Member Data Documentation

6.257.3.1 _stats

```
SimulationStats _stats = new SimulationStats()
```

[Simulation](#) Stats

6.257.4 Property Documentation

6.257.4.1 ActivePlayers

```
virtual IEnumerable<PlayerRef> ActivePlayers [get]
```

List of Active players in the [Simulation](#)

6.257.4.2 Config

```
SimulationConfig Config [get]
```

The [SimulationConfig](#) file used by this [Simulation](#).

6.257.4.3 DeltaTime

```
float DeltaTime [get]
```

Gets the fixed tick time interval. Derived from the [SimulationRuntimeConfig.TickRate](#).

6.257.4.4 InputCount

```
int InputCount [get]
```

The current input collection size

6.257.4.5 IsClient

```
bool IsClient [get]
```

If this peer is a client. True for client peers in Server/Client topologies, and true for all peers in Shared Mode.

6.257.4.6 IsFirstTick

```
bool IsFirstTick [get]
```

Use in conjunction with IsResimulation/IsForward inside of FixedUpdateNetwork to determine if the current tick being simulated is the first tick of the resimulation or forward phase of the simulation loop.

'Resimulation' describes simulating a tick that has been previously been simulated.

'Forward' describes simulating a tick that is being simulated for the first time locally.

'Prediction' describes simulating ticks higher than the most current known StateAuthority snapshot tick.

6.257.4.7 IsForward

```
bool IsForward [get]
```

Use inside of FixedUpdateNetwork to determine if the tick currently being simulated has NOT previously been simulated locally.

6.257.4.8 IsLastTick

```
bool IsLastTick [get]
```

Use in conjunction with IsResimulation/IsForward inside of FixedUpdateNetwork to determine if the current tick being simulated is the last tick of the resimulation or forward phase of the simulation loop.

'Resimulation' describes simulating a tick that has been previously been simulated.

'Forward' describes simulating a tick that is being simulated for the first time locally.

'Prediction' describes simulating ticks higher than the most current known StateAuthority snapshot tick.

6.257.4.9 IsLocalPlayerFirstExecution

```
bool IsLocalPlayerFirstExecution [get]
```

True if the current stage of the simulation loop is Forward. False during resimulations.

'Resimulation' describes simulating a tick that has been previously been simulated.

'Forward' describes simulating a tick that is being simulated for the first time locally.

'Prediction' describes simulating ticks higher than the most current known StateAuthority snapshot tick.

6.257.4.10 IsMasterClient

```
bool IsMasterClient [get]
```

Only valid in Shared Mode. Indicates if this peer is flagged as the MasterClient, which means it is default State↔ Authority

6.257.4.11 IsPlayer

```
bool IsPlayer [get]
```

True for any peer that represents a human player. This is true for all peers except a dedicated server.

6.257.4.12 IsResimulation

```
bool IsResimulation [get]
```

Use inside of FixedUpdateNetwork to determine if the tick currently being simulated has previously been simulated locally. Resimulation occurs in client prediction when new states arrive from the StateAuthority. Networked objects are set to the most current authority state tick, and simulations are repeated from that tick to the local current tick.

6.257.4.13 IsRunning

```
bool IsRunning [get]
```

Signal if the [Simulation](#) is currently running

6.257.4.14 IsServer

```
bool IsServer [get]
```

If this peer is the server. True for the Server or Host peer in Server/Client topologies, and always false for all peers in Shared Mode (the relay is the server).

6.257.4.15 IsShutdown

```
bool IsShutdown [get]
```

6.257.4.16 IsSinglePlayer

```
bool IsSinglePlayer [get]
```

Indicates that this simulation is operating in Single Player mode, which is a Host that accepts no connections.

6.257.4.17 LatestServerTick

```
abstract Tick LatestServerTick [get]
```

latest tick on server we are aware of

6.257.4.18 LocalAddress

```
NetAddress LocalAddress [get]
```

Bound Address of the internal socket

6.257.4.19 LocalAlpha

```
float LocalAlpha [get]
```

6.257.4.20 LocalPlayer

```
abstract PlayerRef LocalPlayer [get]
```

Get LocalPlayer [PlayerRef](#)

6.257.4.21 Mode

```
SimulationModes Mode [get]
```

Gets the [SimulationModes](#) flags for The type of network peer this simulation represents.

6.257.4.22 NetConfigPointer

```
NetConfig* NetConfigPointer [get]
```

Current NetConfig

6.257.4.23 ObjectCount

```
int ObjectCount [get]
```

Returns the number of objects in the simulation.

6.257.4.24 Objects

```
Dictionary<NetworkId, NetworkObjectMeta> Objects [get]
```

Returns a map of all objects in the simulation.

6.257.4.25 ProjectConfig

```
NetworkProjectConfig ProjectConfig [get]
```

The [NetworkProjectConfig](#) file used by this [Simulation](#).

6.257.4.26 RemoteAlpha

```
float RemoteAlpha [get]
```

Remote Interpolation Alpha

6.257.4.27 RemoteTick

```
Tick RemoteTick [get]
```

Remote [Tick](#)

6.257.4.28 RemoteTickPrevious

```
Tick RemoteTickPrevious [get]
```

Remote previous [Tick](#)

6.257.4.29 SendDelta

```
double SendDelta [get]
```

The packet send delta time

6.257.4.30 SendRate

```
int SendRate [get]
```

The packet send rate

6.257.4.31 Stage

```
SimulationStages Stage [get]
```

Gets the current [SimulationStages](#) value.

6.257.4.32 Tick

```
Tick Tick [get]
```

The tick associated with the current state of networked objects, or the current simulation tick being processed (when evaluated during FixedUpdateNetwork).

6.257.4.33 TickDeltaDouble

```
double TickDeltaDouble [get]
```

The delta time of each tick as a double

6.257.4.34 TickDeltaFloat

```
float TickDeltaFloat [get]
```

The delta time of each tick as a float

6.257.4.35 TickPrevious

`Tick TickPrevious [get]`

The previous tick

6.257.4.36 TickRate

`int TickRate [get]`

The current tick rate of the simulation

6.257.4.37 TickStride

`int TickStride [get]`

How large the ticks the current simulation takes are

6.257.4.38 Time

`double Time [get]`

The current simulation time in seconds

6.257.4.39 Topology

`Topologies Topology [get]`

Indicates if a Server/Client or Shared Mode (relay server) topology is being used.

6.258 Simulation.AreaOfInterest Struct Reference

Area of Interest Definition

Static Public Member Functions

- static int int int z **ClampCellCoords** (int x, int y, int z)
- static int [GetCellSize](#) ()
Get the size of each cell in the AOI grid.
- static int int int z **GetGridSize** ()
- static void [SphereToCells](#) (Vector3 position, float radius, HashSet< int > cells)
Convert a sphere into a set of AOI cells.
- static int [ToCell](#) (int x, int y, int z)
Convert a cell coordinate into the respective cell index.
- static int [ToCell](#) (Vector3 position)
Convert a position into the respective cell index.
- static Vector3 [ToCellCenter](#) (int index)
Convert a cell index into the respective cell center position.
- static int int int z **ToCellCoords** (int index)
- static int int int z **ToCellCoords** (Vector3 position)

Static Public Attributes

- static int [CELL_SIZE](#) = SIZE_DEFAULT
Size of each cell in the AOI grid.
- static int x
Get the size of the AOI grid.
- static int int y

6.258.1 Detailed Description

Area of Interest Definition

6.258.2 Member Function Documentation

6.258.2.1 GetCellSize()

```
static int GetCellSize ( ) [static]
```

Get the size of each cell in the AOI grid.

Returns

The size of each cell in the AOI grid.

6.258.2.2 SphereToCells()

```
static void SphereToCells (
    Vector3 position,
    float radius,
    HashSet< int > cells ) [static]
```

Convert a sphere into a set of AOI cells.

Parameters

<i>position</i>	Sphere center
<i>radius</i>	Sphere radius
<i>cells</i>	Resulting set of cells

6.258.2.3 ToCell() [1/2]

```
static int ToCell (  
    int x,  
    int y,  
    int z ) [static]
```

Convert a cell coordinate into the respective cell index.

Parameters

<i>x</i>	X coordinate
<i>y</i>	Y coordinate
<i>z</i>	Z coordinate

Returns

Cell index

6.258.2.4 ToCell() [2/2]

```
static int ToCell (  
    Vector3 position ) [static]
```

Convert a position into the respective cell index.

Parameters

<i>position</i>	Position
-----------------	----------

Returns

Cell index

6.258.2.5 ToCellCenter()

```
static Vector3 ToCellCenter (
    int index ) [static]
```

Convert a cell index into the respective cell center position.

Parameters

<i>index</i>	Cell index
--------------	------------

Returns

Cell center position

6.258.3 Member Data Documentation

6.258.3.1 CELL_SIZE

```
int CELL_SIZE = SIZE_DEFAULT [static]
```

Size of each cell in the AOI grid.

6.258.3.2 x

```
static int x [static]
```

Get the size of the AOI grid.

Clamp cell coordinates to the valid range.

Converts a cell index into its corresponding cell coordinates.

Convert a position into the respective cell coordinate.

Returns

The size of the AOI grid.

Parameters

<i>position</i>	Position
-----------------	----------

Returns

Cell coordinate

Parameters

<i>index</i>	The index of the cell to be converted.
--------------	--

Returns

A tuple containing the x, y, and z coordinates of the cell.

Parameters

<i>x</i>	X coordinate
<i>y</i>	Y coordinate
<i>z</i>	Z coordinate

Returns

Clamped cell coordinates

6.259 SimulationBehaviour Class Reference

Base class for a [Fusion](#) aware [Behaviour](#) (derived from `UnityEngine.MonoBehaviour`). Objects derived from this object can be associated with a [NetworkRunner](#) and [Simulation](#). If a parent [NetworkObject](#) is found, this component will also be associated with that network entity.

Inherits [Behaviour](#).

Inherited by [HitboxManager](#), and [NetworkBehaviour](#).

Public Member Functions

- virtual void [FixedUpdateNetwork](#) ()
Fusion FixedUpdate timing callback.
- virtual void [Render](#) ()
Post simulation frame rendering callback. Runs after all simulations have finished. Use in place of Unity's Update when Fusion is handling Physics.

Properties

- bool [CanReceiveRenderCallback](#) [get]
Gets a value indicating whether this instance can receive render callbacks.
- bool [CanReceiveSimulationCallback](#) [get]
Gets a value indicating whether this instance can receive simulation callbacks.
- [NetworkObject](#) [Object](#) [get]
The NetworkObject this component is associated with.
- [NetworkRunner](#) [Runner](#) [get]
The NetworkRunner this component is associated with.

Additional Inherited Members

6.259.1 Detailed Description

Base class for a [Fusion](#) aware [Behaviour](#) (derived from `UnityEngine.MonoBehaviour`). Objects derived from this object can be associated with a [NetworkRunner](#) and [Simulation](#). If a parent [NetworkObject](#) is found, this component will also be associated with that network entity.

6.259.2 Member Function Documentation

6.259.2.1 FixedUpdateNetwork()

```
virtual void FixedUpdateNetwork ( ) [virtual]
```

[Fusion](#) FixedUpdate timing callback.

Reimplemented in [NetworkBehaviour](#).

6.259.2.2 Render()

```
virtual void Render ( ) [virtual]
```

Post simulation frame rendering callback. Runs after all simulations have finished. Use in place of Unity's Update when [Fusion](#) is handling Physics.

Reimplemented in [NetworkTransform](#), and [NetworkMecanimAnimator](#).

6.259.3 Property Documentation

6.259.3.1 CanReceiveRenderCallback

```
bool CanReceiveRenderCallback [get]
```

Gets a value indicating whether this instance can receive render callbacks.

`true` if this instance can receive render callbacks; otherwise, `false`.

This property checks the current flags of the instance against various conditions to determine if it can receive render callbacks.

6.259.3.2 CanReceiveSimulationCallback

```
bool CanReceiveSimulationCallback [get]
```

Gets a value indicating whether this instance can receive simulation callbacks.

`true` if this instance can receive simulation callbacks; otherwise, `false`.

This property checks the current flags of the instance against various conditions to determine if it can receive simulation callbacks.

6.259.3.3 Object

```
NetworkObject Object [get]
```

The [NetworkObject](#) this component is associated with.

6.259.3.4 Runner

```
NetworkRunner Runner [get]
```

The [NetworkRunner](#) this component is associated with.

6.260 SimulationBehaviourAttribute Class Reference

Attribute for specifying which [SimulationStages](#) and [SimulationModes](#) this [SimulationBehaviour](#) will execute in. Can be used to limit execution to only Host, Server or Client peers, or to only execute on Resimulation or Forward ticks. Usage:

Inherits Attribute.

Properties

- [SimulationModes Modes](#) [get, set]
Flag for which indicated peers in [SimulationModes](#) will execute this script.
- [SimulationStages Stages](#) [get, set]
Flag for which stages of the simulation loop this component will execute this script.
- [Topologies Topologies](#) [get, set]
Flag for which topologies this script will execute in

6.260.1 Detailed Description

Attribute for specifying which [SimulationStages](#) and [SimulationModes](#) this [SimulationBehaviour](#) will execute in. Can be used to limit execution to only Host, Server or Client peers, or to only execute on Resimulation or Forward ticks. Usage:

```
[SimulationBehaviour(Stages = SimulationStages.Forward, Modes = SimulationModes.Server  
| SimulationModes.Host)]
```

6.260.2 Property Documentation

6.260.2.1 Modes

`SimulationModes` Modes [get], [set]

Flag for which indicated peers in `SimulationModes` will execute this script.

6.260.2.2 Stages

`SimulationStages` Stages [get], [set]

Flag for which stages of the simulation loop this component will execute this script.

6.260.2.3 Topologies

`Topologies` Topologies [get], [set]

Flag for which topologies this script will execute in

6.261 SimulationBehaviourListScope Struct Reference

Provides a scope for a `SimulationBehaviourUpdater.BehaviourList`, incrementing its lock count on creation and decrementing it on disposal. If the lock count reaches zero on disposal, all pending removals in the list are performed.

Inherits `IDisposable`.

Public Member Functions

- void `Dispose` ()
Dispose unmanaged resources.

6.261.1 Detailed Description

Provides a scope for a `SimulationBehaviourUpdater.BehaviourList`, incrementing its lock count on creation and decrementing it on disposal. If the lock count reaches zero on disposal, all pending removals in the list are performed.

6.261.2 Member Function Documentation

6.261.2.1 Dispose()

```
void Dispose ( )
```

Dispose unmanaged resources.

6.262 SimulationConfig Class Reference

Project configuration settings specific to how the [Simulation](#) class behaves.

Public Types

- enum class [DataConsistency](#)
- enum class [InputTransferModes](#)

Public Attributes

- bool [HostMigration](#)
If, in host mode, we should allow host migration if the current host leaves.
- int [InputDataWordCount](#)
Input Data Word Count
- [InputTransferModes](#) [InputTransferMode](#)
The way which input is transferred
- [DataConsistency](#) [ObjectDataConsistency](#)
How the server chooses to send [NetworkObject](#) updates to balance consistency and bandwidth consumption.
- int [PlayerCount](#) = 10
The default number of players allowed to join a game instance. Can also be changed in code when starting [Fusion](#).
- [NetworkProjectConfig.ReplicationFeatures](#) [ReplicationFeatures](#)
Features to enabled to replication such as area of interest, etc.
- [TickRate.Selection](#) [TickRateSelection](#) = [TickRate.Default](#)
The default tick rate to use. Can also be changed in code when starting [Fusion](#).
- [Topologies](#) [Topology](#)
The topology used

Properties

- bool [AreaOfInterestEnabled](#) [get]
Signal if AOI is enabled
- int [InputTotalWordCount](#) [get]
- bool [SchedulingEnabled](#) [get]
Signal if scheduling is enabled
- bool [SchedulingWithoutAOI](#) [get]
Signal if scheduling is running without AOI

6.262.1 Detailed Description

Project configuration settings specific to how the [Simulation](#) class behaves.

6.262.2 Member Enumeration Documentation

6.262.2.1 DataConsistency

```
enum DataConsistency [strong]
```

Enumerator

Full	When a NetworkBehaviour 's data changes, the server will send all properties whose changes have not been acknowledged. This option consumes more bandwidth, but guarantees that each NetworkBehaviour has consistent state.
Eventual	When a NetworkBehaviour 's data changes, the server will only send the newly changed properties. This option consumes less bandwidth, but a NetworkBehaviour may have inconsistent state at times (some properties up-to-date but not others).

6.262.2.2 InputTransferModes

```
enum InputTransferModes [strong]
```

Enumerator

Redundancy	Send delta compressed and redundant input, used for most games
LatestState	Only send latest input state, useful for VR, etc.

6.262.3 Member Data Documentation

6.262.3.1 HostMigration

```
bool HostMigration
```

If, in host mode, we should allow host migration if the current host leaves.

6.262.3.2 InputDataWordCount

```
int InputDataWordCount
```

Input Data Word Count

6.262.3.3 InputTransferMode

```
InputTransferModes InputTransferMode
```

The way which input is transferred

6.262.3.4 ObjectDataConsistency

```
DataConsistency ObjectDataConsistency
```

How the server chooses to send [NetworkObject](#) updates to balance consistency and bandwidth consumption.

6.262.3.5 PlayerCount

```
int PlayerCount = 10
```

The default number of players allowed to join a game instance. Can also be changed in code when starting [Fusion](#).

6.262.3.6 ReplicationFeatures

```
NetworkProjectConfig.ReplicationFeatures ReplicationFeatures
```

Features to enabled to replication such as area of interest, etc.

6.262.3.7 TickRateSelection

```
TickRate.Selection TickRateSelection = TickRate.Default
```

The default tick rate to use. Can also be changed in code when starting [Fusion](#).

6.262.3.8 Topology

[Topologies](#) Topology

The topology used

6.262.4 Property Documentation

6.262.4.1 AreaOfInterestEnabled

```
bool AreaOfInterestEnabled [get]
```

Signal if AOI is enabled

6.262.4.2 InputTotalWordCount

```
int InputTotalWordCount [get]
```

6.262.4.3 SchedulingEnabled

```
bool SchedulingEnabled [get]
```

Signal if scheduling is enabled

6.262.4.4 SchedulingWithoutAOI

```
bool SchedulingWithoutAOI [get]
```

Signal if scheduling is running without AOI

6.263 SimulationConnectionStats Class Reference

[Simulation](#) Connection Statistics

Public Attributes

- OverTimeStatBuffer [InMessagesBandwidth](#)
- OverTimeStatBuffer [InMessagesPerPacket](#)
- OverTimeStatBuffer [InObjectBandwidth](#)
- OverTimeStatBuffer [InObjectDestroysPerPacket](#)
- OverTimeStatBuffer [InObjectUpdatesPerPacket](#)
- OverTimeStatBuffer [InPacketsBandwidth](#)
- OverTimeStatBuffer [InPacketsRecv](#)
- OverTimeStatBuffer [InputsBandwidth](#)
- OverTimeStatBuffer [InputsMissing](#)
- OverTimeStatBuffer [InputsPerPacket](#)
- OverTimeStatBuffer [InReliableDataBandwidth](#)
- OverTimeStatBuffer [OutMessagesBandwidth](#)
- OverTimeStatBuffer [OutMessagesPerPacket](#)
- OverTimeStatBuffer [OutObjectBandwidth](#)
- OverTimeStatBuffer [OutObjectDestroysPerPacket](#)
- OverTimeStatBuffer [OutObjectUpdatesPerPacket](#)
- OverTimeStatBuffer [OutPacketsBandwidth](#)
- OverTimeStatBuffer [OutPacketsDelivered](#)
- OverTimeStatBuffer [OutPacketsLost](#)
- OverTimeStatBuffer [OutPacketsSent](#)
- OverTimeStatBuffer [OutReliableDataBandwidth](#)
- OverTimeStatBuffer [RoundTripTime](#)

6.263.1 Detailed Description

[Simulation](#) Connection Statistics

6.263.2 Member Data Documentation

6.263.2.1 InMessagesBandwidth

OverTimeStatBuffer [InMessagesBandwidth](#)

6.263.2.2 InMessagesPerPacket

OverTimeStatBuffer [InMessagesPerPacket](#)

6.263.2.3 InObjectBandwidth

OverTimeStatBuffer [InObjectBandwidth](#)

6.263.2.4 InObjectDestroysPerPacket

OverTimeStatBuffer InObjectDestroysPerPacket

6.263.2.5 InObjectUpdatesPerPacket

OverTimeStatBuffer InObjectUpdatesPerPacket

6.263.2.6 InPacketsBandwidth

OverTimeStatBuffer InPacketsBandwidth

6.263.2.7 InPacketsRecv

OverTimeStatBuffer InPacketsRecv

6.263.2.8 InputsBandwidth

OverTimeStatBuffer InputsBandwidth

6.263.2.9 InputsMissing

OverTimeStatBuffer InputsMissing

6.263.2.10 InputsPerPacket

OverTimeStatBuffer InputsPerPacket

6.263.2.11 InReliableDataBandwidth

OverTimeStatBuffer InReliableDataBandwidth

6.263.2.12 OutMessagesBandwidth

OverTimeStatBuffer OutMessagesBandwidth

6.263.2.13 OutMessagesPerPacket

OverTimeStatBuffer OutMessagesPerPacket

6.263.2.14 OutObjectBandwidth

OverTimeStatBuffer OutObjectBandwidth

6.263.2.15 OutObjectDestroysPerPacket

OverTimeStatBuffer OutObjectDestroysPerPacket

6.263.2.16 OutObjectUpdatesPerPacket

OverTimeStatBuffer OutObjectUpdatesPerPacket

6.263.2.17 OutPacketsBandwidth

OverTimeStatBuffer OutPacketsBandwidth

6.263.2.18 OutPacketsDelivered

OverTimeStatBuffer OutPacketsDelivered

6.263.2.19 OutPacketsLost

OverTimeStatBuffer OutPacketsLost

6.263.2.20 OutPacketsSent

OverTimeStatBuffer OutPacketsSent

6.263.2.21 OutReliableDataBandwidth

OverTimeStatBuffer OutReliableDataBandwidth

6.263.2.22 RoundTripTime

OverTimeStatBuffer RoundTripTime

6.264 SimulationInput Class Reference

[Simulation](#) Input

Classes

- class [Buffer](#)
Buffer for [SimulationInputs](#).

Public Member Functions

- void [Clear](#) (int wordCount)
Clear a total of wordCount words from this input.
- void [CopyFrom](#) ([SimulationInput](#) source, int wordCount)
Copy wordCount words from source to this input.

Properties

- int * [Data](#) [get]
Data for this input.
- [SimulationInputHeader](#) * [Header](#) [get]
Header for this input.
- [PlayerRef](#) [Player](#) [get, set]
Player that owns this input.
- int [Sent](#) [get, set]
[Simulation](#) input sent count.

6.264.1 Detailed Description

Simulation Input

6.264.2 Member Function Documentation

6.264.2.1 Clear()

```
void Clear (
    int wordCount )
```

Clear a total of *wordCount* words from this input.

Parameters

<i>wordCount</i>	Word count to clear.
------------------	----------------------

6.264.2.2 CopyFrom()

```
void CopyFrom (
    SimulationInput source,
    int wordCount )
```

Copy *wordCount* words from *source* to this input.

Parameters

<i>source</i>	Input to copy from.
<i>wordCount</i>	Word count to copy.

6.264.3 Property Documentation

6.264.3.1 Data

```
int* Data [get]
```

Data for this input.

6.264.3.2 Header

`SimulationInputHeader* Header [get]`

Header for this input.

6.264.3.3 Player

`PlayerRef Player [get], [set]`

Player that owns this input.

6.264.3.4 Sent

`int Sent [get], [set]`

[Simulation](#) input sent count.

6.265 SimulationInput.Buffer Class Reference

[Buffer](#) for [SimulationInputs](#).

Public Member Functions

- bool [Add](#) ([SimulationInput](#) input, double? insertTime=null)
Adds an input to the buffer.
- [Buffer](#) ([NetworkProjectConfig](#) cfg)
Creates a new [Buffer](#).
- void [Clear](#) ()
Clears the buffer.
- bool [Contains](#) ([Tick](#) tick)
Whether the buffer contains an input for tick .
- int [CopySortedTo](#) ([SimulationInput](#)[] array)
Copies the buffer to an array and sorts it.
- [SimulationInput](#) [Get](#) ([Tick](#) tick)
Gets the input for tick .
- double? [GetInsertTime](#) ([Tick](#) tick)
Gets the insert time for tick .
- bool [Remove](#) ([Tick](#) tick, out [SimulationInput](#) removed)
Removes an input for tick from the buffer.

Properties

- int [Count](#) [get]
Number of inputs in the buffer.
- bool [Full](#) [get]
Whether the buffer is full.

6.265.1 Detailed Description

[Buffer](#) for [SimulationInputs](#).

6.265.2 Constructor & Destructor Documentation

6.265.2.1 Buffer()

```
Buffer (
    NetworkProjectConfig cfg )
```

Creates a new [Buffer](#).

Parameters

<i>cfg</i>	Network project configuration.
------------	--------------------------------

6.265.3 Member Function Documentation

6.265.3.1 Add()

```
bool Add (
    SimulationInput input,
    double? insertTime = null )
```

Adds an input to the buffer.

Parameters

<i>input</i>	Input to add.
<i>insertTime</i>	Insert time for <i>input</i> .

Returns

Whether the input was added.

6.265.3.2 Clear()

```
void Clear ( )
```

Clears the buffer.

6.265.3.3 Contains()

```
bool Contains (
    Tick tick )
```

Whether the buffer contains an input for *tick* .

Parameters

<i>tick</i>	Tick to check.
-------------	----------------

Returns

Whether the buffer contains an input for *tick* .

6.265.3.4 CopySortedTo()

```
int CopySortedTo (
    SimulationInput[] array )
```

Copies the buffer to an array and sorts it.

Parameters

<i>array</i>	Array to copy to.
--------------	-------------------

Returns

Number of elements copied.

6.265.3.5 Get()

```
SimulationInput Get (
    Tick tick )
```

Gets the input for *tick* .

Parameters

<i>tick</i>	Tick to get input for.
-------------	------------------------

Returns

Input for *tick* .

6.265.3.6 GetInsertTime()

```
double? GetInsertTime (
    Tick tick )
```

Gets the insert time for *tick* .

Parameters

<i>tick</i>	Tick to get insert time for.
-------------	------------------------------

Returns

Insert time for *tick* .

6.265.3.7 Remove()

```
bool Remove (
    Tick tick,
    out SimulationInput removed )
```

Removes an input for *tick* from the buffer.

Parameters

<i>tick</i>	Tick to remove.
<i>removed</i>	Removed input.

Returns

Whether an input was removed.

6.265.4 Property Documentation

6.265.4.1 Count

```
int Count [get]
```

Number of inputs in the buffer.

6.265.4.2 Full

```
bool Full [get]
```

Whether the buffer is full.

6.266 SimulationInputHeader Struct Reference

[Simulation](#) Input Header

Public Attributes

- float [InterpAlpha](#)
Interpolation alpha of the input.
- Tick [InterpFrom](#)
Interpolation from tick of the input.
- Tick [InterpTo](#)
Interpolation to tick of the input.
- Tick [Tick](#)
Tick of the input.

Static Public Attributes

- const int [SIZE](#) = [WORD_COUNT](#) * [Allocator.REPLICATE_WORD_SIZE](#)
Size of the header.
- const int [WORD_COUNT](#) = 4
Word count of the header.

6.266.1 Detailed Description

[Simulation](#) Input Header

6.266.2 Member Data Documentation

6.266.2.1 InterpAlpha

`float InterpAlpha`

Interpolation alpha of the input.

6.266.2.2 InterpFrom

`Tick InterpFrom`

Interpolation from tick of the input.

6.266.2.3 InterpTo

`Tick InterpTo`

Interpolation to tick of the input.

6.266.2.4 SIZE

```
const int SIZE = WORD_COUNT * Allocator.REPLICATE_WORD_SIZE [static]
```

Size of the header.

6.266.2.5 Tick

`Tick Tick`

[Tick](#) of the input.

6.266.2.6 WORD_COUNT

```
const int WORD_COUNT = 4 [static]
```

Word count of the header.

6.267 SimulationMessage Struct Reference

[Simulation](#) Message

Inherits [ILogDumpable](#).

Public Member Functions

- void [ILogDumpable](#). **Dump** (StringBuilder builder)
- bool [GetFlag](#) (int flag)
Get if a flag is set on this [SimulationMessage](#)
- bool [IsTargeted](#) ()
Signal if this [SimulationMessage](#) is Targeted
- void [ReferenceCountAdd](#) ()
Add a reference to this [SimulationMessage](#)
- bool [ReferenceCountSub](#) ()
Subtract a reference from this [SimulationMessage](#)
- void [SetDummy](#) ()
Set this [SimulationMessage](#) as Dummy
- void [SetNotTickAligned](#) ()
Set this [SimulationMessage](#) as Not [Tick](#) Aligned
- void [SetStatic](#) ()
Set this [SimulationMessage](#) as Static
- void [SetTarget](#) ([PlayerRef](#) target)
Set the player target of this [SimulationMessage](#)
- void [SetUnreliable](#) ()
Set this [SimulationMessage](#) as Unreliable
- override string [ToString](#) ()
[Simulation](#) Message ToString
- string [ToString](#) (bool useBrackets)
[Simulation](#) Message ToString

Static Public Member Functions

- static [SimulationMessage](#) * [Allocate](#) ([Simulation](#) sim, int capacityInBytes)
Allocate a new [SimulationMessage](#)
- static [SimulationMessage](#) * [Clone](#) ([Simulation](#) sim, [SimulationMessage](#) *message)
Create a copy of a [SimulationMessage](#)
- static byte * [GetData](#) ([SimulationMessage](#) *message)
Get the byte pointer content of a [SimulationMessage](#)
- static int [ReadInt](#) ([SimulationMessage](#) *message)
Read a int from a [SimulationMessage](#)
- static [NetworkId](#) [ReadNetworkedObjectRef](#) ([SimulationMessage](#) *message)
Read a [NetworkId](#) from a [SimulationMessage](#)
- static [Vector3](#) [ReadVector3](#) ([SimulationMessage](#) *message)
Read a [Vector3](#) from a [SimulationMessage](#)
- static void [WriteInt](#) ([SimulationMessage](#) *message, int value)
Write a int to a [SimulationMessage](#)
- static void [WriteNetworkedObjectRef](#) ([SimulationMessage](#) *message, [NetworkId](#) value)
Write a [NetworkId](#) to a [SimulationMessage](#)
- static void [WriteVector3](#) ([SimulationMessage](#) *message, [Vector3](#) value)
Write a [Vector3](#) to a [SimulationMessage](#)

Public Attributes

- int [Capacity](#)
Capacity in Bits of this [SimulationMessage](#)
- int [Flags](#)
Flags
- int [Offset](#)
Current offset in Bits
- int [References](#)
Reference Count
- [PlayerRef](#) [Source](#)
Source Player of this [SimulationMessage](#)
- [PlayerRef](#) [Target](#)
Target Player of this [SimulationMessage](#)
- int [Tick](#)
Tick of this [SimulationMessage](#)

Static Public Attributes

- const int [FLAG_DUMMY](#) = 1 << 8
Flag for dummy messages.
- const int [FLAG_INTERNAL](#) = 1 << 6
Flag for internal messages.
- const int [FLAG_NOT_TICK_ALIGNED](#) = 1 << 7
Flag for messages that are not tick aligned.
- const int [FLAG_REMOTE](#) = 1 << 1
Flag for remote messages.
- const int [FLAG_STATIC](#) = 1 << 2

- Flag for static messages.*
- const int [FLAG_TARGET_PLAYER](#) = 1 << 4
- Flag for targeted messages to a player.*
- const int [FLAG_TARGET_SERVER](#) = 1 << 5
- Flag for targeted messages to the server.*
- const int [FLAG_UNRELIABLE](#) = 1 << 3
- Flag for unreliable messages.*
- const int [FLAG_USER_FLAGS_START](#) = 1 << 16
- Flag for user flags.*
- const int [FLAG_USER_MESSAGE](#) = 1 << 0
- Flag for user messages.*
- const int [FLAGS_RESERVED](#) = 0xFFFF
- Flag for reserved flags.*
- const int [FLAGS_RESERVED_BITS](#) = 16
- Flag for reserved bits.*
- const int [SIZE](#) = 28
- [SimulationMessage](#) size in bytes.*

Properties

- bool [IsUnreliable](#) [get]
Signal if this [SimulationMessage](#) is Unreliable

6.267.1 Detailed Description

[Simulation](#) Message

6.267.2 Member Function Documentation

6.267.2.1 Allocate()

```
static SimulationMessage* Allocate (
    Simulation sim,
    int capacityInBytes ) [static]
```

Allocate a new [SimulationMessage](#)

Parameters

<i>sim</i>	Simulation to get the Memory from
<i>capacityInBytes</i>	Size in bytes of the new SimulationMessage

Returns

Pointer to the new [SimulationMessage](#)

6.267.2.2 Clone()

```
static SimulationMessage* Clone (
    Simulation sim,
    SimulationMessage * message ) [static]
```

Create a copy of a [SimulationMessage](#)

Parameters

<i>sim</i>	Simulation to allocate from
<i>message</i>	SimulationMessage to copy

Returns

Copy of the [SimulationMessage](#)

6.267.2.3 GetData()

```
static byte* GetData (
    SimulationMessage * message ) [static]
```

Get the byte pointer content of a [SimulationMessage](#)

Parameters

<i>message</i>	SimulationMessage to get the byte pointer of
----------------	--

Returns

Byte pointer of the [SimulationMessage](#)

6.267.2.4 GetFlag()

```
bool GetFlag (
    int flag )
```

Get if a flag is set on this [SimulationMessage](#)

Parameters

<i>flag</i>	Flag to check
-------------	---------------

Returns

True if the flag is set

6.267.2.5 IsTargeted()

```
bool IsTargeted ( )
```

Signal if this [SimulationMessage](#) is Targeted

Returns

True if this [SimulationMessage](#) is Targeted

6.267.2.6 ReadInt()

```
static int ReadInt (
    SimulationMessage * message ) [static]
```

Read a int from a [SimulationMessage](#)

Parameters

<i>message</i>	SimulationMessage to read from
----------------	--

Returns

int read

6.267.2.7 ReadNetworkedObjectRef()

```
static NetworkId ReadNetworkedObjectRef (
    SimulationMessage * message ) [static]
```

Read a [NetworkId](#) from a [SimulationMessage](#)

Parameters

<i>message</i>	SimulationMessage to read from
----------------	--

Returns

[NetworkId](#) read

6.267.2.8 ReadVector3()

```
static Vector3 ReadVector3 (
    SimulationMessage * message ) [static]
```

Read a Vector3 from a [SimulationMessage](#)

Parameters

<i>message</i>	SimulationMessage to read from
----------------	--

Returns

Vector3 read

6.267.2.9 ReferenceCountAdd()

```
void ReferenceCountAdd ( )
```

Add a reference to this [SimulationMessage](#)

6.267.2.10 ReferenceCountSub()

```
bool ReferenceCountSub ( )
```

Subtract a reference from this [SimulationMessage](#)

Returns

True if the reference count is now 0

6.267.2.11 SetDummy()

```
void SetDummy ( )
```

Set this [SimulationMessage](#) as Dummy

6.267.2.12 SetNotTickAligned()

```
void SetNotTickAligned ( )
```

Set this [SimulationMessage](#) as Not [Tick](#) Aligned

6.267.2.13 SetStatic()

```
void SetStatic ( )
```

Set this [SimulationMessage](#) as Static

6.267.2.14 SetTarget()

```
void SetTarget (
    PlayerRef target )
```

Set the player target of this [SimulationMessage](#)

Parameters

<i>target</i>	Target Player
---------------	---------------

6.267.2.15 SetUnreliable()

```
void SetUnreliable ( )
```

Set this [SimulationMessage](#) as Unreliable

6.267.2.16 ToString() [1/2]

```
override string ToString ( )
```

[Simulation](#) Message ToString

6.267.2.17 ToString() [2/2]

```
string ToString (
    bool useBrackets )
```

[Simulation](#) Message ToString

6.267.2.18 WriteInt()

```
static void WriteInt (
    SimulationMessage * message,
    int value ) [static]
```

Write a int to a [SimulationMessage](#)

Parameters

<i>message</i>	SimulationMessage to write to
<i>value</i>	int to write

6.267.2.19 WriteNetworkedObjectRef()

```
static void WriteNetworkedObjectRef (
    SimulationMessage * message,
    NetworkId value ) [static]
```

Write a [NetworkId](#) to a [SimulationMessage](#)

Parameters

<i>message</i>	SimulationMessage to write to
<i>value</i>	NetworkId to write

6.267.2.20 WriteVector3()

```
static void WriteVector3 (
    SimulationMessage * message,
    Vector3 value ) [static]
```

Write a Vector3 to a [SimulationMessage](#)

Parameters

<i>message</i>	SimulationMessage to write to
<i>value</i>	Vector3 to write

6.267.3 Member Data Documentation

6.267.3.1 Capacity

```
int Capacity
```

Capacity in Bits of this [SimulationMessage](#)

6.267.3.2 FLAG_DUMMY

```
const int FLAG_DUMMY = 1 << 8 [static]
```

Flag for dummy messages.

6.267.3.3 FLAG_INTERNAL

```
const int FLAG_INTERNAL = 1 << 6 [static]
```

Flag for internal messages.

6.267.3.4 FLAG_NOT_TICK_ALIGNED

```
const int FLAG_NOT_TICK_ALIGNED = 1 << 7 [static]
```

Flag for messages that are not tick aligned.

6.267.3.5 FLAG_REMOTE

```
const int FLAG_REMOTE = 1 << 1 [static]
```

Flag for remote messages.

6.267.3.6 FLAG_STATIC

```
const int FLAG_STATIC = 1 << 2 [static]
```

Flag for static messages.

6.267.3.7 FLAG_TARGET_PLAYER

```
const int FLAG_TARGET_PLAYER = 1 << 4 [static]
```

Flag for targeted messages to a player.

6.267.3.8 FLAG_TARGET_SERVER

```
const int FLAG_TARGET_SERVER = 1 << 5 [static]
```

Flag for targeted messages to the server.

6.267.3.9 FLAG_UNRELIABLE

```
const int FLAG_UNRELIABLE = 1 << 3 [static]
```

Flag for unreliable messages.

6.267.3.10 FLAG_USER_FLAGS_START

```
const int FLAG_USER_FLAGS_START = 1 << 16 [static]
```

Flag for user flags.

6.267.3.11 FLAG_USER_MESSAGE

```
const int FLAG_USER_MESSAGE = 1 << 0 [static]
```

Flag for user messages.

6.267.3.12 Flags

```
int Flags
```

Flags

6.267.3.13 FLAGS_RESERVED

```
const int FLAGS_RESERVED = 0xFFFF [static]
```

Flag for reserved flags.

6.267.3.14 FLAGS_RESERVED_BITS

```
const int FLAGS_RESERVED_BITS = 16 [static]
```

Flag for reserved bits.

6.267.3.15 Offset

```
int Offset
```

Current offset in Bits

6.267.3.16 References

```
int References
```

Reference Count

6.267.3.17 SIZE

```
const int SIZE = 28 [static]
```

[SimulationMessage](#) size in bytes.

6.267.3.18 Source

[PlayerRef](#) Source

Source Player of this [SimulationMessage](#)

6.267.3.19 Target

[PlayerRef](#) Target

Target Player of this [SimulationMessage](#)

6.267.3.20 Tick

```
int Tick
```

[Tick](#) of this [SimulationMessage](#)

6.267.4 Property Documentation

6.267.4.1 IsUnreliable

```
bool IsUnreliable [get]
```

Signal if this [SimulationMessage](#) is Unreliable

6.268 SimulationMessagePtr Struct Reference

[Simulation](#) Message Pointer

Public Attributes

- [SimulationMessage](#) * [Message](#)

Pointer to the message.

6.268.1 Detailed Description

[Simulation](#) Message Pointer

6.268.2 Member Data Documentation

6.268.2.1 Message

[SimulationMessage](#)* [Message](#)

Pointer to the message.

6.269 SimulationRuntimeConfig Struct Reference

Stores the runtime configuration of the simulation

Public Attributes

- [PlayerRef](#) [HostPlayer](#)
Current master client (in shared mode)
- [PlayerRef](#) [MasterClient](#)
Current master client (in shared mode)
- int [PlayerMaxCount](#)
Current player count
- [SimulationModes](#) [ServerMode](#)
Current [Simulation](#) Mode
- [TickRate.Resolved](#) [TickRate](#)
Current tick rates and send rates for server and client
- [Topologies](#) [Topology](#)
Current master client (in shared mode)

6.269.1 Detailed Description

Stores the runtime configuration of the simulation

6.269.2 Member Data Documentation

6.269.2.1 HostPlayer

`PlayerRef` HostPlayer

Current master client (in shared mode)

6.269.2.2 MasterClient

`PlayerRef` MasterClient

Current master client (in shared mode)

6.269.2.3 PlayerMaxCount

`int` PlayerMaxCount

Current player count

6.269.2.4 ServerMode

`SimulationModes` ServerMode

Current `Simulation` Mode

6.269.2.5 TickRate

`TickRate.Resolved` TickRate

Current tick rates and send rates for server and client

6.269.2.6 Topology

`Topologies` Topology

Current master client (in shared mode)

6.270 SimulationStats Class Reference

Simulation Stats

Public Attributes

- OverTimeStatBuffer [EngineDelta](#)
Engine Delta
- OverTimeStatBuffer [ForwardSteps](#)
The number of forward simulation steps
- OverTimeStatBuffer [InBandwidth](#)
Input Bandwidth
- OverTimeStatBuffer [InPackets](#)
Input Packets
- OverTimeStatBuffer [InputReceiveDelta](#)
Input Receive Delta
- OverTimeStatBuffer [InputReceiveDeltaDeviation](#)
Input Receive Delta Deviation
- OverTimeStatBuffer [InterpolationOffset](#)
Interpolation Offset
- OverTimeStatBuffer [InterpolationOffsetDeviation](#)
Interpolation Offset Deviation
- OverTimeStatBuffer [InterpolationOffsetTarget](#)
Interpolation Offset Target
- OverTimeStatBuffer [InterpolationSpeed](#)
Interpolation Speed
- OverTimeStatBuffer [ObjectsCount](#)
Objects Count
- OverTimeStatBuffer [ObjectsGlobalCount](#)
Object Global Count
- OverTimeStatBuffer [ObjectsPredictedCount](#)
Object Predicted Count
- OverTimeStatBuffer [OutBandwidth](#)
Output Bandwidth
- OverTimeStatBuffer [OutPackets](#)
Output Packets
- OverTimeStatBuffer [PlayersCount](#)
Player Count
- OverTimeStatBuffer [Resimulations](#)
The number of re-simulations per [Fusion](#) simulation loop cycle.
- OverTimeStatBuffer [RoundTripTime](#)
Round Trip Time
- OverTimeStatBuffer [SimulationSpeed](#)
[Simulation](#) Speed
- OverTimeStatBuffer [SimulationTimeOffset](#)
[Simulation](#) Time Offset
- OverTimeStatBuffer [SimulationTimeOffsetDeviation](#)
[Simulation](#) Time Offset Deviation
- OverTimeStatBuffer [SimulationTimeOffsetTarget](#)

- Simulation Time Offset Target*
- OverTimeStatBuffer [SpawnQueueSize](#)
Engine Spawn Queue Size
- OverTimeStatBuffer [StateReceiveDelta](#)
State Receive Delta
- OverTimeStatBuffer [StateReceiveDeltaDeviation](#)
State Receive Delta Deviation
- OverTimeStatBuffer [TimeResets](#)
Time Resets

6.270.1 Detailed Description

[Simulation](#) Stats

6.270.2 Member Data Documentation

6.270.2.1 EngineDelta

OverTimeStatBuffer EngineDelta

Engine Delta

6.270.2.2 ForwardSteps

OverTimeStatBuffer ForwardSteps

The number of forward simulation steps

6.270.2.3 InBandwidth

OverTimeStatBuffer InBandwidth

Input Bandwidth

6.270.2.4 InPackets

OverTimeStatBuffer InPackets

Input Packets

6.270.2.5 InputReceiveDelta

OverTimeStatBuffer InputReceiveDelta

Input Receive Delta

6.270.2.6 InputReceiveDeltaDeviation

OverTimeStatBuffer InputReceiveDeltaDeviation

Input Receive Delta Deviation

6.270.2.7 InterpolationOffset

OverTimeStatBuffer InterpolationOffset

Interpolation Offset

6.270.2.8 InterpolationOffsetDeviation

OverTimeStatBuffer InterpolationOffsetDeviation

Interpolation Offset Deviation

6.270.2.9 InterpolationOffsetTarget

OverTimeStatBuffer InterpolationOffsetTarget

Interpolation Offset Target

6.270.2.10 InterpolationSpeed

OverTimeStatBuffer InterpolationSpeed

Interpolation Speed

6.270.2.11 ObjectsCount

OverTimeStatBuffer ObjectsCount

Objects Count

6.270.2.12 ObjectsGlobalCount

OverTimeStatBuffer ObjectsGlobalCount

Object Global Count

6.270.2.13 ObjectsPredictedCount

OverTimeStatBuffer ObjectsPredictedCount

Object Predicted Count

6.270.2.14 OutBandwidth

OverTimeStatBuffer OutBandwidth

Output Bandwidth

6.270.2.15 OutPackets

OverTimeStatBuffer OutPackets

Output Packets

6.270.2.16 PlayersCount

OverTimeStatBuffer PlayersCount

Player Count

6.270.2.17 Resimulations

OverTimeStatBuffer Resimulations

The number of re-simulations per [Fusion](#) simulation loop cycle.

6.270.2.18 RoundTripTime

OverTimeStatBuffer RoundTripTime

Round Trip Time

6.270.2.19 SimulationSpeed

OverTimeStatBuffer SimulationSpeed

[Simulation](#) Speed

6.270.2.20 SimulationTimeOffset

OverTimeStatBuffer SimulationTimeOffset

[Simulation](#) Time Offset

6.270.2.21 SimulationTimeOffsetDeviation

OverTimeStatBuffer SimulationTimeOffsetDeviation

[Simulation](#) Time Offset Deviation

6.270.2.22 SimulationTimeOffsetTarget

OverTimeStatBuffer SimulationTimeOffsetTarget

[Simulation](#) Time Offset Target

6.270.2.23 SpawnQueueSize

OverTimeStatBuffer SpawnQueueSize

Engine Spawn Queue Size

6.270.2.24 StateReceiveDelta

OverTimeStatBuffer StateReceiveDelta

State Receive Delta

6.270.2.25 StateReceiveDeltaDeviation

OverTimeStatBuffer StateReceiveDeltaDeviation

State Receive Delta Deviation

6.270.2.26 TimeResets

OverTimeStatBuffer TimeResets

Time Resets

6.271 NetAddress Struct Reference

Represents a Network Address, which includes a IP and Port This can contains either a IPv4 or a IPv6 address

Inherits `IEquatable< NetAddress >`.

Public Member Functions

- bool **Equals** ([NetAddress](#) other)
- override bool **Equals** (object obj)
- override int **GetHashCode** ()
- override string **ToString** ()

Static Public Member Functions

- static [NetAddress Any](#) (ushort port=0)
Create a new [NetAddress](#) using the "Any" IPv4 Address representation (0.0.0.0) with the Port passed as argument
- static [NetAddress AnyIPv6](#) (ushort port=0)
Create a new [NetAddress](#) using the "Any" IPv6 Address representation (::) with the Port passed as argument
- static [NetAddress CreateFromIpPort](#) (string ip, ushort port)
Create a new [NetAddress](#) based on the IP and Port passed as argument
- static [NetAddress FromActorId](#) (int actorId)
Build a new [NetAddress](#) based on an ActorId
- static [NetAddress LocalhostIPv4](#) (ushort port=0)
Create a new [NetAddress](#) on the LocalHost address with the desired Port
- static [NetAddress LocalhostIPv6](#) (ushort port=0)
Create a new [NetAddress](#) on the LocalHost IPv6 Address with the desired Port

Public Attributes

- int [_actorId](#)

Properties

- int [ActorId](#) [get]
Retrieves the Remote Actor ID which this [NetAddress](#) Represents
- bool [IsIPv6](#) [get]
Signal if the [NetAddress](#) represents an IPv6 Address
- bool [IsRelayAddr](#) [get]
Signal if the [NetAddress](#) is a Relayed connection
- bool [IsValid](#) [get]
Signal if this [NetAddress](#) is not default/empty

6.271.1 Detailed Description

Represents a Network Address, which includes a IP and Port This can contains either a IPv4 or a IPv6 address

6.271.2 Member Function Documentation

6.271.2.1 Any()

```
static NetAddress Any (
    ushort port = 0 ) [static]
```

Create a new [NetAddress](#) using the "Any" IPv4 Address representation (0.0.0.0) with the Port passed as argument

Parameters

<i>port</i>	Port used to build the NetAddress
-------------	---

Returns

New [NetAddress](#) reference

6.271.2.2 AnyIPv6()

```
static NetAddress AnyIPv6 (  
    ushort port = 0 ) [static]
```

Create a new [NetAddress](#) using the "Any" IPv6 Address representation (::) with the Port passed as argument

Parameters

<i>port</i>	Port used to build the NetAddress
-------------	---

Returns

New [NetAddress](#) reference

6.271.2.3 CreateFromIpPort()

```
static NetAddress CreateFromIpPort (  
    string ip,  
    ushort port ) [static]
```

Create a new [NetAddress](#) based on the IP and Port passed as argument

Parameters

<i>ip</i>	String representation of an IP, either IPv4 or IPv6
<i>port</i>	Port used to build the NetAddress

Returns

New [NetAddress](#) reference

Exceptions

<i>ArgumentException</i>	If IP is empty/null or an invalid IP, or port < 0
<i>AssertException</i>	If unable to parse IP

6.271.2.4 FromActorId()

```
static NetAddress FromActorId (  
    int actorId ) [static]
```

Build a new [NetAddress](#) based on an ActorId

Parameters

<i>actorId</i>	ActorId used to build the NetAddress
----------------	--

Returns

Relay [NetAddress](#) that references the ActorId

ActorId must be 0 or greater

6.271.2.5 LocalhostIPv4()

```
static NetAddress LocalhostIPv4 (  
    ushort port = 0 ) [static]
```

Create a new [NetAddress](#) on the LocalHost address with the desired Port

Parameters

<i>port</i>	Port used to build the NetAddress
-------------	---

Returns

New [NetAddress](#) reference

6.271.2.6 LocalhostIPv6()

```
static NetAddress LocalhostIPv6 (  
    ushort port = 0 ) [static]
```

Create a new [NetAddress](#) on the LocalHost IPv6 Address with the desired Port

Parameters

<i>port</i>	Port used to build the NetAddress
-------------	---

Returns

New [NetAddress](#) reference

6.271.3 Property Documentation

6.271.3.1 ActorId

```
int ActorId [get]
```

Retrieves the Remote Actor ID which this [NetAddress](#) Represents

6.271.3.2 IsIPv6

```
bool IsIPv6 [get]
```

Signal if the [NetAddress](#) represents an IPv6 Address

6.271.3.3 IsRelayAddr

```
bool IsRelayAddr [get]
```

Signal if the [NetAddress](#) is a Relayed connection

6.271.3.4 IsValid

```
bool IsValid [get]
```

Signal if this [NetAddress](#) is not default/empty

6.272 NetBitBufferList Struct Reference

Represents a linked list of Fusion.Sockets.NetBitBuffer

Public Member Functions

- void [AddFirst](#) (NetBitBuffer *item)
Add a Fusion.Sockets.NetBitBuffer at the beginning of the List
- void [AddLast](#) (NetBitBuffer *item)
Add a Fusion.Sockets.NetBitBuffer at the end of the list.
- bool [IsInList](#) (NetBitBuffer *item)
Check if a specific Fusion.Sockets.NetBitBuffer is in the list
- void [Remove](#) (NetBitBuffer *item)
Remove a specific Fusion.Sockets.NetBitBuffer from the list
- NetBitBuffer * [RemoveHead](#) ()
Removes the first element of the list

Public Attributes

- int **Count**
- NetBitBuffer * **Head**
- NetBitBuffer * **Tail**

6.272.1 Detailed Description

Represents a linked list of Fusion.Sockets.NetBitBuffer

6.272.2 Member Function Documentation

6.272.2.1 AddFirst()

```
void AddFirst (
    NetBitBuffer * item )
```

Add a Fusion.Sockets.NetBitBuffer at the beginning of the List

Parameters

<i>item</i>	NetBitBuffer to add to the list
-------------	---------------------------------

6.272.2.2 AddLast()

```
void AddLast (
    NetBitBuffer * item )
```

Add a Fusion.Sockets.NetBitBuffer at the end of the list.

Parameters

<i>item</i>	NetBitBuffer to add to the list
-------------	---------------------------------

6.272.2.3 IsInList()

```
bool IsInList (
    NetBitBuffer * item )
```

Check if a specific Fusion.Sockets.NetBitBuffer is in the list

Parameters

<i>item</i>	NetBitBuffer to check
-------------	-----------------------

Returns

True if the list contains the item, false otherwise

6.272.2.4 Remove()

```
void Remove (
    NetBitBuffer * item )
```

Remove a specific Fusion.Sockets.NetBitBuffer from the list

Parameters

<i>item</i>	NetBitBuffer to remove
-------------	------------------------

6.272.2.5 RemoveHead()

```
NetBitBuffer* RemoveHead ( )
```

Removes the first element of the list

Returns

NetBitBuffer reference

6.273 NetCommandAccepted Struct Reference

Accepted Command, sent by the server when a remote client connection is accepted

Static Public Member Functions

- static [NetCommandAccepted](#) **Create** (NetConnectionId localId, NetConnectionId remoteId, uint counter)

Public Attributes

- NetConnectionId **AcceptedLocalId**
- NetConnectionId **AcceptedRemoteId**
- uint **Counter**
- [NetCommandHeader](#) **Header**

6.273.1 Detailed Description

Accepted Command, sent by the server when a remote client connection is accepted

6.274 NetCommandConnect Struct Reference

Connect Command used to signal a remote server that a client is trying to connect to it

Static Public Member Functions

- static int **ClampTokenLength** (int tokenLength)
- static [NetCommandConnect](#) **Create** (NetConnectionId id, byte *token=null, int tokenLength=0, byte *uniqueId=null)
- static byte[] **GetTokenDataAsArray** ([NetCommandConnect](#) command)
- static byte[] **GetUniqueIdAsArray** ([NetCommandConnect](#) command)

Public Attributes

- NetConnectionId **ConnectionId**
- [NetCommandHeader](#) **Header**
- fixed byte **TokenData** [TOKEN_MAX_LENGTH_BYTES]
- int **TokenLength**
- fixed byte **UniqueId** [UNIQUE_ID_LENGTH_BYTES]

Static Public Attributes

- const int **SIZE_BITS** = SIZE_BYTES * 8
- const int **SIZE_BYTES** = 16 + TOKEN_MAX_LENGTH_BYTES + UNIQUE_ID_LENGTH_BYTES
- const int **TOKEN_MAX_LENGTH_BYTES** = 128
- const int **UNIQUE_ID_LENGTH_BYTES** = NetConnection.UNIQUE_ID_SIZE

6.274.1 Detailed Description

Connect Command used to signal a remote server that a client is trying to connect to it

6.275 NetCommandDisconnect Struct Reference

Disconnect Command, it can be used by either side of the connection

Static Public Member Functions

- static [NetCommandDisconnect](#) **Create** ([NetDisconnectReason](#) reason, byte *token, int tokenLength)
- static [NetCommandDisconnect](#) **Create** ([NetDisconnectReason](#) reason, byte[] token)

Public Attributes

- [NetCommandHeader](#) **Header**
- [NetDisconnectReason](#) **Reason**
- fixed byte **TokenData** [TOKEN_MAX_LENGTH_BYTES]
- int **TokenLength**

Static Public Attributes

- const int **TOKEN_MAX_LENGTH_BYTES** = 128

6.275.1 Detailed Description

Disconnect Command, it can be used by either side of the connection

6.276 NetCommandHeader Struct Reference

Network Command Header Describe its type and usual settings for all commands

Static Public Member Functions

- static [NetCommandHeader](#) **Create** ([NetCommands](#) command)
Create a new [NetCommandHeader](#) based on a [NetCommands](#) type
- static implicit **operator NetCommandHeader** ([NetCommands](#) commands)

Public Attributes

- [NetCommands](#) **Command**
- [NetPacketType](#) **PacketType**

Static Public Attributes

- const int **SIZE_BITS** = SIZE_BYTES * 8
- const int **SIZE_BYTES** = 2

6.276.1 Detailed Description

Network Command Header Describe its type and usual settings for all commands

6.276.2 Member Function Documentation

6.276.2.1 Create()

```
static NetCommandHeader Create (
    NetCommands command ) [static]
```

Create a new [NetCommandHeader](#) based on a [NetCommands](#) type

Parameters

<i>command</i>	Type of Command that should be created
----------------	--

Returns

New [NetCommandHeader](#) reference based on the Command Type

6.277 NetCommandRefused Struct Reference

Refuse Command, sent by the server when the connection was refused. This happens when the server has reached its max connection capacity.

Static Public Member Functions

- static [NetCommandRefused](#) **Create** ([NetConnectFailedReason](#) reason)

Public Attributes

- [NetCommandHeader](#) **Header**
- [NetConnectFailedReason](#) **Reason**

Static Public Attributes

- const int **SIZE_IN_BITS** = SIZE_IN_BYTES * 8
- const int **SIZE_IN_BYTES** = 3

6.277.1 Detailed Description

Refuse Command, sent by the server when the connection was refused. This happens when the server has reached its max connection capacity.

6.278 NetConfig Struct Reference

General configuration used to drive the behavior of the Socket library

Public Attributes

- [NetAddress Address](#)
Network Address used to bind the internal Socket
- int [ConnectAttempts](#)
Number of Connection Attempts tried by the peer before cancel the connection
- double [ConnectInterval](#)
Interval in Seconds between attempts to connect to a remote server
- double [ConnectionDefaultRtt](#)
Initial RTT
- int [ConnectionGroups](#)
Number of Connection Groups supported by the local instance
- double [ConnectionPingInterval](#)
Interval in Seconds between ping being sent to a remote end
- int [ConnectionSendBuffers](#)
Pre-allocated number of data buffers used to send data
- double [ConnectionShutdownTime](#)
Timeout in Seconds to allow a disconnected Connection to be released from the Group Mapping
- double [ConnectionTimeout](#)
Connection Timeout in seconds
- int [DefaultMtu](#)
default Maximum Transmission Unit
- int [MaxConnections](#)
Max Number of Connections supported by the local instance
- NetConfigNotify [Notify](#)
Package acknowledgment system configuration
- double [OperationExpireTime](#)
Max Allowed time for the Send and Receive operations, in milliseconds
- int [PacketSize](#)
UDP Packet Size in Bytes
- NetConfigSimulation [Simulation](#)
Network simulation system configuration
- int [SocketRecvBuffer](#)
Size of the internal Socket receive buffer
- int [SocketSendBuffer](#)
Size of the internal Socket send buffer

Properties

- int [ConnectionsPerGroup](#) [get]
Max number of Connection per Group based on the [ConnectionGroups](#) and [MaxConnections](#)
- static [NetConfig Defaults](#) [get]
Builds a [NetConfig](#) with the default values
- int [PacketSizeInBits](#) [get]
UDP Packet Size in Bits based on [PacketSize](#)

6.278.1 Detailed Description

General configuration used to drive the behavior of the Socket library

6.278.2 Member Data Documentation

6.278.2.1 Address

[NetAddress](#) Address

Network Address used to bind the internal Socket

6.278.2.2 ConnectAttempts

int ConnectAttempts

Number of Connection Attempts tried by the peer before cancel the connection

6.278.2.3 ConnectInterval

double ConnectInterval

Interval in Seconds between attempts to connect to a remote server

6.278.2.4 ConnectionDefaultRtt

double ConnectionDefaultRtt

Initial RTT

6.278.2.5 ConnectionGroups

```
int ConnectionGroups
```

Number of Connection Groups supported by the local instance

6.278.2.6 ConnectionPingInterval

```
double ConnectionPingInterval
```

Interval in Seconds between ping being sent to a remote end

6.278.2.7 ConnectionSendBuffers

```
int ConnectionSendBuffers
```

Pre-allocated number of data buffers used to send data

6.278.2.8 ConnectionShutdownTime

```
double ConnectionShutdownTime
```

Timeout in Seconds to allow a disconnected Connection to be released from the Group Mapping

NetPeerGroup.UpdateShutdown

6.278.2.9 ConnectionTimeout

```
double ConnectionTimeout
```

Connection Timeout in seconds

6.278.2.10 DefaultMtu

```
int DefaultMtu
```

default Maximum Transmission Unit

6.278.2.11 MaxConnections

```
int MaxConnections
```

Max Number of Connections supported by the local instance

6.278.2.12 Notify

```
NetConfigNotify Notify
```

Package acknowledgment system configuration

6.278.2.13 OperationExpireTime

```
double OperationExpireTime
```

Max Allowed time for the Send and Receive operations, in milliseconds

6.278.2.14 PacketSize

```
int PacketSize
```

UDP Packet Size in Bytes

6.278.2.15 Simulation

```
NetConfigSimulation Simulation
```

Network simulation system configuration

6.278.2.16 SocketRecvBuffer

```
int SocketRecvBuffer
```

Size of the internal Socket receive buffer

6.278.2.17 SocketSendBuffer

`int SocketSendBuffer`

Size of the internal Socket send buffer

6.278.3 Property Documentation

6.278.3.1 ConnectionsPerGroup

`int ConnectionsPerGroup` [get]

Max number of Connection per Group based on the [ConnectionGroups](#) and [MaxConnections](#)

6.278.3.2 Defaults

`NetConfig Defaults` [static], [get]

Builds a [NetConfig](#) with the default values

6.278.3.3 PacketSizeInBits

`int PacketSizeInBits` [get]

UDP Packet Size in Bits based on [PacketSize](#)

6.279 StunClient.TestIPs Class Reference

List of public DNS Servers

Static Public Attributes

- static `IPEndPoint TEST_NET_IPV4` = new `IPEndPoint(IPAddress.Parse("203.0.113.0"), 65530)`
- static `IPEndPoint TEST_NET_IPV6` = new `IPEndPoint(IPAddress.Parse("2001:db8::"), 65530)`

6.279.1 Detailed Description

List of public DNS Servers

6.280 StartGameArgs Struct Reference

[Fusion](#) Start Arguments, used to configure the simulation mode and other settings

Public Member Functions

- override string [ToString](#) ()
StartGameArgs ToString()

Public Attributes

- [NetAddress?](#) [Address](#)
Peer Binding Address
- AuthenticationValues [AuthValues](#)
Custom Authentication Data
- [NetworkProjectConfig](#) [Config](#)
Custom [NetworkProjectConfig](#) used to start the simulation
- byte[] [ConnectionToken](#)
Connection token sent by client to server. Not used in shared mode.
- Type[] [CustomCallbackInterfaces](#)
User defined callback interfaces we will provide O(1) constant time lookup for
- string [CustomLobbyName](#)
Session Custom Lobby to be published in
- FusionAppSettings [CustomPhotonAppSettings](#)
Custom Photon Application Settings
- [NetAddress?](#) [CustomPublicAddress](#)
Custom Public Reflexive Address
- string [CustomSTUNServer](#)
Specify a Custom STUN Server used to Resolve the peer Reflexive Addresses
- bool [DisableNATPunchthrough](#)
Flag to disable the NAT Punchthrough implementation and connect only via Relay
- bool? [EnableClientSessionCreation](#)
Enables the Session creation when starting a Client with an specific Session Name
- [GameMode](#) [GameMode](#)
[Fusion.GameMode](#) in which this peer will start
- Action< [NetworkRunner](#) > [HostMigrationResume](#)
Callback invoked when the new Host is migrating from the old Host state
- [HostMigrationToken](#) [HostMigrationToken](#)
Host Migration Token used when restarting the [Fusion Simulation](#)
- bool? [IsOpen](#)
Session should be created Open or Closed to accept joins
- bool? [IsVisible](#)
Session should be Visible or not in the Session Lobby list
- MatchmakingMode? [MatchmakingMode](#)
*Session Join Matchmaking Mode when joining a Session. For more information, check [Fusion.Photon.Realtime](#).↔
[MatchmakingMode](#)*
- [INetworkObjectInitializer](#) [ObjectInitializer](#)
See [INetworkRunnerUpdater](#)
- [INetworkObjectProvider](#) [ObjectProvider](#)

Object pool to use

- Action< [NetworkRunner](#) > [OnGameStarted](#)

Callback that is invoked when the [Fusion](#) has fully started

- int? [PlayerCount](#)

Number of players allowed to connect to this peer, when running in Server/Host Mode

- [NetworkSceneInfo](#)? [Scene](#)

Scene that will be set as the starting Scene when running in Server/Host Mode

- [INetworkSceneManager](#) [SceneManager](#)

See [INetworkSceneManager](#).

- string [SessionName](#)

Photon Cloud Session Name used either to Create or Join a Session.

- Dictionary< string, SessionProperty > [SessionProperties](#)

Custom Session Properties. This dictionary can be used to either setup the initial Session Properties when creating a Session but also to set the matchmaking filters when joining a Random Session.

- CancellationToken [StartGameCancellationToken](#)

Optional CancellationToken used to cancel the [NetworkRunner](#) start up process and shutdown

- [INetworkRunnerUpdater](#) [Updater](#)

See [INetworkRunnerUpdater](#)

- bool [UseCachedRegions](#)

Enables the usage of the previous cached regions pings. This speeds up the region ping process and the runner startup process.

- bool? [UseDefaultPhotonCloudPorts](#)

Signal if the internal Realtime Client should use the Default Photon ports to connect to the Photon Cloud. By default, [Fusion](#) uses ports: 27000, 27001 and 27002. Set this to True to use ports: 5058, 5055 and 5056.

6.280.1 Detailed Description

[Fusion](#) Start Arguments, used to configure the simulation mode and other settings

More about matchmaking: <https://doc.photonengine.com/en-us/fusion/current/manual/matchmaking>

6.280.2 Member Function Documentation

6.280.2.1 ToString()

```
override string ToString ( )
```

[StartGameArgs](#) ToString()

6.280.3 Member Data Documentation

6.280.3.1 Address

`NetAddress?` Address

Peer Binding Address

Default: `NetAddress.Any(ushort)`

6.280.3.2 AuthValues

`AuthenticationValues` AuthValues

Custom Authentication Data

Default: null (default authentication values)

6.280.3.3 Config

`NetworkProjectConfig` Config

Custom `NetworkProjectConfig` used to start the simulation

Default: Global `NetworkProjectConfig`

More about `NetworkProjectConfig`: <https://doc.photonengine.com/en-us/fusion/current/manual/network>

6.280.3.4 ConnectionToken

`byte []` ConnectionToken

Connection token sent by client to server. Not used in shared mode.

Default: null (empty connection token)

6.280.3.5 CustomCallbackInterfaces

`Type []` CustomCallbackInterfaces

User defined callback interfaces we will provide O(1) constant time lookup for

Default: null

6.280.3.6 CustomLobbyName

`string` CustomLobbyName

Session Custom Lobby to be published in

Default: null (default Lobby for each Session Type, `LobbyClientServer` or `LobbyShared`)

6.280.3.7 CustomPhotonAppSettings

`FusionAppSettings CustomPhotonAppSettings`

Custom Photon Application Settings

Default: null (Global PhotonAppSettings)

6.280.3.8 CustomPublicAddress

`NetAddress? CustomPublicAddress`

Custom Public Reflexive Address

Default: null

6.280.3.9 CustomSTUNServer

`string CustomSTUNServer`

Specify a Custom STUN Server used to Resolve the peer Reflexive Addresses

Default: null (no custom STUN Server)

6.280.3.10 DisableNATPunchthrough

`bool DisableNATPunchthrough`

Flag to disable the NAT Punchthrough implementation and connect only via Relay

Default: false

6.280.3.11 EnableClientSessionCreation

`bool? EnableClientSessionCreation`

Enables the Session creation when starting a Client with an specific Session Name

Default: false (clients *can not* create new Sessions)

6.280.3.12 GameMode

`GameMode GameMode`

`Fusion.GameMode` in which this peer will start

6.280.3.13 HostMigrationResume

Action<[NetworkRunner](#)> HostMigrationResume

Callback invoked when the new Host is migrating from the old Host state

Default: null

6.280.3.14 HostMigrationToken

[HostMigrationToken](#) HostMigrationToken

Host Migration Token used when restarting the [Fusion Simulation](#)

Default: null

6.280.3.15 IsOpen

bool? IsOpen

Session should be created Open or Closed to accept joins

Default: true

6.280.3.16 IsVisible

bool? IsVisible

Session should be Visible or not in the Session Lobby list

Default: true

6.280.3.17 MatchmakingMode

MatchmakingMode? MatchmakingMode

Session Join Matchmaking Mode when joining a Session. For more information, check [Fusion.Photon.Realtime.MatchmakingMode](#).

Default: MatchmakingMode.FillRoom

6.280.3.18 ObjectInitializer

[INetworkObjectInitializer](#) ObjectInitializer

See [INetworkRunnerUpdater](#)

6.280.3.19 ObjectProvider

`INetworkObjectProvider` ObjectProvider

Object pool to use

Default: null

6.280.3.20 OnGameStarted

`Action<NetworkRunner>` OnGameStarted

Callback that is invoked when the `Fusion` has fully started

Default: null

6.280.3.21 PlayerCount

`int?` PlayerCount

Number of players allowed to connect to this peer, when running in Server/Host Mode

Default: DefaultPlayers from the Global `NetworkProjectConfig`

6.280.3.22 Scene

`NetworkSceneInfo?` Scene

Scene that will be set as the starting Scene when running in Server/Host Mode

Default: null (no scene set)

6.280.3.23 SceneManager

`INetworkSceneManager` SceneManager

See `INetworkSceneManager`.

Default: null

More about Scene Loading: <https://doc.photonengine.com/en-us/fusion/current/manual/scene-load>

6.280.3.24 SessionName

`string` SessionName

Photon Cloud Session Name used either to Create or Join a Session.

Default: null (random session matching)

6.280.3.25 SessionProperties

`Dictionary<string, SessionProperty> SessionProperties`

Custom Session Properties. This dictionary can be used to either setup the initial Session Properties when creating a Session but also to set the matchmaking filters when joining a Random Session.

Default: null (empty custom properties)

6.280.3.26 StartGameCancellationToken

`CancellationToken StartGameCancellationToken`

Optional CancellationToken used to cancel the [NetworkRunner](#) start up process and shutdown

Defaults: null

6.280.3.27 Updater

`INetworkRunnerUpdater Updater`

See [INetworkRunnerUpdater](#)

6.280.3.28 UseCachedRegions

`bool UseCachedRegions`

Enables the usage of the previous cached regions pings. This speeds up the region ping process and the runner startup process.

Defaults: false

6.280.3.29 UseDefaultPhotonCloudPorts

`bool? UseDefaultPhotonCloudPorts`

Signal if the internal Realtime Client should use the Default Photon ports to connect to the Photon Cloud. By default, [Fusion](#) uses ports: 27000, 27001 and 27002. Set this to True to use ports: 5058, 5055 and 5056.

Default: false (uses ports 27000, 27001 and 27002)

6.281 StartGameResult Class Reference

Represents the result of starting the [Fusion Simulation](#)

Public Member Functions

- override string [ToString](#) ()
String representation of the [StartGameResult](#)

Properties

- string [ErrorMessage](#) [get]
Custom Error Message filled with data about the Shutdown. Usually used to store custom data when the StartGame fails.
- bool [Ok](#) [get]
Signal if the Start was OK
- [ShutdownReason](#) [ShutdownReason](#) [get]
Start Game Shutdown Reason
- string [StackTrace](#) [get]
Optional Exception StackTrace

6.281.1 Detailed Description

Represents the result of starting the [Fusion Simulation](#)

6.281.2 Member Function Documentation

6.281.2.1 ToString()

```
override string ToString ( )
```

String representation of the [StartGameResult](#)

6.281.3 Property Documentation

6.281.3.1 ErrorMessage

```
string ErrorMessage [get]
```

Custom Error Message filled with data about the Shutdown. Usually used to store custom data when the StartGame fails.

6.281.3.2 Ok

`bool Ok [get]`

Signal if the Start was OK

6.281.3.3 ShutdownReason

`ShutdownReason ShutdownReason [get]`

Start Game Shutdown Reason

6.281.3.4 StackTrace

`string StackTrace [get]`

Optional Exception StackTrace

6.282 StatsMetaAttribute Class Reference

This stat goes on field elements of classes/structs and is used by [FieldsMask](#).

Inherits DisplayNameAttribute.

Public Member Functions

- **StatsMetaAttribute** (bool defaultEnabled=false, int decimals=3, float multiplier=1, float warnThreshold=float.PositiveInfinity, float errorThreshold=float.PositiveInfinity, StatAveraging averaging=StatAveraging.PerSample)
- **StatsMetaAttribute** (string shortName, bool defaultEnabled=false, int decimals=3, float multiplier=1, float warnThreshold=float.PositiveInfinity, float errorThreshold=float.PositiveInfinity, StatAveraging averaging=StatAveraging.PerSample)
- **StatsMetaAttribute** (string shortName, string longName, bool defaultEnabled=false, int decimals=3, float multiplier=1, float warnThreshold=float.PositiveInfinity, float errorThreshold=float.PositiveInfinity, StatAveraging averaging=StatAveraging.PerSample)

Public Attributes

- readonly StatAveraging **Averaging**
- readonly int **Decimals**
- readonly bool **DefaultEnabled**
- readonly float **ErrorThreshold**
- readonly float **Multiplier**
- readonly string **ShortName**
- readonly float **WarnThreshold**

6.282.1 Detailed Description

This stat goes on field elements of classes/structs and is used by [FieldsMask](#).

6.283 Tick Struct Reference

A tick is a 32-bit integer that represents a frame number.

Inherits `Comparable< Tick >`, and `IEquatable< Tick >`.

Classes

- class [EqualityComparer](#)
Provides a mechanism for comparing two [Tick](#) objects for equality.
- class [RelationalComparer](#)
Provides a mechanism for comparing two [Tick](#) objects.

Public Member Functions

- int [CompareTo](#) ([Tick](#) other)
Compares the current [Tick](#) with another [Tick](#).
- override bool [Equals](#) (object obj)
Determines whether the specified object is equal to the current [Tick](#).
- bool [Equals](#) ([Tick](#) other)
Determines whether the specified [Tick](#) is equal to the current [Tick](#).
- override int [GetHashCode](#) ()
Serves as the default hash function.
- [Tick](#) [Next](#) (int increment)
Returns the next [Tick](#), incremented by a specified value.
- override string [ToString](#) ()
String representation of the [Tick](#).

Static Public Member Functions

- static implicit [operator bool](#) ([Tick](#) value)
Converts a [Tick](#) to a boolean.
- static implicit [operator int](#) ([Tick](#) value)
Converts a [Tick](#) to an integer.
- static implicit [operator Tick](#) (int value)
Converts an integer to a [Tick](#).
- static bool [operator!=](#) ([Tick](#) a, [Tick](#) b)
Determines whether the first specified [Tick](#) is not equal to the second specified [Tick](#).
- static bool [operator<](#) ([Tick](#) a, [Tick](#) b)
Determines whether the first specified [Tick](#) is less than the second specified [Tick](#).
- static bool [operator<=](#) ([Tick](#) a, [Tick](#) b)
Determines whether the first specified [Tick](#) is less than or equal to the second specified [Tick](#).
- static bool [operator==](#) ([Tick](#) a, [Tick](#) b)
Determines whether the first specified [Tick](#) is equal to the second specified [Tick](#).
- static bool [operator>](#) ([Tick](#) a, [Tick](#) b)
Determines whether the first specified [Tick](#) is greater than the second specified [Tick](#).
- static bool [operator>=](#) ([Tick](#) a, [Tick](#) b)
Determines whether the first specified [Tick](#) is greater than or equal to the second specified [Tick](#).

Public Attributes

- int [Raw](#)

The raw value of the [Tick](#). This represents a frame number.

Static Public Attributes

- const int [ALIGNMENT](#) = 4

The alignment of the [Tick](#) structure in bytes.

- const int [SIZE](#) = 4

The size of the [Tick](#) structure in bytes.

6.283.1 Detailed Description

A tick is a 32-bit integer that represents a frame number.

6.283.2 Member Function Documentation

6.283.2.1 CompareTo()

```
int CompareTo (  
    Tick other )
```

Compares the current [Tick](#) with another [Tick](#).

Parameters

<i>other</i>	A Tick to compare with this Tick .
--------------	--

Returns

A value that indicates the relative order of the objects being compared.

6.283.2.2 Equals() [1/2]

```
override bool Equals (  
    object obj )
```

Determines whether the specified object is equal to the current [Tick](#).

Parameters

<i>obj</i>	The object to compare with the current Tick .
------------	---

Returns

true if the specified object is equal to the current [Tick](#); otherwise, false.

6.283.2.3 Equals() [2/2]

```
bool Equals (
    Tick other )
```

Determines whether the specified [Tick](#) is equal to the current [Tick](#).

Parameters

<i>other</i>	The Tick to compare with the current Tick .
--------------	---

Returns

true if the specified [Tick](#) is equal to the current [Tick](#); otherwise, false.

6.283.2.4 GetHashCode()

```
override int GetHashCode ( )
```

Serves as the default hash function.

Returns

A hash code for the current [Tick](#).

6.283.2.5 Next()

```
Tick Next (
    int increment )
```

Returns the next [Tick](#), incremented by a specified value.

Parameters

<i>increment</i>	The value to increment the Tick by.
------------------	---

Returns

A new [Tick](#) that represents the current [Tick](#) incremented by the specified value.

6.283.2.6 operator bool()

```
static implicit operator bool (  
    Tick value ) [static]
```

Converts a [Tick](#) to a boolean.

Parameters

<i>value</i>	The Tick to convert.
--------------	--------------------------------------

Returns

true if the [Tick](#)'s raw value is greater than 0; otherwise, false.

6.283.2.7 operator int()

```
static implicit operator int (  
    Tick value ) [static]
```

Converts a [Tick](#) to an integer.

Parameters

<i>value</i>	The Tick to convert.
--------------	--------------------------------------

Returns

An integer that represents the raw value of the specified [Tick](#).

6.283.2.8 operator Tick()

```
static implicit operator Tick (  
    int value ) [static]
```


Converts an integer to a [Tick](#).

Parameters

<i>value</i>	The integer to convert.
--------------	-------------------------

Returns

A [Tick](#) that represents the specified integer. If the integer is less than 0, the [Tick](#)'s raw value is set to 0.

6.283.2.9 operator"!=()

```
static bool operator!= (
    Tick a,
    Tick b ) [static]
```

Determines whether the first specified [Tick](#) is not equal to the second specified [Tick](#).

6.283.2.10 operator<()

```
static bool operator< (
    Tick a,
    Tick b ) [static]
```

Determines whether the first specified [Tick](#) is less than the second specified [Tick](#).

6.283.2.11 operator<=()

```
static bool operator<= (
    Tick a,
    Tick b ) [static]
```

Determines whether the first specified [Tick](#) is less than or equal to the second specified [Tick](#).

6.283.2.12 operator==(())

```
static bool operator==(
    Tick a,
    Tick b ) [static]
```

Determines whether the first specified [Tick](#) is equal to the second specified [Tick](#).

6.283.2.13 operator>()

```
static bool operator> (
    Tick a,
    Tick b ) [static]
```

Determines whether the first specified [Tick](#) is greater than the second specified [Tick](#).

6.283.2.14 operator>=()

```
static bool operator>= (
    Tick a,
    Tick b ) [static]
```

Determines whether the first specified [Tick](#) is greater than or equal to the second specified [Tick](#).

6.283.2.15 ToString()

```
override string ToString ( )
```

String representation of the [Tick](#).

6.283.3 Member Data Documentation

6.283.3.1 ALIGNMENT

```
const int ALIGNMENT = 4 [static]
```

The alignment of the [Tick](#) structure in bytes.

6.283.3.2 Raw

```
int Raw
```

The raw value of the [Tick](#). This represents a frame number.

6.283.3.3 SIZE

```
const int SIZE = 4 [static]
```

The size of the [Tick](#) structure in bytes.

6.284 Tick.EqualityComparer Class Reference

Provides a mechanism for comparing two [Tick](#) objects for equality.

Inherits `IEqualityComparer< Tick >`.

Public Member Functions

- `bool Equals (Tick x, Tick y)`
Determines whether the specified [Tick](#) objects are equal.
- `int GetHashCode (Tick obj)`
Serves as a hash function for a [Tick](#) object.

6.284.1 Detailed Description

Provides a mechanism for comparing two [Tick](#) objects for equality.

6.284.2 Member Function Documentation

6.284.2.1 Equals()

```
bool Equals (  
    Tick x,  
    Tick y )
```

Determines whether the specified [Tick](#) objects are equal.

Parameters

<code>x</code>	The first Tick object to compare.
<code>y</code>	The second Tick object to compare.

Returns

true if the specified [Tick](#) objects are equal; otherwise, false.

6.284.2.2 GetHashCode()

```
int GetHashCode (
    Tick obj )
```

Serves as a hash function for a [Tick](#) object.

Parameters

<i>obj</i>	The Tick object for which to get a hash code.
------------	---

Returns

A hash code for the specified [Tick](#) object.

6.285 Tick.RelationalComparer Class Reference

Provides a mechanism for comparing two [Tick](#) objects.

Inherits `IComparer< Tick >`.

Public Member Functions

- `int Compare (Tick x, Tick y)`

Compares two [Tick](#) objects and returns a value indicating whether one is less than, equal to, or greater than the other.

6.285.1 Detailed Description

Provides a mechanism for comparing two [Tick](#) objects.

6.285.2 Member Function Documentation

6.285.2.1 Compare()

```
int Compare (
    Tick x,
    Tick y )
```

Compares two [Tick](#) objects and returns a value indicating whether one is less than, equal to, or greater than the other.

Parameters

<i>x</i>	The first Tick object to compare.
<i>y</i>	The second Tick object to compare.

Returns

A signed integer that indicates the relative values of x and y.

6.286 TickAccumulator Struct Reference

A tick accumulator.

Public Member Functions

- void [AddTicks](#) (int ticks)
Adds a specified number of ticks to the [TickAccumulator](#).
- void [AddTime](#) (double dt, double step, int? maxTicks=null)
Adds a specified amount of time to the [TickAccumulator](#), incrementing the tick count as necessary.
- float [Alpha](#) (double step)
Calculates the alpha value based on the given step.
- bool [ConsumeTick](#) (out bool last)
Consumes a tick from the [TickAccumulator](#).
- void [Start](#) ()
Starts the [TickAccumulator](#), allowing it to accumulate ticks.
- void [Stop](#) ()
Stops the [TickAccumulator](#) from accumulating ticks.

Static Public Member Functions

- static [TickAccumulator StartNew](#) ()
Starts a new [TickAccumulator](#).

Public Attributes

- bool [_running](#)
- double [_scale](#)
- int [_ticks](#)
- double [_time](#)

Properties

- int [Pending](#) [get]
Gets the number of pending ticks in the [TickAccumulator](#).
- double [Remainder](#) [get]
Gets the remaining time in the [TickAccumulator](#).
- bool [Running](#) [get]
Gets a value indicating whether the [TickAccumulator](#) is running.
- double [TimeScale](#) [get, set]
Gets or sets the time scale of the [TickAccumulator](#).

6.286.1 Detailed Description

A tick accumulator.

6.286.2 Member Function Documentation

6.286.2.1 AddTicks()

```
void AddTicks (
    int ticks )
```

Adds a specified number of ticks to the [TickAccumulator](#).

Parameters

<i>ticks</i>	The number of ticks to add.
--------------	-----------------------------

6.286.2.2 AddTime()

```
void AddTime (
    double dt,
    double step,
    int? maxTicks = null )
```

Adds a specified amount of time to the [TickAccumulator](#), incrementing the tick count as necessary.

Parameters

<i>dt</i>	The amount of time to add.
<i>step</i>	The time step value.
<i>maxTicks</i>	The maximum number of ticks to add. If this value is reached, the remaining time is set to 0.

6.286.2.3 Alpha()

```
float Alpha (
    double step )
```

Calculates the alpha value based on the given step.

Parameters

<i>step</i>	The step value used to calculate the alpha.
-------------	---

Returns

The calculated alpha value.

6.286.2.4 ConsumeTick()

```
bool ConsumeTick (
    out bool last )
```

Consumes a tick from the [TickAccumulator](#).

Parameters

<i>last</i>	When this method returns, contains a boolean indicating whether the consumed tick was the last one.
-------------	---

Returns

true if a tick was successfully consumed; otherwise, false.

6.286.2.5 Start()

```
void Start ( )
```

Starts the [TickAccumulator](#), allowing it to accumulate ticks.

6.286.2.6 StartNew()

```
static TickAccumulator StartNew ( ) [static]
```

Starts a new [TickAccumulator](#).

Returns

A new [TickAccumulator](#).

6.286.2.7 Stop()

```
void Stop ( )
```

Stops the [TickAccumulator](#) from accumulating ticks.

6.286.3 Property Documentation

6.286.3.1 Pending

```
int Pending [get]
```

Gets the number of pending ticks in the [TickAccumulator](#).

6.286.3.2 Remainder

```
double Remainder [get]
```

Gets the remaining time in the [TickAccumulator](#).

6.286.3.3 Running

```
bool Running [get]
```

Gets a value indicating whether the [TickAccumulator](#) is running.

6.286.3.4 TimeScale

```
double TimeScale [get], [set]
```

Gets or sets the time scale of the [TickAccumulator](#).

Exceptions

<i>InvalidOperationException</i>	Thrown when the value is less than or equal to 0.
----------------------------------	---

6.287 TickRate Struct Reference

A tick rate is a collection of tick rates.

Classes

- struct [Resolved](#)
Represents a resolved tick rate.
- struct [Selection](#)
Represents a selection of tick rates for client and server.

Public Types

- enum class [ValidateResult](#)
Enumerates the possible results of validating a tick rate selection.

Public Member Functions

- [Selection ClampSelection](#) ([Selection](#) selection)
Clamps the indices in the specified [Selection](#) to valid ranges.
- int [GetDivisor](#) (int index)
Gets the divisor for the tick rate at the specified index.
- int [GetTickRate](#) (int index)
Gets the tick rate at the specified index.
- **TickRate** (params int[] rates)
- int[] [ToArray](#) ()
Converts the tick rates to an array.
- bool [Validate](#) ()
Validates the tick rates in the [TickRate](#).
- [ValidateResult ValidateSelection](#) ([Selection](#) selected)
Validates the tick rates in the specified [Selection](#).

Static Public Member Functions

- static [TickRate Get](#) (int rate)
Retrieves the [TickRate](#) associated with the specified tick rate.
- static void [Init](#) ()
Initializes the [TickRate](#) class by setting up the valid tick rates and their lookup dictionary.
- static void **InitChecked** ()
- static bool [IsValid](#) (int rate)
Checks if the provided tick rate is valid.
- static bool [IsValid](#) ([TickRate](#) rate)
Checks if the provided [TickRate](#) is valid.
- static [Resolved Resolve](#) ([Selection](#) selection)
Resolves the specified [Selection](#) into a [Resolved](#) structure.

Public Attributes

- int **_count**
- fixed int **_rates** [4]

Static Public Attributes

- static Dictionary< int, [TickRate](#) > **_lookup**
- static [TickRate](#)[] **_valid**
- static ReadOnlyCollection< [TickRate](#) > **_validReadOnly**

Properties

- static IReadOnlyList< [TickRate](#) > [Available](#) [get]
Gets a read-only list of all available TickRates.
- int [Client](#) [get]
Gets the tick rate for the client.
- int [Count](#) [get]
Gets the count of tick rates in the [TickRate](#).
- int [this\[int index\]](#) [get]
Gets the tick rate at the specified index.

6.287.1 Detailed Description

A tick rate is a collection of tick rates.

6.287.2 Member Enumeration Documentation

6.287.2.1 ValidateResult

```
enum ValidateResult [strong]
```

Enumerates the possible results of validating a tick rate selection.

Enumerator

Ok	The tick rate selection is valid.
Error	An error occurred during validation.
NotFound	The tick rate selection was not found.
InvalidTickRate	The tick rate selection is invalid.
ServerIndexOutOfRange	The server index in the tick rate selection is out of range.
ClientSendIndexOutOfRange	The client send index in the tick rate selection is out of range.
ServerSendIndexOutOfRange	The server send index in the tick rate selection is out of range.
ServerSendRateLargerThanTickRate	The server send rate in the tick rate selection is larger than the tick rate.

6.287.3 Member Function Documentation

6.287.3.1 ClampSelection()

```
Selection ClampSelection (
    Selection selection )
```

Clamps the indices in the specified [Selection](#) to valid ranges.

Parameters

<i>selection</i>	The Selection to clamp.
------------------	---

Returns

A new [Selection](#) with clamped indices. If the [TickRate](#) is invalid, returns a default [Selection](#).

6.287.3.2 Get()

```
static TickRate Get (
    int rate ) [static]
```

Retrieves the [TickRate](#) associated with the specified tick rate.

Parameters

<i>rate</i>	The tick rate to retrieve the TickRate for.
-------------	---

Returns

The [TickRate](#) associated with the specified tick rate.

Exceptions

<i>InvalidOperationException</i>	Thrown when the tick rate is invalid.
----------------------------------	---------------------------------------

6.287.3.3 GetDivisor()

```
int GetDivisor (
    int index )
```

Gets the divisor for the tick rate at the specified index.

Parameters

<i>index</i>	The index of the tick rate to get the divisor for.
--------------	--

Returns

The divisor for the tick rate at the specified index.

Exceptions

<i>ArgumentOutOfRangeException</i>	Thrown when the index is out of range.
<i>InvalidOperationException</i>	Thrown when the client tick rate is not divisible by the tick rate at the specified index.

6.287.3.4 GetTickRate()

```
int GetTickRate (
    int index )
```

Gets the tick rate at the specified index.

Parameters

<i>index</i>	The index of the tick rate to get.
--------------	------------------------------------

Returns

The tick rate at the specified index.

Exceptions

<i>ArgumentOutOfRangeException</i>	Thrown when the index is out of range.
------------------------------------	--

6.287.3.5 Init()

```
static void Init ( ) [static]
```

Initializes the [TickRate](#) class by setting up the valid tick rates and their lookup dictionary.

6.287.3.6 IsValid() [1/2]

```
static bool IsValid (  
    int rate ) [static]
```

Checks if the provided tick rate is valid.

Parameters

<i>rate</i>	The tick rate to validate.
-------------	----------------------------

Returns

true if the tick rate is valid; otherwise, false.

6.287.3.7 IsValid() [2/2]

```
static bool IsValid (  
    TickRate rate ) [static]
```

Checks if the provided [TickRate](#) is valid.

Parameters

<i>rate</i>	The TickRate to validate.
-------------	---

Returns

true if the [TickRate](#) is valid; otherwise, false.

6.287.3.8 Resolve()

```
static Resolved Resolve (  
    Selection selection ) [static]
```

Resolves the specified [Selection](#) into a [Resolved](#) structure.

Parameters

<i>selection</i>	The Selection to resolve.
------------------	---

Returns

A [Resolved](#) structure that represents the resolved tick rates.

6.287.3.9 ToArray()

```
int [] ToArray ( )
```

Converts the tick rates to an array.

Returns

An array containing the tick rates.

6.287.3.10 Validate()

```
bool Validate ( )
```

Validates the tick rates in the [TickRate](#).

Returns

true if the tick rates are valid; otherwise, false.

The tick rates are valid if:

- There is at least one tick rate.
- There are no more than four tick rates.
- The first tick rate is greater than 0.
- Each tick rate is a divisor of the first tick rate.

6.287.3.11 ValidateSelection()

```
ValidateResult ValidateSelection (
    Selection selected )
```

Validates the tick rates in the specified [Selection](#).

Parameters

<i>selected</i>	The Selection to validate.
-----------------	--

Returns

A `ValidateResult` that indicates the result of the validation.

The `Selection` is valid if:

- The `TickRate` is valid.
- The client tick rate in the `Selection` matches the client tick rate in the `TickRate`.
- The server index in the `Selection` is within the range of available tick rates.
- The server send index in the `Selection` is within the range of available tick rates.
- The client send index in the `Selection` is within the range of available tick rates.
- The server send rate in the `Selection` is not larger than the server tick rate.

6.287.4 Property Documentation

6.287.4.1 Available

```
ICollection<TickRate> Available [static], [get]
```

Gets a read-only list of all available `TickRates`.

This property ensures that the `TickRate` class is initialized before returning the list.

6.287.4.2 Client

```
int Client [get]
```

Gets the tick rate for the client.

6.287.4.3 Count

```
int Count [get]
```

Gets the count of tick rates in the `TickRate`.

6.287.4.4 this[int index]

```
int this[int index] [get]
```

Gets the tick rate at the specified index.

Parameters

<i>index</i>	The index of the tick rate to get.
--------------	------------------------------------

Returns

The tick rate at the specified index.

6.288 TickRate.Resolved Struct Reference

Represents a resolved tick rate.

Public Attributes

- int [Client](#)
The tick rate for the client.
- int [ClientSend](#)
The send tick rate for the client.
- int [Server](#)
The tick rate for the server.
- int [ServerSend](#)
The send tick rate for the server.

Static Public Attributes

- const int [SIZE](#) = 16
The size of the [Resolved](#) structure in bytes.
- const int [WORDS](#) = [SIZE](#) / [Allocator.REPLICATE_WORD_SIZE](#)
The size of the [Resolved](#) structure in words.

Properties

- double [ClientSendDelta](#) [get]
Gets the delta time for the client send rate.
- double [ClientTickDelta](#) [get]
Gets the delta time for the client tick rate.
- int [ClientTickStride](#) [get]
Gets the stride of the client tick rate. This is always 1.
- double [ServerSendDelta](#) [get]
Gets the delta time for the server send rate.
- double [ServerTickDelta](#) [get]
Gets the delta time for the server tick rate.
- int [ServerTickStride](#) [get]
Gets the stride of the server tick rate relative to the client tick rate.

6.288.1 Detailed Description

Represents a resolved tick rate.

The tick rate is resolved by the client and server tick rates.

6.288.2 Member Data Documentation

6.288.2.1 Client

```
int Client
```

The tick rate for the client.

6.288.2.2 ClientSend

```
int ClientSend
```

The send tick rate for the client.

6.288.2.3 Server

```
int Server
```

The tick rate for the server.

6.288.2.4 ServerSend

```
int ServerSend
```

The send tick rate for the server.

6.288.2.5 SIZE

```
const int SIZE = 16 [static]
```

The size of the [Resolved](#) structure in bytes.

6.288.2.6 WORDS

```
const int WORDS = SIZE / Allocator.REPLICATE_WORD_SIZE [static]
```

The size of the [Resolved](#) structure in words.

6.288.3 Property Documentation

6.288.3.1 ClientSendDelta

```
double ClientSendDelta [get]
```

Gets the delta time for the client send rate.

6.288.3.2 ClientTickDelta

```
double ClientTickDelta [get]
```

Gets the delta time for the client tick rate.

6.288.3.3 ClientTickStride

```
int ClientTickStride [get]
```

Gets the stride of the client tick rate. This is always 1.

6.288.3.4 ServerSendDelta

```
double ServerSendDelta [get]
```

Gets the delta time for the server send rate.

6.288.3.5 ServerTickDelta

```
double ServerTickDelta [get]
```

Gets the delta time for the server tick rate.

6.288.3.6 ServerTickStride

```
int ServerTickStride [get]
```

Gets the stride of the server tick rate relative to the client tick rate.

6.289 TickRate.Selection Struct Reference

Represents a selection of tick rates for client and server.

Public Attributes

- int [Client](#)
The tick rate for the client.
- int [ClientSendIndex](#)
The index of the client's send tick rate in the available tick rates.
- int [ServerIndex](#)
The index of the server's tick rate in the available tick rates.
- int [ServerSendIndex](#)
The index of the server's send tick rate in the available tick rates.

6.289.1 Detailed Description

Represents a selection of tick rates for client and server.

6.289.2 Member Data Documentation

6.289.2.1 Client

```
int Client
```

The tick rate for the client.

6.289.2.2 ClientSendIndex

```
int ClientSendIndex
```

The index of the client's send tick rate in the available tick rates.

6.289.2.3 ServerIndex

```
int ServerIndex
```

The index of the server's tick rate in the available tick rates.

6.289.2.4 ServerSendIndex

```
int ServerSendIndex
```

The index of the server's send tick rate in the available tick rates.

6.290 TickTimer Struct Reference

A timer that is based on ticks instead of seconds.

Inherits [INetworkStruct](#).

Public Member Functions

- bool [Expired](#) ([NetworkRunner](#) runner)
Checks if the [TickTimer](#) has expired.
- bool [ExpiredOrNotRunning](#) ([NetworkRunner](#) runner)
Checks if the [TickTimer](#) has expired or is not running.
- int? [RemainingTicks](#) ([NetworkRunner](#) runner)
Gets the number of remaining ticks until the [TickTimer](#) expires.
- float? [RemainingTime](#) ([NetworkRunner](#) runner)
Gets the remaining time in seconds until the [TickTimer](#) expires.
- override string [ToString](#) ()
Returns a string that represents the current [TickTimer](#).

Static Public Member Functions

- static [TickTimer CreateFromSeconds](#) ([NetworkRunner](#) runner, float delayInSeconds)
Creates a [TickTimer](#) from a specified delay in seconds.
- static [TickTimer CreateFromTicks](#) ([NetworkRunner](#) runner, int ticks)
Creates a [TickTimer](#) from a specified number of ticks.

Public Attributes

- int [_target](#)

Properties

- bool `IsRunning` [get]
Gets a value indicating whether the `TickTimer` is running.
- static `TickTimer None` [get]
Gets a `TickTimer` that is not running.
- int? `TargetTick` [get]
Gets the target tick of the `TickTimer`.

6.290.1 Detailed Description

A timer that is based on ticks instead of seconds.

6.290.2 Member Function Documentation

6.290.2.1 `CreateFromSeconds()`

```
static TickTimer CreateFromSeconds (  
    NetworkRunner runner,  
    float delayInSeconds ) [static]
```

Creates a `TickTimer` from a specified delay in seconds.

Parameters

<code>runner</code>	The <code>NetworkRunner</code> associated with the <code>TickTimer</code> .
<code>delayInSeconds</code>	The delay in seconds to set the <code>TickTimer</code> to.

Returns

A `TickTimer` that will expire after the specified delay in seconds. If the `NetworkRunner` is not alive or not running, returns a default `TickTimer`.

6.290.2.2 `CreateFromTicks()`

```
static TickTimer CreateFromTicks (  
    NetworkRunner runner,  
    int ticks ) [static]
```

Creates a `TickTimer` from a specified number of ticks.

Parameters

<i>runner</i>	The NetworkRunner associated with the TickTimer .
<i>ticks</i>	The number of ticks to set the TickTimer to.

Returns

A [TickTimer](#) that will expire after the specified number of ticks. If the [NetworkRunner](#) is not alive or not running, returns a default [TickTimer](#).

6.290.2.3 Expired()

```
bool Expired (  
    NetworkRunner runner )
```

Checks if the [TickTimer](#) has expired.

Parameters

<i>runner</i>	The NetworkRunner associated with the TickTimer .
---------------	---

Returns

true if the [TickTimer](#) is alive, the runner is running, and the target tick has been reached or passed; otherwise, false.

6.290.2.4 ExpiredOrNotRunning()

```
bool ExpiredOrNotRunning (  
    NetworkRunner runner )
```

Checks if the [TickTimer](#) has expired or is not running.

Parameters

<i>runner</i>	The NetworkRunner associated with the TickTimer .
---------------	---

Returns

true if the [TickTimer](#) is not running, the runner is not running, or the [TickTimer](#) has expired; otherwise, false.

6.290.2.5 RemainingTicks()

```
int? RemainingTicks (
    NetworkRunner runner )
```

Gets the number of remaining ticks until the [TickTimer](#) expires.

Parameters

<i>runner</i>	The NetworkRunner associated with the TickTimer .
---------------	---

Returns

The number of remaining ticks if the [TickTimer](#) is alive and running; otherwise, null.

6.290.2.6 RemainingTime()

```
float? RemainingTime (
    NetworkRunner runner )
```

Gets the remaining time in seconds until the [TickTimer](#) expires.

Parameters

<i>runner</i>	The NetworkRunner associated with the TickTimer .
---------------	---

Returns

The remaining time in seconds if there are remaining ticks; otherwise, null.

6.290.2.7 ToString()

```
override string ToString ( )
```

Returns a string that represents the current [TickTimer](#).

Returns

A string that represents the current [TickTimer](#).

6.290.3 Property Documentation

6.290.3.1 IsRunning

```
bool IsRunning [get]
```

Gets a value indicating whether the [TickTimer](#) is running.

true if the [TickTimer](#) is running; otherwise, false.

6.290.3.2 None

```
TickTimer None [static], [get]
```

Gets a [TickTimer](#) that is not running.

6.290.3.3 TargetTick

```
int? TargetTick [get]
```

Gets the target tick of the [TickTimer](#).

The target tick if the [TickTimer](#) is running; otherwise, null.

6.291 TimeSyncConfiguration Class Reference

Time Synchronization Configuration

Public Attributes

- int [ExtraInterpolationOffset](#) = 1
- int [ExtraSimulationOffset](#) = 1
- double [MaxLateInputs](#) = 1.0
- double [MaxLateSnapshots](#) = 1.0

6.291.1 Detailed Description

Time Synchronization Configuration

6.291.2 Member Data Documentation

6.291.2.1 ExtraInterpolationOffset

```
int ExtraInterpolationOffset = 1
```

Increases the target interpolation delay by a fixed duration.

This is effectively how many extra chances clients have to receive new snapshots in time.

6.291.2.2 ExtraSimulationOffset

```
int ExtraSimulationOffset = 1
```

Increases the target simulation offset by a fixed duration.

This is effectively how many extra chances inputs have to reach the server in time.

6.291.2.3 MaxLateInputs

```
double MaxLateInputs = 1.0
```

The maximum amount (%) of inputs allowed to arrive late because of jitter.

Determines the minimum target simulation offset.

6.291.2.4 MaxLateSnapshots

```
double MaxLateSnapshots = 1.0
```

The maximum amount (%) of snapshots allowed to arrive late because of jitter.

Determines the minimum target interpolation delay.

6.292 UnitAttribute Class Reference

Unit Attribute class. Used to mark a field with the respective [Units](#)

Inherits DecoratingPropertyAttribute.

Public Member Functions

- **UnitAttribute** ([Units](#) units)

Properties

- **Units Unit** [get]

6.292.1 Detailed Description

Unit Attribute class. Used to mark a field with the respective [Units](#)

6.293 UnityContextMenuAttribute Class Reference

Unity ContextMenuAttribute

Inherits Attribute.

Public Member Functions

- [UnityContextMenuAttribute](#) (string function, string name)
ContextMenuAttribute Constructor

Properties

- int [order](#) [get, set]
ContextMenuAttribute Order

6.293.1 Detailed Description

Unity ContextMenuAttribute

6.293.2 Constructor & Destructor Documentation

6.293.2.1 UnityContextMenuAttribute()

```
UnityContextMenuAttribute (  
    string function,  
    string name )
```

ContextMenuAttribute Constructor

6.293.3 Property Documentation

6.293.3.1 order

```
int order [get], [set]
```

ContextMenuAttribute Order

6.294 UnityDelayedAttribute Class Reference

Unity DelayedAttribute

Inherits Attribute.

Properties

- int [order](#) [get, set]
DelayedAttribute Order

6.294.1 Detailed Description

Unity DelayedAttribute

6.294.2 Property Documentation

6.294.2.1 order

```
int order [get], [set]
```

DelayedAttribute Order

6.295 UnityFormerlySerializedAsAttribute Class Reference

Unity FormerlySerializedAsAttribute

Inherits Attribute.

Public Member Functions

- [UnityFormerlySerializedAsAttribute](#) (string oldName)
FormerlySerializedAsAttribute Constructor

6.295.1 Detailed Description

Unity FormerlySerializedAsAttribute

6.295.2 Constructor & Destructor Documentation

6.295.2.1 UnityFormerlySerializedAsAttribute()

```
UnityFormerlySerializedAsAttribute (  
    string oldName )
```

FormerlySerializedAsAttribute Constructor

6.296 UnityHeaderAttribute Class Reference

Unity HeaderAttribute

Inherits Attribute.

Public Member Functions

- [UnityHeaderAttribute](#) (string header)
HeaderAttribute Constructor

Properties

- int [order](#) [get, set]
HeaderAttribute Order

6.296.1 Detailed Description

Unity HeaderAttribute

6.296.2 Constructor & Destructor Documentation

6.296.2.1 UnityHeaderAttribute()

```
UnityHeaderAttribute (  
    string header )
```

HeaderAttribute Constructor

6.296.3 Property Documentation

6.296.3.1 order

```
int order [get], [set]
```

HeaderAttribute Order

6.297 UnityMinAttribute Class Reference

Unity MinAttribute

Inherits Attribute.

Public Member Functions

- [UnityMinAttribute](#) (float min)
MinAttribute Constructor

Properties

- int [order](#) [get, set]
MinAttribute Order

6.297.1 Detailed Description

Unity MinAttribute

6.297.2 Constructor & Destructor Documentation

6.297.2.1 UnityMinAttribute()

```
UnityMinAttribute (  
    float min )
```

MinAttribute Constructor

6.297.3 Property Documentation

6.297.3.1 order

```
int order [get], [set]
```

MinAttribute Order

6.298 UnityMultilineAttribute Class Reference

Unity MultilineAttribute

Inherits Attribute.

Properties

- int [order](#) [get, set]
MultilineAttribute Order

6.298.1 Detailed Description

Unity MultilineAttribute

6.298.2 Property Documentation

6.298.2.1 order

```
int order [get], [set]
```

MultilineAttribute Order

6.299 UnityNonReorderableAttribute Class Reference

Unity NonReorderableAttribute

Inherits Attribute.

Properties

- int [order](#) [get, set]
NonReorderableAttribute Order

6.299.1 Detailed Description

Unity NonReorderableAttribute

6.299.2 Property Documentation

6.299.2.1 order

```
int order [get], [set]
```

NonReorderableAttribute Order

6.300 UnityNonSerializedAttribute Class Reference

Unity NonSerializedAttribute

Inherits Attribute.

6.300.1 Detailed Description

Unity NonSerializedAttribute

6.301 UnityRangeAttribute Class Reference

Unity RangeAttribute

Inherits Attribute.

Public Member Functions

- [UnityRangeAttribute](#) (float min, float max)
RangeAttribute Constructor

Properties

- int [order](#) [get, set]
RangeAttribute Order

6.301.1 Detailed Description

Unity RangeAttribute

6.301.2 Constructor & Destructor Documentation

6.301.2.1 UnityRangeAttribute()

```
UnityRangeAttribute (
    float min,
    float max )
```

RangeAttribute Constructor

6.301.3 Property Documentation

6.301.3.1 order

```
int order [get], [set]
```

RangeAttribute Order

6.302 UnitySerializeField Class Reference

Unity SerializeField

Inherits Attribute.

6.302.1 Detailed Description

Unity SerializeField

6.303 UnitySerializeReference Class Reference

Unity SerializeReference

Inherits Attribute.

6.303.1 Detailed Description

Unity SerializeReference

6.304 UnitySpaceAttribute Class Reference

Unity SpaceAttribute

Inherits Attribute.

Public Member Functions

- [UnitySpaceAttribute](#) (float space)
SpaceAttribute Constructor

Properties

- int [order](#) [get, set]
SpaceAttribute Order

6.304.1 Detailed Description

Unity SpaceAttribute

6.304.2 Constructor & Destructor Documentation

6.304.2.1 UnitySpaceAttribute()

```
UnitySpaceAttribute (  
    float space )
```

SpaceAttribute Constructor

6.304.3 Property Documentation

6.304.3.1 order

```
int order [get], [set]
```

SpaceAttribute Order

6.305 UnityTooltipAttribute Class Reference

Unity TooltipAttribute

Inherits Attribute.

Public Member Functions

- [UnityTooltipAttribute](#) (string tooltip)
TooltipAttribute Constructor

Properties

- int [order](#) [get, set]
TooltipAttribute Order

6.305.1 Detailed Description

Unity TooltipAttribute

6.305.2 Constructor & Destructor Documentation

6.305.2.1 UnityTooltipAttribute()

```
UnityTooltipAttribute (  
    string tooltip )
```

TooltipAttribute Constructor

6.305.3 Property Documentation

6.305.3.1 order

```
int order [get], [set]
```

TooltipAttribute Order

6.306 Vector2Compressed Struct Reference

Represents a compressed Vector2 value for network transmission.

Inherits [INetworkStruct](#), and [IEquatable< Vector2Compressed >](#).

Public Member Functions

- override bool [Equals](#) (object obj)
Checks if the provided object is a [Vector2Compressed](#) instance and if it's equal to the current [Vector2Compressed](#) instance.
- bool [Equals](#) ([Vector2Compressed](#) other)
Checks if the current [Vector2Compressed](#) instance is equal to the other [Vector2Compressed](#) instance.
- override int [GetHashCode](#) ()
Returns the hash code for the current [Vector2Compressed](#) instance.

Static Public Member Functions

- static implicit [operator Vector2](#) ([Vector2Compressed](#) q)
Implicit conversion from [Vector2Compressed](#) to Vector2.
- static implicit [operator Vector2Compressed](#) (Vector2 v)
Implicit conversion from Vector2 to [Vector2Compressed](#).
- static bool [operator!=](#) ([Vector2Compressed](#) left, [Vector2Compressed](#) right)
Inequality operator for [Vector2Compressed](#) struct.
- static bool [operator==](#) ([Vector2Compressed](#) left, [Vector2Compressed](#) right)
Equality operator for [Vector2Compressed](#) struct.

Public Attributes

- int [xEncoded](#)
Encoded value of the x component.
- int [yEncoded](#)
Encoded value of the y component.

Properties

- float [X](#) [get, set]
Gets or sets the x component.
- float [Y](#) [get, set]
Gets or sets the y component.

6.306.1 Detailed Description

Represents a compressed Vector2 value for network transmission.

6.306.2 Member Function Documentation

6.306.2.1 Equals() [1/2]

```
override bool Equals (  
    object obj )
```

Checks if the provided object is a [Vector2Compressed](#) instance and if it's equal to the current [Vector2Compressed](#) instance.

Parameters

<i>obj</i>	The object to compare with the current Vector2Compressed instance.
------------	--

Returns

True if the provided object is a [Vector2Compressed](#) instance and it's equal to the current [Vector2Compressed](#) instance, otherwise false.

6.306.2.2 Equals() [2/2]

```
bool Equals (  
    Vector2Compressed other )
```

Checks if the current [Vector2Compressed](#) instance is equal to the other [Vector2Compressed](#) instance.

Parameters

<i>other</i>	The other Vector2Compressed instance to compare with the current Vector2Compressed instance.
--------------	--

Returns

True if the values of both [Vector2Compressed](#) instances are equal, otherwise false.

6.306.2.3 GetHashCode()

```
override int GetHashCode ( )
```

Returns the hash code for the current [Vector2Compressed](#) instance.

Returns

A hash code for the current [Vector2Compressed](#) instance.

6.306.2.4 operator Vector2()

```
static implicit operator Vector2 (
    Vector2Compressed q ) [static]
```

Implicit conversion from [Vector2Compressed](#) to Vector2.

Parameters

<i>q</i>	The Vector2Compressed instance to convert.
----------	--

Returns

The decompressed Vector2 value of the [Vector2Compressed](#) instance.

6.306.2.5 operator Vector2Compressed()

```
static implicit operator Vector2Compressed (
    Vector2 v ) [static]
```

Implicit conversion from Vector2 to [Vector2Compressed](#).

Parameters

<i>v</i>	The Vector2 value to convert.
----------	-------------------------------

Returns

A new [Vector2Compressed](#) instance with the compressed value of the Vector2.

6.306.2.6 operator"!=()"

```
static bool operator!= (
    Vector2Compressed left,
    Vector2Compressed right ) [static]
```

Inequality operator for [Vector2Compressed](#) struct.

Parameters

<i>left</i>	First Vector2Compressed instance.
<i>right</i>	Second Vector2Compressed instance.

Returns

True if the value of the first [Vector2Compressed](#) instance is not equal to the value of the second [Vector2Compressed](#) instance, otherwise false.

6.306.2.7 operator==()

```
static bool operator== (
    Vector2Compressed left,
    Vector2Compressed right ) [static]
```

Equality operator for [Vector2Compressed](#) struct.

Parameters

<i>left</i>	First Vector2Compressed instance.
<i>right</i>	Second Vector2Compressed instance.

Returns

True if the value of the first [Vector2Compressed](#) instance is equal to the value of the second [Vector2Compressed](#) instance, otherwise false.

6.306.3 Member Data Documentation

6.306.3.1 xEncoded

```
int xEncoded
```

Encoded value of the x component.

6.306.3.2 yEncoded

```
int yEncoded
```

Encoded value of the y component.

6.306.4 Property Documentation

6.306.4.1 X

```
float X [get], [set]
```

Gets or sets the x component.

6.306.4.2 Y

```
float Y [get], [set]
```

Gets or sets the y component.

6.307 Vector3Compressed Struct Reference

Represents a compressed Vector3 value for network transmission.

Inherits [INetworkStruct](#), and [IEquatable< Vector3Compressed >](#).

Public Member Functions

- override bool [Equals](#) (object obj)
Checks if the provided object is a [Vector3Compressed](#) instance and if it's equal to the current [Vector3Compressed](#) instance.
- bool [Equals](#) ([Vector3Compressed](#) other)
Checks if the current [Vector3Compressed](#) instance is equal to the other [Vector3Compressed](#) instance.
- override int [GetHashCode](#) ()
Returns the hash code for the current [Vector3Compressed](#) instance.

Static Public Member Functions

- static implicit [operator Vector2](#) ([Vector3Compressed](#) q)
Implicit conversion from [Vector3Compressed](#) to Vector2.
- static implicit [operator Vector3](#) ([Vector3Compressed](#) q)
Implicit conversion from [Vector3Compressed](#) to Vector3.
- static implicit [operator Vector3Compressed](#) (Vector2 v)
Implicit conversion from Vector2 to [Vector3Compressed](#).
- static implicit [operator Vector3Compressed](#) (Vector3 v)
Implicit conversion from Vector3 to [Vector3Compressed](#).
- static bool [operator!=](#) ([Vector3Compressed](#) left, [Vector3Compressed](#) right)
Inequality operator for [Vector3Compressed](#) struct.
- static bool [operator==](#) ([Vector3Compressed](#) left, [Vector3Compressed](#) right)
Equality operator for [Vector3Compressed](#) struct.

Public Attributes

- int [xEncoded](#)
Encoded value of the x component.
- int [yEncoded](#)
Encoded value of the y component.
- int [zEncoded](#)
Encoded value of the z component.

Properties

- float [X](#) [get, set]
Gets or sets the x component.
- float [Y](#) [get, set]
Gets or sets the y component.
- float [Z](#) [get, set]
Gets or sets the z component.

6.307.1 Detailed Description

Represents a compressed Vector3 value for network transmission.

6.307.2 Member Function Documentation

6.307.2.1 Equals() [1/2]

```
override bool Equals (  
    object obj )
```

Checks if the provided object is a [Vector3Compressed](#) instance and if it's equal to the current [Vector3Compressed](#) instance.

Parameters

<i>obj</i>	The object to compare with the current Vector3Compressed instance.
------------	--

Returns

True if the provided object is a [Vector3Compressed](#) instance and it's equal to the current [Vector3Compressed](#) instance, otherwise false.

6.307.2.2 Equals() [2/2]

```
bool Equals (
    Vector3Compressed other )
```

Checks if the current [Vector3Compressed](#) instance is equal to the other [Vector3Compressed](#) instance.

Parameters

<i>other</i>	The other Vector3Compressed instance to compare with the current Vector3Compressed instance.
--------------	--

Returns

True if the values of both [Vector3Compressed](#) instances are equal, otherwise false.

6.307.2.3 GetHashCode()

```
override int GetHashCode ( )
```

Returns the hash code for the current [Vector3Compressed](#) instance.

Returns

A hash code for the current [Vector3Compressed](#) instance.

6.307.2.4 operator Vector2()

```
static implicit operator Vector2 (
    Vector3Compressed q ) [static]
```

Implicit conversion from [Vector3Compressed](#) to Vector2.

Parameters

<i>q</i>	The Vector3Compressed instance to convert.
----------	--

Returns

The decompressed Vector2 value of the [Vector3Compressed](#) instance.

6.307.2.5 operator Vector3()

```
static implicit operator Vector3 (  
    Vector3Compressed q ) [static]
```

Implicit conversion from [Vector3Compressed](#) to Vector3.

Parameters

<i>q</i>	The Vector3Compressed instance to convert.
----------	--

Returns

The decompressed Vector3 value of the [Vector3Compressed](#) instance.

6.307.2.6 operator Vector3Compressed() [1/2]

```
static implicit operator Vector3Compressed (  
    Vector2 v ) [static]
```

Implicit conversion from Vector2 to [Vector3Compressed](#).

Parameters

<i>v</i>	The Vector2 value to convert.
----------	-------------------------------

Returns

A new [Vector3Compressed](#) instance with the compressed value of the Vector2.

6.307.2.7 operator Vector3Compressed() [2/2]

```
static implicit operator Vector3Compressed (  
    Vector3 v ) [static]
```

Implicit conversion from Vector3 to [Vector3Compressed](#).

Parameters

<i>v</i>	The Vector3 value to convert.
----------	-------------------------------

Returns

A new [Vector3Compressed](#) instance with the compressed value of the Vector3.

6.307.2.8 operator"!=()

```
static bool operator!= (
    Vector3Compressed left,
    Vector3Compressed right ) [static]
```

Inequality operator for [Vector3Compressed](#) struct.

Parameters

<i>left</i>	First Vector3Compressed instance.
<i>right</i>	Second Vector3Compressed instance.

Returns

True if the value of the first [Vector3Compressed](#) instance is not equal to the value of the second [Vector3Compressed](#) instance, otherwise false.

6.307.2.9 operator=="()

```
static bool operator== (
    Vector3Compressed left,
    Vector3Compressed right ) [static]
```

Equality operator for [Vector3Compressed](#) struct.

Parameters

<i>left</i>	First Vector3Compressed instance.
<i>right</i>	Second Vector3Compressed instance.

Returns

True if the value of the first [Vector3Compressed](#) instance is equal to the value of the second [Vector3Compressed](#) instance, otherwise false.

6.307.3 Member Data Documentation

6.307.3.1 xEncoded

```
int xEncoded
```

Encoded value of the x component.

6.307.3.2 yEncoded

```
int yEncoded
```

Encoded value of the y component.

6.307.3.3 zEncoded

```
int zEncoded
```

Encoded value of the z component.

6.307.4 Property Documentation

6.307.4.1 X

```
float X [get], [set]
```

Gets or sets the x component.

6.307.4.2 Y

```
float Y [get], [set]
```

Gets or sets the y component.

6.307.4.3 Z

```
float Z [get], [set]
```

Gets or sets the z component.

6.308 Vector4Compressed Struct Reference

Represents a compressed Vector4 value for network transmission.

Inherits [INetworkStruct](#), and `IEquatable< Vector4Compressed >`.

Public Member Functions

- override bool [Equals](#) (object obj)
Checks if the provided object is a [Vector4Compressed](#) instance and if it's equal to the current [Vector4Compressed](#) instance.
- bool [Equals](#) ([Vector4Compressed](#) other)
Checks if the current [Vector4Compressed](#) instance is equal to the other [Vector4Compressed](#) instance.
- override int [GetHashCode](#) ()
Returns the hash code for the current [Vector4Compressed](#) instance.

Static Public Member Functions

- static implicit [operator Vector4](#) ([Vector4Compressed](#) q)
Implicit conversion from [Vector4Compressed](#) to [Vector4](#).
- static implicit [operator Vector4Compressed](#) ([Vector4](#) v)
Implicit conversion from [Vector4](#) to [Vector4Compressed](#).
- static bool [operator!=](#) ([Vector4Compressed](#) left, [Vector4Compressed](#) right)
Inequality operator for [Vector4Compressed](#) struct.
- static bool [operator==](#) ([Vector4Compressed](#) left, [Vector4Compressed](#) right)
Equality operator for [Vector4Compressed](#) struct.

Public Attributes

- int [wEncoded](#)
Encoded value of the w component.
- int [xEncoded](#)
Encoded value of the x component.
- int [yEncoded](#)
Encoded value of the y component.
- int [zEncoded](#)
Encoded value of the z component.

Properties

- float [W](#) [get, set]
Gets or sets the w component.
- float [X](#) [get, set]
Gets or sets the x component.
- float [Y](#) [get, set]
Gets or sets the y component.
- float [Z](#) [get, set]
Gets or sets the z component.

6.308.1 Detailed Description

Represents a compressed Vector4 value for network transmission.

6.308.2 Member Function Documentation

6.308.2.1 Equals() [1/2]

```
override bool Equals (  
    object obj )
```

Checks if the provided object is a [Vector4Compressed](#) instance and if it's equal to the current [Vector4Compressed](#) instance.

Parameters

<i>obj</i>	The object to compare with the current Vector4Compressed instance.
------------	--

Returns

True if the provided object is a [Vector4Compressed](#) instance and it's equal to the current [Vector4Compressed](#) instance, otherwise false.

6.308.2.2 Equals() [2/2]

```
bool Equals (  
    Vector4Compressed other )
```

Checks if the current [Vector4Compressed](#) instance is equal to the other [Vector4Compressed](#) instance.

Parameters

<i>other</i>	The other Vector4Compressed instance to compare with the current Vector4Compressed instance.
--------------	--

Returns

True if the values of both [Vector4Compressed](#) instances are equal, otherwise false.

6.308.2.3 GetHashCode()

```
override int GetHashCode ( )
```

Returns the hash code for the current [Vector4Compressed](#) instance.

Returns

A hash code for the current [Vector4Compressed](#) instance.

6.308.2.4 operator Vector4()

```
static implicit operator Vector4 (
    Vector4Compressed q ) [static]
```

Implicit conversion from [Vector4Compressed](#) to Vector4.

Parameters

<i>q</i>	The Vector4Compressed instance to convert.
----------	--

Returns

The decompressed Vector4 value of the [Vector4Compressed](#) instance.

6.308.2.5 operator Vector4Compressed()

```
static implicit operator Vector4Compressed (
    Vector4 v ) [static]
```

Implicit conversion from Vector4 to [Vector4Compressed](#).

Parameters

<i>v</i>	The Vector4 value to convert.
----------	-------------------------------

Returns

A new [Vector4Compressed](#) instance with the compressed value of the Vector4.

6.308.2.6 operator"!=()"

```
static bool operator!= (
    Vector4Compressed left,
    Vector4Compressed right ) [static]
```

Inequality operator for [Vector4Compressed](#) struct.

Parameters

<i>left</i>	First Vector4Compressed instance.
<i>right</i>	Second Vector4Compressed instance.

Returns

True if the value of the first [Vector4Compressed](#) instance is not equal to the value of the second [Vector4Compressed](#) instance, otherwise false.

6.308.2.7 operator==()

```
static bool operator== (
    Vector4Compressed left,
    Vector4Compressed right ) [static]
```

Equality operator for [Vector4Compressed](#) struct.

Parameters

<i>left</i>	First Vector4Compressed instance.
<i>right</i>	Second Vector4Compressed instance.

Returns

True if the value of the first [Vector4Compressed](#) instance is equal to the value of the second [Vector4Compressed](#) instance, otherwise false.

6.308.3 Member Data Documentation

6.308.3.1 wEncoded

```
int wEncoded
```

Encoded value of the w component.

6.308.3.2 xEncoded

```
int xEncoded
```

Encoded value of the x component.

6.308.3.3 yEncoded

```
int yEncoded
```

Encoded value of the y component.

6.308.3.4 zEncoded

```
int zEncoded
```

Encoded value of the z component.

6.308.4 Property Documentation**6.308.4.1 W**

```
float W [get], [set]
```

Gets or sets the w component.

6.308.4.2 X

```
float X [get], [set]
```

Gets or sets the x component.

6.308.4.3 Y

```
float Y [get], [set]
```

Gets or sets the y component.

6.308.4.4 Z

```
float Z [get], [set]
```

Gets or sets the z component.

6.309 WarnIfAttribute Class Reference

Editor attribute for adding notices to fields if the condition member evaluates as true. Condition member can be a property, field or method (with a return value).

Inherits [DofAttributeBase](#).

Public Member Functions

- **WarnIfAttribute** (string propertyPath, bool compareToValue, string message, [CompareOperator](#) compare=[CompareOperator.Equal](#))
- **WarnIfAttribute** (string propertyPath, double compareToValue, string message, [CompareOperator](#) compare=[CompareOperator.Equal](#))
- **WarnIfAttribute** (string propertyPath, long compareToValue, string message, [CompareOperator](#) compare=[CompareOperator.Equal](#))
- **WarnIfAttribute** (string propertyPath, string message)

Public Attributes

- bool **AsBox**
- string [Message](#)

The default warning text, when a warning is shown.

Additional Inherited Members

6.309.1 Detailed Description

Editor attribute for adding notices to fields if the condition member evaluates as true. Condition member can be a property, field or method (with a return value).

Value of condition method is converted to a long. Null = 0, False = 0, True = 1, Unity Object = InstanceId

6.309.2 Member Data Documentation

6.309.2.1 Message

```
string Message
```

The default warning text, when a warning is shown.

6.310 WeaverGeneratedAttribute Class Reference

Weaver Generated Attribute

Inherits [Attribute](#).

6.310.1 Detailed Description

Weaver Generated Attribute

Index

- [_128, 61](#)
 - [Data, 61](#)
 - [SIZE, 61](#)
 - [_16, 62](#)
 - [Data, 62](#)
 - [SIZE, 62](#)
 - [_2, 63](#)
 - [Data, 63](#)
 - [SIZE, 63](#)
 - [_256, 63](#)
 - [Data, 64](#)
 - [SIZE, 64](#)
 - [_32, 64](#)
 - [Data, 65](#)
 - [SIZE, 65](#)
 - [_4, 65](#)
 - [Data, 66](#)
 - [SIZE, 66](#)
 - [_512, 66](#)
 - [Data, 67](#)
 - [SIZE, 67](#)
 - [_64, 67](#)
 - [Data, 67](#)
 - [SIZE, 68](#)
 - [_8, 68](#)
 - [Data, 68](#)
 - [SIZE, 68](#)
 - [_debruijnTable](#)
 - [DynamicHeap, 100](#)
 - [_reserved](#)
 - [NetworkObjectHeader, 426](#)
 - [_stats](#)
 - [Simulation, 712](#)
 - [_value0](#)
 - [NetworkObjectTypeId, 448](#)
 - [_value1](#)
 - [NetworkObjectTypeId, 448](#)
- [AABB, 208](#)
 - [AABB, 209](#)
 - [Center, 210](#)
 - [Extents, 210](#)
 - [Max, 210](#)
 - [Min, 210](#)
- [Accept](#)
 - [NetworkRunnerCallbackArgs.ConnectRequest, 561](#)
- [ACCURACY](#)
 - [ReadWriteUtils, 657](#)
- [Acquire](#)
 - [INetworkAssetSource< T >, 166](#)
- [AcquirePrefabInstance](#)
 - [INetworkObjectProvider, 170](#)
- [ActivePlayers](#)
 - [NetworkRunner, 552](#)
 - [Simulation, 713](#)
- [ActorId](#)
 - [NetAddress, 765](#)
- [Add](#)
 - [INetworkDictionary, 168](#)
 - [INetworkLinkedList, 169](#)
 - [NetworkDictionary< K, V >, 351](#)
 - [NetworkLinkedList< T >, 382, 383](#)
 - [SerializableDictionary< TKey, TValue >, 694](#)
 - [SimulationInput.Buffer, 737](#)
- [AddBehaviour< T >](#)
 - [Behaviour, 89](#)
- [AddCallbacks](#)
 - [NetworkRunner, 511](#)
- [AddFirst](#)
 - [NetBitBufferList, 766](#)
- [AddGlobal](#)
 - [NetworkRunner, 511](#)
- [AddInstance](#)
 - [NetworkPrefabTable, 474](#)
- [AdditionalJitter](#)
 - [NetworkSimulationConfiguration, 586](#)
- [AdditionalLoss](#)
 - [NetworkSimulationConfiguration, 587](#)
- [AddLast](#)
 - [NetBitBufferList, 766](#)
- [AddMode](#)
 - [NetworkRunnerUpdaterDefaultInvokeSettings, 568](#)
- [AddOnCompleted](#)
 - [NetworkSceneAsyncOp, 569](#)
- [AddPlayerAreaOfInterest](#)
 - [NetworkRunner, 511](#)
- [Address](#)
 - [NetConfig, 772](#)
 - [Ptr, 643](#)
 - [StartGameArgs, 777](#)
- [AddSceneRef](#)
 - [NetworkSceneInfo, 576](#)
- [AddSource](#)
 - [NetworkPrefabTable, 474](#)
- [AddTicks](#)
 - [TickAccumulator, 795](#)
- [AddTime](#)
 - [TickAccumulator, 795](#)

- After
 - Fusion, [54](#)
- AfterAllTicks
 - IAfterAllTicks, [149](#)
- AfterClientPredictionReset
 - IAfterClientPredictionReset, [150](#)
- AfterHostMigration
 - IAfterHostMigration, [151](#)
- AfterRender
 - IAfterRender, [151](#)
- AfterSimulation
 - Simulation, [705](#)
- AfterSpawned
 - IAfterSpawned, [152](#)
- AfterTick
 - HitboxManager, [130](#)
 - IAfterTick, [152](#)
- AfterUpdate
 - HitboxManager, [130](#)
 - IAfterUpdate, [153](#)
 - Simulation, [705](#)
- ALIGNMENT
 - NetworkId, [372](#)
 - NetworkObjectGuid, [419](#)
 - NetworkObjectNestingKey, [434](#)
 - NetworkObjectTypeId, [449](#)
 - NetworkPrefabId, [460](#)
 - NetworkPrefabRef, [470](#)
 - Tick, [791](#)
- ALL
 - AuthorityMasks, [87](#)
- All
 - Fusion, [49](#)
- Allocate
 - DynamicHeapInstance, [101](#)
 - SimulationMessage, [744](#)
- AllocateArray< T >
 - DynamicHeapInstance, [101](#)
- AllocateArrayPointers< T >
 - DynamicHeapInstance, [102](#)
- AllocateTracked< T >
 - DynamicHeapInstance, [102](#)
- AllocateTrackedArray< T >
 - DynamicHeapInstance, [103](#)
- AllocateTrackedArrayPointers< T >
 - DynamicHeapInstance, [103](#)
- Allocator, [69](#)
 - BUCKET_COUNT, [70](#)
 - BUCKET_INVALID, [70](#)
 - HEAP_ALIGNMENT, [70](#)
 - REPLICATE_WORD_ALIGN, [70](#)
 - REPLICATE_WORD_SHIFT, [71](#)
 - REPLICATE_WORD_SIZE, [71](#)
- Allocator.Config, [71](#)
 - BlockByteSize, [75](#)
 - BlockCount, [74](#)
 - BlockShift, [74](#)
 - BlockWordCount, [75](#)
 - Config, [72](#)
 - DEFAULT_BLOCK_COUNT, [74](#)
 - DEFAULT_BLOCK_SHIFT, [74](#)
 - Equals, [72](#), [73](#)
 - GetHashCode, [73](#)
 - GlobalsSize, [74](#)
 - HeapSizeAllocated, [75](#)
 - HeapSizeUsable, [75](#)
 - SIZE, [74](#)
 - ToString, [73](#)
- AllowStateAuthorityOverride
 - Fusion, [43](#)
- Alpha
 - NetworkBehaviourBufferInterpolator, [308](#)
 - Query, [225](#)
 - QueryParams, [227](#)
 - TickAccumulator, [795](#)
- AlreadyRunning
 - Fusion, [51](#)
- Angle, [75](#)
 - Clamp, [77](#)
 - Equals, [77](#), [78](#)
 - GetHashCode, [78](#)
 - Lerp, [78](#)
 - Max, [78](#)
 - Min, [79](#)
 - NetworkBehaviourBufferInterpolator, [299](#), [300](#)
 - operator Angle, [79](#), [80](#)
 - operator double, [80](#)
 - operator float, [80](#)
 - operator !=, [81](#)
 - operator <, [82](#)
 - operator <=, [82](#)
 - operator >, [83](#)
 - operator >=, [84](#)
 - operator +, [81](#)
 - operator -, [81](#)
 - operator ==, [83](#)
 - SIZE, [84](#)
 - ToString, [84](#)
- Animator
 - NetworkMecanimAnimator, [397](#)
- Any
 - NetAddress, [762](#)
- AnyIPv6
 - NetAddress, [763](#)
- ApplyTiming
 - NetworkMecanimAnimator, [397](#)
- AreaOfInterest
 - Fusion, [43](#)
- AreaOfInterestEnabled
 - SimulationConfig, [730](#)
- AreaOfInterestOverride
 - NetworkTRSPData, [627](#)
- AreaOfInterestPlayerCount
 - NetworkObjectStats, [442](#)
- AsCustom
 - NetworkObjectTypeId, [449](#)

- AsIndex
 - NetworkPrefabId, 461
 - PlayerRef, 636
 - SceneRef, 692
- AsInternalStructId
 - NetworkObjectTypeId, 450
- AsPathHash
 - SceneRef, 692
- AspectRatio
 - NormalizedRectAttribute, 630
- AsPrefabId
 - NetworkObjectTypeId, 450
- AsSceneObjectId
 - NetworkObjectTypeId, 450
- AssembliesToWeave
 - NetworkProjectConfig, 486
- AssetGuid
 - INetworkPrefabSource, 171
- AssetObject, 84
- Assign
 - NetworkString< TSize >, 596
- AssignInputAuthority
 - NetworkObject, 400
- Attach
 - NetworkRunner, 511, 512
- AuthenticationTicketExpired
 - Fusion, 51
- AuthenticationValues
 - NetworkRunner, 552
- AuthorityMasks, 87
 - ALL, 87
 - INPUT, 87
 - NONE, 87
 - PROXY, 88
 - STATE, 88
- AuthValues
 - StartGameArgs, 778
- Auto
 - Fusion, 46
- AutoHostOrClient
 - Fusion, 42
- AutoUpdateAreaOfInterestOverride
 - NetworkTransform, 623
- Available
 - TickRate, 804
- Awaiter
 - NetworkSceneAsyncOp.Awaiter, 573
 - NetworkSpawnOp.Awaiter, 591
- Awake
 - NetworkObject, 401
- Before
 - Fusion, 54
- BeforeAllTicks
 - HitboxManager, 131
 - IBeforeAllTicks, 155
- BeforeClientPredictionReset
 - IBeforeClientPredictionReset, 156
- BeforeCopyPreviousState
 - IBeforeCopyPreviousState, 156
- BeforeFirstTick
 - Simulation, 705
- BeforeHitboxRegistration
 - IBeforeHitboxRegistration, 157
- BeforeSimulation
 - Simulation, 705
- BeforeTick
 - IBeforeTick, 158
- BeforeUpdate
 - IBeforeUpdate, 158
 - Simulation, 706
- Behaviour, 88
 - AddBehaviour< T >, 89
 - DestroyBehaviour, 89
 - GetBehaviour< T >, 89
 - NetworkBehaviourBufferInterpolator, 308
 - NetworkBehaviourId, 312
 - RpcHeader, 675
 - TryGetBehaviour< T >, 89
- BehaviourCount
 - NetworkObjectHeader, 426
- BehaviourMeta
 - NetworkProjectConfigAsset, 492
- BehaviourStats, 90
 - FixedUpdateExecutionTime, 90
 - FixedUpdateInvocations, 90
 - RenderExecutionTime, 91
 - RenderInvocations, 91
- Bits
 - NetworkButtons, 344
- BLOCK_SIZE
 - NetworkId, 372
- BlockByteSize
 - Allocator.Config, 75
- BlockCount
 - Allocator.Config, 74
- BlockShift
 - Allocator.Config, 74
- BlockWordCount
 - Allocator.Config, 75
- Bool
 - NetworkBehaviourBufferInterpolator, 300
- Bounds
 - BVHNodeDrawInfo, 216
- Box
 - Fusion, 42
- Box2D
 - Fusion.LagCompensation, 57
- BoxExtents
 - ColliderDrawInfo, 217
 - Hitbox, 126
- BoxOverlapQuery, 210
 - BoxOverlapQuery, 211
 - Center, 212
 - Check, 212
 - Extents, 212
 - Rotation, 212

- BoxOverlapQueryParams, 213
 - BoxOverlapQueryParams, 213
 - Center, 214
 - Extents, 214
 - QueryParams, 214
 - Rotation, 214
 - StaticHitsCapacity, 214
- BroadRadius
 - HitboxRoot, 146
- BUCKET_COUNT
 - Allocator, 70
- BUCKET_INVALID
 - Allocator, 70
- Buffer
 - SimulationInput.Buffer, 737
- BuildType
 - NetworkRunner, 552
- BuildTypes
 - NetworkProjectConfig, 486
 - NetworkRunner, 510
- BVHDepth
 - HitboxManager, 142
- BVHDraw, 215
 - GetEnumerator, 215
 - LagCompensationDraw, 221
- BVHNodeDrawInfo, 215
 - Bounds, 216
 - Depth, 216
 - MaxDepth, 216
- BVHNodes
 - HitboxManager, 142
- ByteCount
 - NetworkObjectHeader, 428
- Bytes
 - Fusion, 52
- CachedStaticCollidersSize
 - LagCompensationSettings, 238
- CanReceiveRenderCallback
 - SimulationBehaviour, 724
- CanReceiveSimulationCallback
 - SimulationBehaviour, 724
- CanSpawn
 - NetworkRunner, 553
- Capacity
 - FixedBufferPropertyAttribute, 117
 - NetworkDictionary< K, V >, 355
 - NetworkDictionaryReadOnly< K, V >, 359
 - NetworkLinkedList< T >, 386
 - NetworkLinkedListReadOnly< T >, 391
 - NetworkString< TSize >, 618
 - SimulationMessage, 750
- CapacityAttribute, 91
 - CapacityAttribute, 91
 - Length, 92
- Capsule
 - Fusion, 42
- CapsuleHeight
 - ColliderDrawInfo, 217
- Hitbox, 126
- CapsuleRadius
 - Hitbox, 126
- CELL_SIZE
 - Simulation.AreaOfInterest, 722
- Center
 - AABB, 210
 - BoxOverlapQuery, 212
 - BoxOverlapQueryParams, 214
 - SphereOverlapQuery, 236
 - SphereOverlapQueryParams, 237
- Changed
 - NetworkBehaviour.ChangeDetector.Enumerable, 285
- ChangedTick
 - NetworkBehaviour, 279
- Channel
 - RpcAttribute, 671
 - RpcInfo, 678
- Check
 - BoxOverlapQuery, 212
 - Query, 224
 - RaycastQuery, 230
 - SphereOverlapQuery, 235
- CheckNetworkedPropertiesBeingEmpty
 - NetworkProjectConfig, 486
- CheckRpcAttributeUsage
 - NetworkProjectConfig, 486
- Clamp
 - Angle, 77
- ClampSelection
 - TickRate, 800
- Clear
 - FixedArray< T >, 109
 - NetworkArray< T >, 250
 - NetworkDictionary< K, V >, 352
 - NetworkLinkedList< T >, 383
 - NetworkPrefabTable, 474
 - SerializableDictionary< TKey, TValue >, 694
 - SimulationInput, 735
 - SimulationInput.Buffer, 738
- ClearPlayerAreaOfInterest
 - NetworkRunner, 512
- Client
 - Fusion, 42, 51
 - TickRate, 804
 - TickRate.Resolved, 806
 - TickRate.Selection, 808
- ClientSend
 - TickRate.Resolved, 806
- ClientSendDelta
 - TickRate.Resolved, 807
- ClientSendIndex
 - TickRate.Selection, 808
- ClientSendIndexOutOfRange
 - TickRate, 799
- ClientServer
 - Fusion, 50, 52

- ClientTickDelta
 - TickRate.Resolved, [807](#)
- ClientTickStride
 - TickRate.Resolved, [807](#)
- ClientToClientWithServerProxy
 - NetworkConfiguration, [345](#)
- ClientToServer
 - NetworkConfiguration, [345](#)
- Clone
 - NetworkSimulationConfiguration, [586](#)
 - SimulationMessage, [745](#)
- CloneArray< T >
 - NetworkBehaviourUtils, [315](#)
- CollectGarbage
 - DynamicHeap, [98](#)
- CollectGarbageDelegate
 - DynamicHeap, [99](#)
- Collider
 - LagCompensatedHit, [207](#)
- Collider2D
 - LagCompensatedHit, [207](#)
- ColliderDrawInfo, [216](#)
 - BoxExtents, [217](#)
 - CapsuleHeight, [217](#)
 - LocalToWorldMatrix, [217](#)
 - Offset, [217](#)
 - Radius, [217](#)
 - Type, [218](#)
- ColliderIndex
 - Hitbox, [127](#)
- Compare
 - NetworkObjectSortKeyComparer, [439](#)
 - NetworkString< TSize >, [596](#), [597](#)
 - Tick.RelationalComparer, [793](#)
- Compare< TOtherSize >
 - NetworkString< TSize >, [597](#), [598](#)
- CompareOperator
 - Fusion, [40](#)
- Comparer
 - NetworkId, [373](#)
 - NetworkObjectTypeId, [450](#)
 - PlayerRef, [636](#)
- CompareTo
 - NetworkId, [369](#)
 - NetworkObjectGuid, [415](#)
 - NetworkPrefabId, [458](#)
 - NetworkPrefabRef, [466](#)
 - Tick, [786](#)
- Completed
 - IAsyncOperation, [154](#)
- Compress
 - FloatUtils, [122](#)
- Config
 - Allocator.Config, [72](#)
 - HitboxRoot, [146](#)
 - NetworkProjectConfigAsset, [492](#)
 - NetworkRunner, [553](#)
 - Simulation, [713](#)
 - StartGameArgs, [778](#)
- ConfigFlags
 - HitboxRoot, [144](#)
- ConnectAttempts
 - NetConfig, [772](#)
 - NetworkConfiguration, [346](#)
- ConnectInterval
 - NetConfig, [772](#)
 - NetworkConfiguration, [346](#)
- ConnectionDefaultRtt
 - NetConfig, [772](#)
 - NetworkConfiguration, [347](#)
- ConnectionGroups
 - NetConfig, [772](#)
- ConnectionPingInterval
 - NetConfig, [773](#)
 - NetworkConfiguration, [347](#)
- ConnectionRefused
 - Fusion, [51](#)
- ConnectionSendBuffers
 - NetConfig, [773](#)
- ConnectionShutdownTime
 - NetConfig, [773](#)
 - NetworkConfiguration, [346](#)
- ConnectionsPerGroup
 - NetConfig, [775](#)
- ConnectionTimeout
 - Fusion, [51](#)
 - NetConfig, [773](#)
 - NetworkConfiguration, [346](#)
- ConnectionToken
 - StartGameArgs, [778](#)
- ConnectionType
 - Fusion, [41](#)
- ConsumeTick
 - TickAccumulator, [796](#)
- Contains
 - NetworkLinkedList< T >, [383](#)
 - NetworkLinkedListReadOnly< T >, [389](#)
 - NetworkPrefabTable, [475](#)
 - NetworkString< TSize >, [598](#), [599](#)
 - SimulationInput.Buffer, [738](#)
- Contains< TOtherSize >
 - NetworkString< TSize >, [600](#)
- ContainsKey
 - NetworkDictionary< K, V >, [352](#)
 - SerializableDictionary< TKey, TValue >, [695](#)
- ContainsValue
 - NetworkDictionary< K, V >, [352](#)
- ConterMask
 - Fusion, [44](#)
- ContinueWhenAll
 - TaskManager, [85](#)
- Convert< T >
 - NetworkInput, [375](#)
- CopyBackingFieldsToState
 - NetworkBehaviour, [262](#)
- CopyFrom

- FixedArray< T >, 109, 110
- NetworkArray< T >, 251
- SimulationInput, 735
- CopyFromNetworkArray< T >
 - NetworkBehaviourUtils, 316
- CopyFromNetworkDictionary< D, K, V >
 - NetworkBehaviourUtils, 316
- CopyFromNetworkList< T >
 - NetworkBehaviourUtils, 317
- CopySortedTo
 - SimulationInput.Buffer, 738
- CopyStateFrom
 - NetworkBehaviour, 263
 - NetworkObject, 401
- CopyStateToBackingFields
 - NetworkBehaviour, 263
- CopyTo
 - FixedArray< T >, 110
 - NetworkArray< T >, 252
- Count
 - Fusion, 52
 - NetworkDictionary< K, V >, 355
 - NetworkDictionaryReadOnly< K, V >, 359
 - NetworkLinkedList< T >, 386
 - NetworkLinkedListReadOnly< T >, 391
 - SerializableDictionary< TKey, TValue >, 697
 - SimulationInput.Buffer, 740
 - TickRate, 804
- Create
 - NetCommandHeader, 770
 - NetworkSimulationConfiguration, 586
 - RpcHeader, 673
- Create< T >
 - FixedArray< T >, 111
- Create< TActual, TAdapted >
 - FixedArray< T >, 111
- Create< TKey, TValue >
 - SerializableDictionary< TKey, TValue >, 695
- CreateFromFieldSequence< T >
 - FixedArray< T >, 112
- CreateFromIpPort
 - NetAddress, 763
- CreateFromSeconds
 - TickTimer, 810
- CreateFromTicks
 - TickTimer, 810
- Current
 - FixedArray< T >.Enumerator, 115
 - NetworkArray< T >.Enumerator, 256
 - NetworkBehaviour.ChangeDetector.Enumerator, 287
 - NetworkDictionary< K, V >.Enumerator, 357
 - NetworkLinkedList< T >.Enumerator, 387
- CurrentConnectionType
 - NetworkRunner, 553
- CurrentTypeId
 - NetworkProjectConfig, 486
- CurrentVersion
 - NetworkProjectConfig, 486
- Custom
 - Fusion, 45, 50
- CustomAuthenticationFailed
 - Fusion, 51
- CustomCallbackInterfaces
 - StartGameArgs, 778
- CustomLobbyName
 - StartGameArgs, 778
- CustomPhotonAppSettings
 - StartGameArgs, 778
- CustomPublicAddress
 - StartGameArgs, 779
- CustomSTUNServer
 - StartGameArgs, 779
- Data
 - _128, 61
 - _16, 62
 - _2, 63
 - _256, 64
 - _32, 65
 - _4, 66
 - _512, 67
 - _64, 67
 - _8, 68
 - NetworkInput, 377
 - NetworkPrefabAcquireContext, 455
 - NetworkPrefabInfo, 463
 - NetworkTRSP, 625
 - SimulationInput, 735
- DataConsistency
 - SimulationConfig, 728
- DataProperty
 - IUnityValueSurrogate< T >, 187
 - UnityArraySurrogate< T, ReaderWriter >, 189
 - UnityDictionarySurrogate< KeyType, KeyReader-Writer, ValueType, ValueReaderWriter >, 191
 - UnityLinkedListSurrogate< T, ReaderWriter >, 193
 - UnityValueSurrogate< T, TReaderWriter >, 197
- Debug
 - NetworkRunner, 510
- Decompress
 - FloatUtils, 122
- Default
 - HitboxRoot, 144
 - NetworkedAttribute, 360
 - NetworkPrefabTableOptions, 481
- DEFAULT_ACCURACY
 - FloatUtils, 123
- DEFAULT_BLOCK_COUNT
 - Allocator.Config, 74
- DEFAULT_BLOCK_SHIFT
 - Allocator.Config, 74
- DefaultForPropertyAttribute, 92
 - DefaultForPropertyAttribute, 92
 - PropertyName, 93
 - WordCount, 93
 - WordOffset, 93

- DefaultMtu
 - NetConfig, 773
- DefaultResourceName
 - NetworkProjectConfig, 487
- Defaults
 - NetConfig, 775
- Degrees
 - Fusion, 52
- DegreesPerSecond
 - Fusion, 52
- DelayMax
 - NetworkSimulationConfiguration, 587
- DelayMin
 - NetworkSimulationConfiguration, 587
- DelayPeriod
 - NetworkSimulationConfiguration, 587
- DelayShape
 - NetworkSimulationConfiguration, 587
- DelayThreshold
 - NetworkSimulationConfiguration, 587
- Delegate
 - RpcInvokeData, 679
- DeltaTime
 - NetworkRunner, 553
 - Simulation, 713
- Depth
 - BVHNodeDrawInfo, 216
- Description
 - INetworkAssetSource< T >, 167
- Deserialize
 - NetworkProjectConfig, 484
- Despawn
 - NetworkRunner, 512
- Despawned
 - IDespawned, 159
 - NetworkBehaviour, 263
- DestroyBehaviour
 - Behaviour, 89
- DestroySingleton< T >
 - NetworkRunner, 513
- DestroyWhenStateAuthorityLeaves
 - Fusion, 43
- DetectChanges
 - NetworkBehaviour.ChangeDetector, 284
- Direct
 - Fusion, 41
- Direction
 - RaycastQuery, 231
 - RaycastQueryParams, 233
- DisableNATPunchthrough
 - StartGameArgs, 779
- DisableSharedModelInterpolation
 - NetworkTransform, 622
- Disconnect
 - NetworkRunner, 513
- DisconnectedByPluginLogic
 - Fusion, 50
- DisplayAsEnumAttribute, 93
- Dispose
 - FixedArray< T >.Enumerator, 115
 - NetworkArray< T >.Enumerator, 256
 - NetworkDictionary< K, V >.Enumerator, 356
 - NetworkLinkedList< T >.Enumerator, 387
 - SimulationBehaviourListScope, 727
- Distance
 - LagCompensatedHit, 207
- DolfAttributeBase, 94
- DontDestroyOnLoad
 - Fusion, 43, 45
 - NetworkPrefabAcquireContext, 455
- DrawGizmos
 - Hitbox, 126
 - HitboxRoot, 144
- DrawIfAttribute, 94
 - DrawIfAttribute, 95, 96
 - Mode, 96
- DrawInfo
 - HitboxManager, 142
- DynamicHeap, 96
 - _debruijnTable, 100
 - CollectGarbage, 98
 - CollectGarbageDelegate, 99
 - Free, 99
 - SetForcedAlive< T >, 99
- DynamicHeap.Ignore, 100
- DynamicHeap.Instance, 100
 - Allocate, 101
 - AllocateArray< T >, 101
 - AllocateArrayPointers< T >, 102
 - AllocateTracked< T >, 102
 - AllocateTrackedArray< T >, 103
 - AllocateTrackedArrayPointers< T >, 103
 - DynamicHeap.Instance, 101
 - Free, 105
- DynamicWordCount
 - NetworkBehaviour, 279
 - NetworkMecanimAnimator, 398
- ELEMENT_WORDS
 - NetworkLinkedList< T >, 385
 - NetworkLinkedList.ReadOnly< T >, 390
- Empty
 - NetworkObjectGuid, 420
 - NetworkPrefabRef, 471
- EnableAutoUpdate
 - HostMigrationConfig, 148
- EnableClientSessionCreation
 - StartGameArgs, 779
- Enabled
 - LagCompensationSettings, 239
 - NetworkSimulationConfiguration, 588
- EndsWith
 - NetworkString< TSize >, 601
- EndsWith< TOtherSize >
 - NetworkString< TSize >, 601
- EngineDelta
 - SimulationStats, 757

- EnqueueIncompleteSynchronousSpawns
 - NetworkProjectConfig, [487](#)
- EnsureRootComponentExists< T, TStopOn >
 - NestedComponentUtilities, [242](#)
- EnsureRunnerScenelsActive
 - NetworkRunner, [513](#)
- EntryKeyPropertyPath
 - SerializableDictionary< TKey, TValue >, [697](#)
- Enumerator
 - FixedArray< T >.Enumerator, [114](#)
 - NetworkArray< T >.Enumerator, [255](#)
- Equal
 - Fusion, [41](#)
- Equals
 - Allocator.Config, [72](#), [73](#)
 - Angle, [77](#), [78](#)
 - FloatCompressed, [119](#)
 - NetworkBehaviourId, [310](#), [311](#)
 - NetworkBool, [333](#)
 - NetworkButtons, [336](#)
 - NetworkId, [369](#), [370](#)
 - NetworkId.EqualityComparer, [374](#)
 - NetworkLoadSceneParameters, [392](#), [393](#)
 - NetworkObjectGuid, [415](#), [416](#)
 - NetworkObjectGuid.EqualityComparer, [420](#)
 - NetworkObjectHeader, [422](#), [423](#)
 - NetworkObjectNestingKey, [432](#), [433](#)
 - NetworkObjectNestingKey.EqualityComparer, [435](#)
 - NetworkObjectTypeId, [445](#)
 - NetworkObjectTypeId.EqualityComparer, [452](#)
 - NetworkPrefabId, [458](#)
 - NetworkPrefabId.EqualityComparer, [462](#)
 - NetworkPrefabRef, [467](#)
 - NetworkPrefabRef.EqualityComparer, [472](#)
 - NetworkRunnerUpdaterDefaultInvokeSettings, [566](#)
 - NetworkSceneInfo, [576](#)
 - NetworkSceneLoadId, [580](#), [581](#)
 - NetworkSceneObjectId, [582](#), [583](#)
 - NetworkString< TSize >, [602](#), [603](#)
 - PlayerRef, [632](#)
 - Ptr, [640](#)
 - Ptr.EqualityComparer, [644](#)
 - QuaternionCompressed, [646](#)
 - SceneRef, [686](#), [687](#)
 - Tick, [786](#), [787](#)
 - Tick.EqualityComparer, [792](#)
 - Vector2Compressed, [825](#)
 - Vector3Compressed, [829](#)
 - Vector4Compressed, [835](#)
- Equals< TOtherSize >
 - NetworkString< TSize >, [603](#), [604](#)
- Error
 - Fusion, [50](#)
 - IAsyncOperation, [154](#)
 - NetworkSceneAsyncOp, [572](#)
 - TickRate, [799](#)
- ErrorMessage
 - StartGameResult, [783](#)
- Eventual
 - SimulationConfig, [728](#)
- ExecutionOrder
 - NetworkProjectConfigAsset.SerializableSimulationBehaviourMeta, [493](#)
- Exists
 - NetworkRunner, [514](#)
- ExpansionFactor
 - LagCompensationSettings, [239](#)
- Expired
 - TickTimer, [811](#)
- ExpiredOrNotRunning
 - TickTimer, [811](#)
- Extents
 - AABB, [210](#)
 - BoxOverlapQuery, [212](#)
 - BoxOverlapQueryParams, [214](#)
- ExtraInterpolationOffset
 - TimeSyncConfiguration, [813](#)
- ExtraSimulationOffset
 - TimeSyncConfiguration, [814](#)
- Failed
 - Fusion, [43](#)
- FailedClientCantSpawn
 - Fusion, [45](#)
- FailedLocalPlayerNotYetSet
 - Fusion, [45](#)
- FailedToCreateInstance
 - Fusion, [45](#)
- FailedToLoadPrefabSynchronously
 - Fusion, [45](#)
- FieldsMask
 - FieldsMask< T >, [106](#), [107](#)
- FieldsMask< T >, [105](#)
 - FieldsMask, [106](#), [107](#)
 - operator Mask256, [107](#)
- FindObject
 - NetworkRunner, [514](#)
- FindObjectsOfTypeInOrder< T >
 - NestedComponentUtilities, [243](#)
- FindObjectsOfTypeInOrder< T, TCast >
 - NestedComponentUtilities, [244](#)
- FirstChild
 - Fusion, [54](#)
- FixedArray
 - FixedArray< T >, [109](#)
- FixedArray< T >, [107](#)
 - Clear, [109](#)
 - CopyFrom, [109](#), [110](#)
 - CopyTo, [110](#)
 - Create< T >, [111](#)
 - Create< TActual, TAdapted >, [111](#)
 - CreateFromFieldSequence< T >, [112](#)
 - FixedArray, [109](#)
 - GetEnumerator, [112](#)
 - IndexOf< T >, [112](#)
 - Length, [113](#)
 - this[int index], [114](#)

- ToArray, [113](#)
- ToListString, [113](#)
- ToString, [113](#)
- FixedArray< T >.Enumerator, [114](#)
 - Current, [115](#)
 - Dispose, [115](#)
 - Enumerator, [114](#)
 - MoveNext, [115](#)
 - Reset, [115](#)
- FixedBufferPropertyAttribute, [116](#)
 - Capacity, [117](#)
 - FixedBufferPropertyAttribute, [116](#)
 - SurrogateType, [117](#)
 - Type, [117](#)
- FixedStorage, [117](#)
 - GetWordCount< T >, [117](#)
- FixedUpdateExecutionTime
 - BehaviourStats, [90](#)
- FixedUpdateInvocations
 - BehaviourStats, [90](#)
- FixedUpdateNetwork
 - NetworkBehaviour, [263](#)
 - SimulationBehaviour, [724](#)
- FLAG_ADDRESSABLE
 - SceneRef, [691](#)
- FLAG_DUMMY
 - SimulationMessage, [750](#)
- FLAG_INTERNAL
 - SimulationMessage, [750](#)
- FLAG_NOT_TICK_ALIGNED
 - SimulationMessage, [750](#)
- FLAG_REMOTE
 - SimulationMessage, [750](#)
- FLAG_STATIC
 - SimulationMessage, [751](#)
- FLAG_TARGET_PLAYER
 - SimulationMessage, [751](#)
- FLAG_TARGET_SERVER
 - SimulationMessage, [751](#)
- FLAG_UNRELIABLE
 - SimulationMessage, [751](#)
- FLAG_USER_FLAGS_START
 - SimulationMessage, [751](#)
- FLAG_USER_MESSAGE
 - SimulationMessage, [751](#)
- Flags
 - NetworkObject, [405](#)
 - NetworkObjectHeader, [426](#)
 - SimulationMessage, [752](#)
- FLAGS_RESERVED
 - SimulationMessage, [752](#)
- FLAGS_RESERVED_BITS
 - SimulationMessage, [752](#)
- Float
 - NetworkBehaviourBufferInterpolator, [302](#)
- FloatCompressed, [118](#)
 - Equals, [119](#)
 - GetHashCode, [119](#)
 - operator float, [119](#)
 - operator FloatCompressed, [120](#)
 - operator!=, [120](#)
 - operator==, [121](#)
 - valueEncoded, [121](#)
- FloatUtils, [121](#)
 - Compress, [122](#)
 - Decompress, [122](#)
 - DEFAULT_ACCURACY, [123](#)
- Forward
 - Fusion, [51](#)
- ForwardSteps
 - SimulationStats, [757](#)
- Frames
 - Fusion, [52](#)
- FramesPerSecond
 - Fusion, [52](#)
- Free
 - DynamicHeap, [99](#)
 - DynamicHeapInstance, [105](#)
- From
 - Fusion, [46](#)
 - NetworkBehaviourBufferInterpolator, [309](#)
- FromActorId
 - NetAddress, [764](#)
- FromAsyncOperation
 - NetworkSceneAsyncOp, [569](#)
- FromCompleted
 - NetworkSceneAsyncOp, [570](#)
- FromCoroutine
 - NetworkSceneAsyncOp, [570](#)
- FromCustom
 - NetworkObjectTypeId, [446](#)
- FromEncoded
 - PlayerRef, [632](#)
- FromError
 - NetworkSceneAsyncOp, [571](#)
- FromIndex
 - NetworkPrefabId, [458](#)
 - PlayerRef, [633](#)
 - SceneRef, [687](#)
- FromLocal
 - RpcInfo, [677](#)
- FromMessage
 - RpcInfo, [677](#)
- FromPath
 - SceneRef, [687](#)
- FromPrefabId
 - NetworkObjectTypeId, [446](#)
- FromRaw
 - NetworkPrefabId, [459](#)
 - SceneRef, [688](#)
- FromSceneRefAndObjectIndex
 - NetworkObjectTypeId, [446](#)
- FromStruct
 - NetworkObjectTypeId, [447](#)
- FromTask
 - NetworkSceneAsyncOp, [571](#)

- Full
 - SimulationConfig, 728
 - SimulationInput.Buffer, 740
- FullCone
 - Fusion.Sockets.Stun, 60
- Fusion, 29
 - After, 54
 - All, 49
 - AllowStateAuthorityOverride, 43
 - AlreadyRunning, 51
 - AreaOfInterest, 43
 - AuthenticationTicketExpired, 51
 - Auto, 46
 - AutoHostOrClient, 42
 - Before, 54
 - Box, 42
 - Bytes, 52
 - Capsule, 42
 - Client, 42, 51
 - ClientServer, 50, 52
 - CompareOperator, 40
 - ConnectionRefused, 51
 - ConnectionTimeout, 51
 - ConnectionType, 41
 - ConterMask, 44
 - Count, 52
 - Custom, 45, 50
 - CustomAuthenticationFailed, 51
 - Degrees, 52
 - DegreesPerSecond, 52
 - DestroyWhenStateAuthorityLeaves, 43
 - Direct, 41
 - DisconnectedByPluginLogic, 50
 - DontDestroyOnLoad, 43, 45
 - Equal, 41
 - Error, 50
 - Failed, 43
 - FailedClientCantSpawn, 45
 - FailedLocalPlayerNotYetSet, 45
 - FailedToCreateInstance, 45
 - FailedToLoadPrefabSynchronously, 45
 - FirstChild, 54
 - Forward, 51
 - Frames, 52
 - FramesPerSecond, 52
 - From, 46
 - GameClosed, 50
 - GameIdAlreadyExists, 50
 - GameIsFull, 51
 - GameMode, 41
 - GameNotFound, 50
 - GlobalObjectInterest, 43
 - Greater, 41
 - GreaterOrEqual, 41
 - HasMainNetworkTRSP, 43
 - High, 46
 - HitboxTypes, 42
 - HitOptions, 42
 - Host, 42, 51
 - HostMigration, 51
 - Ignore, 43
 - IgnoreInputAuthority, 42
 - IncludeBox2D, 42
 - IncludePhysX, 42
 - IncompatibleConfiguration, 50
 - Initial, 44
 - InProgress, 44
 - InputAuthority, 49
 - InsufficientSourceAuthority, 47, 48
 - InsufficientTargetAuthority, 47
 - InternalStruct, 45
 - Interpolated, 46
 - Invalid, 45, 50
 - InvalidArguments, 51
 - InvalidAuthentication, 51
 - InvalidRegion, 50
 - Invoked, 47
 - IsZero, 41
 - Kilobytes, 52
 - LastChild, 54
 - Latest, 46
 - Less, 41
 - LessOrEqual, 41
 - LoadError, 44
 - Local, 46
 - Low, 46
 - Lowest, 46
 - MaskBroadcast, 48
 - MaskCulled, 48
 - MaskNotSent, 48
 - MaskSent, 48
 - MaskVersion, 43
 - MasterClientObject, 43
 - MaxCcuReached, 50
 - Medium, 46
 - Megabytes, 52
 - MilliSecs, 52
 - Multiplier, 52
 - NetworkObjectAcquireResult, 42
 - NetworkObjectFlags, 43
 - NetworkObjectHeaderFlags, 43
 - NetworkObjectSpawnDelegate, 54
 - NetworkPrefabTableGetPrefabResult, 44
 - NetworkSceneInfoChangeSource, 44
 - NetworkSceneInfoDefaultFlags, 44
 - NetworkSpawnFlags, 44
 - NetworkSpawnStatus, 45
 - NetworkTypeIdKind, 45
 - NoActiveConnections, 48
 - None, 41–44, 48, 52
 - Normalized, 52
 - NormalizedPercentage, 52
 - NotCulled, 48
 - NotEqual, 41
 - NotFound, 44
 - NotInvokableDuringResim, 47, 48

- NotInvokableLocally, [47](#)
- NotSentBroadcastNoActiveConnections, [48](#)
- NotSentBroadcastNoConfirmedNorInterested-
Clients, [48](#)
- NotSentTargetClientNotAvailable, [48](#)
- NotSentTargetObjectNotConfirmed, [48](#)
- NotSentTargetObjectNotInPlayerInterest, [48](#)
- NotZero, [41](#)
- Ok, [50](#)
- OperationCanceled, [51](#)
- OperationTimeout, [51](#)
- Packets, [52](#)
- PageSizes, [45](#)
- Percentage, [52](#)
- PerSecond, [52](#)
- PhotonCloudTimeout, [51](#)
- Player, [46](#)
- Prefab, [45](#)
- PriorityLevel, [46](#)
- Proxies, [49](#)
- Queued, [45](#)
- Radians, [52](#)
- RadiansPerSecond, [52](#)
- Relayed, [41](#)
- Reliable, [47](#)
- Remote, [44](#), [46](#), [49](#)
- RenderSource, [46](#)
- RenderTimeframe, [46](#)
- Resimulate, [51](#)
- Retry, [43](#)
- RpcChannel, [47](#)
- RpcHostMode, [47](#)
- RpcInvokeDelegate, [54](#)
- RpcLocalInvokeResult, [47](#)
- RpcSendCullResult, [47](#)
- RpcSendMessageResult, [48](#)
- RpcSources, [48](#)
- RpcStaticInvokeDelegate, [54](#)
- RpcTargets, [49](#)
- RpcTargetStatus, [49](#)
- SceneCountMask, [44](#)
- SceneObject, [45](#)
- ScriptHeaderBackColor, [49](#)
- ScriptHeaderIcon, [50](#)
- Seconds, [52](#)
- Self, [49](#)
- SentBroadcast, [48](#)
- SentToServerForForwarding, [48](#)
- SentToTargetClient, [48](#)
- Server, [41](#), [51](#)
- ServerInRoom, [50](#)
- SessionLobby, [50](#)
- Shared, [41](#), [50](#), [52](#)
- SharedModeStateAuthLocalPlayer, [45](#)
- SharedModeStateAuthMasterClient, [45](#)
- ShutdownReason, [50](#)
- SimulationModes, [51](#)
- SimulationStages, [51](#)
- Single, [41](#)
- SourcesHostPlayer, [47](#)
- SourcesServer, [47](#)
- Spawned, [45](#)
- SpawnedByClient, [43](#)
- Sphere, [42](#)
- SquareMagnitude, [52](#)
- StateAuthority, [49](#)
- Struct, [43](#)
- StructArray, [43](#)
- SubtickAccuracy, [42](#)
- Success, [43](#), [44](#)
- TargetPlayerIsNotLocal, [47](#)
- TargetPlayerIsLocalButRpcIsNotInvokableLocally,
[48](#)
- TargetPlayerUnreachable, [48](#)
- Ticks, [52](#)
- TicksPerSecond, [52](#)
- To, [46](#)
- Topologies, [51](#)
- Units, [52](#)
- UnityPlayerLoopSystemAddMode, [52](#)
- Unreachable, [49](#)
- Unreliable, [47](#)
- V1, [43](#)
- Fusion.Analyzer, [55](#)
- Fusion.Async, [55](#)
- Fusion.Internal, [55](#)
- Fusion.LagCompensation, [56](#)
 - Box2D, [57](#)
 - Hitbox, [57](#)
 - HitType, [57](#)
 - None, [57](#)
 - PhysX, [57](#)
 - PreProcessingDelegate, [57](#)
- Fusion.Protocol, [58](#)
- Fusion.Runtime, [58](#)
- Fusion.Runtime.Unity, [58](#)
- Fusion.Sockets, [58](#)
 - NetCommands, [59](#)
 - NetConnectFailedReason, [59](#)
 - NetDisconnectReason, [59](#)
 - NetPacketType, [59](#)
 - ServerFull, [59](#)
 - ServerRefused, [59](#)
 - Timeout, [59](#)
- Fusion.Sockets.Stun, [59](#)
 - FullCone, [60](#)
 - Invalid, [60](#)
 - NATType, [60](#)
 - OpenInternet, [60](#)
 - Symmetric, [60](#)
 - UdpBlocked, [60](#)
- GameClosed
 - Fusion, [50](#)
- GameldAlreadyExists
 - Fusion, [50](#)
- GamelsFull

- Fusion, [51](#)
- GameMode
 - Fusion, [41](#)
 - HostMigrationToken, [149](#)
 - NetworkRunner, [553](#)
 - StartGameArgs, [779](#)
- GameNotFound
 - Fusion, [50](#)
- GameObject
 - LagCompensatedHit, [207](#)
- Get
 - NetworkArray< T >, [253](#)
 - NetworkDictionary< K, V >, [352](#)
 - NetworkDictionaryReadOnly< K, V >, [358](#)
 - NetworkLinkedList< T >, [383](#)
 - NetworkLinkedListReadOnly< T >, [389](#)
 - NetworkString< TSize >, [604](#)
 - SimulationInput.Buffer, [738](#)
 - TickRate, [800](#)
- Get< T >
 - NetworkInput, [375](#)
- GetAllBehaviours
 - NetworkRunner, [514](#)
- GetAllBehaviours< T >
 - NetworkRunner, [515](#)
- GetAllNetworkBehaviourTypes
 - ReflectionUtils, [664](#)
- GetAllSimulationBehaviourTypes
 - ReflectionUtils, [664](#)
- GetAllWeavedAssemblies
 - ReflectionUtils, [664](#)
- GetAllWeavedNetworkBehaviourTypes
 - ReflectionUtils, [664](#)
- GetAllWeavedSimulationBehaviourTypes
 - ReflectionUtils, [664](#)
- GetAllWeaverGeneratedTypes
 - ReflectionUtils, [665](#)
- GetAreaOfInterestGizmoData
 - NetworkRunner, [516](#)
 - Simulation, [706](#)
- GetArrayReader< T >
 - NetworkBehaviour, [264](#)
- GetAwaiter
 - NetworkSceneAsyncOp, [571](#)
 - NetworkSpawnOp, [590](#)
- GetBehaviour< T >
 - Behaviour, [89](#)
- GetBehaviourChangedTickArray
 - NetworkObjectHeader, [423](#)
- GetBehaviourReader< T >
 - NetworkBehaviour, [265](#)
- GetBehaviourReader< TBehaviour, TProperty >
 - NetworkBehaviour, [266](#)
- GetByteCountUtf8NoHash
 - ReadWriteUtilsForWeaver, [658](#)
- GetCapacity< TSize >
 - NetworkString< TSize >, [605](#)
- GetCellSize
 - Simulation.AreaOfInterest, [720](#)
- GetChangeDetector
 - NetworkBehaviour, [266](#)
- GetCharCount
 - NetworkString< TSize >, [605](#)
- GetCustomAttributeOrThrow< T >
 - ReflectionUtils, [665](#)
- GetData
 - SimulationMessage, [745](#)
- GetDataPointer
 - NetworkObjectHeader, [423](#)
- GetDataWordCount
 - NetworkObjectHeader, [424](#)
- GetDictionaryReader< K, V >
 - NetworkBehaviour, [267](#)
- GetDivisor
 - TickRate, [800](#)
- GetElementWordCount
 - IElementReaderWriter< T >, [160](#)
- GetEntries
 - NetworkPrefabTable, [475](#)
- GetEnumerator
 - BVHDraw, [215](#)
 - FixedArray< T >, [112](#)
 - HitboxColliderContainerDraw, [218](#)
 - NetworkArray< T >, [253](#)
 - NetworkBehaviour.ChangeDetector.Enumerable, [286](#)
 - NetworkDictionary< K, V >, [352](#)
 - NetworkLinkedList< T >, [384](#)
 - NetworkString< TSize >, [605](#)
 - SerializableDictionary< TKey, TValue >, [695](#)
 - SnapshotHistoryDraw, [234](#)
- GetExecutionOrder
 - NetworkProjectConfig, [485](#)
- GetFlag
 - SimulationMessage, [745](#)
- GetGuid
 - NetworkPrefabTable, [475](#)
- GetHashCode
 - Allocator.Config, [73](#)
 - Angle, [78](#)
 - FloatCompressed, [119](#)
 - NetworkBehaviourId, [311](#)
 - NetworkBool, [333](#)
 - NetworkButtons, [337](#)
 - NetworkId, [370](#)
 - NetworkId.EqualityComparer, [374](#)
 - NetworkLoadSceneParameters, [393](#)
 - NetworkObjectGuid, [416](#)
 - NetworkObjectGuid.EqualityComparer, [421](#)
 - NetworkObjectHeader, [424](#)
 - NetworkObjectNestingKey, [433](#)
 - NetworkObjectNestingKey.EqualityComparer, [435](#)
 - NetworkObjectTypeId, [447](#)
 - NetworkObjectTypeId.EqualityComparer, [452](#)
 - NetworkPrefabId, [459](#)
 - NetworkPrefabId.EqualityComparer, [462](#)

- NetworkPrefabRef, [467](#)
- NetworkPrefabRef.EqualityComparer, [472](#)
- NetworkRunnerUpdaterDefaultInvokeSettings, [566](#)
- NetworkSceneInfo, [577](#)
- NetworkSceneLoadId, [581](#)
- NetworkSceneObjectId, [583](#)
- NetworkString< TSize >, [605](#)
- PlayerRef, [633](#)
- Ptr, [640](#)
- Ptr.EqualityComparer, [644](#)
- QuaternionCompressed, [646](#)
- SceneRef, [688](#)
- Tick, [787](#)
- Tick.EqualityComparer, [792](#)
- Vector2Compressed, [825](#)
- Vector3Compressed, [830](#)
- Vector4Compressed, [835](#)
- GetId
 - NetworkPrefabTable, [475](#)
- GetInput< T >
 - NetworkBehaviour, [268](#)
- GetInputAuthority
 - Simulation, [706](#)
- GetInputForPlayer
 - Simulation, [707](#)
- GetInputForPlayer< T >
 - NetworkRunner, [516](#)
- GetInsertTime
 - SimulationInput.Buffer, [739](#)
- GetInstancesCount
 - NetworkPrefabTable, [476](#)
- GetInstancesEnumerator
 - NetworkRunner, [516](#)
- GetInterfaceListHead
 - NetworkRunner, [516](#)
- GetInterfaceListNext
 - NetworkRunner, [517](#)
- GetInterfaceListPrev
 - NetworkRunner, [517](#)
- GetInterfaceListsCount
 - NetworkRunner, [517](#)
- GetLinkListReader< T >
 - NetworkBehaviour, [268](#), [269](#)
- GetLocalAuthorityMask
 - NetworkBehaviour, [269](#)
 - NetworkObject, [401](#)
- GetMainNetworkTRSPData
 - NetworkObjectHeader, [424](#)
- GetMaxWordCount
 - NetworkInputUtils, [378](#)
- GetMetaData
 - NetworkBehaviourUtils, [317](#)
- GetNestedComponentInChildren< T, TStopOn >
 - NestedComponentUtilities, [245](#)
- GetNestedComponentInParent< T, TStopOn >
 - NestedComponentUtilities, [245](#)
- GetNestedComponentInParents< T, TStopOn >
 - NestedComponentUtilities, [245](#)
- GetNestedComponentsInChildren< T >
 - NestedComponentUtilities, [246](#)
- GetNestedComponentsInChildren< T, TSearch, TStop >
 - NestedComponentUtilities, [246](#)
- GetNestedComponentsInChildren< T, TStopOn >
 - NestedComponentUtilities, [247](#)
- GetNestedComponentsInParents< T >
 - NestedComponentUtilities, [247](#)
- GetNestedComponentsInParents< T, TStop >
 - NestedComponentUtilities, [247](#)
- GetObjectsAndPlayersInAreaOfInterestCell
 - Simulation, [707](#)
- GetParentComponent< T >
 - NestedComponentUtilities, [248](#)
- GetPhysicsScene
 - NetworkRunner, [518](#)
- GetPhysicsScene2D
 - NetworkRunner, [518](#)
- GetPlayerActorId
 - NetworkRunner, [518](#)
- GetPlayerConnectionToken
 - NetworkRunner, [519](#)
- GetPlayerConnectionType
 - NetworkRunner, [519](#)
- GetPlayerObject
 - NetworkRunner, [519](#)
- GetPlayerRtt
 - NetworkRunner, [520](#)
- GetPlayerUserId
 - NetworkRunner, [520](#)
- GetPressed
 - NetworkButtons, [337](#)
- GetPropertyReader< T >
 - NetworkBehaviour, [269](#), [270](#)
- GetPropertyReader< TBehaviour, TProperty >
 - NetworkBehaviour, [270](#)
- GetRawInputForPlayer
 - NetworkRunner, [520](#)
- GetRef< T >
 - NetworkArrayExtensions, [257](#)
- GetReleased
 - NetworkButtons, [337](#)
- GetRenderBuffers
 - RenderTimeline, [668](#)
- GetResult
 - NetworkSceneAsyncOp.Awaiter, [574](#)
 - NetworkSpawnOp.Awaiter, [592](#)
- GetResumeSnapshotNetworkObjects
 - NetworkRunner, [520](#)
- GetResumeSnapshotNetworkSceneObjects
 - NetworkRunner, [521](#)
- GetRpcStaticIndexOrThrow
 - NetworkBehaviourUtils, [318](#)
- GetRpcTargetStatus
 - NetworkRunner, [521](#)
- GetRunnerForGameObject
 - NetworkRunner, [521](#)

- GetRunnerForScene
 - NetworkRunner, [522](#)
- GetSceneRef
 - INetworkSceneManager, [180](#), [181](#)
- GetSingleton< T >
 - NetworkRunner, [522](#)
- GetSource
 - NetworkPrefabTable, [476](#), [477](#)
- GetStateAuthority
 - Simulation, [707](#)
- GetStaticWordCount
 - NetworkBehaviourUtils, [318](#)
- GetTickRate
 - TickRate, [801](#)
- GetType
 - NetworkInputUtils, [378](#)
- GetTypeKey
 - NetworkInputUtils, [378](#)
- GetVersion
 - NetworkObjectFlagsExtensions, [409](#)
- GetWeavedAttributeOrThrow
 - ReflectionUtils, [666](#)
- GetWordCount
 - NetworkBehaviourUtils, [319](#)
 - NetworkInputUtils, [379](#)
 - NetworkObject, [401](#)
- GetWordCount< T >
 - FixedStorage, [117](#)
 - NetworkStructUtils, [619](#)
- GetWordCountString
 - ReadWriteUtilsForWeaver, [658](#)
- GizmosColor
 - Hitbox, [126](#)
 - HitboxRoot, [146](#)
- GizmosDrawWireCapsule
 - LagCompensationDraw, [220](#)
- Global
 - NetworkProjectConfig, [490](#)
 - NetworkProjectConfigAsset, [492](#)
- GlobalObjectInterest
 - Fusion, [43](#)
- GlobalsSize
 - Allocator.Config, [74](#)
 - HeapConfiguration, [124](#)
- Greater
 - Fusion, [41](#)
- GreaterOrEqual
 - Fusion, [41](#)
- Guid
 - NetworkObjectPrefabData, [436](#)
- HasAnyActiveConnections
 - Simulation, [707](#)
- HasHeader
 - NetworkPrefabAcquireContext, [456](#)
 - NetworkPrefabInfo, [463](#)
- HasInputAuthority
 - NetworkBehaviour, [279](#)
 - NetworkObject, [406](#)
- HasMainNetworkTRSP
 - Fusion, [43](#)
 - NetworkObjectHeader, [424](#)
- HasReplicateToOverride
 - NetworkBehaviourUtils.Metadata, [330](#)
- HasSingleton< T >
 - NetworkRunner, [522](#)
- HasStateAuthority
 - NetworkBehaviour, [279](#)
 - NetworkObject, [406](#)
- HasStaticWordCount
 - NetworkBehaviourUtils, [319](#)
- Header
 - NetworkPrefabInfo, [463](#)
 - SimulationInput, [735](#)
- Heap
 - NetworkProjectConfig, [487](#)
- HEAP_ALIGNMENT
 - Allocator, [70](#)
- HeapConfiguration, [123](#)
 - GlobalsSize, [124](#)
 - Init, [123](#)
 - PageCount, [124](#)
 - PageShift, [124](#)
 - ToString, [124](#)
- HeapSizeAllocated
 - Allocator.Config, [75](#)
- HeapSizeUsable
 - Allocator.Config, [75](#)
- HideNetworkObjectInactivityGuard
 - NetworkProjectConfig, [487](#)
- High
 - Fusion, [46](#)
- Hitbox, [124](#)
 - BoxExtents, [126](#)
 - CapsuleHeight, [126](#)
 - CapsuleRadius, [126](#)
 - ColliderIndex, [127](#)
 - DrawGizmos, [126](#)
 - Fusion.LagCompensation, [57](#)
 - GizmosColor, [126](#)
 - HitboxActive, [127](#)
 - HitboxIndex, [128](#)
 - LagCompensatedHit, [208](#)
 - Offset, [127](#)
 - OnDrawGizmos, [126](#)
 - Position, [128](#)
 - PositionRotationQueryParams, [223](#)
 - Root, [127](#)
 - SphereRadius, [127](#)
 - Type, [127](#)
- HitboxActive
 - Hitbox, [127](#)
- HitboxBufferLengthInMs
 - LagCompensationSettings, [239](#)
- HitboxColliderContainerDraw, [218](#)
 - GetEnumerator, [218](#)
- HitboxDefaultCapacity

- LagCompensationSettings, [239](#)
- Hitboxes
 - HitboxRoot, [147](#)
- HitboxIndex
 - Hitbox, [128](#)
- HitboxManager, [128](#)
 - AfterTick, [130](#)
 - AfterUpdate, [130](#)
 - BeforeAllTicks, [131](#)
 - BVHDepth, [142](#)
 - BVHNodes, [142](#)
 - DrawInfo, [142](#)
 - OverlapBox, [131](#), [132](#)
 - OverlapSphere, [133–135](#)
 - PositionRotation, [136](#)
 - Raycast, [137](#), [138](#)
 - RaycastAll, [139](#), [140](#)
 - TotalHitboxes, [142](#)
 - WriteBenchmarkResults, [141](#)
- HitboxRoot, [142](#)
 - BroadRadius, [146](#)
 - Config, [146](#)
 - ConfigFlags, [144](#)
 - Default, [144](#)
 - DrawGizmos, [144](#)
 - GizmosColor, [146](#)
 - Hitboxes, [147](#)
 - HitboxRootActive, [147](#)
 - IncludeInactiveHitboxes, [144](#)
 - InInterest, [147](#)
 - InitHitboxes, [144](#)
 - IsHitboxActive, [145](#)
 - Legacy, [144](#)
 - Manager, [148](#)
 - MAX_HITBOXES, [147](#)
 - Offset, [147](#)
 - OnDrawGizmos, [145](#)
 - ReinitializeHitboxesBeforeRegistration, [144](#)
 - SetHitboxActive, [145](#)
 - SetMinBoundingRadius, [146](#)
- HitboxRootActive
 - HitboxRoot, [147](#)
- HitboxTypes
 - Fusion, [42](#)
- HitOptions
 - Fusion, [42](#)
- HitType
 - Fusion.LagCompensation, [57](#)
- Host
 - Fusion, [42](#), [51](#)
- HostMigration
 - Fusion, [51](#)
 - NetworkProjectConfig, [487](#)
 - SimulationConfig, [728](#)
- HostMigrationConfig, [148](#)
 - EnableAutoUpdate, [148](#)
 - UpdateDelay, [148](#)
- HostMigrationResume
 - StartGameArgs, [779](#)
- HostMigrationToken, [149](#)
 - GameMode, [149](#)
 - StartGameArgs, [780](#)
- HostMode
 - RpcAttribute, [671](#)
- HostPlayer
 - SimulationRuntimeConfig, [755](#)
- IAfterAllTicks, [149](#)
 - AfterAllTicks, [149](#)
- IAfterClientPredictionReset, [150](#)
 - AfterClientPredictionReset, [150](#)
- IAfterHostMigration, [150](#)
 - AfterHostMigration, [151](#)
- IAfterRender, [151](#)
 - AfterRender, [151](#)
- IAfterSpawned, [151](#)
 - AfterSpawned, [152](#)
- IAfterTick, [152](#)
 - AfterTick, [152](#)
- IAfterUpdate, [153](#)
 - AfterUpdate, [153](#)
- IAsyncOperation, [153](#)
 - Completed, [154](#)
 - Error, [154](#)
 - IsDone, [154](#)
- IBeforeAllTicks, [155](#)
 - BeforeAllTicks, [155](#)
- IBeforeClientPredictionReset, [155](#)
 - BeforeClientPredictionReset, [156](#)
- IBeforeCopyPreviousState, [156](#)
 - BeforeCopyPreviousState, [156](#)
- IBeforeHitboxRegistration, [157](#)
 - BeforeHitboxRegistration, [157](#)
- IBeforeTick, [157](#)
 - BeforeTick, [158](#)
- IBeforeUpdate, [158](#)
 - BeforeUpdate, [158](#)
- ICoroutine, [159](#)
- Id
 - NetworkBehaviour, [279](#)
 - NetworkObject, [407](#)
 - NetworkObjectHeader, [426](#)
 - NetworkObjectHeaderPtr, [429](#)
 - NetworkObjectMeta, [430](#)
- IDespawned, [159](#)
 - Despawned, [159](#)
- IElementReaderWriter< T >, [160](#)
 - GetElementWordCount, [160](#)
 - Read, [160](#)
 - ReadRef, [161](#)
 - Write, [161](#)
- IFixedStorage, [162](#)
- Ignore
 - Fusion, [43](#)
- IgnoreInputAuthority
 - Fusion, [42](#)
- IInputAuthorityGained, [162](#)

- InputAuthorityGained, 162
- IInputAuthorityLost, 162
 - InputAuthorityLost, 163
- IIInterestEnter, 163
 - InterestEnter, 163
- IIInterestExit, 164
 - InterestExit, 164
- ILocalPrefabCreated, 164
 - LocalPrefabCreated, 165
- IMessage, 638
- InBandwidth
 - NetworkObjectStats, 442
 - SimulationStats, 757
- IncludeBox2D
 - Fusion, 42
- IncludeInactiveHitboxes
 - HitboxRoot, 144
- IncludePhysX
 - Fusion, 42
- IncompatibleConfiguration
 - Fusion, 50
- IndexOf
 - NetworkLinkedList< T >, 384
 - NetworkLinkedListReadOnly< T >, 389, 390
 - NetworkSceneInfo, 577
 - NetworkString< TSize >, 606–608
- IndexOf< T >
 - FixedArray< T >, 112
 - NetworkArrayExtensions, 257
- IndexOf< TOtherSize >
 - NetworkString< TSize >, 609–611
- INetworkArray, 165
 - this[int index], 165
- INetworkAssetSource< T >, 166
 - Acquire, 166
 - Description, 167
 - IsCompleted, 167
 - Release, 166
 - WaitForResult, 167
- INetworkDictionary, 167
 - Add, 168
- INetworkInput, 168
- INetworkLinkedList, 168
 - Add, 169
- INetworkObjectInitializer, 169
 - InitializeNetworkState, 169
- INetworkObjectProvider, 170
 - AcquirePrefabInstance, 170
 - ReleaseInstance, 171
- INetworkPrefabSource, 171
 - AssetGuid, 171
- INetworkRunnerCallbacks, 172
 - OnConnectedToServer, 173
 - OnConnectFailed, 173
 - OnConnectRequest, 173
 - OnCustomAuthenticationResponse, 174
 - OnDisconnectedFromServer, 174
 - OnHostMigration, 174
- OnInput, 174
- OnInputMissing, 175
- OnObjectEnterAOI, 175
- OnObjectExitAOI, 175
- OnPlayerJoined, 176
- OnPlayerLeft, 176
- OnReliableDataProgress, 176
- OnReliableDataReceived, 177
- OnSceneLoadDone, 177
- OnSceneLoadStart, 177
- OnSessionListUpdated, 177
- OnShutdown, 178
- OnUserSimulationMessage, 178
- INetworkRunnerUpdater, 178
 - Initialize, 179
 - Shutdown, 179
- INetworkSceneManager, 180
 - GetSceneRef, 180, 181
 - Initialize, 181
 - IsBusy, 183
 - IsRunnerScene, 181
 - LoadScene, 181
 - MainRunnerScene, 183
 - MakeDontDestroyOnLoad, 181
 - MoveGameObjectToScene, 182
 - OnSceneInfoChanged, 182
 - Shutdown, 182
 - TryGetPhysicsScene2D, 182
 - TryGetPhysicsScene3D, 183
 - UnloadScene, 183
- INetworkStruct, 184
- INetworkTRSPTeleport, 184
 - Teleport, 184
- InInterest
 - HitboxRoot, 147
- Init
 - HeapConfiguration, 123
 - NetworkBehaviour.ChangeDetector, 285
 - NetworkConfiguration, 345
 - TickRate, 801
 - UnityArraySurrogate< T, ReaderWriter >, 188
 - UnityDictionarySurrogate< KeyType, KeyReaderWriter, ValueType, ValueReaderWriter >, 190
 - UnityLinkedListSurrogate< T, ReaderWriter >, 192
 - UnitySurrogateBase, 194
 - UnityValueSurrogate< T, TReaderWriter >, 196
- InitHitboxes
 - HitboxRoot, 144
- Initial
 - Fusion, 44
- Initialize
 - INetworkRunnerUpdater, 179
 - INetworkSceneManager, 181
- InitializeNetworkArray< T >
 - NetworkBehaviourUtils, 320
- InitializeNetworkDictionary< D, K, V >
 - NetworkBehaviourUtils, 320
- InitializeNetworkList< T >

- NetworkBehaviourUtils, 321
- InitializeNetworkState
 - INetworkObjectInitializer, 169
 - NetworkObjectInitializerUnity, 429
- InMessagesBandwidth
 - SimulationConnectionStats, 731
- InMessagesPerPacket
 - SimulationConnectionStats, 731
- InObjectBandwidth
 - SimulationConnectionStats, 731
- InObjectDestroysPerPacket
 - SimulationConnectionStats, 731
- InObjectUpdatesPerPacket
 - SimulationConnectionStats, 732
- InPackets
 - SimulationStats, 757
- InPacketsBandwidth
 - SimulationConnectionStats, 732
- InPacketsRecv
 - SimulationConnectionStats, 732
- InProgress
 - Fusion, 44
- INPUT
 - AuthorityMasks, 87
- InputAuthority
 - Fusion, 49
 - NetworkObject, 407
 - NetworkObjectHeader, 426
 - NetworkObjectMeta, 430
- InputAuthorityGained
 - IInputAuthorityGained, 162
- InputAuthorityLost
 - IInputAuthorityLost, 163
- InputCount
 - Simulation, 713
- InputDataWordCount
 - SimulationConfig, 728
- InputReceiveDelta
 - SimulationStats, 757
- InputReceiveDeltaDeviation
 - SimulationStats, 758
- InputsBandwidth
 - SimulationConnectionStats, 732
- InputsMissing
 - SimulationConnectionStats, 732
- InputsPerPacket
 - SimulationConnectionStats, 732
- InputTotalWordCount
 - SimulationConfig, 730
- InputTransferMode
 - SimulationConfig, 729
- InputTransferModes
 - SimulationConfig, 728
- InReliableDataBandwidth
 - SimulationConnectionStats, 732
- Instance
 - NetworkObjectSortKeyComparer, 440
- Instances
 - NetworkRunner, 553
- InstantiateInRunnerScene
 - NetworkRunner, 522, 523
- InstantiateInRunnerScene< T >
 - NetworkRunner, 523
- InsufficientSourceAuthority
 - Fusion, 47, 48
- InsufficientTargetAuthority
 - Fusion, 47
- Int
 - NetworkBehaviourBufferInterpolator, 302, 304
- InterestEnter
 - IInterestEnter, 163
- InterestExit
 - IInterestExit, 164
- InternalOnDestroy
 - NetworkBehaviourUtils, 321
- InternalOnDisable
 - NetworkBehaviourUtils, 322
- InternalOnEnable
 - NetworkBehaviourUtils, 322
- InternalStruct
 - Fusion, 45
- InterpAlpha
 - SimulationInputHeader, 741
- InterpFrom
 - SimulationInputHeader, 741
- Interpolated
 - Fusion, 46
- InterpolatedErrorCorrectionSettings, 197
 - MaxRate, 197
 - MinRate, 198
 - PosBlendEnd, 198
 - PosBlendStart, 198
 - PosMinCorrection, 198
 - PosTeleportDistance, 199
 - RotBlendEnd, 199
 - RotBlendStart, 199
 - RotTeleportRadians, 199
- InterpolationOffset
 - SimulationStats, 758
- InterpolationOffsetDeviation
 - SimulationStats, 758
- InterpolationOffsetTarget
 - SimulationStats, 758
- InterpolationSpeed
 - SimulationStats, 758
- InterpTo
 - SimulationInputHeader, 741
- InUpdates
 - NetworkObjectStats, 442
- Invalid
 - Fusion, 45, 50
 - Fusion.Sockets.Stun, 60
- InvalidArguments
 - Fusion, 51
- InvalidAuthentication
 - Fusion, 51

- InvalidRegion
 - Fusion, [50](#)
- InvalidTickRate
 - TickRate, [799](#)
- InvertY
 - NormalizedRectAttribute, [630](#)
- Invoked
 - Fusion, [47](#)
- InvokeLocal
 - RpcAttribute, [671](#)
- InvokeRenderInBatchMode
 - NetworkProjectConfig, [488](#)
- InvokeRpc
 - NetworkBehaviourUtils, [327](#)
- InvokeSceneLoadDone
 - NetworkRunner, [523](#)
- InvokeSceneLoadStart
 - NetworkRunner, [524](#)
- IPlayerJoined, [200](#)
 - PlayerJoined, [200](#)
- IPlayerLeft, [200](#)
 - PlayerLeft, [201](#)
- IRemotePrefabCreated, [201](#)
 - RemotePrefabCreated, [201](#)
- Is < T >
 - NetworkInput, [375](#)
- IsAcquired
 - NetworkPrefabTable, [477](#)
- IsActiveOnLoad
 - NetworkLoadSceneParameters, [394](#)
- IsBeingDestroyed
 - NetworkObjectReleaseContext, [438](#)
- IsBusy
 - INetworkSceneManager, [183](#)
- ISceneLoadDone, [202](#)
 - SceneLoadDone, [202](#)
- ISceneLoadStart, [202](#)
 - SceneLoadStart, [203](#)
- IsClient
 - NetworkRunner, [554](#)
 - Simulation, [713](#)
- IsCloudReady
 - NetworkRunner, [554](#)
- IsCompleted
 - INetworkAssetSource < T >, [167](#)
 - NetworkSceneAsyncOp.Awaiter, [574](#)
 - NetworkSpawnOp.Awaiter, [592](#)
- IsConnectedToServer
 - NetworkRunner, [554](#)
- IsCustom
 - NetworkObjectTypeId, [451](#)
- IsDone
 - IAsyncOperation, [154](#)
 - NetworkSceneAsyncOp, [572](#)
- IsFailed
 - NetworkSpawnOp, [590](#)
- IsFirstTick
 - NetworkRunner, [554](#)
- Simulation, [713](#)
- IsForward
 - NetworkRunner, [554](#)
 - Simulation, [714](#)
- IsGlobalLoaded
 - NetworkProjectConfigAsset, [493](#)
- IsHitboxActive
 - HitboxRoot, [145](#)
- IsIgnored
 - NetworkObjectFlagsExtensions, [410](#)
- ISimulationEnter, [203](#)
 - SimulationEnter, [203](#)
- ISimulationExit, [204](#)
 - SimulationExit, [204](#)
- IsIndex
 - SceneRef, [692](#)
- IsInList
 - NetBitBufferList, [767](#)
- IsInputAuthority
 - Simulation, [708](#)
- IsInSimulation
 - NetworkObject, [407](#)
- IsInterestedIn
 - NetworkRunner, [524](#)
 - Simulation, [708](#)
- IsInvokeLocal
 - RpcInfo, [678](#)
- IsIPv6
 - NetAddress, [765](#)
- IsLastTick
 - NetworkRunner, [554](#)
 - Simulation, [714](#)
- IsLocalPhysics2D
 - NetworkLoadSceneParameters, [394](#)
- IsLocalPhysics3D
 - NetworkLoadSceneParameters, [395](#)
- IsLocalPlayerFirstExecution
 - Simulation, [714](#)
- IsLocalSimulationInputAuthority
 - Simulation, [708](#)
- IsLocalSimulationStateAuthority
 - Simulation, [709](#)
- IsLocalSimulationStateOrInputSource
 - Simulation, [710](#)
- IsMainTRSP
 - NetworkTRSP, [626](#)
- IsMasterClient
 - PlayerRef, [636](#)
 - Simulation, [714](#)
- IsNestedObject
 - NetworkObjectReleaseContext, [438](#)
- IsNone
 - NetworkObjectNestingKey, [434](#)
 - NetworkObjectTypeId, [451](#)
 - NetworkPrefabId, [461](#)
 - PlayerRef, [636](#)
- IsOpen
 - SessionInfo, [700](#)

- StartGameArgs, 780
- IsPath
 - SceneRef, 688
- IsSpawned, 204
 - Spawned, 205
- IsPlayer
 - NetworkRunner, 555
 - Simulation, 714
- IsPlayerValid
 - NetworkRunner, 524
- IsPrefab
 - NetworkObjectTypeId, 451
- IsProxy
 - NetworkBehaviour, 280
 - NetworkObject, 407
- IsQueued
 - NetworkSpawnOp, 590
- IsReadOnly
 - SerializableDictionary< TKey, TValue >, 698
- IsRealPlayer
 - PlayerRef, 637
- IsRelayAddr
 - NetAddress, 765
- IsReserved
 - NetworkId, 373
- IsResimulation
 - NetworkRunner, 555
 - Simulation, 715
- IsResume
 - NetworkObject, 405
 - NetworkRunner, 555
- IsRunnerScene
 - INetworkSceneManager, 181
- IsRunning
 - NetworkRunner, 555
 - Simulation, 715
 - TickTimer, 812
- IsSceneAuthority
 - NetworkRunner, 555
- IsSceneManagerBusy
 - NetworkRunner, 555
- IsSceneObject
 - NetworkObjectTypeId, 451
- IsServer
 - NetworkRunner, 556
 - Simulation, 715
- IsSet
 - NetworkButtons, 338
- IsSet< T >
 - NetworkButtons, 338
- IsSharedModeMasterClient
 - NetworkRunner, 556
- IsShutdown
 - NetworkRunner, 556
 - Simulation, 715
- IsSingleLoad
 - NetworkLoadSceneParameters, 395
- IsSinglePlayer
 - NetworkRunner, 556
 - Simulation, 715
- IsSpawnable
 - NetworkObject, 407
- IsSpawned
 - NetworkSpawnOp, 590
- IsStarting
 - NetworkRunner, 556
- IsStateAuthority
 - Simulation, 710
- IsStruct
 - NetworkObjectTypeId, 451
- IsSynchronous
 - NetworkPrefabAcquireContext, 455
 - NetworkPrefabInfo, 463
- IsTargeted
 - SimulationMessage, 746
- IStateAuthorityChanged, 205
 - StateAuthorityChanged, 205
- IsUnreliable
 - SimulationMessage, 753
- IsValid
 - LobbyInfo, 240
 - NetAddress, 765
 - NetworkBehaviourId, 313
 - NetworkId, 373
 - NetworkInput, 377
 - NetworkObject, 407
 - NetworkObjectGuid, 420
 - NetworkObjectNestingKey, 434
 - NetworkObjectTypeId, 451
 - NetworkPrefabId, 461
 - NetworkPrefabRef, 471
 - NetworkSceneAsyncOp, 572
 - NetworkSceneObjectId, 584
 - SceneRef, 692
 - SessionInfo, 700
 - TickRate, 801, 802
- IsVersionCurrent
 - NetworkObjectFlagsExtensions, 410
- IsVisible
 - SessionInfo, 700
 - StartGameArgs, 780
- IsZero
 - Fusion, 41
- ItemsPropertyPath
 - SerializableDictionary< TKey, TValue >, 697
- IUnitySurrogate, 185
 - Read, 185
 - Write, 186
- IUnityValueSurrogate< T >, 186
 - DataProperty, 187
- JoinSessionLobby
 - NetworkRunner, 524
- Key
 - NetworkRpcStaticWeavedInvokerAttribute, 500
 - NetworkRpcWeavedInvokerAttribute, 501

- RpcInvokeData, 679
- Keys
 - SerializableDictionary< TKey, TValue >, 698
- Kilobytes
 - Fusion, 52
- Kind
 - NetworkObjectTypeId, 451
- LagCompensatedExt, 218
 - SortDistance, 219
 - SortReference, 219
- LagCompensatedHit, 205
 - Collider, 207
 - Collider2D, 207
 - Distance, 207
 - GameObject, 207
 - Hitbox, 208
 - Normal, 208
 - operator LagCompensatedHit, 206, 207
 - Point, 208
 - Type, 208
- LagCompensation
 - NetworkProjectConfig, 488
 - NetworkRunner, 556
- LagCompensationDraw, 220
 - BVHDraw, 221
 - GizmosDrawWireCapsule, 220
 - SnapshotHistoryDraw, 221
- LagCompensationSettings, 238
 - CachedStaticCollidersSize, 238
 - Enabled, 239
 - ExpansionFactor, 239
 - HitboxBufferLengthInMs, 239
 - HitboxDefaultCapacity, 239
 - Optimize, 239
- LagCompensationUtils.ContactData, 221
 - Normal, 221
 - Penetration, 221
 - Point, 222
- LastChild
 - Fusion, 54
- LastReceiveTick
 - NetworkObject, 408
- Latest
 - Fusion, 46
- LatestServerTick
 - NetworkRunner, 557
 - Simulation, 715
- LatestState
 - SimulationConfig, 728
- LayerMask
 - Query, 225
 - QueryParams, 227
- Legacy
 - HitboxRoot, 144
- Length
 - CapacityAttribute, 92
 - FixedArray< T >, 113
 - NetworkArray< T >, 254
 - NetworkArrayReadOnly< T >, 259
 - NetworkBehaviourBuffer, 296
 - NetworkString< TSize >, 618
 - RaycastQuery, 231
 - RaycastQueryParams, 233
- Lerp
 - Angle, 78
- Less
 - Fusion, 41
- LessOrEqual
 - Fusion, 41
- Load
 - NetworkPrefabTable, 477
- LoadError
 - Fusion, 44
- LoadId
 - NetworkLoadSceneParameters, 394
- LoadScene
 - INetworkSceneManager, 181
 - NetworkRunner, 525, 526
- LoadSceneMode
 - NetworkLoadSceneParameters, 395
- LoadSceneParameters
 - NetworkLoadSceneParameters, 395
- LobbyInfo, 240
 - IsValid, 240
 - Name, 240
 - NetworkRunner, 557
 - Region, 240
- Local
 - Fusion, 46
- LocalAddress
 - Simulation, 716
- LocalAlpha
 - NetworkRunner, 557
 - Simulation, 716
- LocalhostIPv4
 - NetAddress, 764
- LocalhostIPv6
 - NetAddress, 764
- LocalInvokeResult
 - RpcInvokeInfo, 681
- LocalPhysicsMode
 - NetworkLoadSceneParameters, 395
- LocalPlayer
 - NetworkRunner, 557
 - Simulation, 716
- LocalPrefabCreated
 - ILocalPrefabCreated, 165
- LocalRenderTime
 - NetworkRunner, 557
- LocalToWorldMatrix
 - ColliderDrawInfo, 217
- LogSimpleUnity, 241
- LossChanceMax
 - NetworkSimulationConfiguration, 588
- LossChanceMin
 - NetworkSimulationConfiguration, 588

- LossChancePeriod
 - NetworkSimulationConfiguration, [588](#)
- LossChanceShape
 - NetworkSimulationConfiguration, [588](#)
- LossChanceThreshold
 - NetworkSimulationConfiguration, [588](#)
- Low
 - Fusion, [46](#)
- Lowest
 - Fusion, [46](#)
- MainRunnerScene
 - INetworkSceneManager, [183](#)
- MakeDontDestroyOnLoad
 - INetworkSceneManager, [181](#)
 - NetworkRunner, [526](#)
- MakeInitializer< K, V >
 - NetworkBehaviour, [271](#)
- MakeInitializer< T >
 - NetworkBehaviour, [271](#)
- MakePtr< T >
 - NetworkBehaviour, [271](#), [272](#)
- MakeRef< T >
 - NetworkBehaviour, [272](#), [273](#)
- MakeSerializableDictionary< K, V >
 - NetworkBehaviourUtils, [322](#)
- Manager
 - HitboxRoot, [148](#)
- MaskBroadcast
 - Fusion, [48](#)
- MaskCulled
 - Fusion, [48](#)
- MaskNotSent
 - Fusion, [48](#)
- MaskSent
 - Fusion, [48](#)
- MaskVersion
 - Fusion, [43](#)
- MASTER_CLIENT_RAW
 - PlayerRef, [635](#)
- MasterClient
 - PlayerRef, [637](#)
 - SimulationRuntimeConfig, [755](#)
- MasterClientObject
 - Fusion, [43](#)
- MatchmakingMode
 - StartGameArgs, [780](#)
- MAX
 - NetworkRNG, [498](#)
- Max
 - AABB, [210](#)
 - Angle, [78](#)
- MAX_HITBOXES
 - HitboxRoot, [147](#)
- MAX_INDEX
 - NetworkPrefabId, [460](#)
- MAX_SCENE_OBJECT_INDEX
 - NetworkObjectTypeId, [449](#)
- MaxCcuReached
 - Fusion, [50](#)
- MaxConnections
 - NetConfig, [773](#)
- MaxDepth
 - BVHNodeDrawInfo, [216](#)
- MaxLateInputs
 - TimeSyncConfiguration, [814](#)
- MaxLateSnapshots
 - TimeSyncConfiguration, [814](#)
- MaxPlayers
 - SessionInfo, [701](#)
- MaxRate
 - InterpolatedErrorCorrectionSettings, [197](#)
- MaxScenes
 - NetworkSceneInfo, [578](#)
- MaxSize
 - NetworkSerializeMethodAttribute, [585](#)
- Medium
 - Fusion, [46](#)
- Megabytes
 - Fusion, [52](#)
- Message
 - NetworkObjectSpawnException, [441](#)
 - SimulationMessagePtr, [754](#)
 - WarnIfAttribute, [839](#)
- MessageSize
 - RpcSendResult, [682](#)
- Meta
 - NetworkPrefabAcquireContext, [455](#)
- META_WORD_COUNT
 - NetworkDictionary< K, V >, [355](#)
- META_WORDS
 - NetworkLinkedList< T >, [385](#)
 - NetworkLinkedListReadOnly< T >, [390](#)
- Method
 - RenderAttribute, [667](#)
 - RpcHeader, [675](#)
- MilliSecs
 - Fusion, [52](#)
- Min
 - AABB, [210](#)
 - Angle, [79](#)
- MinRate
 - InterpolatedErrorCorrectionSettings, [198](#)
- Mode
 - DrawIfAttribute, [96](#)
 - NetworkRunner, [557](#)
 - Simulation, [716](#)
- Modes
 - SimulationBehaviourAttribute, [726](#)
- MoveGameObjectToSameScene
 - NetworkRunner, [527](#)
- MoveGameObjectToScene
 - INetworkSceneManager, [182](#)
 - NetworkRunner, [527](#)
- MoveNext
 - FixedArray< T >.Enumerator, [115](#)
 - NetworkArray< T >.Enumerator, [256](#)

- NetworkBehaviour.ChangeDetector.Enumerator, 286
- NetworkDictionary< K, V >.Enumerator, 356
- NetworkLinkedList< T >.Enumerator, 387
- MoveToRunnerScene
 - NetworkRunner, 528
- MoveToRunnerScene< T >
 - NetworkRunner, 528
- MtuDefault
 - NetworkConfiguration, 347
- Multiple
 - NetworkProjectConfig, 484
- Multiplier
 - Fusion, 52
- Name
 - LobbyInfo, 240
 - NetworkObject, 408
 - SessionInfo, 701
- NATType
 - Fusion.Sockets.Stun, 60
 - NetworkRunner, 558
- NestedComponentUtilities, 241
 - EnsureRootComponentExists< T, TStopOn >, 242
 - FindObjectsOfTypeInOrder< T >, 243
 - FindObjectsOfTypeInOrder< T, TCast >, 244
 - GetNestedComponentInChildren< T, TStopOn >, 245
 - GetNestedComponentInParent< T, TStopOn >, 245
 - GetNestedComponentInParents< T, TStopOn >, 245
 - GetNestedComponentsInChildren< T >, 246
 - GetNestedComponentsInChildren< T, TSearch, TStop >, 246
 - GetNestedComponentsInChildren< T, TStopOn >, 247
 - GetNestedComponentsInParents< T >, 247
 - GetNestedComponentsInParents< T, TStop >, 247
 - GetParentComponent< T >, 248
- NestedObjects
 - NetworkObject, 405
- NestingKey
 - NetworkObjectHeader, 426
- NestingRoot
 - NetworkObjectHeader, 427
- NetAddress, 761
 - ActorId, 765
 - Any, 762
 - AnyIPv6, 763
 - CreateFromIpPort, 763
 - FromActorId, 764
 - IsIPv6, 765
 - IsRelayAddr, 765
 - IsValid, 765
 - LocalhostIPv4, 764
 - LocalhostIPv6, 764
- NetBitBufferList, 765
 - AddFirst, 766
 - AddLast, 766
 - IsInList, 767
 - Remove, 767
 - RemoveHead, 767
- NetCommandAccepted, 768
- NetCommandConnect, 768
- NetCommandDisconnect, 769
- NetCommandHeader, 769
 - Create, 770
- NetCommandRefused, 770
- NetCommands
 - Fusion.Sockets, 59
- NetConfig, 771
 - Address, 772
 - ConnectAttempts, 772
 - ConnectInterval, 772
 - ConnectionDefaultRtt, 772
 - ConnectionGroups, 772
 - ConnectionPingInterval, 773
 - ConnectionSendBuffers, 773
 - ConnectionShutdownTime, 773
 - ConnectionsPerGroup, 775
 - ConnectionTimeout, 773
 - DefaultMtu, 773
 - Defaults, 775
 - MaxConnections, 773
 - Notify, 774
 - OperationExpireTime, 774
 - PacketSize, 774
 - PacketSizeInBits, 775
 - Simulation, 774
 - SocketRecvBuffer, 774
 - SocketSendBuffer, 774
- NetConfigPointer
 - Simulation, 716
- NetConnectFailedReason
 - Fusion.Sockets, 59
- NetDisconnectReason
 - Fusion.Sockets, 59
- NetPacketType
 - Fusion.Sockets, 59
- Network
 - NetworkProjectConfig, 488
- NetworkArray
 - NetworkArray< T >, 250
- NetworkArray< T >, 248
 - Clear, 250
 - CopyFrom, 251
 - CopyTo, 252
 - Get, 253
 - GetEnumerator, 253
 - Length, 254
 - NetworkArray, 250
 - operator NetworkArrayReadOnly< T >, 253
 - Set, 253
 - this[int index], 254
 - ToArray, 253

- ToListString, [254](#)
- ToReadOnly, [254](#)
- ToString, [254](#)
- NetworkArray< T >.Enumerator, [255](#)
 - Current, [256](#)
 - Dispose, [256](#)
 - Enumerator, [255](#)
 - MoveNext, [256](#)
 - Reset, [256](#)
- NetworkArrayExtensions, [257](#)
 - GetRef< T >, [257](#)
 - IndexOf< T >, [257](#)
- NetworkArrayReadOnly< T >, [258](#)
 - Length, [259](#)
 - this[int index], [259](#)
- NetworkAssemblyIgnoreAttribute, [259](#)
- NetworkAssemblyWeavedAttribute, [259](#)
- NetworkBehaviour, [259](#)
 - ChangedTick, [279](#)
 - CopyBackingFieldsToState, [262](#)
 - CopyStateFrom, [263](#)
 - CopyStateToBackingFields, [263](#)
 - Despawned, [263](#)
 - DynamicWordCount, [279](#)
 - FixedUpdateNetwork, [263](#)
 - GetArrayReader< T >, [264](#)
 - GetBehaviourReader< T >, [265](#)
 - GetBehaviourReader< TBehaviour, TProperty >, [266](#)
 - GetChangeDetector, [266](#)
 - GetDictionaryReader< K, V >, [267](#)
 - GetInput< T >, [268](#)
 - GetLinkedListReader< T >, [268](#), [269](#)
 - GetLocalAuthorityMask, [269](#)
 - GetPropertyReader< T >, [269](#), [270](#)
 - GetPropertyReader< TBehaviour, TProperty >, [270](#)
 - HasInputAuthority, [279](#)
 - HasStateAuthority, [279](#)
 - Id, [279](#)
 - IsProxy, [280](#)
 - MakeInitializer< K, V >, [271](#)
 - MakeInitializer< T >, [271](#)
 - MakePtr< T >, [271](#), [272](#)
 - MakeRef< T >, [272](#), [273](#)
 - NetworkDeserialize, [274](#)
 - NetworkSerialize, [274](#)
 - NetworkUnwrap, [275](#)
 - NetworkWrap, [275](#)
 - offset, [278](#)
 - operator NetworkBehaviourId, [275](#)
 - ReinterpretState< T >, [277](#)
 - ReplicateTo, [277](#)
 - ResetState, [278](#)
 - Spawned, [278](#)
 - StateBuffer, [280](#)
 - StateBufferIsValid, [280](#)
 - TryGetSnapshotsBuffers, [278](#)
- NetworkBehaviour.ArrayReader< T >, [280](#)
 - Read, [281](#)
- NetworkBehaviour.BehaviourReader< T >, [281](#)
 - Read, [282](#)
 - T, [282](#)
- NetworkBehaviour.ChangeDetector, [283](#)
 - DetectChanges, [284](#)
 - Init, [285](#)
 - SimulationState, [284](#)
 - SnapshotFrom, [284](#)
 - SnapshotTo, [284](#)
 - Source, [283](#)
- NetworkBehaviour.ChangeDetector.Enumerable, [285](#)
 - Changed, [285](#)
 - GetEnumerator, [286](#)
- NetworkBehaviour.ChangeDetector.Enumerator, [286](#)
 - Current, [287](#)
 - MoveNext, [286](#)
 - Reset, [287](#)
- NetworkBehaviour.DictionaryReader< K, V >, [287](#)
 - Read, [288](#)
- NetworkBehaviour.LinkListReader< T >, [288](#)
 - Read, [289](#)
- NetworkBehaviour.PropertyReader< T >, [289](#)
 - PropertyReader, [290](#)
 - Read, [290](#)
 - T, [290](#)
- NetworkBehaviourBuffer, [291](#)
 - Length, [296](#)
 - operator bool, [292](#)
 - Read, [292](#), [293](#)
 - Read< T >, [295](#)
 - ReinterpretState< T >, [296](#)
 - this[int index], [296](#)
 - Tick, [297](#)
 - Valid, [297](#)
- NetworkBehaviourBufferInterpolator, [297](#)
 - Alpha, [308](#)
 - Angle, [299](#), [300](#)
 - Behaviour, [308](#)
 - Bool, [300](#)
 - Float, [302](#)
 - From, [309](#)
 - Int, [302](#), [304](#)
 - NetworkBehaviourBufferInterpolator, [299](#)
 - operator bool, [304](#)
 - Quaternion, [304](#), [305](#)
 - Select< T >, [305](#), [306](#)
 - To, [309](#)
 - Valid, [309](#)
 - Vector2, [306](#)
 - Vector3, [307](#)
 - Vector4, [308](#)
- NetworkBehaviourId, [309](#)
 - Behaviour, [312](#)
 - Equals, [310](#), [311](#)
 - GetHashCode, [311](#)
 - IsValid, [313](#)

- None, [313](#)
- Object, [313](#)
- operator!=, [311](#)
- operator==, [312](#)
- SIZE, [313](#)
- ToString, [312](#)
- NetworkBehaviourUtils, [313](#)
 - CloneArray< T >, [315](#)
 - CopyFromNetworkArray< T >, [316](#)
 - CopyFromNetworkDictionary< D, K, V >, [316](#)
 - CopyFromNetworkList< T >, [317](#)
 - GetMetaData, [317](#)
 - GetRpcStaticIndexOrThrow, [318](#)
 - GetStaticWordCount, [318](#)
 - GetWordCount, [319](#)
 - HasStaticWordCount, [319](#)
 - InitializeNetworkArray< T >, [320](#)
 - InitializeNetworkDictionary< D, K, V >, [320](#)
 - InitializeNetworkList< T >, [321](#)
 - InternalOnDestroy, [321](#)
 - InternalOnDisable, [322](#)
 - InternalOnEnable, [322](#)
 - InvokeRpc, [327](#)
 - MakeSerializableDictionary< K, V >, [322](#)
 - NotifyLocalSimulationNotAllowedToSendRpc, [323](#)
 - NotifyLocalTargetedRpcCulled, [323](#)
 - NotifyNetworkUnwrapFailed< T >, [324](#)
 - NotifyNetworkWrapFailed< T >, [324](#)
 - NotifyRpcTargetUnreachable, [325](#)
 - RegisterMetaData, [325](#)
 - RegisterRpcInvokeDelegates, [325](#)
 - ShouldRegisterRpcInvokeDelegates, [326](#)
 - ThrowIfBehaviourNotInitialized, [326](#)
 - TryGetRpcInvokeDelegateArray, [326](#)
 - TryGetRpcStaticInvokeDelegate, [327](#)
- NetworkBehaviourUtils.ArrayInitializer< T >, [328](#)
 - operator NetworkArray< T >, [328](#)
 - operator NetworkLinkedList< T >, [329](#)
- NetworkBehaviourUtils.DictionaryInitializer< K, V >, [329](#)
 - operator NetworkDictionary< K, V >, [330](#)
- NetworkBehaviourUtils.MetaData, [330](#)
 - HasReplicateToOverride, [330](#)
- NetworkBehaviourWeavedAttribute, [331](#)
 - NetworkBehaviourWeavedAttribute, [331](#)
 - WordCount, [332](#)
- NetworkBool, [332](#)
 - Equals, [333](#)
 - GetHashCode, [333](#)
 - NetworkBool, [332](#)
 - operator bool, [334](#)
 - operator NetworkBool, [334](#)
 - ToString, [334](#)
- NetworkButtons, [334](#)
 - Bits, [344](#)
 - Equals, [336](#)
 - GetHashCode, [337](#)
 - GetPressed, [337](#)
 - GetReleased, [337](#)
 - IsSet, [338](#)
 - IsSet< T >, [338](#)
 - NetworkButtons, [336](#), [343](#)
 - Set, [339](#)
 - Set< T >, [339](#)
 - SetAllDown, [339](#)
 - SetAllUp, [340](#)
 - SetDown, [340](#)
 - SetDown< T >, [340](#)
 - SetUp, [341](#)
 - SetUp< T >, [341](#)
 - WasPressed, [341](#)
 - WasPressed< T >, [342](#)
 - WasReleased, [342](#)
 - WasReleased< T >, [343](#)
- NetworkConditions
 - NetworkProjectConfig, [488](#)
- NetworkConfiguration, [344](#)
 - ClientToClientWithServerProxy, [345](#)
 - ClientToServer, [345](#)
 - ConnectAttempts, [346](#)
 - ConnectInterval, [346](#)
 - ConnectionDefaultRtt, [347](#)
 - ConnectionPingInterval, [347](#)
 - ConnectionShutdownTime, [346](#)
 - ConnectionTimeout, [346](#)
 - Init, [345](#)
 - MtuDefault, [347](#)
 - ReliableDataTransferModes, [346](#)
 - ReliableDataTransfers, [345](#)
 - SocketRecvBufferSize, [347](#)
 - SocketSendBufferSize, [347](#)
- NetworkConnected
 - Simulation, [711](#)
- NetworkDelegates, [348](#)
- NetworkDeserialize
 - NetworkBehaviour, [274](#)
- NetworkDeserializeMethodAttribute, [348](#)
- NetworkDictionary
 - NetworkDictionary< K, V >, [351](#)
- NetworkDictionary< K, V >, [349](#)
 - Add, [351](#)
 - Capacity, [355](#)
 - Clear, [352](#)
 - ContainsKey, [352](#)
 - ContainsValue, [352](#)
 - Count, [355](#)
 - Get, [352](#)
 - GetEnumerator, [352](#)
 - META_WORD_COUNT, [355](#)
 - NetworkDictionary, [351](#)
 - operator NetworkDictionaryReadOnly< K, V >, [353](#)
 - Remove, [353](#)
 - Set, [354](#)
 - this[K key], [355](#)
 - ToReadOnly, [354](#)

- TryGet, [354](#)
- NetworkDictionary< K, V >.Enumerator, [355](#)
 - Current, [357](#)
 - Dispose, [356](#)
 - MoveNext, [356](#)
 - Reset, [356](#)
- NetworkDictionaryReadOnly< K, V >, [357](#)
 - Capacity, [359](#)
 - Count, [359](#)
 - Get, [358](#)
 - TryGet, [358](#)
- NetworkDisconnected
 - Simulation, [711](#)
- NetworkedAttribute, [359](#)
 - Default, [360](#)
 - NetworkedAttribute, [360](#)
- NetworkedBehaviours
 - NetworkObject, [405](#)
- NetworkedWeavedAttribute, [360](#)
 - NetworkedWeavedAttribute, [361](#)
 - WordCount, [361](#)
 - WordOffset, [361](#)
- NetworkEvents, [362](#)
- NetworkEvents.ConnectFailedEvent, [363](#)
- NetworkEvents.ConnectRequestEvent, [363](#)
- NetworkEvents.CustomAuthenticationResponse, [364](#)
- NetworkEvents.DisconnectFromServerEvent, [364](#)
- NetworkEvents.HostMigrationEvent, [364](#)
- NetworkEvents.InputEvent, [364](#)
- NetworkEvents.InputPlayerEvent, [365](#)
- NetworkEvents.ObjectEvent, [365](#)
- NetworkEvents.ObjectPlayerEvent, [365](#)
- NetworkEvents.PlayerEvent, [365](#)
- NetworkEvents.ReliableDataEvent, [366](#)
- NetworkEvents.ReliableProgressEvent, [366](#)
- NetworkEvents.RunnerEvent, [366](#)
- NetworkEvents.SessionListUpdateEvent, [366](#)
- NetworkEvents.ShutdownEvent, [367](#)
- NetworkEvents.SimulationMessageEvent, [367](#)
- NetworkId, [367](#)
 - ALIGNMENT, [372](#)
 - BLOCK_SIZE, [372](#)
 - Comparer, [373](#)
 - CompareTo, [369](#)
 - Equals, [369](#), [370](#)
 - GetHashCode, [370](#)
 - IsReserved, [373](#)
 - IsValid, [373](#)
 - operator bool, [370](#)
 - operator !=, [370](#)
 - operator ==, [370](#)
 - Raw, [372](#)
 - Read, [371](#)
 - SIZE, [372](#)
 - ToNamePrefixString, [371](#)
 - ToString, [371](#)
 - Write, [371](#), [372](#)
- NetworkId.EqualityComparer, [373](#)
 - Equals, [374](#)
 - GetHashCode, [374](#)
- NetworkIdsObjectName
 - NetworkProjectConfig, [488](#)
- NetworkInput, [374](#)
 - Convert< T >, [375](#)
 - Data, [377](#)
 - Get< T >, [375](#)
 - Is< T >, [375](#)
 - IsValid, [377](#)
 - Set< T >, [376](#)
 - TryGet< T >, [376](#)
 - TrySet< T >, [376](#)
 - Type, [377](#)
 - WordCount, [377](#)
- NetworkInputUtils, [377](#)
 - GetMaxWordCount, [378](#)
 - GetType, [378](#)
 - GetTypeKey, [378](#)
 - GetWordCount, [379](#)
- NetworkInputWeavedAttribute, [379](#)
 - NetworkInputWeavedAttribute, [379](#)
 - WordCount, [380](#)
- NetworkLinkedList
 - NetworkLinkedList< T >, [382](#)
- NetworkLinkedList< T >, [380](#)
 - Add, [382](#), [383](#)
 - Capacity, [386](#)
 - Clear, [383](#)
 - Contains, [383](#)
 - Count, [386](#)
 - ELEMENT_WORDS, [385](#)
 - Get, [383](#)
 - GetEnumerator, [384](#)
 - IndexOf, [384](#)
 - META_WORDS, [385](#)
 - NetworkLinkedList, [382](#)
 - Remap, [384](#)
 - Remove, [385](#)
 - Set, [385](#)
 - this[int index], [386](#)
- NetworkLinkedList< T >.Enumerator, [386](#)
 - Current, [387](#)
 - Dispose, [387](#)
 - MoveNext, [387](#)
 - Reset, [387](#)
- NetworkLinkedListReadOnly< T >, [388](#)
 - Capacity, [391](#)
 - Contains, [389](#)
 - Count, [391](#)
 - ELEMENT_WORDS, [390](#)
 - Get, [389](#)
 - IndexOf, [389](#), [390](#)
 - META_WORDS, [390](#)
 - this[int index], [391](#)
- NetworkLoadSceneParameters, [391](#)
 - Equals, [392](#), [393](#)
 - GetHashCode, [393](#)

- IsActiveOnLoad, [394](#)
- IsLocalPhysics2D, [394](#)
- IsLocalPhysics3D, [395](#)
- IsSingleLoad, [395](#)
- LoadId, [394](#)
- LoadSceneMode, [395](#)
- LoadSceneParameters, [395](#)
- LocalPhysicsMode, [395](#)
- operator!=, [393](#)
- operator==, [393](#)
- ToString, [394](#)
- NetworkMecanimAnimator, [396](#)
 - Animator, [397](#)
 - ApplyTiming, [397](#)
 - DynamicWordCount, [398](#)
 - SetTrigger, [396](#), [397](#)
- NetworkObject, [398](#)
 - AssignInputAuthority, [400](#)
 - Awake, [401](#)
 - CopyStateFrom, [401](#)
 - Flags, [405](#)
 - GetLocalAuthorityMask, [401](#)
 - GetWordCount, [401](#)
 - HasInputAuthority, [406](#)
 - HasStateAuthority, [406](#)
 - Id, [407](#)
 - InputAuthority, [407](#)
 - IsInSimulation, [407](#)
 - IsProxy, [407](#)
 - IsResume, [405](#)
 - IsSpawnable, [407](#)
 - IsValid, [407](#)
 - LastReceiveTick, [408](#)
 - Name, [408](#)
 - NestedObjects, [405](#)
 - NetworkedBehaviours, [405](#)
 - NetworkTypeId, [405](#)
 - NetworkUnwrap, [402](#)
 - NetworkWrap, [402](#)
 - OnDestroy, [403](#)
 - operator NetworkId, [403](#)
 - PriorityCallback, [406](#)
 - PriorityLevelDelegate, [403](#)
 - ReleaseStateAuthority, [404](#)
 - RemoveInputAuthority, [404](#)
 - RenderSource, [408](#)
 - RenderTime, [408](#)
 - RenderTimeframe, [408](#)
 - ReplicateTo, [406](#)
 - ReplicateToDelegate, [404](#)
 - RequestStateAuthority, [404](#)
 - Runner, [408](#)
 - SetPlayerAlwaysInterested, [404](#)
 - SortKey, [406](#)
 - StateAuthority, [409](#)
- NetworkObjectAcquireResult
 - Fusion, [42](#)
- NetworkObjectFlags
 - Fusion, [43](#)
- NetworkObjectFlagsExtensions, [409](#)
 - GetVersion, [409](#)
 - IsIgnored, [410](#)
 - IsVersionCurrent, [410](#)
 - SetCurrentVersion, [410](#)
 - SetIgnored, [412](#)
- NetworkObjectGuid, [412](#)
 - ALIGNMENT, [419](#)
 - CompareTo, [415](#)
 - Empty, [420](#)
 - Equals, [415](#), [416](#)
 - GetHashCode, [416](#)
 - IsValid, [420](#)
 - NetworkObjectGuid, [414](#), [415](#)
 - operator Guid, [416](#)
 - operator NetworkObjectGuid, [417](#)
 - operator NetworkPrefabRef, [417](#)
 - operator!=, [417](#)
 - operator==, [417](#)
 - Parse, [418](#)
 - RawGuidValue, [419](#)
 - SIZE, [419](#)
 - ToString, [418](#)
 - ToUnityGuidString, [418](#)
 - TryParse, [419](#)
- NetworkObjectGuid.EqualityComparer, [420](#)
 - Equals, [420](#)
 - GetHashCode, [421](#)
- NetworkObjectHeader, [421](#)
 - _reserved, [426](#)
 - BehaviourCount, [426](#)
 - ByteCount, [428](#)
 - Equals, [422](#), [423](#)
 - Flags, [426](#)
 - GetBehaviourChangedTickArray, [423](#)
 - GetDataPointer, [423](#)
 - GetDataWordCount, [424](#)
 - GetHashCode, [424](#)
 - GetMainNetworkTRSPData, [424](#)
 - HasMainNetworkTRSP, [424](#)
 - Id, [426](#)
 - InputAuthority, [426](#)
 - NestingKey, [426](#)
 - NestingRoot, [427](#)
 - operator!=, [425](#)
 - operator==, [425](#)
 - PLAYER_DATA_WORD, [427](#)
 - SIZE, [427](#)
 - StateAuthority, [427](#)
 - ToString, [425](#)
 - Type, [427](#)
 - WordCount, [427](#)
 - WORDS, [428](#)
- NetworkObjectHeaderFlags
 - Fusion, [43](#)
- NetworkObjectHeaderPtr, [428](#)
 - Id, [429](#)

- Ptr, [429](#)
- Type, [429](#)
- NetworkObjectInitializerUnity, [429](#)
 - InitializeNetworkState, [429](#)
- NetworkObjectMeta, [430](#)
 - Id, [430](#)
 - InputAuthority, [430](#)
 - StateAuthority, [430](#)
 - Type, [431](#)
- NetworkObjectNestingKey, [431](#)
 - ALIGNMENT, [434](#)
 - Equals, [432](#), [433](#)
 - GetHashCode, [433](#)
 - IsNone, [434](#)
 - IsValid, [434](#)
 - NetworkObjectNestingKey, [432](#)
 - SIZE, [434](#)
 - ToString, [433](#)
 - Value, [434](#)
- NetworkObjectNestingKey.EqualityComparer, [435](#)
 - Equals, [435](#)
 - GetHashCode, [435](#)
- NetworkObjectPrefabData, [436](#)
 - Guid, [436](#)
- NetworkObjectProviderDummy, [436](#)
- NetworkObjectReleaseContext, [437](#)
 - IsBeingDestroyed, [438](#)
 - IsNestedObject, [438](#)
 - NetworkObjectReleaseContext, [437](#)
 - Object, [438](#)
 - ToString, [438](#)
 - TypeId, [438](#)
- NetworkObjectSortKeyComparer, [439](#)
 - Compare, [439](#)
 - Instance, [440](#)
- NetworkObjectSpawnDelegate
 - Fusion, [54](#)
- NetworkObjectSpawnException, [440](#)
 - Message, [441](#)
 - NetworkObjectSpawnException, [440](#)
 - Status, [441](#)
 - TypeId, [441](#)
- NetworkObjectStats, [441](#)
 - AreaOfInterestPlayerCount, [442](#)
 - InBandwidth, [442](#)
 - InUpdates, [442](#)
 - OutBandwidth, [443](#)
 - OutUpdates, [443](#)
 - Reset, [442](#)
- NetworkObjectTypeId, [443](#)
 - _value0, [448](#)
 - _value1, [448](#)
 - ALIGNMENT, [449](#)
 - AsCustom, [449](#)
 - AsInternalStructId, [450](#)
 - AsPrefabId, [450](#)
 - AsSceneObjectId, [450](#)
 - Comparer, [450](#)
 - Equals, [445](#)
 - FromCustom, [446](#)
 - FromPrefabId, [446](#)
 - FromSceneRefAndObjectIndex, [446](#)
 - FromStruct, [447](#)
 - GetHashCode, [447](#)
 - IsCustom, [451](#)
 - IsNone, [451](#)
 - IsPrefab, [451](#)
 - IsSceneObject, [451](#)
 - IsStruct, [451](#)
 - IsValid, [451](#)
 - Kind, [451](#)
 - MAX_SCENE_OBJECT_INDEX, [449](#)
 - operator NetworkObjectTypeId, [447](#)
 - operator!=, [448](#)
 - operator==, [448](#)
 - PlayerData, [452](#)
 - SIZE, [449](#)
 - ToString, [448](#)
- NetworkObjectTypeId.EqualityComparer, [452](#)
 - Equals, [452](#)
 - GetHashCode, [452](#)
- NetworkPhysicsInfo, [453](#)
 - SIZE, [453](#)
 - TimeScale, [453](#)
 - WORD_COUNT, [453](#)
- NetworkPrefabAcquireContext, [454](#)
 - Data, [455](#)
 - DontDestroyOnLoad, [455](#)
 - HasHeader, [456](#)
 - IsSynchronous, [455](#)
 - Meta, [455](#)
 - NetworkPrefabAcquireContext, [454](#)
 - PrefabId, [455](#)
- NetworkPrefabAttribute, [456](#)
- NetworkPrefabId, [456](#)
 - ALIGNMENT, [460](#)
 - AsIndex, [461](#)
 - CompareTo, [458](#)
 - Equals, [458](#)
 - FromIndex, [458](#)
 - FromRaw, [459](#)
 - GetHashCode, [459](#)
 - IsNone, [461](#)
 - IsValid, [461](#)
 - MAX_INDEX, [460](#)
 - operator!=, [459](#)
 - operator==, [459](#)
 - RawValue, [460](#)
 - SIZE, [460](#)
 - ToString, [459](#), [460](#)
- NetworkPrefabId.EqualityComparer, [461](#)
 - Equals, [462](#)
 - GetHashCode, [462](#)
- NetworkPrefabInfo, [462](#)
 - Data, [463](#)
 - HasHeader, [463](#)

- Header, [463](#)
- IsSynchronous, [463](#)
- Prefab, [463](#)
- NetworkPrefabRef, [464](#)
 - ALIGNMENT, [470](#)
 - CompareTo, [466](#)
 - Empty, [471](#)
 - Equals, [467](#)
 - GetHashCode, [467](#)
 - IsValid, [471](#)
 - NetworkPrefabRef, [465](#), [466](#)
 - operator Guid, [468](#)
 - operator NetworkObjectGuid, [468](#)
 - operator NetworkPrefabRef, [468](#)
 - operator!=, [469](#)
 - operator==, [469](#)
 - Parse, [469](#)
 - RawGuidValue, [471](#)
 - SIZE, [471](#)
 - ToString, [469](#), [470](#)
 - ToUnityGuidString, [470](#)
 - TryParse, [470](#)
- NetworkPrefabRef.EqualityComparer, [471](#)
 - Equals, [472](#)
 - GetHashCode, [472](#)
- NetworkPrefabTable, [472](#)
 - AddInstance, [474](#)
 - AddSource, [474](#)
 - Clear, [474](#)
 - Contains, [475](#)
 - GetEntries, [475](#)
 - GetGuid, [475](#)
 - GetId, [475](#)
 - GetInstancesCount, [476](#)
 - GetSource, [476](#), [477](#)
 - IsAcquired, [477](#)
 - Load, [477](#)
 - Options, [480](#)
 - Prefabs, [480](#)
 - RemoveInstance, [478](#)
 - TryAddSource, [478](#)
 - Unload, [479](#)
 - UnloadAll, [479](#)
 - UnloadUnreferenced, [479](#)
 - Version, [480](#)
- NetworkPrefabTable.GetPrefabResult
 - Fusion, [44](#)
- NetworkPrefabTableOptions, [480](#)
 - Default, [481](#)
 - UnloadPrefabOnReleasingLastInstance, [481](#)
 - UnloadUnusedPrefabsOnShutdown, [481](#)
- NetworkProjectConfig, [481](#)
 - AssembliesToWeave, [486](#)
 - BuildTypes, [486](#)
 - CheckNetworkedPropertiesBeingEmpty, [486](#)
 - CheckRpcAttributeUsage, [486](#)
 - CurrentTypeId, [486](#)
 - CurrentVersion, [486](#)
 - DefaultResourceName, [487](#)
 - Deserialize, [484](#)
 - EnqueueIncompleteSynchronousSpawns, [487](#)
 - GetExecutionOrder, [485](#)
 - Global, [490](#)
 - Heap, [487](#)
 - HideNetworkObjectInactivityGuard, [487](#)
 - HostMigration, [487](#)
 - InvokeRenderInBatchMode, [488](#)
 - LagCompensation, [488](#)
 - Multiple, [484](#)
 - Network, [488](#)
 - NetworkConditions, [488](#)
 - NetworkIdsObjectName, [488](#)
 - None, [484](#)
 - NullChecksForNetworkedProperties, [488](#)
 - PeerMode, [489](#)
 - PeerModes, [483](#)
 - PrefabTable, [489](#)
 - ReplicationFeatures, [484](#)
 - Scheduling, [484](#)
 - SchedulingAndInterestManagement, [484](#)
 - Serialize, [485](#)
 - Simulation, [489](#)
 - Single, [484](#)
 - TimeSynchronizationOverride, [489](#)
 - ToString, [485](#)
 - TypeId, [489](#)
 - UnloadGlobal, [485](#)
 - UseSerializableDictionary, [489](#)
 - Version, [490](#)
- NetworkProjectConfigAsset, [490](#)
 - BehaviourMeta, [492](#)
 - Config, [492](#)
 - Global, [492](#)
 - IsGlobalLoaded, [493](#)
 - PrefabOptions, [492](#)
 - Prefabs, [492](#)
 - TryGetGlobal, [491](#)
 - UnloadGlobal, [491](#)
- NetworkProjectConfigAsset.SerializableSimulationBehaviourMeta, [493](#)
 - ExecutionOrder, [493](#)
 - Type, [493](#)
- NetworkReceiveDone
 - Simulation, [711](#)
- NetworkRNG, [494](#)
 - MAX, [498](#)
 - NetworkRNG, [495](#)
 - Next, [495](#)
 - NextExclusive, [495](#)
 - NextInt32, [496](#)
 - NextSingle, [496](#)
 - NextSingleExclusive, [496](#)
 - NextUInt32, [496](#)
 - Peek, [499](#)
 - RangeExclusive, [497](#)
 - RangeInclusive, [497](#), [498](#)

- SIZE, 498
- ToString, 498
- NetworkRpcStaticWeavedInvokerAttribute, 499
 - Key, 500
 - NetworkRpcStaticWeavedInvokerAttribute, 499
- NetworkRpcWeavedInvokerAttribute, 500
 - Key, 501
 - NetworkRpcWeavedInvokerAttribute, 500
 - Sources, 501
 - Targets, 501
- NetworkRunner, 501
 - ActivePlayers, 552
 - AddCallbacks, 511
 - AddGlobal, 511
 - AddPlayerAreaOfInterest, 511
 - Attach, 511, 512
 - AuthenticationValues, 552
 - BuildType, 552
 - BuildTypes, 510
 - CanSpawn, 553
 - ClearPlayerAreaOfInterest, 512
 - Config, 553
 - CurrentConnectionType, 553
 - Debug, 510
 - DeltaTime, 553
 - Despawn, 512
 - DestroySingleton< T >, 513
 - Disconnect, 513
 - EnsureRunnerSceneIsActive, 513
 - Exists, 514
 - FindObject, 514
 - GameMode, 553
 - GetAllBehaviours, 514
 - GetAllBehaviours< T >, 515
 - GetAreaOfInterestGizmoData, 516
 - GetInputForPlayer< T >, 516
 - GetInstancesEnumerator, 516
 - GetInterfaceListHead, 516
 - GetInterfaceListNext, 517
 - GetInterfaceListPrev, 517
 - GetInterfaceListsCount, 517
 - GetPhysicsScene, 518
 - GetPhysicsScene2D, 518
 - GetPlayerActorId, 518
 - GetPlayerConnectionToken, 519
 - GetPlayerConnectionType, 519
 - GetPlayerObject, 519
 - GetPlayerRtt, 520
 - GetPlayerUserId, 520
 - GetRawInputForPlayer, 520
 - GetResumeSnapshotNetworkObjects, 520
 - GetResumeSnapshotNetworkSceneObjects, 521
 - GetRpcTargetStatus, 521
 - GetRunnerForGameObject, 521
 - GetRunnerForScene, 522
 - GetSingleton< T >, 522
 - HasSingleton< T >, 522
 - Instances, 553
 - InstantiateInRunnerScene, 522, 523
 - InstantiateInRunnerScene< T >, 523
 - InvokeSceneLoadDone, 523
 - InvokeSceneLoadStart, 524
 - IsClient, 554
 - IsCloudReady, 554
 - IsConnectedToServer, 554
 - IsFirstTick, 554
 - IsForward, 554
 - IsInterestedIn, 524
 - IsLastTick, 554
 - IsPlayer, 555
 - IsPlayerValid, 524
 - IsResimulation, 555
 - IsResume, 555
 - IsRunning, 555
 - IsSceneAuthority, 555
 - IsSceneManagerBusy, 555
 - IsServer, 556
 - IsSharedModeMasterClient, 556
 - IsShutdown, 556
 - IsSinglePlayer, 556
 - IsStarting, 556
 - JoinSessionLobby, 524
 - LagCompensation, 556
 - LatestServerTick, 557
 - LoadScene, 525, 526
 - LobbyInfo, 557
 - LocalAlpha, 557
 - LocalPlayer, 557
 - LocalRenderTime, 557
 - MakeDontDestroyOnLoad, 526
 - Mode, 557
 - MoveGameObjectToSameScene, 527
 - MoveGameObjectToScene, 527
 - MoveToRunnerScene, 528
 - MoveToRunnerScene< T >, 528
 - NATType, 558
 - ObjectAcquired, 560
 - ObjectDelegate, 528
 - ObjectProvider, 558
 - OnBeforeSpawned, 528
 - Prefabs, 558
 - ProvideInput, 558
 - PushHostMigrationSnapshot, 529
 - RegisterSceneObjects, 529
 - Release, 510
 - RemoteRenderTime, 558
 - RemoveCallbacks, 529
 - RemoveGlobal, 530
 - RemoveSimulationBehavior, 530
 - RenderInternal, 530
 - Running, 510
 - SceneManager, 558
 - SendReliableDataToPlayer, 530
 - SendReliableDataToServer, 531
 - SendRpc, 531
 - SessionInfo, 559

- SetAreaOfInterestCellSize, [532](#)
- SetAreaOfInterestGrid, [532](#)
- SetIsSimulated, [532](#)
- SetMasterClient, [533](#)
- SetPlayerAlwaysInterested, [533](#)
- SetPlayerObject, [533](#)
- Shutdown, [510](#), [534](#)
- SimulationTime, [559](#)
- SimulationUnityScene, [559](#)
- SinglePlayerContinue, [534](#)
- SinglePlayerPause, [534](#)
- Spawn, [534–537](#)
- Spawn< T >, [537](#)
- SpawnAsync, [538–540](#)
- SpawnAsync< T >, [541](#)
- Stage, [559](#)
- StartGame, [542](#)
- Starting, [510](#)
- State, [559](#)
- States, [510](#)
- Tick, [559](#)
- TickRate, [560](#)
- TicksExecuted, [560](#)
- Topology, [560](#)
- TryFindBehaviour, [542](#)
- TryFindBehaviour< T >, [543](#)
- TryFindObject, [543](#)
- TryGetBehaviourStats, [544](#)
- TryGetInputForPlayer< T >, [544](#)
- TryGetNetworkedBehaviourFromNetworkedObjectRef< T >, [544](#)
- TryGetNetworkedBehaviourId, [545](#)
- TryGetObjectRefFromNetworkedBehaviour, [545](#)
- TryGetObjectStats, [546](#)
- TryGetPhysicsInfo, [546](#)
- TryGetPlayerObject, [546](#)
- TryGetPlayerStats, [547](#)
- TryGetSceneInfo, [547](#)
- TryGetSimulationStats, [547](#)
- TrySetPhysicsInfo, [547](#)
- TrySpawn, [548–550](#)
- TrySpawn< T >, [551](#)
- UnloadScene, [552](#)
- UpdateInternal, [552](#)
- UserId, [560](#)
- NetworkRunnerCallbackArgs, [561](#)
- NetworkRunnerCallbackArgs.ConnectRequest, [561](#)
 - Accept, [561](#)
 - Refuse, [562](#)
 - RemoteAddress, [562](#)
 - Waiting, [562](#)
- NetworkRunnerUpdaterDefault, [562](#)
 - RegisterInPlayerLoop, [563](#)
 - RenderSettings, [564](#)
 - UnregisterFromPlayerLoop, [563](#)
 - UpdateSettings, [564](#)
- NetworkRunnerUpdaterDefault.NetworkRunnerRender, [564](#)
- NetworkRunnerUpdaterDefault.NetworkRunnerUpdate, [565](#)
- NetworkRunnerUpdaterDefault.InvokeSettings, [565](#)
 - AddMode, [568](#)
 - Equals, [566](#)
 - GetHashCode, [566](#)
 - operator!=, [566](#)
 - operator==, [567](#)
 - ReferencePlayerLoopSystem, [568](#)
 - ToString, [567](#)
- NetworkSceneAsyncOp, [568](#)
 - AddOnCompleted, [569](#)
 - Error, [572](#)
 - FromAsyncOperation, [569](#)
 - FromCompleted, [570](#)
 - FromCoroutine, [570](#)
 - FromError, [571](#)
 - FromTask, [571](#)
 - GetAwaiter, [571](#)
 - IsDone, [572](#)
 - IsValid, [572](#)
 - SceneRef, [572](#)
- NetworkSceneAsyncOp.Awaiter, [573](#)
 - Awaiter, [573](#)
 - GetResult, [574](#)
 - IsCompleted, [574](#)
 - OnCompleted, [574](#)
- NetworkSceneInfo, [574](#)
 - AddSceneRef, [576](#)
 - Equals, [576](#)
 - GetHashCode, [577](#)
 - IndexOf, [577](#)
 - MaxScenes, [578](#)
 - operator NetworkSceneInfo, [577](#)
 - RemoveSceneRef, [578](#)
 - SceneCount, [579](#)
 - SceneParams, [579](#)
 - Scenes, [579](#)
 - SIZE, [578](#)
 - ToString, [578](#)
 - Version, [579](#)
 - WORD_COUNT, [579](#)
- NetworkSceneInfoChangeSource
 - Fusion, [44](#)
- NetworkSceneInfoDefaultFlags
 - Fusion, [44](#)
- NetworkSceneLoadId, [580](#)
 - Equals, [580](#), [581](#)
 - GetHashCode, [581](#)
 - NetworkSceneLoadId, [580](#)
 - Value, [581](#)
- NetworkSceneObjectId, [582](#)
 - Equals, [582](#), [583](#)
 - GetHashCode, [583](#)
 - IsValid, [584](#)
 - ObjectId, [583](#)
 - Scene, [584](#)
 - SceneLoadId, [584](#)

- [ToString](#), [583](#)
- [NetworkSerialize](#)
 - [NetworkBehaviour](#), [274](#)
- [NetworkSerializeMethodAttribute](#), [584](#)
 - [MaxSize](#), [585](#)
- [NetworkSimulationConfiguration](#), [585](#)
 - [AdditionalJitter](#), [586](#)
 - [AdditionalLoss](#), [587](#)
 - [Clone](#), [586](#)
 - [Create](#), [586](#)
 - [DelayMax](#), [587](#)
 - [DelayMin](#), [587](#)
 - [DelayPeriod](#), [587](#)
 - [DelayShape](#), [587](#)
 - [DelayThreshold](#), [587](#)
 - [Enabled](#), [588](#)
 - [LossChanceMax](#), [588](#)
 - [LossChanceMin](#), [588](#)
 - [LossChancePeriod](#), [588](#)
 - [LossChanceShape](#), [588](#)
 - [LossChanceThreshold](#), [588](#)
- [NetworkSpawnFlags](#)
 - [Fusion](#), [44](#)
- [NetworkSpawnOp](#), [589](#)
 - [GetAwaiter](#), [590](#)
 - [IsFailed](#), [590](#)
 - [IsQueued](#), [590](#)
 - [IsSpawned](#), [590](#)
 - [Object](#), [590](#)
 - [Runner](#), [590](#)
 - [Status](#), [591](#)
- [NetworkSpawnOp.Awaiter](#), [591](#)
 - [Awaiter](#), [591](#)
 - [GetResult](#), [592](#)
 - [IsCompleted](#), [592](#)
 - [OnCompleted](#), [592](#)
- [NetworkSpawnStatus](#)
 - [Fusion](#), [45](#)
- [NetworkString](#)
 - [NetworkString< TSize >](#), [596](#)
- [NetworkString< TSize >](#), [593](#)
 - [Assign](#), [596](#)
 - [Capacity](#), [618](#)
 - [Compare](#), [596](#), [597](#)
 - [Compare< TOtherSize >](#), [597](#), [598](#)
 - [Contains](#), [598](#), [599](#)
 - [Contains< TOtherSize >](#), [600](#)
 - [EndsWith](#), [601](#)
 - [EndsWith< TOtherSize >](#), [601](#)
 - [Equals](#), [602](#), [603](#)
 - [Equals< TOtherSize >](#), [603](#), [604](#)
 - [Get](#), [604](#)
 - [GetCapacity< TSize >](#), [605](#)
 - [GetCharCount](#), [605](#)
 - [GetEnumerator](#), [605](#)
 - [GetHashCode](#), [605](#)
 - [IndexOf](#), [606–608](#)
 - [IndexOf< TOtherSize >](#), [609–611](#)
 - [Length](#), [618](#)
 - [NetworkString](#), [596](#)
 - [operator NetworkString< TSize >](#), [611](#)
 - [operator string](#), [612](#)
 - [operator !=](#), [612](#), [613](#)
 - [operator ==](#), [613](#), [614](#)
 - [Set](#), [614](#)
 - [StartsWith](#), [615](#)
 - [StartsWith< TOtherSize >](#), [615](#)
 - [Substring](#), [616](#)
 - [this\[int index\]](#), [618](#)
 - [ToLower](#), [617](#)
 - [ToString](#), [617](#)
 - [ToUpper](#), [617](#)
 - [Value](#), [618](#)
- [NetworkStructUtils](#), [618](#)
 - [GetWordCount< T >](#), [619](#)
- [NetworkStructWeavedAttribute](#), [619](#)
 - [NetworkStructWeavedAttribute](#), [620](#)
 - [WordCount](#), [620](#)
- [NetworkTransform](#), [620](#)
 - [AutoUpdateAreaOfInterestOverride](#), [623](#)
 - [DisableSharedModelInterpolation](#), [622](#)
 - [SetAreaOfInterestOverride](#), [621](#)
 - [SyncParent](#), [622](#)
 - [SyncScale](#), [622](#)
 - [Teleport](#), [622](#)
- [NetworkTRSP](#), [623](#)
 - [Data](#), [625](#)
 - [IsMainTRSP](#), [626](#)
 - [Render](#), [624](#)
 - [ResolveAOIOVERRIDE](#), [624](#)
 - [SetAreaOfInterestOverride](#), [625](#)
 - [SetParentTransform](#), [625](#)
 - [State](#), [626](#)
 - [Teleport](#), [625](#)
- [NetworkTRSPData](#), [626](#)
 - [AreaOfInterestOverride](#), [627](#)
 - [NonNetworkedParent](#), [629](#)
 - [Parent](#), [627](#)
 - [Position](#), [627](#)
 - [POSITION_OFFSET](#), [627](#)
 - [Rotation](#), [628](#)
 - [Scale](#), [628](#)
 - [SIZE](#), [628](#)
 - [TeleportKey](#), [628](#)
 - [WORDS](#), [628](#)
- [NetworkTypeId](#)
 - [NetworkObject](#), [405](#)
- [NetworkTypeIdKind](#)
 - [Fusion](#), [45](#)
- [NetworkUnwrap](#)
 - [NetworkBehaviour](#), [275](#)
 - [NetworkObject](#), [402](#)
- [NetworkWrap](#)
 - [NetworkBehaviour](#), [275](#)
 - [NetworkObject](#), [402](#)
- [Next](#)

- NetworkRNG, [495](#)
- Tick, [787](#)
- NextExclusive
 - NetworkRNG, [495](#)
- NextInt32
 - NetworkRNG, [496](#)
- NextSingle
 - NetworkRNG, [496](#)
- NextSingleExclusive
 - NetworkRNG, [496](#)
- NextUInt32
 - NetworkRNG, [496](#)
- NoActiveConnections
 - Fusion, [48](#)
- NONE
 - AuthorityMasks, [87](#)
- None
 - Fusion, [41–44](#), [48](#), [52](#)
 - Fusion.LagCompensation, [57](#)
 - NetworkBehaviourId, [313](#)
 - NetworkProjectConfig, [484](#)
 - PlayerRef, [637](#)
 - SceneRef, [692](#)
 - TickTimer, [813](#)
- NonNetworkedParent
 - NetworkTRSPData, [629](#)
- Normal
 - LagCompensatedHit, [208](#)
 - LagCompensationUtils.ContactData, [221](#)
- Normalized
 - Fusion, [52](#)
- NormalizedPercentage
 - Fusion, [52](#)
- NormalizedRectAttribute, [629](#)
 - AspectRatio, [630](#)
 - InvertY, [630](#)
 - NormalizedRectAttribute, [629](#)
- NoSimulation
 - Simulation, [711](#)
- NotCulled
 - Fusion, [48](#)
- NotEqual
 - Fusion, [41](#)
- NotFound
 - Fusion, [44](#)
 - TickRate, [799](#)
- Notify
 - NetConfig, [774](#)
- NotifyLocalSimulationNotAllowedToSendRpc
 - NetworkBehaviourUtils, [323](#)
- NotifyLocalTargetedRpcCulled
 - NetworkBehaviourUtils, [323](#)
- NotifyNetworkUnwrapFailed< T >
 - NetworkBehaviourUtils, [324](#)
- NotifyNetworkWrapFailed< T >
 - NetworkBehaviourUtils, [324](#)
- NotifyRpcTargetUnreachable
 - NetworkBehaviourUtils, [325](#)
- NotInvokableDuringResim
 - Fusion, [47](#), [48](#)
- NotInvokableLocally
 - Fusion, [47](#)
- NotSentBroadcastNoActiveConnections
 - Fusion, [48](#)
- NotSentBroadcastNoConfirmedNorInterestedClients
 - Fusion, [48](#)
- NotSentTargetClientNotAvailable
 - Fusion, [48](#)
- NotSentTargetObjectNotConfirmed
 - Fusion, [48](#)
- NotSentTargetObjectNotInPlayerInterest
 - Fusion, [48](#)
- NotZero
 - Fusion, [41](#)
- Null
 - Ptr, [643](#)
- NullChecksForNetworkedProperties
 - NetworkProjectConfig, [488](#)
- Object
 - NetworkBehaviourId, [313](#)
 - NetworkObjectReleaseContext, [438](#)
 - NetworkSpawnOp, [590](#)
 - RpcHeader, [675](#)
 - SimulationBehaviour, [725](#)
- ObjectAcquired
 - NetworkRunner, [560](#)
- ObjectCount
 - Simulation, [716](#)
- ObjectDataConsistency
 - SimulationConfig, [729](#)
- ObjectDelegate
 - NetworkRunner, [528](#)
- ObjectId
 - NetworkSceneObjectId, [583](#)
- ObjectInitializer
 - StartGameArgs, [780](#)
- ObjectProvider
 - NetworkRunner, [558](#)
 - StartGameArgs, [780](#)
- Objects
 - Simulation, [717](#)
- ObjectsCount
 - SimulationStats, [758](#)
- ObjectsGlobalCount
 - SimulationStats, [759](#)
- ObjectsPredictedCount
 - SimulationStats, [759](#)
- Offset
 - ColliderDrawInfo, [217](#)
 - Hitbox, [127](#)
 - HitboxRoot, [147](#)
 - SimulationMessage, [752](#)
- offset
 - NetworkBehaviour, [278](#)
- Ok
 - Fusion, [50](#)

- StartGameResult, 783
- TickRate, 799
- OnBeforeSpawned
 - NetworkRunner, 528
- OnCompleted
 - NetworkSceneAsyncOp.Awaiter, 574
 - NetworkSpawnOp.Awaiter, 592
- OnConnectedToServer
 - INetworkRunnerCallbacks, 173
- OnConnectFailed
 - INetworkRunnerCallbacks, 173
- OnConnectRequest
 - INetworkRunnerCallbacks, 173
- OnCustomAuthenticationResponse
 - INetworkRunnerCallbacks, 174
- OnDestroy
 - NetworkObject, 403
- OnDisconnectedFromServer
 - INetworkRunnerCallbacks, 174
- OnDrawGizmos
 - Hitbox, 126
 - HitboxRoot, 145
- OnGameStarted
 - StartGameArgs, 781
- OnHostMigration
 - INetworkRunnerCallbacks, 174
- OnInput
 - INetworkRunnerCallbacks, 174
- OnInputMissing
 - INetworkRunnerCallbacks, 175
- OnObjectEnterAOI
 - INetworkRunnerCallbacks, 175
- OnObjectExitAOI
 - INetworkRunnerCallbacks, 175
- OnPlayerJoined
 - INetworkRunnerCallbacks, 176
- OnPlayerLeft
 - INetworkRunnerCallbacks, 176
- OnReliableDataProgress
 - INetworkRunnerCallbacks, 176
- OnReliableDataReceived
 - INetworkRunnerCallbacks, 177
- OnSceneInfoChanged
 - INetworkSceneManager, 182
- OnSceneLoadDone
 - INetworkRunnerCallbacks, 177
- OnSceneLoadStart
 - INetworkRunnerCallbacks, 177
- OnSessionListUpdated
 - INetworkRunnerCallbacks, 177
- OnShutdown
 - INetworkRunnerCallbacks, 178
- OnUserSimulationMessage
 - INetworkRunnerCallbacks, 178
- OpenInternet
 - Fusion.Sockets.Stun, 60
- OperationCanceled
 - Fusion, 51
- OperationExpireTime
 - NetConfig, 774
- OperationTimeout
 - Fusion, 51
- operator Angle
 - Angle, 79, 80
- operator bool
 - NetworkBehaviourBuffer, 292
 - NetworkBehaviourBufferInterpolator, 304
 - NetworkBool, 334
 - NetworkId, 370
 - Ptr, 640
 - SessionInfo, 699
 - Tick, 788
- operator double
 - Angle, 80
- operator float
 - Angle, 80
 - FloatCompressed, 119
- operator FloatCompressed
 - FloatCompressed, 120
- operator Guid
 - NetworkObjectGuid, 416
 - NetworkPrefabRef, 468
- operator int
 - Tick, 788
- operator LagCompensatedHit
 - LagCompensatedHit, 206, 207
- operator Mask256
 - FieldsMask< T >, 107
- operator NetworkArray< T >
 - NetworkBehaviourUtils.ArrayInitializer< T >, 328
- operator NetworkArrayReadOnly< T >
 - NetworkArray< T >, 253
- operator NetworkBehaviourId
 - NetworkBehaviour, 275
- operator NetworkBool
 - NetworkBool, 334
- operator NetworkDictionary< K, V >
 - NetworkBehaviourUtils.DictionaryInitializer< K, V >, 330
- operator NetworkDictionaryReadOnly< K, V >
 - NetworkDictionary< K, V >, 353
- operator NetworkId
 - NetworkObject, 403
- operator NetworkLinkedList< T >
 - NetworkBehaviourUtils.ArrayInitializer< T >, 329
- operator NetworkObjectGuid
 - NetworkObjectGuid, 417
 - NetworkPrefabRef, 468
- operator NetworkObjectTypeId
 - NetworkObjectTypeId, 447
- operator NetworkPrefabRef
 - NetworkObjectGuid, 417
 - NetworkPrefabRef, 468
- operator NetworkSceneInfo
 - NetworkSceneInfo, 577
- operator NetworkString< TSize >

- NetworkString< TSize >, 611
- operator Quaternion
 - QuaternionCompressed, 646
- operator QuaternionCompressed
 - QuaternionCompressed, 647
- operator string
 - NetworkString< TSize >, 612
- operator Tick
 - Tick, 788
- operator Vector2
 - Vector2Compressed, 825
 - Vector3Compressed, 830
- operator Vector2Compressed
 - Vector2Compressed, 826
- operator Vector3
 - Vector3Compressed, 830
- operator Vector3Compressed
 - Vector3Compressed, 831
- operator Vector4
 - Vector4Compressed, 835
- operator Vector4Compressed
 - Vector4Compressed, 836
- operator!=
 - Angle, 81
 - FloatCompressed, 120
 - NetworkBehaviourId, 311
 - NetworkId, 370
 - NetworkLoadSceneParameters, 393
 - NetworkObjectGuid, 417
 - NetworkObjectHeader, 425
 - NetworkObjectTypeId, 448
 - NetworkPrefabId, 459
 - NetworkPrefabRef, 469
 - NetworkRunnerUpdaterDefaultInvokeSettings, 566
 - NetworkString< TSize >, 612, 613
 - PlayerRef, 633
 - Ptr, 641
 - QuaternionCompressed, 647
 - SceneRef, 690
 - Tick, 790
 - Vector2Compressed, 826
 - Vector3Compressed, 832
 - Vector4Compressed, 836
- operator<
 - Angle, 82
 - Tick, 790
- operator<=
 - Angle, 82
 - Tick, 790
- operator>
 - Angle, 83
 - Tick, 790
- operator>=
 - Angle, 84
 - Tick, 791
- operator+
 - Angle, 81
 - Ptr, 641
- operator-
 - Angle, 81
 - Ptr, 642
- operator==
 - Angle, 83
 - FloatCompressed, 121
 - NetworkBehaviourId, 312
 - NetworkId, 370
 - NetworkLoadSceneParameters, 393
 - NetworkObjectGuid, 417
 - NetworkObjectHeader, 425
 - NetworkObjectTypeId, 448
 - NetworkPrefabId, 459
 - NetworkPrefabRef, 469
 - NetworkRunnerUpdaterDefaultInvokeSettings, 567
 - NetworkString< TSize >, 613, 614
 - PlayerRef, 634
 - Ptr, 642
 - QuaternionCompressed, 648
 - SceneRef, 690
 - Tick, 790
 - Vector2Compressed, 827
 - Vector3Compressed, 832
 - Vector4Compressed, 837
- Optimize
 - LagCompensationSettings, 239
- Options
 - NetworkPrefabTable, 480
 - Query, 225
 - QueryParams, 227
- order
 - UnityContextMenuUItemAttribute, 815
 - UnityDelayedAttribute, 816
 - UnityHeaderAttribute, 818
 - UnityMinAttribute, 818
 - UnityMultilineAttribute, 819
 - UnityNonReorderableAttribute, 820
 - UnityRangeAttribute, 821
 - UnitySpaceAttribute, 822
 - UnityTooltipAttribute, 823
- Origin
 - RaycastQuery, 231
 - RaycastQueryParams, 233
- OutBandwidth
 - NetworkObjectStats, 443
 - SimulationStats, 759
- OutMessagesBandwidth
 - SimulationConnectionStats, 732
- OutMessagesPerPacket
 - SimulationConnectionStats, 733
- OutObjectBandwidth
 - SimulationConnectionStats, 733
- OutObjectDestroysPerPacket
 - SimulationConnectionStats, 733
- OutObjectUpdatesPerPacket
 - SimulationConnectionStats, 733
- OutPackets
 - SimulationStats, 759

- OutPacketsBandwidth
 - SimulationConnectionStats, [733](#)
- OutPacketsDelivered
 - SimulationConnectionStats, [733](#)
- OutPacketsLost
 - SimulationConnectionStats, [733](#)
- OutPacketsSent
 - SimulationConnectionStats, [733](#)
- OutReliableDataBandwidth
 - SimulationConnectionStats, [734](#)
- OutUpdates
 - NetworkObjectStats, [443](#)
- OverlapBox
 - HitboxManager, [131](#), [132](#)
- OverlapSphere
 - HitboxManager, [133–135](#)
- Packets
 - Fusion, [52](#)
- PacketSize
 - NetConfig, [774](#)
- PacketSizeInBits
 - NetConfig, [775](#)
- PageCount
 - HeapConfiguration, [124](#)
- PageShift
 - HeapConfiguration, [124](#)
- PageSizes
 - Fusion, [45](#)
- Parent
 - NetworkTRSPData, [627](#)
- Parse
 - NetworkObjectGuid, [418](#)
 - NetworkPrefabRef, [469](#)
- Peek
 - NetworkRNG, [499](#)
- PeerMode
 - NetworkProjectConfig, [489](#)
- PeerModes
 - NetworkProjectConfig, [483](#)
- Pending
 - TickAccumulator, [797](#)
- Penetration
 - LagCompensationUtils.ContactData, [221](#)
- Percentage
 - Fusion, [52](#)
- PerSecond
 - Fusion, [52](#)
- PhotonCloudTimeout
 - Fusion, [51](#)
- PhysX
 - Fusion.LagCompensation, [57](#)
- Player
 - Fusion, [46](#)
 - Query, [225](#)
 - QueryParams, [227](#)
 - SimulationInput, [736](#)
- PLAYER_DATA_WORD
 - NetworkObjectHeader, [427](#)
- PlayerCount
 - SessionInfo, [701](#)
 - SimulationConfig, [729](#)
 - StartGameArgs, [781](#)
- PlayerData
 - NetworkObjectTypeId, [452](#)
- PlayerId
 - PlayerRef, [637](#)
- PlayerJoined
 - IPlayerJoined, [200](#)
- PlayerLeft
 - IPlayerLeft, [201](#)
- PlayerMaxCount
 - SimulationRuntimeConfig, [755](#)
- PlayerRef, [630](#)
 - AsIndex, [636](#)
 - Comparer, [636](#)
 - Equals, [632](#)
 - FromEncoded, [632](#)
 - FromIndex, [633](#)
 - GetHashCode, [633](#)
 - IsMasterClient, [636](#)
 - IsNone, [636](#)
 - IsRealPlayer, [637](#)
 - MASTER_CLIENT_RAW, [635](#)
 - MasterClient, [637](#)
 - None, [637](#)
 - operator!=, [633](#)
 - operator==, [634](#)
 - PlayerId, [637](#)
 - RawEncoded, [637](#)
 - Read, [634](#)
 - SIZE, [636](#)
 - ToString, [634](#)
 - Write, [635](#)
 - Write< T >, [635](#)
- PlayersCount
 - SimulationStats, [759](#)
- Point
 - LagCompensatedHit, [208](#)
 - LagCompensationUtils.ContactData, [222](#)
- PosBlendEnd
 - InterpolatedErrorCorrectionSettings, [198](#)
- PosBlendStart
 - InterpolatedErrorCorrectionSettings, [198](#)
- Position
 - Hitbox, [128](#)
 - NetworkTRSPData, [627](#)
- POSITION_OFFSET
 - NetworkTRSPData, [627](#)
- PositionRotation
 - HitboxManager, [136](#)
- PositionRotationQueryParams, [222](#)
 - Hitbox, [223](#)
 - PositionRotationQueryParams, [222](#)
 - QueryParams, [223](#)
- PosMinCorrection
 - InterpolatedErrorCorrectionSettings, [198](#)

- PosTeleportDistance
 - InterpolatedErrorCorrectionSettings, [199](#)
- Prefab
 - Fusion, [45](#)
 - NetworkPrefabInfo, [463](#)
- PrefabId
 - NetworkPrefabAcquireContext, [455](#)
- PrefabOptions
 - NetworkProjectConfigAsset, [492](#)
- Prefabs
 - NetworkPrefabTable, [480](#)
 - NetworkProjectConfigAsset, [492](#)
 - NetworkRunner, [558](#)
- PrefabTable
 - NetworkProjectConfig, [489](#)
- PreProcessingDelegate
 - Fusion.LagCompensation, [57](#)
 - Query, [225](#)
 - QueryParams, [227](#)
- PreserveInPluginAttribute, [638](#)
 - PreserveInPluginAttribute, [638](#)
- PriorityCallback
 - NetworkObject, [406](#)
- PriorityLevel
 - Fusion, [46](#)
- PriorityLevelDelegate
 - NetworkObject, [403](#)
- ProjectConfig
 - Simulation, [717](#)
- Properties
 - SessionInfo, [701](#)
- PropertyName
 - DefaultForPropertyAttribute, [93](#)
- PropertyReader
 - NetworkBehaviour.PropertyReader< T >, [290](#)
- ProvideInput
 - NetworkRunner, [558](#)
- Proxies
 - Fusion, [49](#)
- PROXY
 - AuthorityMasks, [88](#)
- Ptr, [638](#)
 - Address, [643](#)
 - Equals, [640](#)
 - GetHashCode, [640](#)
 - NetworkObjectHeaderPtr, [429](#)
 - Null, [643](#)
 - operator bool, [640](#)
 - operator !=, [641](#)
 - operator +, [641](#)
 - operator -, [642](#)
 - operator ==, [642](#)
 - SIZE, [643](#)
 - ToString, [642](#)
- Ptr.EqualityComparer, [643](#)
 - Equals, [644](#)
 - GetHashCode, [644](#)
- PushHostMigrationSnapshot
 - NetworkRunner, [529](#)
- Quaternion
 - NetworkBehaviourBufferInterpolator, [304](#), [305](#)
- QuaternionCompressed, [644](#)
 - Equals, [646](#)
 - GetHashCode, [646](#)
 - operator Quaternion, [646](#)
 - operator QuaternionCompressed, [647](#)
 - operator !=, [647](#)
 - operator ==, [648](#)
 - W, [649](#)
 - wEncoded, [648](#)
 - X, [649](#)
 - xEncoded, [648](#)
 - Y, [649](#)
 - yEncoded, [648](#)
 - Z, [649](#)
 - zEncoded, [649](#)
- Query, [223](#)
 - Alpha, [225](#)
 - Check, [224](#)
 - LayerMask, [225](#)
 - Options, [225](#)
 - Player, [225](#)
 - PreProcessingDelegate, [225](#)
 - Query, [224](#)
 - Tick, [225](#)
 - TickTo, [226](#)
 - TriggerInteraction, [226](#)
 - UserArgs, [226](#)
- QueryParams, [226](#)
 - Alpha, [227](#)
 - BoxOverlapQueryParams, [214](#)
 - LayerMask, [227](#)
 - Options, [227](#)
 - Player, [227](#)
 - PositionRotationQueryParams, [223](#)
 - PreProcessingDelegate, [227](#)
 - RaycastQueryParams, [233](#)
 - SphereOverlapQueryParams, [237](#)
 - Tick, [227](#)
 - TickTo, [228](#)
 - TriggerInteraction, [228](#)
 - UserArgs, [228](#)
- Queued
 - Fusion, [45](#)
- Radians
 - Fusion, [52](#)
- RadiansPerSecond
 - Fusion, [52](#)
- Radius
 - ColliderDrawInfo, [217](#)
 - SphereOverlapQuery, [236](#)
 - SphereOverlapQueryParams, [237](#)
- RangeExclusive
 - NetworkRNG, [497](#)
- RangeInclusive

- NetworkRNG, [497](#), [498](#)
- Raw
 - NetworkId, [372](#)
 - Tick, [791](#)
- RawEncoded
 - PlayerRef, [637](#)
- RawGuidValue
 - NetworkObjectGuid, [419](#)
 - NetworkPrefabRef, [471](#)
- RawValue
 - NetworkPrefabId, [460](#)
 - SceneRef, [691](#)
- Raycast
 - HitboxManager, [137](#), [138](#)
- RaycastAll
 - HitboxManager, [139](#), [140](#)
- RaycastAllQuery, [228](#)
 - RaycastAllQuery, [229](#)
- RaycastQuery, [229](#)
 - Check, [230](#)
 - Direction, [231](#)
 - Length, [231](#)
 - Origin, [231](#)
 - RaycastQuery, [230](#)
- RaycastQueryParams, [231](#)
 - Direction, [233](#)
 - Length, [233](#)
 - Origin, [233](#)
 - QueryParams, [233](#)
 - RaycastQueryParams, [232](#)
 - StaticHitsCapacity, [233](#)
- Read
 - IEnumeratorReaderWriter< T >, [160](#)
 - IUnitySurrogate, [185](#)
 - NetworkBehaviour.ArrayReader< T >, [281](#)
 - NetworkBehaviour.BehaviourReader< T >, [282](#)
 - NetworkBehaviour.DictionaryReader< K, V >, [288](#)
 - NetworkBehaviour.LinkListReader< T >, [289](#)
 - NetworkBehaviour.PropertyReader< T >, [290](#)
 - NetworkBehaviourBuffer, [292](#), [293](#)
 - NetworkId, [371](#)
 - PlayerRef, [634](#)
 - RpcHeader, [674](#)
 - UnityArraySurrogate< T, ReaderWriter >, [188](#)
 - UnityDictionarySurrogate< KeyType, KeyReaderWriter, ValueType, ValueReaderWriter >, [190](#)
 - UnityLinkedListSurrogate< T, ReaderWriter >, [192](#)
 - UnitySurrogateBase, [194](#)
 - UnityValueSurrogate< T, TReaderWriter >, [196](#)
- Read< T >
 - NetworkBehaviourBuffer, [295](#)
- ReadBoolean
 - ReadWriteUtilsForWeaver, [659](#)
- ReadFloat
 - ReadWriteUtils, [650](#)
- ReadInt
 - SimulationMessage, [746](#)
- ReadNetworkBehaviourRef
 - ReadWriteUtils, [652](#)
- ReadNetworkedObjectRef
 - SimulationMessage, [746](#)
- ReadQuaternion
 - ReadWriteUtils, [652](#)
- ReadRef
 - IEnumeratorReaderWriter< T >, [161](#)
- ReadSize
 - RpcHeader, [674](#)
- ReadStringUtf32NoHash
 - ReadWriteUtilsForWeaver, [659](#)
- ReadStringUtf32WithHash
 - ReadWriteUtilsForWeaver, [660](#)
- ReadStringUtf8NoHash
 - ReadWriteUtilsForWeaver, [660](#)
- ReadVector2
 - ReadWriteUtils, [652](#)
- ReadVector3
 - ReadWriteUtils, [653](#)
 - SimulationMessage, [747](#)
- ReadVector4
 - ReadWriteUtils, [653](#)
- ReadWriteUtils, [650](#)
 - ACCURACY, [657](#)
 - ReadFloat, [650](#)
 - ReadNetworkBehaviourRef, [652](#)
 - ReadQuaternion, [652](#)
 - ReadVector2, [652](#)
 - ReadVector3, [653](#)
 - ReadVector4, [653](#)
 - WriteEmptyNetworkBehaviourRef, [654](#)
 - WriteFloat, [654](#)
 - WriteNetworkBehaviourRef, [654](#)
 - WriteNullBehaviourRef, [654](#)
 - WriteQuaternion, [655](#)
 - WriteVector2, [655](#)
 - WriteVector3, [655](#)
 - WriteVector4, [657](#)
- ReadWriteUtilsForWeaver, [657](#)
 - GetByteCountUtf8NoHash, [658](#)
 - GetWordCountString, [658](#)
 - ReadBoolean, [659](#)
 - ReadStringUtf32NoHash, [659](#)
 - ReadStringUtf32WithHash, [660](#)
 - ReadStringUtf8NoHash, [660](#)
 - VerifyRawNetworkUnwrap< T >, [660](#)
 - VerifyRawNetworkWrap< T >, [661](#)
 - WriteBoolean, [661](#)
 - WriteStringUtf32NoHash, [662](#)
 - WriteStringUtf32WithHash, [662](#)
 - WriteStringUtf8NoHash, [663](#)
- Redundancy
 - SimulationConfig, [728](#)
- ReferenceCountAdd
 - SimulationMessage, [747](#)
- ReferenceCountSub
 - SimulationMessage, [747](#)
- ReferencePlayerLoopSystem

- NetworkRunnerUpdaterDefaultInvokeSettings, 568
- References
 - SimulationMessage, 752
- ReflectionUtils, 663
 - GetAllNetworkBehaviourTypes, 664
 - GetAllSimulationBehaviourTypes, 664
 - GetAllWeavedAssemblies, 664
 - GetAllWeavedNetworkBehaviourTypes, 664
 - GetAllWeavedSimulationBehaviourTypes, 664
 - GetAllWeaverGeneratedTypes, 665
 - GetCustomAttributeOrThrow< T >, 665
 - GetWeavedAttributeOrThrow, 666
- Refuse
 - NetworkRunnerCallbackArgs.ConnectRequest, 562
- Region
 - LobbyInfo, 240
 - SessionInfo, 701
- RegisterInPlayerLoop
 - NetworkRunnerUpdaterDefault, 563
- RegisterMetaData
 - NetworkBehaviourUtils, 325
- RegisterRpcInvokeDelegates
 - NetworkBehaviourUtils, 325
- RegisterSceneObjects
 - NetworkRunner, 529
- ReinitializeHitboxesBeforeRegistration
 - HitboxRoot, 144
- ReinterpretState< T >
 - NetworkBehaviour, 277
 - NetworkBehaviourBuffer, 296
- Relayed
 - Fusion, 41
- Release
 - INetworkAssetSource< T >, 166
 - NetworkRunner, 510
- ReleaseInstance
 - INetworkObjectProvider, 171
- ReleaseStateAuthority
 - NetworkObject, 404
- Reliable
 - Fusion, 47
- ReliableDataTransferModes
 - NetworkConfiguration, 346
- ReliableDataTransfers
 - NetworkConfiguration, 345
- Remainder
 - TickAccumulator, 797
- RemainingTicks
 - TickTimer, 811
- RemainingTime
 - TickTimer, 812
- Remap
 - NetworkLinkedList< T >, 384
- Remote
 - Fusion, 44, 46, 49
- RemoteAddress
 - NetworkRunnerCallbackArgs.ConnectRequest, 562
- RemoteAlpha
 - Simulation, 717
- RemotePrefabCreated
 - IRemotePrefabCreated, 201
- RemoteRenderTime
 - NetworkRunner, 558
- RemoteTick
 - Simulation, 717
- RemoteTickPrevious
 - Simulation, 717
- Remove
 - NetBitBufferList, 767
 - NetworkDictionary< K, V >, 353
 - NetworkLinkedList< T >, 385
 - SerializableDictionary< TKey, TValue >, 695
 - SimulationInput.Buffer, 739
- RemoveCallbacks
 - NetworkRunner, 529
- RemoveGlobal
 - NetworkRunner, 530
- RemoveHead
 - NetBitBufferList, 767
- RemoveInputAuthority
 - NetworkObject, 404
- RemoveInstance
 - NetworkPrefabTable, 478
- RemoveSceneRef
 - NetworkSceneInfo, 578
- RemoveSimulationBehavior
 - NetworkRunner, 530
- Render
 - NetworkTRSP, 624
 - SimulationBehaviour, 724
- RenderAttribute, 666
 - Method, 667
 - RenderAttribute, 667
 - Source, 667
 - Timeframe, 667
- RenderExecutionTime
 - BehaviourStats, 91
- RenderInternal
 - NetworkRunner, 530
- RenderInvocations
 - BehaviourStats, 91
- RenderSettings
 - NetworkRunnerUpdaterDefault, 564
- RenderSource
 - Fusion, 46
 - NetworkObject, 408
- RenderTime
 - NetworkObject, 408
- RenderTimeframe
 - Fusion, 46
 - NetworkObject, 408
- RenderTimeline, 668
 - GetRenderBuffers, 668

- RenderWeavedAttribute, 669
 - RenderWeavedAttribute, 669
- REPLICATE_WORD_ALIGN
 - Allocator, 70
- REPLICATE_WORD_SHIFT
 - Allocator, 71
- REPLICATE_WORD_SIZE
 - Allocator, 71
- ReplicateTo
 - NetworkBehaviour, 277
 - NetworkObject, 406
- ReplicateToDelegate
 - NetworkObject, 404
- ReplicationFeatures
 - NetworkProjectConfig, 484
 - SimulationConfig, 729
- RequestStateAuthority
 - NetworkObject, 404
- Reset
 - FixedArray< T >.Enumerator, 115
 - NetworkArray< T >.Enumerator, 256
 - NetworkBehaviour.ChangeDetector.Enumerator, 287
 - NetworkDictionary< K, V >.Enumerator, 356
 - NetworkLinkedList< T >.Enumerator, 387
 - NetworkObjectStats, 442
 - SerializableDictionary< TKey, TValue >, 696
- ResetState
 - NetworkBehaviour, 278
- Resimulate
 - Fusion, 51
- Resimulations
 - SimulationStats, 759
- Resolve
 - TickRate, 802
- ResolveAOIOVERRIDE
 - NetworkTRSP, 624
- ResolveNetworkPrefabSourceAttribute, 669
- Result
 - RpcSendResult, 682
- Retry
 - Fusion, 43
- Root
 - Hitbox, 127
- RootGameObjects
 - SceneLoadDoneArgs, 684
- Rotation
 - BoxOverlapQuery, 212
 - BoxOverlapQueryParams, 214
 - NetworkTRSPData, 628
- RotBlendEnd
 - InterpolatedErrorCorrectionSettings, 199
- RotBlendStart
 - InterpolatedErrorCorrectionSettings, 199
- RotTeleportRadians
 - InterpolatedErrorCorrectionSettings, 199
- RoundTripTime
 - SimulationConnectionStats, 734
- SimulationStats, 760
- RpcAttribute, 669
 - Channel, 671
 - HostMode, 671
 - InvokeLocal, 671
 - RpcAttribute, 670, 671
 - Sources, 671
 - Targets, 672
 - TickAligned, 672
- RpcChannel
 - Fusion, 47
- RpcHeader, 672
 - Behaviour, 675
 - Create, 673
 - Method, 675
 - Object, 675
 - Read, 674
 - ReadSize, 674
 - SIZE, 676
 - ToString, 674
 - Write, 675
- RpcHostMode
 - Fusion, 47
- RpcInfo, 676
 - Channel, 678
 - FromLocal, 677
 - FromMessage, 677
 - IsInvokeLocal, 678
 - Source, 678
 - Tick, 678
 - ToString, 677
- RpcInvokeData, 678
 - Delegate, 679
 - Key, 679
 - Sources, 680
 - Targets, 680
 - ToString, 679
- RpcInvokeDelegate
 - Fusion, 54
- RpcInvokeInfo, 680
 - LocalInvokeResult, 681
 - SendCullResult, 681
 - SendResult, 681
 - ToString, 681
- RpcLocalInvokeResult
 - Fusion, 47
- RpcSendCullResult
 - Fusion, 47
- RpcSendMessageResult
 - Fusion, 48
- RpcSendResult, 682
 - MessageSize, 682
 - Result, 682
 - ToString, 682
- RpcSources
 - Fusion, 48
- RpcStaticInvokeDelegate
 - Fusion, 54

- RpcTargetAttribute, [683](#)
 - RpcTargetAttribute, [683](#)
- RpcTargets
 - Fusion, [49](#)
- RpcTargetStatus
 - Fusion, [49](#)
- Run
 - TaskManager, [86](#)
- Runner
 - NetworkObject, [408](#)
 - NetworkSpawnOp, [590](#)
 - SimulationBehaviour, [725](#)
- Running
 - NetworkRunner, [510](#)
 - TickAccumulator, [797](#)
- Scale
 - NetworkTRSPData, [628](#)
- Scene
 - NetworkSceneObjectId, [584](#)
 - SceneLoadDoneArgs, [684](#)
 - StartGameArgs, [781](#)
- SceneCount
 - NetworkSceneInfo, [579](#)
- SceneCountMask
 - Fusion, [44](#)
- SceneLoadDone
 - ISceneLoadDone, [202](#)
- SceneLoadDoneArgs, [683](#)
 - RootGameObjects, [684](#)
 - Scene, [684](#)
 - SceneLoadDoneArgs, [684](#)
 - SceneObjects, [685](#)
 - SceneRef, [685](#)
- SceneLoadId
 - NetworkSceneObjectId, [584](#)
- SceneLoadStart
 - ISceneLoadStart, [203](#)
- SceneManager
 - NetworkRunner, [558](#)
 - StartGameArgs, [781](#)
- SceneObject
 - Fusion, [45](#)
- SceneObjects
 - SceneLoadDoneArgs, [685](#)
- SceneParams
 - NetworkSceneInfo, [579](#)
- SceneRef, [685](#)
 - AsIndex, [692](#)
 - AsPathHash, [692](#)
 - Equals, [686](#), [687](#)
 - FLAG_ADDRESSABLE, [691](#)
 - FromIndex, [687](#)
 - FromPath, [687](#)
 - FromRaw, [688](#)
 - GetHashCode, [688](#)
 - IsIndex, [692](#)
 - IsPath, [688](#)
 - IsValid, [692](#)
 - NetworkSceneAsyncOp, [572](#)
 - None, [692](#)
 - operator!=, [690](#)
 - operator==, [690](#)
 - RawValue, [691](#)
 - SceneLoadDoneArgs, [685](#)
 - SIZE, [691](#)
 - ToString, [690](#), [691](#)
- Scenes
 - NetworkSceneInfo, [579](#)
- Scheduling
 - NetworkProjectConfig, [484](#)
- SchedulingAndInterestManagement
 - NetworkProjectConfig, [484](#)
- SchedulingEnabled
 - SimulationConfig, [730](#)
- SchedulingWithoutAOI
 - SimulationConfig, [730](#)
- ScriptHeaderBackColor
 - Fusion, [49](#)
- ScriptHeaderIcon
 - Fusion, [50](#)
- Seconds
 - Fusion, [52](#)
- Select< T >
 - NetworkBehaviourBufferInterpolator, [305](#), [306](#)
- Self
 - Fusion, [49](#)
- SendCullResult
 - RpcInvokeInfo, [681](#)
- SendDelta
 - Simulation, [717](#)
- SendRate
 - Simulation, [718](#)
- SendReliableDataToPlayer
 - NetworkRunner, [530](#)
- SendReliableDataToServer
 - NetworkRunner, [531](#)
- SendResult
 - RpcInvokeInfo, [681](#)
- SendRpc
 - NetworkRunner, [531](#)
- Sent
 - SimulationInput, [736](#)
- SentBroadcast
 - Fusion, [48](#)
- SentToServerForForwarding
 - Fusion, [48](#)
- SentToTargetClient
 - Fusion, [48](#)
- SerializableDictionary< TKey, TValue >, [693](#)
 - Add, [694](#)
 - Clear, [694](#)
 - ContainsKey, [695](#)
 - Count, [697](#)
 - Create< TKey, TValue >, [695](#)
 - EntryKeyPropertyPath, [697](#)
 - GetEnumerator, [695](#)

- IsReadOnly, 698
- ItemsPropertyPath, 697
- Keys, 698
- Remove, 695
- Reset, 696
- Store, 696
- this[TKey key], 698
- TryGetValue, 696
- Values, 698
- Wrap, 697
- Serialize
 - NetworkProjectConfig, 485
- Server
 - Fusion, 41, 51
 - TickRate.Resolved, 806
- ServerFull
 - Fusion.Sockets, 59
- ServerIndex
 - TickRate.Selection, 808
- ServerIndexOutOfRange
 - TickRate, 799
- ServerInRoom
 - Fusion, 50
- ServerMode
 - SimulationRuntimeConfig, 755
- ServerRefused
 - Fusion.Sockets, 59
- ServerSend
 - TickRate.Resolved, 806
- ServerSendDelta
 - TickRate.Resolved, 807
- ServerSendIndex
 - TickRate.Selection, 809
- ServerSendIndexOutOfRange
 - TickRate, 799
- ServerSendRateLargerThanTickRate
 - TickRate, 799
- ServerTickDelta
 - TickRate.Resolved, 807
- ServerTickStride
 - TickRate.Resolved, 807
- Service
 - TaskManager, 86
- SessionInfo, 699
 - IsOpen, 700
 - IsValid, 700
 - IsVisible, 700
 - MaxPlayers, 701
 - Name, 701
 - NetworkRunner, 559
 - operator bool, 699
 - PlayerCount, 701
 - Properties, 701
 - Region, 701
 - ToString, 700
 - UpdateCustomProperties, 700
- SessionLobby
 - Fusion, 50
- SessionName
 - StartGameArgs, 781
- SessionProperties
 - StartGameArgs, 781
- Set
 - NetworkArray< T >, 253
 - NetworkButtons, 339
 - NetworkDictionary< K, V >, 354
 - NetworkLinkedList< T >, 385
 - NetworkString< TSize >, 614
- Set< T >
 - NetworkButtons, 339
 - NetworkInput, 376
- SetAllDown
 - NetworkButtons, 339
- SetAllUp
 - NetworkButtons, 340
- SetAreaOfInterestCellSize
 - NetworkRunner, 532
- SetAreaOfInterestGrid
 - NetworkRunner, 532
- SetAreaOfInterestOverride
 - NetworkTransform, 621
 - NetworkTRSP, 625
- SetCurrentVersion
 - NetworkObjectFlagsExtensions, 410
- SetDown
 - NetworkButtons, 340
- SetDown< T >
 - NetworkButtons, 340
- SetDummy
 - SimulationMessage, 747
- SetForcedAlive< T >
 - DynamicHeap, 99
- SetHitboxActive
 - HitboxRoot, 145
- SetIgnored
 - NetworkObjectFlagsExtensions, 412
- SetIsSimulated
 - NetworkRunner, 532
- SetMasterClient
 - NetworkRunner, 533
- SetMinBoundingRadius
 - HitboxRoot, 146
- SetNotTickAligned
 - SimulationMessage, 748
- SetParentTransform
 - NetworkTRSP, 625
- SetPlayerAlwaysInterested
 - NetworkObject, 404
 - NetworkRunner, 533
- SetPlayerObject
 - NetworkRunner, 533
- SetStatic
 - SimulationMessage, 748
- SetTarget
 - SimulationMessage, 748
- SetTrigger

- NetworkMecanimAnimator, [396](#), [397](#)
- SetUnreliable
 - SimulationMessage, [748](#)
- SetUp
 - NetworkButtons, [341](#)
- Setup
 - TaskManager, [86](#)
- SetUp< T >
 - NetworkButtons, [341](#)
- Shared
 - Fusion, [41](#), [50](#), [52](#)
- SharedModeStateAuthLocalPlayer
 - Fusion, [45](#)
- SharedModeStateAuthMasterClient
 - Fusion, [45](#)
- ShouldRegisterRpcInvokeDelegates
 - NetworkBehaviourUtils, [326](#)
- Shutdown
 - INetworkRunnerUpdater, [179](#)
 - INetworkSceneManager, [182](#)
 - NetworkRunner, [510](#), [534](#)
- ShutdownReason
 - Fusion, [50](#)
 - StartGameResult, [784](#)
- Simulation, [702](#)
 - _stats, [712](#)
 - ActivePlayers, [713](#)
 - AfterSimulation, [705](#)
 - AfterUpdate, [705](#)
 - BeforeFirstTick, [705](#)
 - BeforeSimulation, [705](#)
 - BeforeUpdate, [706](#)
 - Config, [713](#)
 - DeltaTime, [713](#)
 - GetAreaOfInterestGizmoData, [706](#)
 - GetInputAuthority, [706](#)
 - GetInputForPlayer, [707](#)
 - GetObjectsAndPlayersInAreaOfInterestCell, [707](#)
 - GetStateAuthority, [707](#)
 - HasAnyActiveConnections, [707](#)
 - InputCount, [713](#)
 - IsClient, [713](#)
 - IsFirstTick, [713](#)
 - IsForward, [714](#)
 - IsInputAuthority, [708](#)
 - IsInterestedIn, [708](#)
 - IsLastTick, [714](#)
 - IsLocalPlayerFirstExecution, [714](#)
 - IsLocalSimulationInputAuthority, [708](#)
 - IsLocalSimulationStateAuthority, [709](#)
 - IsLocalSimulationStateOrInputSource, [710](#)
 - IsMasterClient, [714](#)
 - IsPlayer, [714](#)
 - IsResimulation, [715](#)
 - IsRunning, [715](#)
 - IsServer, [715](#)
 - IsShutdown, [715](#)
 - IsSinglePlayer, [715](#)
 - IsStateAuthority, [710](#)
 - LatestServerTick, [715](#)
 - LocalAddress, [716](#)
 - LocalAlpha, [716](#)
 - LocalPlayer, [716](#)
 - Mode, [716](#)
 - NetConfig, [774](#)
 - NetConfigPointer, [716](#)
 - NetworkConnected, [711](#)
 - NetworkDisconnected, [711](#)
 - NetworkProjectConfig, [489](#)
 - NetworkReceiveDone, [711](#)
 - NoSimulation, [711](#)
 - ObjectCount, [716](#)
 - Objects, [717](#)
 - ProjectConfig, [717](#)
 - RemoteAlpha, [717](#)
 - RemoteTick, [717](#)
 - RemoteTickPrevious, [717](#)
 - SendDelta, [717](#)
 - SendRate, [718](#)
 - Stage, [718](#)
 - Tick, [718](#)
 - TickDeltaDouble, [718](#)
 - TickDeltaFloat, [718](#)
 - TickPrevious, [718](#)
 - TickRate, [719](#)
 - TickStride, [719](#)
 - Time, [719](#)
 - Topology, [719](#)
 - TryGetHostPlayer, [712](#)
 - Update, [712](#)
- Simulation.AreaOfInterest, [719](#)
 - CELL_SIZE, [722](#)
 - GetCellSize, [720](#)
 - SphereToCells, [720](#)
 - ToCell, [721](#)
 - ToCellCenter, [721](#)
 - x, [722](#)
- SimulationBehaviour, [723](#)
 - CanReceiveRenderCallback, [724](#)
 - CanReceiveSimulationCallback, [724](#)
 - FixedUpdateNetwork, [724](#)
 - Object, [725](#)
 - Render, [724](#)
 - Runner, [725](#)
- SimulationBehaviourAttribute, [725](#)
 - Modes, [726](#)
 - Stages, [726](#)
 - Topologies, [726](#)
- SimulationBehaviourListScope, [726](#)
 - Dispose, [727](#)
- SimulationConfig, [727](#)
 - AreaOfInterestEnabled, [730](#)
 - DataConsistency, [728](#)
 - Eventual, [728](#)
 - Full, [728](#)
 - HostMigration, [728](#)

- InputDataWordCount, [728](#)
- InputTotalWordCount, [730](#)
- InputTransferMode, [729](#)
- InputTransferModes, [728](#)
- LatestState, [728](#)
- ObjectDataConsistency, [729](#)
- PlayerCount, [729](#)
- Redundancy, [728](#)
- ReplicationFeatures, [729](#)
- SchedulingEnabled, [730](#)
- SchedulingWithoutAOI, [730](#)
- TickRateSelection, [729](#)
- Topology, [729](#)
- SimulationConnectionStats, [730](#)
 - InMessagesBandwidth, [731](#)
 - InMessagesPerPacket, [731](#)
 - InObjectBandwidth, [731](#)
 - InObjectDestroysPerPacket, [731](#)
 - InObjectUpdatesPerPacket, [732](#)
 - InPacketsBandwidth, [732](#)
 - InPacketsRecv, [732](#)
 - InputsBandwidth, [732](#)
 - InputsMissing, [732](#)
 - InputsPerPacket, [732](#)
 - InReliableDataBandwidth, [732](#)
 - OutMessagesBandwidth, [732](#)
 - OutMessagesPerPacket, [733](#)
 - OutObjectBandwidth, [733](#)
 - OutObjectDestroysPerPacket, [733](#)
 - OutObjectUpdatesPerPacket, [733](#)
 - OutPacketsBandwidth, [733](#)
 - OutPacketsDelivered, [733](#)
 - OutPacketsLost, [733](#)
 - OutPacketsSent, [733](#)
 - OutReliableDataBandwidth, [734](#)
 - RoundTripTime, [734](#)
- SimulationEnter
 - ISimulationEnter, [203](#)
- SimulationExit
 - ISimulationExit, [204](#)
- SimulationInput, [734](#)
 - Clear, [735](#)
 - CopyFrom, [735](#)
 - Data, [735](#)
 - Header, [735](#)
 - Player, [736](#)
 - Sent, [736](#)
- SimulationInput.Buffer, [736](#)
 - Add, [737](#)
 - Buffer, [737](#)
 - Clear, [738](#)
 - Contains, [738](#)
 - CopySortedTo, [738](#)
 - Count, [740](#)
 - Full, [740](#)
 - Get, [738](#)
 - GetInsertTime, [739](#)
 - Remove, [739](#)
- SimulationInputHeader, [740](#)
 - InterpAlpha, [741](#)
 - InterpFrom, [741](#)
 - InterpTo, [741](#)
 - SIZE, [741](#)
 - Tick, [741](#)
 - WORD_COUNT, [741](#)
- SimulationMessage, [742](#)
 - Allocate, [744](#)
 - Capacity, [750](#)
 - Clone, [745](#)
 - FLAG_DUMMY, [750](#)
 - FLAG_INTERNAL, [750](#)
 - FLAG_NOT_TICK_ALIGNED, [750](#)
 - FLAG_REMOTE, [750](#)
 - FLAG_STATIC, [751](#)
 - FLAG_TARGET_PLAYER, [751](#)
 - FLAG_TARGET_SERVER, [751](#)
 - FLAG_UNRELIABLE, [751](#)
 - FLAG_USER_FLAGS_START, [751](#)
 - FLAG_USER_MESSAGE, [751](#)
 - Flags, [752](#)
 - FLAGS_RESERVED, [752](#)
 - FLAGS_RESERVED_BITS, [752](#)
 - GetData, [745](#)
 - GetFlag, [745](#)
 - IsTargeted, [746](#)
 - IsUnreliable, [753](#)
 - Offset, [752](#)
 - ReadInt, [746](#)
 - ReadNetworkedObjectRef, [746](#)
 - ReadVector3, [747](#)
 - ReferenceCountAdd, [747](#)
 - ReferenceCountSub, [747](#)
 - References, [752](#)
 - SetDummy, [747](#)
 - SetNotTickAligned, [748](#)
 - SetStatic, [748](#)
 - SetTarget, [748](#)
 - SetUnreliable, [748](#)
 - SIZE, [752](#)
 - Source, [753](#)
 - Target, [753](#)
 - Tick, [753](#)
 - ToString, [748](#), [749](#)
 - WriteInt, [749](#)
 - WriteNetworkedObjectRef, [749](#)
 - WriteVector3, [749](#)
- SimulationMessagePtr, [753](#)
 - Message, [754](#)
- SimulationModes
 - Fusion, [51](#)
- SimulationRuntimeConfig, [754](#)
 - HostPlayer, [755](#)
 - MasterClient, [755](#)
 - PlayerMaxCount, [755](#)
 - ServerMode, [755](#)
 - TickRate, [755](#)

- Topology, [755](#)
- SimulationSpeed
 - SimulationStats, [760](#)
- SimulationStages
 - Fusion, [51](#)
- SimulationState
 - NetworkBehaviour.ChangeDetector, [284](#)
- SimulationStats, [756](#)
 - EngineDelta, [757](#)
 - ForwardSteps, [757](#)
 - InBandwidth, [757](#)
 - InPackets, [757](#)
 - InputReceiveDelta, [757](#)
 - InputReceiveDeltaDeviation, [758](#)
 - InterpolationOffset, [758](#)
 - InterpolationOffsetDeviation, [758](#)
 - InterpolationOffsetTarget, [758](#)
 - InterpolationSpeed, [758](#)
 - ObjectsCount, [758](#)
 - ObjectsGlobalCount, [759](#)
 - ObjectsPredictedCount, [759](#)
 - OutBandwidth, [759](#)
 - OutPackets, [759](#)
 - PlayersCount, [759](#)
 - Resimulations, [759](#)
 - RoundTripTime, [760](#)
 - SimulationSpeed, [760](#)
 - SimulationTimeOffset, [760](#)
 - SimulationTimeOffsetDeviation, [760](#)
 - SimulationTimeOffsetTarget, [760](#)
 - SpawnQueueSize, [760](#)
 - StateReceiveDelta, [761](#)
 - StateReceiveDeltaDeviation, [761](#)
 - TimeResets, [761](#)
- SimulationTime
 - NetworkRunner, [559](#)
- SimulationTimeOffset
 - SimulationStats, [760](#)
- SimulationTimeOffsetDeviation
 - SimulationStats, [760](#)
- SimulationTimeOffsetTarget
 - SimulationStats, [760](#)
- SimulationUnityScene
 - NetworkRunner, [559](#)
- Single
 - Fusion, [41](#)
 - NetworkProjectConfig, [484](#)
- SinglePlayerContinue
 - NetworkRunner, [534](#)
- SinglePlayerPause
 - NetworkRunner, [534](#)
- SIZE
 - _128, [61](#)
 - _16, [62](#)
 - _2, [63](#)
 - _256, [64](#)
 - _32, [65](#)
 - _4, [66](#)
 - _512, [67](#)
 - _64, [68](#)
 - _8, [68](#)
 - Allocator.Config, [74](#)
 - Angle, [84](#)
 - NetworkBehaviourId, [313](#)
 - NetworkId, [372](#)
 - NetworkObjectGuid, [419](#)
 - NetworkObjectHeader, [427](#)
 - NetworkObjectNestingKey, [434](#)
 - NetworkObjectTypeId, [449](#)
 - NetworkPhysicsInfo, [453](#)
 - NetworkPrefabId, [460](#)
 - NetworkPrefabRef, [471](#)
 - NetworkRNG, [498](#)
 - NetworkSceneInfo, [578](#)
 - NetworkTRSPData, [628](#)
 - PlayerRef, [636](#)
 - Ptr, [643](#)
 - RpcHeader, [676](#)
 - SceneRef, [691](#)
 - SimulationInputHeader, [741](#)
 - SimulationMessage, [752](#)
 - Tick, [791](#)
 - TickRate.Resolved, [806](#)
- SnapshotFrom
 - NetworkBehaviour.ChangeDetector, [284](#)
- SnapshotHistoryDraw, [233](#)
 - GetEnumerator, [234](#)
 - LagCompensationDraw, [221](#)
- SnapshotTo
 - NetworkBehaviour.ChangeDetector, [284](#)
- SocketRecvBuffer
 - NetConfig, [774](#)
- SocketRecvBufferSize
 - NetworkConfiguration, [347](#)
- SocketSendBuffer
 - NetConfig, [774](#)
- SocketSendBufferSize
 - NetworkConfiguration, [347](#)
- SortDistance
 - LagCompensatedExt, [219](#)
- SortKey
 - NetworkObject, [406](#)
- SortReference
 - LagCompensatedExt, [219](#)
- Source
 - NetworkBehaviour.ChangeDetector, [283](#)
 - RenderAttribute, [667](#)
 - RpcInfo, [678](#)
 - SimulationMessage, [753](#)
- SourcesHostPlayer
 - Fusion, [47](#)
- SourcesServer
 - Fusion, [47](#)
- Sources
 - NetworkRpcWeavedInvokerAttribute, [501](#)
 - RpcAttribute, [671](#)

- RpcInvokeData, 680
- Spawn
 - NetworkRunner, 534–537
- Spawn< T >
 - NetworkRunner, 537
- SpawnAsync
 - NetworkRunner, 538–540
- SpawnAsync< T >
 - NetworkRunner, 541
- Spawned
 - Fusion, 45
 - ISpawned, 205
 - NetworkBehaviour, 278
- SpawnedByClient
 - Fusion, 43
- SpawnQueueSize
 - SimulationStats, 760
- Sphere
 - Fusion, 42
- SphereOverlapQuery, 234
 - Center, 236
 - Check, 235
 - Radius, 236
 - SphereOverlapQuery, 235
- SphereOverlapQueryParams, 236
 - Center, 237
 - QueryParams, 237
 - Radius, 237
 - SphereOverlapQueryParams, 237
 - StaticHitsCapacity, 238
- SphereRadius
 - Hitbox, 127
- SphereToCells
 - Simulation.AreaOfInterest, 720
- SquareMagnitude
 - Fusion, 52
- StackTrace
 - StartGameResult, 784
- Stage
 - NetworkRunner, 559
 - Simulation, 718
- Stages
 - SimulationBehaviourAttribute, 726
- Start
 - TickAccumulator, 796
- StartGame
 - NetworkRunner, 542
- StartGameArgs, 776
 - Address, 777
 - AuthValues, 778
 - Config, 778
 - ConnectionToken, 778
 - CustomCallbackInterfaces, 778
 - CustomLobbyName, 778
 - CustomPhotonAppSettings, 778
 - CustomPublicAddress, 779
 - CustomSTUNServer, 779
 - DisableNATPunchthrough, 779
 - EnableClientSessionCreation, 779
 - GameMode, 779
 - HostMigrationResume, 779
 - HostMigrationToken, 780
 - IsOpen, 780
 - IsVisible, 780
 - MatchmakingMode, 780
 - ObjectInitializer, 780
 - ObjectProvider, 780
 - OnGameStarted, 781
 - PlayerCount, 781
 - Scene, 781
 - SceneManager, 781
 - SessionName, 781
 - SessionProperties, 781
 - StartGameCancellationToken, 782
 - ToString, 777
 - Updater, 782
 - UseCachedRegions, 782
 - UseDefaultPhotonCloudPorts, 782
- StartGameCancellationToken
 - StartGameArgs, 782
- StartGameResult, 782
 - ErrorMessage, 783
 - Ok, 783
 - ShutdownReason, 784
 - StackTrace, 784
 - ToString, 783
- Starting
 - NetworkRunner, 510
- StartNew
 - TickAccumulator, 796
- StartsWith
 - NetworkString< TSize >, 615
- StartsWith< TOtherSize >
 - NetworkString< TSize >, 615
- STATE
 - AuthorityMasks, 88
- State
 - NetworkRunner, 559
 - NetworkTRSP, 626
- StateAuthority
 - Fusion, 49
 - NetworkObject, 409
 - NetworkObjectHeader, 427
 - NetworkObjectMeta, 430
- StateAuthorityChanged
 - IStateAuthorityChanged, 205
- StateBuffer
 - NetworkBehaviour, 280
- StateBufferIsValid
 - NetworkBehaviour, 280
- StateReceiveDelta
 - SimulationStats, 761
- StateReceiveDeltaDeviation
 - SimulationStats, 761
- States
 - NetworkRunner, 510

- StaticHitsCapacity
 - BoxOverlapQueryParams, [214](#)
 - RaycastQueryParams, [233](#)
 - SphereOverlapQueryParams, [238](#)
- StatsMetaAttribute, [784](#)
- Status
 - NetworkObjectSpawnException, [441](#)
 - NetworkSpawnOp, [591](#)
- Stop
 - TickAccumulator, [796](#)
- Store
 - SerializableDictionary< TKey, TValue >, [696](#)
- Struct
 - Fusion, [43](#)
- StructArray
 - Fusion, [43](#)
- StunClient.TestIPs, [775](#)
- Substring
 - NetworkString< TSize >, [616](#)
- SubtickAccuracy
 - Fusion, [42](#)
- Success
 - Fusion, [43](#), [44](#)
- SurrogateType
 - FixedBufferPropertyAttribute, [117](#)
- Symmetric
 - Fusion.Sockets.Stun, [60](#)
- SyncParent
 - NetworkTransform, [622](#)
- SyncScale
 - NetworkTransform, [622](#)
- T
 - NetworkBehaviour.BehaviourReader< T >, [282](#)
 - NetworkBehaviour.PropertyReader< T >, [290](#)
- TagetPlayerIsNotLocal
 - Fusion, [47](#)
- Target
 - SimulationMessage, [753](#)
- TargetPlayerIsLocalButRpcsNotInvokableLocally
 - Fusion, [48](#)
- TargetPlayerUnreachable
 - Fusion, [48](#)
- Targets
 - NetworkRpcWeavedInvokerAttribute, [501](#)
 - RpcAttribute, [672](#)
 - RpcInvokeData, [680](#)
- TargetTick
 - TickTimer, [813](#)
- TaskManager, [85](#)
 - ContinueWhenAll, [85](#)
 - Run, [86](#)
 - Service, [86](#)
 - Setup, [86](#)
- Teleport
 - INetworkTRSPTeleport, [184](#)
 - NetworkTransform, [622](#)
 - NetworkTRSP, [625](#)
- TeleportKey
 - NetworkTRSPData, [628](#)
- this[int index]
 - FixedArray< T >, [114](#)
 - INetworkArray, [165](#)
 - NetworkArray< T >, [254](#)
 - NetworkArrayReadOnly< T >, [259](#)
 - NetworkBehaviourBuffer, [296](#)
 - NetworkLinkedList< T >, [386](#)
 - NetworkLinkedListReadOnly< T >, [391](#)
 - NetworkString< TSize >, [618](#)
 - TickRate, [804](#)
- this[K key]
 - NetworkDictionary< K, V >, [355](#)
- this[TKey key]
 - SerializableDictionary< TKey, TValue >, [698](#)
- ThrowIfBehaviourNotInitialized
 - NetworkBehaviourUtils, [326](#)
- Tick, [785](#)
 - ALIGNMENT, [791](#)
 - CompareTo, [786](#)
 - Equals, [786](#), [787](#)
 - GetHashCode, [787](#)
 - NetworkBehaviourBuffer, [297](#)
 - NetworkRunner, [559](#)
 - Next, [787](#)
 - operator bool, [788](#)
 - operator int, [788](#)
 - operator Tick, [788](#)
 - operator !=, [790](#)
 - operator <, [790](#)
 - operator <=, [790](#)
 - operator >, [790](#)
 - operator >=, [791](#)
 - operator ==, [790](#)
 - Query, [225](#)
 - QueryParams, [227](#)
 - Raw, [791](#)
 - RpcInfo, [678](#)
 - Simulation, [718](#)
 - SimulationInputHeader, [741](#)
 - SimulationMessage, [753](#)
 - SIZE, [791](#)
 - ToString, [791](#)
- Tick.EqualityComparer, [792](#)
 - Equals, [792](#)
 - GetHashCode, [792](#)
- Tick.RelationalComparer, [793](#)
 - Compare, [793](#)
- TickAccumulator, [794](#)
 - AddTicks, [795](#)
 - AddTime, [795](#)
 - Alpha, [795](#)
 - ConsumeTick, [796](#)
 - Pending, [797](#)
 - Remainder, [797](#)
 - Running, [797](#)
 - Start, [796](#)
 - StartNew, [796](#)

- Stop, 796
- TimeScale, 797
- TickAligned
 - RpcAttribute, 672
- TickDeltaDouble
 - Simulation, 718
- TickDeltaFloat
 - Simulation, 718
- TickPrevious
 - Simulation, 718
- TickRate, 798
 - Available, 804
 - ClampSelection, 800
 - Client, 804
 - ClientSendIndexOutOfRange, 799
 - Count, 804
 - Error, 799
 - Get, 800
 - GetDivisor, 800
 - GetTickRate, 801
 - Init, 801
 - InvalidTickRate, 799
 - IsValid, 801, 802
 - NetworkRunner, 560
 - NotFound, 799
 - Ok, 799
 - Resolve, 802
 - ServerIndexOutOfRange, 799
 - ServerSendIndexOutOfRange, 799
 - ServerSendRateLargerThanTickRate, 799
 - Simulation, 719
 - SimulationRuntimeConfig, 755
 - this[int index], 804
 - ToArray, 803
 - Validate, 803
 - ValidateResult, 799
 - ValidateSelection, 803
- TickRate.Resolved, 805
 - Client, 806
 - ClientSend, 806
 - ClientSendDelta, 807
 - ClientTickDelta, 807
 - ClientTickStride, 807
 - Server, 806
 - ServerSend, 806
 - ServerSendDelta, 807
 - ServerTickDelta, 807
 - ServerTickStride, 807
 - SIZE, 806
 - WORDS, 806
- TickRate.Selection, 808
 - Client, 808
 - ClientSendIndex, 808
 - ServerIndex, 808
 - ServerSendIndex, 809
- TickRateSelection
 - SimulationConfig, 729
- Ticks
 - Fusion, 52
- TicksExecuted
 - NetworkRunner, 560
- TicksPerSecond
 - Fusion, 52
- TickStride
 - Simulation, 719
- TickTimer, 809
 - CreateFromSeconds, 810
 - CreateFromTicks, 810
 - Expired, 811
 - ExpiredOrNotRunning, 811
 - IsRunning, 812
 - None, 813
 - RemainingTicks, 811
 - RemainingTime, 812
 - TargetTick, 813
 - ToString, 812
- TickTo
 - Query, 226
 - QueryParams, 228
- Time
 - Simulation, 719
- Timeframe
 - RenderAttribute, 667
- Timeout
 - Fusion.Sockets, 59
- TimeResets
 - SimulationStats, 761
- TimeScale
 - NetworkPhysicsInfo, 453
 - TickAccumulator, 797
- TimeSyncConfiguration, 813
 - ExtraInterpolationOffset, 813
 - ExtraSimulationOffset, 814
 - MaxLateInputs, 814
 - MaxLateSnapshots, 814
- TimeSynchronizationOverride
 - NetworkProjectConfig, 489
- To
 - Fusion, 46
 - NetworkBehaviourBufferInterpolator, 309
- ToArray
 - FixedArray< T >, 113
 - NetworkArray< T >, 253
 - TickRate, 803
- ToCell
 - Simulation.AreaOfInterest, 721
- ToCellCenter
 - Simulation.AreaOfInterest, 721
- ToListString
 - FixedArray< T >, 113
 - NetworkArray< T >, 254
- ToLower
 - NetworkString< TSize >, 617
- ToNamePrefixString
 - NetworkId, 371
- Topologies

- Fusion, [51](#)
- SimulationBehaviourAttribute, [726](#)
- Topology
 - NetworkRunner, [560](#)
 - Simulation, [719](#)
 - SimulationConfig, [729](#)
 - SimulationRuntimeConfig, [755](#)
- ToReadOnly
 - NetworkArray< T >, [254](#)
 - NetworkDictionary< K, V >, [354](#)
- ToString
 - Allocator.Config, [73](#)
 - Angle, [84](#)
 - FixedArray< T >, [113](#)
 - HeapConfiguration, [124](#)
 - NetworkArray< T >, [254](#)
 - NetworkBehaviourId, [312](#)
 - NetworkBool, [334](#)
 - NetworkId, [371](#)
 - NetworkLoadSceneParameters, [394](#)
 - NetworkObjectGuid, [418](#)
 - NetworkObjectHeader, [425](#)
 - NetworkObjectNestingKey, [433](#)
 - NetworkObjectReleaseContext, [438](#)
 - NetworkObjectTypeId, [448](#)
 - NetworkPrefabId, [459](#), [460](#)
 - NetworkPrefabRef, [469](#), [470](#)
 - NetworkProjectConfig, [485](#)
 - NetworkRNG, [498](#)
 - NetworkRunnerUpdaterDefaultInvokeSettings, [567](#)
 - NetworkSceneInfo, [578](#)
 - NetworkSceneObjectId, [583](#)
 - NetworkString< TSize >, [617](#)
 - PlayerRef, [634](#)
 - Ptr, [642](#)
 - RpcHeader, [674](#)
 - RpcInfo, [677](#)
 - RpcInvokeData, [679](#)
 - RpcInvokeInfo, [681](#)
 - RpcSendResult, [682](#)
 - SceneRef, [690](#), [691](#)
 - SessionInfo, [700](#)
 - SimulationMessage, [748](#), [749](#)
 - StartGameArgs, [777](#)
 - StartGameResult, [783](#)
 - Tick, [791](#)
 - TickTimer, [812](#)
- TotalHitboxes
 - HitboxManager, [142](#)
- ToUnityGuidString
 - NetworkObjectGuid, [418](#)
 - NetworkPrefabRef, [470](#)
- ToUpper
 - NetworkString< TSize >, [617](#)
- TriggerInteraction
 - Query, [226](#)
 - QueryParams, [228](#)
- TryAddSource
 - NetworkPrefabTable, [478](#)
- TryFindBehaviour
 - NetworkRunner, [542](#)
- TryFindBehaviour< T >
 - NetworkRunner, [543](#)
- TryFindObject
 - NetworkRunner, [543](#)
- TryGet
 - NetworkDictionary< K, V >, [354](#)
 - NetworkDictionaryReadOnly< K, V >, [358](#)
- TryGet< T >
 - NetworkInput, [376](#)
- TryGetBehaviour< T >
 - Behaviour, [89](#)
- TryGetBehaviourStats
 - NetworkRunner, [544](#)
- TryGetGlobal
 - NetworkProjectConfigAsset, [491](#)
- TryGetHostPlayer
 - Simulation, [712](#)
- TryGetInputForPlayer< T >
 - NetworkRunner, [544](#)
- TryGetNetworkedBehaviourFromNetworkedObjectRef< T >
 - NetworkRunner, [544](#)
- TryGetNetworkedBehaviourId
 - NetworkRunner, [545](#)
- TryGetObjectRefFromNetworkedBehaviour
 - NetworkRunner, [545](#)
- TryGetObjectStats
 - NetworkRunner, [546](#)
- TryGetPhysicsInfo
 - NetworkRunner, [546](#)
- TryGetPhysicsScene2D
 - INetworkSceneManager, [182](#)
- TryGetPhysicsScene3D
 - INetworkSceneManager, [183](#)
- TryGetPlayerObject
 - NetworkRunner, [546](#)
- TryGetPlayerStats
 - NetworkRunner, [547](#)
- TryGetRpcInvokeDelegateArray
 - NetworkBehaviourUtils, [326](#)
- TryGetRpcStaticInvokeDelegate
 - NetworkBehaviourUtils, [327](#)
- TryGetSceneInfo
 - NetworkRunner, [547](#)
- TryGetSimulationStats
 - NetworkRunner, [547](#)
- TryGetSnapshotsBuffers
 - NetworkBehaviour, [278](#)
- TryGetValue
 - SerializableDictionary< TKey, TValue >, [696](#)
- TryParse
 - NetworkObjectGuid, [419](#)
 - NetworkPrefabRef, [470](#)
- TrySet< T >
 - NetworkInput, [376](#)

- TrySetPhysicsInfo
 - NetworkRunner, [547](#)
- TrySpawn
 - NetworkRunner, [548–550](#)
- TrySpawn< T >
 - NetworkRunner, [551](#)
- Type
 - ColliderDrawInfo, [218](#)
 - FixedBufferPropertyAttribute, [117](#)
 - Hitbox, [127](#)
 - LagCompensatedHit, [208](#)
 - NetworkInput, [377](#)
 - NetworkObjectHeader, [427](#)
 - NetworkObjectHeaderPtr, [429](#)
 - NetworkObjectMeta, [431](#)
 - NetworkProjectConfigAsset.SerializableSimulationBehaviour, [493](#)
- TypeId
 - NetworkObjectReleaseContext, [438](#)
 - NetworkObjectSpawnException, [441](#)
 - NetworkProjectConfig, [489](#)
- UdpBlocked
 - Fusion.Sockets.Stun, [60](#)
- UnitAttribute, [814](#)
- Units
 - Fusion, [52](#)
- UnityArraySurrogate< T, ReaderWriter >, [187](#)
 - DataProperty, [189](#)
 - Init, [188](#)
 - Read, [188](#)
 - Write, [188](#)
- UnityContextMenuMenuItemAttribute, [815](#)
 - order, [815](#)
 - UnityContextMenuMenuItemAttribute, [815](#)
- UnityDelayedAttribute, [816](#)
 - order, [816](#)
- UnityDictionarySurrogate< KeyType, KeyReaderWriter, Value
Type, ValueReaderWriter >, [189](#)
 - DataProperty, [191](#)
 - Init, [190](#)
 - Read, [190](#)
 - Write, [190](#)
- UnityEngine, [60](#)
- UnityEngine.SceneManagement, [60](#)
- UnityEngine.Scripting, [60](#)
- UnityEngine.Serialization, [60](#)
- UnityFormerlySerializedAsAttribute, [816](#)
 - UnityFormerlySerializedAsAttribute, [817](#)
- UnityHeaderAttribute, [817](#)
 - order, [818](#)
 - UnityHeaderAttribute, [817](#)
- UnityLinkedListSurrogate< T, ReaderWriter >, [191](#)
 - DataProperty, [193](#)
 - Init, [192](#)
 - Read, [192](#)
 - Write, [192](#)
- UnityMinAttribute, [818](#)
 - order, [818](#)
 - UnityMinAttribute, [818](#)
- UnityMultilineAttribute, [819](#)
 - order, [819](#)
- UnityNonReorderableAttribute, [819](#)
 - order, [820](#)
- UnityNonSerializedAttribute, [820](#)
- UnityPlayerLoopSystemAddMode
 - Fusion, [52](#)
- UnityRangeAttribute, [820](#)
 - order, [821](#)
 - UnityRangeAttribute, [821](#)
- UnitySerializeField, [821](#)
- UnitySerializeReference, [821](#)
- UnitySpaceAttribute, [822](#)
 - order, [822](#)
 - UnitySpaceAttribute, [822](#)
- UnitySurrogateBase, [193](#)
 - Init, [194](#)
 - Read, [194](#)
 - Write, [194](#)
- UnityTooltipAttribute, [823](#)
 - order, [823](#)
 - UnityTooltipAttribute, [823](#)
- UnityValueSurrogate< T, TReaderWriter >, [195](#)
 - DataProperty, [197](#)
 - Init, [196](#)
 - Read, [196](#)
 - Write, [196](#)
- Unload
 - NetworkPrefabTable, [479](#)
- UnloadAll
 - NetworkPrefabTable, [479](#)
- UnloadGlobal
 - NetworkProjectConfig, [485](#)
 - NetworkProjectConfigAsset, [491](#)
- UnloadPrefabOnReleasingLastInstance
 - NetworkPrefabTableOptions, [481](#)
- UnloadScene
 - INetworkSceneManager, [183](#)
 - NetworkRunner, [552](#)
- UnloadUnreferenced
 - NetworkPrefabTable, [479](#)
- UnloadUnusedPrefabsOnShutdown
 - NetworkPrefabTableOptions, [481](#)
- Unreachable
 - Fusion, [49](#)
- UnregisterFromPlayerLoop
 - NetworkRunnerUpdaterDefault, [563](#)
- Unreliable
 - Fusion, [47](#)
- Update
 - Simulation, [712](#)
- UpdateCustomProperties
 - SessionInfo, [700](#)
- UpdateDelay
 - HostMigrationConfig, [148](#)
- UpdateInternal
 - NetworkRunner, [552](#)

- Updater
 - StartGameArgs, 782
- UpdateSettings
 - NetworkRunnerUpdaterDefault, 564
- UseCachedRegions
 - StartGameArgs, 782
- UseDefaultPhotonCloudPorts
 - StartGameArgs, 782
- UserArgs
 - Query, 226
 - QueryParams, 228
- UserId
 - NetworkRunner, 560
- UseSerializableDictionary
 - NetworkProjectConfig, 489
- V1
 - Fusion, 43
- Valid
 - NetworkBehaviourBuffer, 297
 - NetworkBehaviourBufferInterpolator, 309
- Validate
 - TickRate, 803
- ValidateResult
 - TickRate, 799
- ValidateSelection
 - TickRate, 803
- Value
 - NetworkObjectNestingKey, 434
 - NetworkSceneLoadId, 581
 - NetworkString< TSize >, 618
- valueEncoded
 - FloatCompressed, 121
- Values
 - SerializableDictionary< TKey, TValue >, 698
- Vector2
 - NetworkBehaviourBufferInterpolator, 306
- Vector2Compressed, 824
 - Equals, 825
 - GetHashCode, 825
 - operator Vector2, 825
 - operator Vector2Compressed, 826
 - operator!=, 826
 - operator==, 827
 - X, 827
 - xEncoded, 827
 - Y, 828
 - yEncoded, 827
- Vector3
 - NetworkBehaviourBufferInterpolator, 307
- Vector3Compressed, 828
 - Equals, 829
 - GetHashCode, 830
 - operator Vector2, 830
 - operator Vector3, 830
 - operator Vector3Compressed, 831
 - operator!=, 832
 - operator==, 832
 - X, 833
 - xEncoded, 832
 - Y, 833
 - yEncoded, 832
 - Z, 833
 - zEncoded, 833
- Vector4
 - NetworkBehaviourBufferInterpolator, 308
- Vector4Compressed, 833
 - Equals, 835
 - GetHashCode, 835
 - operator Vector4, 835
 - operator Vector4Compressed, 836
 - operator!=, 836
 - operator==, 837
 - W, 838
 - wEncoded, 837
 - X, 838
 - xEncoded, 837
 - Y, 838
 - yEncoded, 837
 - Z, 838
 - zEncoded, 838
- VerifyRawNetworkUnwrap< T >
 - ReadWriteUtilsForWeaver, 660
- VerifyRawNetworkWrap< T >
 - ReadWriteUtilsForWeaver, 661
- Version
 - NetworkPrefabTable, 480
 - NetworkProjectConfig, 490
 - NetworkSceneInfo, 579
- W
 - QuaternionCompressed, 649
 - Vector4Compressed, 838
- WaitForResult
 - INetworkAssetSource< T >, 167
- Waiting
 - NetworkRunnerCallbackArgs.ConnectRequest, 562
- WarnIfAttribute, 839
 - Message, 839
- WasPressed
 - NetworkButtons, 341
- WasPressed< T >
 - NetworkButtons, 342
- WasReleased
 - NetworkButtons, 342
- WasReleased< T >
 - NetworkButtons, 343
- WeaverGeneratedAttribute, 839
- wEncoded
 - QuaternionCompressed, 648
 - Vector4Compressed, 837
- WORD_COUNT
 - NetworkPhysicsInfo, 453
 - NetworkSceneInfo, 579
 - SimulationInputHeader, 741
- WordCount
 - DefaultForPropertyAttribute, 93

- NetworkBehaviourWeavedAttribute, [332](#)
- NetworkedWeavedAttribute, [361](#)
- NetworkInput, [377](#)
- NetworkInputWeavedAttribute, [380](#)
- NetworkObjectHeader, [427](#)
- NetworkStructWeavedAttribute, [620](#)
- WordOffset
 - DefaultForPropertyAttribute, [93](#)
 - NetworkedWeavedAttribute, [361](#)
- WORDS
 - NetworkObjectHeader, [428](#)
 - NetworkTRSPData, [628](#)
 - TickRate.Resolved, [806](#)
- Wrap
 - SerializableDictionary< TKey, TValue >, [697](#)
- Write
 - IElementReaderWriter< T >, [161](#)
 - IUnitySurrogate, [186](#)
 - NetworkId, [371](#), [372](#)
 - PlayerRef, [635](#)
 - RpcHeader, [675](#)
 - UnityArraySurrogate< T, ReaderWriter >, [188](#)
 - UnityDictionarySurrogate< KeyType, KeyReaderWriter, ValueType, ValueReaderWriter >, [190](#)
 - UnityLinkedListSurrogate< T, ReaderWriter >, [192](#)
 - UnitySurrogateBase, [194](#)
 - UnityValueSurrogate< T, TReaderWriter >, [196](#)
- Write< T >
 - PlayerRef, [635](#)
- WriteBenchmarkResults
 - HitboxManager, [141](#)
- WriteBoolean
 - ReadWriteUtilsForWeaver, [661](#)
- WriteEmptyNetworkBehaviourRef
 - ReadWriteUtils, [654](#)
- WriteFloat
 - ReadWriteUtils, [654](#)
- WriteInt
 - SimulationMessage, [749](#)
- WriteNetworkBehaviourRef
 - ReadWriteUtils, [654](#)
- WriteNetworkedObjectRef
 - SimulationMessage, [749](#)
- WriteNullBehaviourRef
 - ReadWriteUtils, [654](#)
- WriteQuaternion
 - ReadWriteUtils, [655](#)
- WriteStringUtf32NoHash
 - ReadWriteUtilsForWeaver, [662](#)
- WriteStringUtf32WithHash
 - ReadWriteUtilsForWeaver, [662](#)
- WriteStringUtf8NoHash
 - ReadWriteUtilsForWeaver, [663](#)
- WriteVector2
 - ReadWriteUtils, [655](#)
- WriteVector3
 - ReadWriteUtils, [655](#)
 - SimulationMessage, [749](#)
- WriteVector4
 - ReadWriteUtils, [657](#)
- X
 - QuaternionCompressed, [649](#)
 - Vector2Compressed, [827](#)
 - Vector3Compressed, [833](#)
 - Vector4Compressed, [838](#)
- x
 - Simulation.AreaOfInterest, [722](#)
- xEncoded
 - QuaternionCompressed, [648](#)
 - Vector2Compressed, [827](#)
 - Vector3Compressed, [832](#)
 - Vector4Compressed, [837](#)
- Y
 - QuaternionCompressed, [649](#)
 - Vector2Compressed, [828](#)
 - Vector3Compressed, [833](#)
 - Vector4Compressed, [838](#)
- yEncoded
 - QuaternionCompressed, [648](#)
 - Vector2Compressed, [827](#)
 - Vector3Compressed, [832](#)
 - Vector4Compressed, [837](#)
- Z
 - QuaternionCompressed, [649](#)
 - Vector3Compressed, [833](#)
 - Vector4Compressed, [838](#)
- zEncoded
 - QuaternionCompressed, [649](#)
 - Vector3Compressed, [833](#)
 - Vector4Compressed, [838](#)