



BroadWorks Hosted Thin Call Center Agent/Supervisor

User Guide

Release 20.0

Document Version 5



BroadWorks® Guide

Copyright Notice

Copyright[©] 2014 BroadSoft, Inc.

All rights reserved.

Any technical documentation that is made available by BroadSoft, Inc. is proprietary and confidential and is considered the copyrighted work of BroadSoft, Inc.

This publication is for distribution under BroadSoft non-disclosure agreement only. No part of this publication may be duplicated without the express written permission of BroadSoft, Inc., 9737 Washingtonian Boulevard, Suite 350, Gaithersburg, MD 20878.

BroadSoft reserves the right to make changes without prior notice.

Trademarks

Any product names mentioned in this document may be trademarks or registered trademarks of BroadSoft or their respective companies and are hereby acknowledged.

This document is printed in the United States of America.



Document Revision History

Release	Version	Reason for Change	Date	Author
17.sp2	1	Created document.	October 14, 2010	Goska Auerbach
17.sp2	1	Edited and published document.	January 25, 2011	Jessica Boyle
17.sp2	2	Updated section 6.4.1 Assign Disposition Codes to Current Call to reflect changes in the interface.	February 17, 2011	Goska Auerbach
17.sp2	2	Updated section 6.3.2 View Incoming Call Details for EV 127533.	February 23, 2011	Goska Auerbach
17.sp2	2	Updated section 17 Configure Call Center for EV 126771.	February 24, 2011	Goska Auerbach
17.sp2	2	Updated section 5 <i>Explore Workspace</i> for EV 127180.	February 28, 2011	Goska Auerbach
17.sp2	2	Updated section 5 <i>Explore Workspace</i> for EV 128936.	March 8, 2011	Goska Auerbach
17.sp2	2	Updated sections 4.6 Sign Out and 17.7 Settings – About to align document with changes in the interface.	March 15, 2011	Goska Auerbach
17.sp2	2	Updated section 5 <i>Explore Workspace</i> for EV 126451.	March 16, 2011	Goska Auerbach
17.sp2	2	Edited changes and published document.	March 17, 2011	Jessica Boyle
17.sp2	3	Updated section 17.1.7 Workspace for EV 119881.	March 23, 2011	Goska Auerbach
17.sp2	3	Updated section 6.3.2 View Incoming Call Details for EV 118621.	March 24, 2011	Goska Auerbach
17.sp2	3	Edited changes and published document.	April 7, 2011	Andrea Fitzwilliam
17.sp2	4	Updated sections 14.1.1 Run Report and 14.1.9 Agent Utilization Report for EV 131031.	April 11, 2011	Goska Auerbach
17.sp2	4	Updated sections 4.6 Sign Out and 13.6 Silently Monitor Agent's Call for EV 131536.	April 12, 2011	Goska Auerbach
17.sp2	4	Updated sections 4.8 Change Your Password and 17.1.1 Account for EV 130633.	April 13, 2011	Goska Auerbach
17.sp2	4	Updated document with changes in the application.	April 23, 2011	Goska Auerbach
17.sp2	4	Updated section 14.2 Select Call Centers to Monitor for EV 141300. Updated Appendix C: Keyboard Shortcuts for EV 130778.	May 11, 2011	Goska Auerbach
17.sp2	4	Updated sections 6.3.2 View Incoming Call Details and 17.4.1 Notification for EV 131521.	May 17, 2011	Goska Auerbach
17.sp2	4	Edited and published the document.	May 26, 2011	Jessica Boyle



Release	Version	Reason for Change	Date	Author
17.sp2	5	Updated section 14 Manage Queued Calls (Supervisor) for EV 141300.	June 10, 2011	Goska Auerbach
17.sp2	5	Updated section for EV 141759.	June 14, 2011	Goska Auerbach
17.sp2	5	Updated section 16.1.2 Schedule Report for EV 144204.	June 20, 2011	Goska Auerbach
17.sp2	5	Updated section 16.1.1 Run Report for EV 143506.	June 27, 2011	Goska Auerbach
17.sp2	5	Edited changes to the document.	July 18, 2011	Jessica Boyle
17.sp2	5	Made minor editorial change.	July 18, 2011	Patricia Renaud
17.sp2	5	Edited document.	August 1, 2011	Andrea Fitzwilliam
17.sp2	5	Updated document with information about the usability enhancements.	August 1, 2011	Goska Auerbach
17.sp2	5	Updated sections 9.4 Manage Personal Contacts and 9.5 Manage Speed Dial Numbers for EV 145992. Removed the section about transferring calls to voice mail for EV 146029. Updated section 14.8 Monitor Next Call for EV 146021. Updated sections 11.2 Supervisor Phone States and 19.3 Phone States for EV 146017.	August 10, 2011	Goska Auerbach
17.sp2	5	Edited changes to the document.	August 12, 2011	Andrea Fitzwilliam
17.sp2	5	Updated section 9.5 Manage Speed Dial Numbers for EV 145992. Updated section 4.6 Sign Out with comments from testing. Updated section 13.3 Agent Phone and ACD States for EV 146017.	August 18, 2011	Goska Auerbach
17.sp2	5	Edited changes to the document and created PDF.	August 19, 2011	Andrea Fitzwilliam
17.sp2	5	Published document.	September 7, 2011	Patricia Renaud
17.sp2	6	Updated section 14.7 Order Queued Calls for EV 142502.	September 12, 2011	Goska Auerbach
18.0	1	Updated document for Release 18.0.	October 18, 2011	Goska Auerbach
18.0	1	Updated sections 4 <i>Getting Started</i> and 17.4.2 <i>Microsoft Outlook</i> for EV 153628.	November 22, 2011	Goska Auerbach
18.0	1	Updated section 17.6.3 Default Service- level Calculations for EV 141759.	January 3, 2012	Goska Auerbach
18.0	1	Edited changes and published document.	January 5, 2012	Patricia Renaud
18.0	2	Updated sections 3.2 Call Center – Supervisor, 14.1 Queued Calls Pane, 14.2 Select Call Centers to Monitor, 14.9 Enable Night Service Override or Forced Forwarding (Premium Call Center), and 14.15 Change Position of Call in Queue and added section 14.3 Modify Number of Calls to Display to align document with changes in the application.	January 31, 2012	Goska Auerbach



Release	Version	Reason for Change	Date	Author
18.0	2	Updated section 14.1 Queued Calls Pane for EV 159630.	February 21, 2012	Goska Auerbach
18.0	2	Edited changes and published document.	March 19, 2012	Jessica Boyle
19.0	1	Updated document for Release 19.0.	March 21, 2012	Goska Auerbach
19.0	1	Updated section 4.2 Sign in from Web Browser for EV 160535. Updated section 14.2 Select Call Centers to Monitor and 14.4 Show or Hide Call Center Panels for EV 165300.	May 11, 2012	Goska Auerbach
19.0	1	Edited changes.	October 5, 2012	Patricia Renaud
19.0	1	Updated section 6.12.1 Make Emergency Call for EV 175261.	November 15, 2012	Goska Auerbach
19.0	1	Edited changes and published document.	December 3, 2012	Jessica Boyle
20.0	1	Updated document for Release 20.0.	January 3, 2013	Goska Auerbach
20.0	1	Updated section <i>9.2.1 Sort Contacts</i> for EV 182669.	January 22, 2013	Goska Auerbach
20.0	1	Updated sections 4 <i>Getting Started</i> and 17.4.2 <i>Microsoft Outlook</i> for EV 192180.	May 6, 2013	Goska Auerbach
20.0	1	Removed section on theme for EV 194697. Updated sections 5 <i>Explore Workspace</i> and 17.1.7 <i>Workspace</i> for EV 175559.	June 7, 2013	Goska Auerbach
20.0	1	Updated section 17.4.5 Call Event Log for EV 196539.	July 26, 2013	Goska Auerbach
20.0	1	Updated section 6.8.5 End Call for EV 198717.	July 29, 2013	Goska Auerbach
20.0	1	Updated section 17.1.7 Workspace for EV 205434.	November 11, 2013	Goska Auerbach
20.0	1	Edited changes and published document.	November 21, 2013	Patricia Renaud
20.0	2	Updated section 11 Monitor Supervisors (Agent) for EV 213354.	January 20, 2014	Goska Auerbach
20.0	2	Updated document for the <i>Thin Clients to</i> Conform to Presence Rules Feature Description (EV 192594).	February 11, 2014	Goska Auerbach
20.0	2	Edited changes and published document.	March 17, 2014	Jessica Boyle
20.0	3	Updated section 5.3.11 Outlook Panel for EV 216467.	March 25, 2014	Goska Auerbach
20.0	3	Edited changes and published document.	May 30, 2014	Jessica Boyle
20.0	4	Revised indexing.	June 13, 2014	Goska Auerbach
20.0	4	Updated sections 11.2 Supervisor Phone States, 13.3 Agent Phone and ACD States, and 19.3 Phone States for EV 224630.	June 19, 2014	Goska Auerbach
20.0	4	Edited changes and published document.	July 8, 2014	Andrea Fitzwilliam
20.0	5	Updated section 13.4 View Agent's Details for EV 235015.	September 15, 2014	Goska Auerbach



Release	Version	Reason for Change	Date	Author
20.0	5	Updated section 6.9.1 Set Your Outgoing Calling Line Identity (Premium Call Center) for EV 231329.	September 15, 2014	Goska Auerbach
20.0	5	Updated the BroadSoft legal notice.	October 29, 2014	Goska Auerbach
20.0	5	Updated sections 6.3 View Calls and 15.3 Agent Information for EV 218533.	October 30, 2014	Goska Auerbach
20.0	5	Added Appendix B: Diagnostic Tool and updated sections 2.2 How This Guide is Organized and 17.7 Settings – About for the Client Side Diagnostic Tool For Thin Clients Feature (for EV 232627).	October 30, 2014	Goska Auerbach
20.0	5	Edited changes and published document.	November 4, 2014	Jessica Boyle



Table of Contents

1 :	Summary of Changes	. 18
1.1	Changes for Release 20.0, Document Version 5	. 18
1.2	Changes for Release 20.0, Document Version 4	. 18
1.3	Changes for Release 20.0, Document Version 3	
1.4	Changes for Release 20.0, Document Version 2	. 18
1.5	Changes for Release 20.0, Document Version 1	. 18
1.6	Changes for Release 19.0, Document Version 1	. 19
1.7	Changes for Release 18.0, Document Version 2	. 20
1.8	Changes for Release 18.0, Document Version 1	. 20
1.9	Changes for Release 17.sp2, Document Version 6	. 20
1.10	Changes for Release 17.sp2, Document Version 5	. 20
1.11	Changes for Release 17.sp2, Document Version 4	. 20
1.12	Changes for Release 17.sp2, Document Version 3	. 21
1.13	Changes for Release 17.sp2, Document Version 2	. 21
1.14	Changes for Release 17.sp2, Document Version 1	. 21
2	About This Document	. 22
2.1	Audience	. 22
2.2	How This Guide is Organized	. 22
2.3	Additional Resources	. 23
3 I	ntroduction to Call Center	. 24
3.1	Call Center – Agent	. 25
3.2	Call Center – Supervisor	. 26
4 (Getting Started	. 28
4.1	Launch Call Center from Web Portal	. 28
4.2	Sign in from Web Browser	. 29
4.3	Hot Desk Sign-in	. 30
4.4	Sign-in Restrictions	. 31
4.5	Get Help	. 32
4.6	Sign Out	. 32
4.7	Set Up Call Center	. 33
4.8	Change Your Password	. 33
4.9	Change Your ACD State (Agents)	. 34
4.10	Change Your Instant Messaging and Presence State	. 34
4.11	Enable or Disable Services	. 35
5 I	Explore Workspace	. 37
5.1	Logo Pane	. 39
į	5.1.1 Global Message Area	. 39
į	5.1.2 Links to Other Interface Elements and Functions	. 39
į	5.1.3 Logged User Information	. 39



5.2	Call	Console	40
0	5.2.1	Header Bar	
	5.2.2	Dialer	
	5.2.3	Current Calls	
	5.2.4	Conference Call	
	5.2.5	Call States and Actions	
5.3	Con	tacts Pane	44
	5.3.1	Search Panel	46
	5.3.2	Enterprise/Group Panel	46
	5.3.3	Common Panel	46
	5.3.4	Personal Panel	47
	5.3.5	Agents Panel (Supervisors)	47
	5.3.6	Supervisors Panel (Agents)	47
	5.3.7	Speed Dial Panel	48
	5.3.8	Queues Panel	48
	5.3.9	Custom Directories Panels	48
	5.3.10	Instant Message Panel	49
	5.3.11	Outlook Panel	49
	5.3.12	Directories Panel	50
5.4	Call	History	51
5.5	Con	trols	52
	5.5.1	Call Action Buttons	54
6	Manag	ge Calls	57
6.1	Call	Management Operations Quick Reference	58
6.2	Drag	g and Drop Call onto Contact	60
6.3	Viev	v Calls	60
	6.3.1	View Current Calls	60
	6.3.2	Group Calls	61
	6.3.3	View Incoming Call Details	62
6.4	Assi	ign Disposition Codes (Premium Call Center)	63
	6.4.1	Assign Disposition Codes to Current Call	63
	6.4.2	Assign Disposition Codes in Wrap-Up	63
6.5	Gen	erate Call Trace	65
	6.5.1	Generate Call Trace for Selected Call	65
	6.5.2	Generate Call Trace for Last Released Call	65
6.6	Rec	ord Calls	65
	6.6.1	Start Call Recording	66
	6.6.2	Pause and Resume Call Recording	66
	6.6.3	Stop Call Recording	66
6.7	Viev	v and Change Security Classification of Calls	66
	6.7.1	Change Security Classification	
6.8	Rec	eive, Answer, and End Calls	68



6	3.1 Answer Call	68
6	3.2 Auto Answer Calls	68
6	3.3 Open URL	68
6	3.4 Save vCard	69
6	3.5 End Call	69
6.9	Make Outbound Calls	69
6	9.1 Set Your Outgoing Calling Line Identity (Premium Call Center)	69
6	9.2 Dial Ad Hoc Number	70
6	9.3 Redial Number	70
6	9.4 Dial Contact	71
6	9.5 Dial from Search	71
6	9.6 Dial from History	72
6.10	Place Calls on Hold, Resume, and Camp Calls	72
6	10.1 Place Call on Hold	72
6	10.2 Resume Held Call	72
6	10.3 Conduct Busy Camp On	73
6.11	Transfer Calls	73
6	11.1 Blind Transfer	73
6	11.2 Transfer with Consultation	74
6	11.3 Transfer to Queue	74
6.12	Escalate Calls	74
6	12.1 Make Emergency Call	74
6	12.2 Blind Escalate Call	75
6	12.3 Escalate with Consultation	76
6	12.4 Escalate with Conference or Handover	76
6	12.5 Escalate with Mid-Conference Hold	76
6.13	Manage Conference Calls	77
6	13.1 Start Three-Way Conference	78
6	13.2 Add Participant to Conference	78
6	13.3 Hold Conference	79
6	13.4 Resume Conference	79
6	13.5 Hold Participant	79
6	13.6 Take Participant Off Hold	79
6	13.7 Leave Conference	79
6	13.8 End Participant	79
6	13.9 End Conference	79
7 I	anage Call History	80
7.1	View Call History	80
7.2	Delete Call History	80
8 E	mail Contacts	81
8.1	Send E-mail Message to Contact	81
	anage Contacts	



9.1 Vie	ew Contacts	83
9.1.1	Show or Hide Directories	83
9.1.2	Display Directory Below Call Console	84
9.1.3	Show or Hide Directory Content	86
9.1.4	Show Contact Details	86
9.1.5	Select Display Order	87
9.2 Or	ganize Contacts	88
9.2.1	Sort Contacts	88
9.3 Se	arch for Contacts	89
9.3.1	Perform Contact Search	89
9.4 Ma	anage Personal Contacts	90
9.4.1	Add Personal Contact	90
9.4.2	Delete Personal Contact	91
9.5 Ma	anage Speed Dial Numbers	92
9.5.1	Add Speed Dial Entry	92
9.5.2	Modify Speed Dial Entry	92
9.5.3	Delete Speed Dial Entry	93
10 Mon	itor IM&P Contacts and Chat with Contacts	94
10.1 Mc	onitor IM&P Contacts	94
10.1.	1 Subscribe to Contact	94
10.1.	2 Add Contact to Instant Message Directory	95
10.1.	3 Modify Contact Name	96
10.1.	4 Unsubscribe from Contact	96
10.1.	5 Accept or Reject Subscription Request	97
10.1.	6 View Unified Presence State of Contacts	97
10.2 Ch	at with IM&P Contacts	98
10.2.	1 Start Instant Messaging Session	98
10.2.	2 Place Call from Chat Window	100
10.2.	3 Establish Multiuser Chat Session	100
10.2.	4 Manage Instant Messaging Sessions	101
11 Mon	itor Supervisors (Agent)	103
11.1 Se	lect Supervisors to Monitor	103
11.2 Su	pervisor Phone States	104
12 Mon	itor Call Centers (Agent)	105
12.1 Da	ishboard Pane	105
12.2 Se	lect Call Centers to Monitor	107
12.3 Se	lect Information to Display	107
	der Call Centersder	
13 Mana	age Agents (Supervisor)	109
13.1 Se	lect Agents to Monitor	109
	ake Agents Join Queues	



13.3	Agent Phone and ACD States	111
13.4	View Agent's Details	112
13.5	Change Agent ACD State	113
13.6	Silently Monitor Agent's Call	114
13.7	Barge in on Agent's Call	115
13.8	Pick Up Agent's Ringing Call	115
14 N	flanage Queued Calls (Supervisor)	116
14.1	Queued Calls Pane	116
14.2	Select Call Centers to Monitor	119
14.3	Modify Number of Calls to Display	120
14.4	Show or Hide Call Center Panels	120
14.5	View Queued Calls	121
14.6	Group Queued Calls	121
14.7	Order Queued Calls	121
14.8	Monitor Next Call	122
14.9	Enable Night Service Override or Forced Forwarding (Premium Call Center)	122
14.10	Retrieve Call from Queue	123
14.11	Promote Call in Queue (Premium Call Center)	123
14.12	2 Transfer Call to Another Queue	123
14.13	3 Transfer Call from Queue to Agent	124
14.14	Transfer Call to Ad Hoc Number	124
14.15	5 Change Position of Call in Queue	124
14.16	Transfer Call to Top of Queue (Premium Call Center)	125
15 V	/iew Real-Time Statistics (Supervisor)	126
15.1	Display Dashboard	126
15.2	Queue Information	127
15.3	Agent Information	128
15.4	Select Information to Display	129
15.5	Navigate to Agent in Agent Directory or Queue in Queued Calls Pane	129
16 G	Senerate Reports	131
1	6.1.1 Run Report	132
1	6.1.2 Schedule Report	138
1	6.1.3 Manage Scheduled Reports	143
17 C	Configure Call Center	144
17.1	Settings – General	145
1	7.1.1 Account	145
	7.1.2 Hotel/Flexible Seating Host	
	7.1.3 Language	
	7.1.4 Screen Pop	
	7.1.5 Date Format	
1	7.1.6. Time Format	147



17.1.7 Workspace	148
17.2 Settings – Application	149
17.2.1 Queue Memberships (Agent)	149
17.2.2 Agent Policies (Agent)	149
17.2.3 Barge-In & Monitor (Supervisor)	150
17.3 Settings – Services	151
17.4 Settings – Plug-ins	152
17.4.1 Notification	152
17.4.2 Microsoft Outlook	153
17.4.3 LDAP v3	153
17.4.4 Program Shortcuts	154
17.4.5 Call Event Log	155
17.5 Settings – Messaging	157
17.5.1 E-mail Messaging	157
17.5.2 Instant Messaging and Presence	157
17.6 Settings – Report	158
17.6.1 Default Thresholds	158
17.6.2 Default Start of the Week	158
17.6.3 Default Service-level Calculations	159
17.7 Settings – About	159
18 Configure Web Browser	161
18.1 Internet Explorer Settings for Full Screen Mode	161
18.2 Firefox Settings Quick Link Navigation	162
19 Appendix A: Glossary and Definitions	163
19.1 ACD States	163
19.2 Agent Skill Levels (Premium Call Centers)	164
19.3 Phone States	164
19.4 Unified Instant Messaging Presence States	165
19.5 Call States	166
19.6 Call Types	166
20 Appendix B: Diagnostic Tool	168
20.1 Launching Diagnostic Tool	168
20.2 Diagnostic Tool GUI	
20.2.1 Session Tab	
20.2.2 Long Polling Tab	
20.2.3 Calls Tab	
20.2.4 Service Tab	
20.2.5 Monitoring Tab	
20.2.6 Support Tab	
20.3 Known Issues	
21 Appendix C: Keyboard Shortcuts	



Index......175



Table of Figures

Figure 1 Call Center – Agent Main Interface	25
Figure 2 Call Center – Supervisor Main Interface	
Figure 3 BroadWorks Web Portal Logo Pane - Launching Call Center as Agent	28
Figure 4 BroadWorks Web Portal Logo Pane – Launching Call Center as Superviso	r28
Figure 5 Call Center Sign-in Page	29
Figure 6 Call Center Sign-in Dialog Box – Advanced Options	30
Figure 7 Sign-in Dialog Box with Error Message	
Figure 8 Main Interface (Top of Page) with Error Message	31
Figure 9 Main Interface (Top of Page) with Information Message	31
Figure 10 Logo Pane with Help Link	32
Figure 11 Dialog Box – Signing Out Last	32
Figure 12 Dialog Box – Saving Workspace on Sign Out	32
Figure 13 Changing Password	33
Figure 14 Logo Pane – ACD State Control	34
Figure 15 Logo Pane – Unavailable Codes	34
Figure 16 IM&P State Drop-Down List	35
Figure 17 Set IM Status Dialog Box	35
Figure 18 IM&P Status Message in ToolTip	35
Figure 19 Call Center – Agent Main Interface	37
Figure 20 Call Center Logo Pane	39
Figure 21 Call Console	40
Figure 22 Call Console Header Bar	
Figure 23 Dialer	
Figure 24 Call Console – Current Calls	
Figure 25 Call Console – Conference Call	43
Figure 26 Contacts Pane	
Figure 27 Group Panel – Contact in Focus with Action Buttons	45
Figure 28 Contacts Pane – Search Panel	
Figure 29 Contacts Pane – Group Panel	46
Figure 30 Contacts Pane – Common Panel	46
Figure 31 Contacts Pane – Personal Panel	47
Figure 32 Contacts Pane – Agents Panel	47
Figure 33 Contacts Pane – Supervisors Panel	47
Figure 34 Contacts Pane – Speed Dial Panel	
Figure 35 Contacts Pane – Queues Panel	
Figure 36 Contacts Pane – Custom Panel	
Figure 37 Contacts Pane – Instant Message Panel	
Figure 38 Contacts Pane – Outlook Panel	49
Figure 39 Contacts Pane – Directories Panel	
Figure 40 Call History Dialog Box	
Figure 41 Call History Dialog Box – Call Log with Call Action Button	
Figure 42 Group Panel – Contact in Focus	
Figure 43 Call Console	
Figure 44 Dragging Call and Dropping on Contact	
Figure 45 Call Console – View Current Calls	
Figure 46 Call Console – Grouped Calls	
Figure 47 Grouping Calls in Call Console	
Figure 48 Call Notification Pop-up Window for Call That Is Not ACD Call	
Figure 49 Call Notification Pop-up Window for ACD Call	
Figure 50. Call Notification Pop-up Window with Diversion Information	



Figure 51	Call Console – Assigning Disposition Code to Active Call	63
Figure 52	Call Console – Assigning Disposition Code in Wrap-Up	64
Figure 53	Call in Call Console with Record Button	65
Figure 54	Call Being Recorded	65
	Security Classification of Calls	
Figure 56	Security Classification Levels	67
Figure 57	Dialer – Setting Outbound CLID	69
Figure 58	Dialer – Dialing Ad Hoc Number	70
	Dialer – Select Recently Dialed Number	
	Dialer – Redialing Number	
Figure 61	Group Panel – Expanded Contact with Action Buttons	71
	Dial From Search	
Figure 63	Call History Dialog Box	72
Figure 64	Supervisors Panel – Making Emergency Calls	75
	Call Console - Conference Call Panel	
Figure 66	Call Console – Starting Conference Call	78
	Conference Call Panel - Conference Call	
Figure 68	Call History Dialog Box	80
	Contacts Pane	
Figure 70	Contacts Pane – Show/Hide Contact Directories	84
-	Directories Panel – Selecting Directory to Display	
	Directories Panel – Selecting Directory	
	Custom Directory Displayed Below Call Console	
	Group Panel Expanded	
	Group Panel – Contact Details	
	Contacts Pane – Displaying Contacts by First Name, Last Name	
Figure 77	Supervisors Panel – Supervisors Listed by First Name, Last Name	87
	Contacts Pane – Sorting Contacts	
	Group Panel – Contacts Sorted by First Name	
	Contacts Pane – Search Panel	
	Contacts Pane – Search Results	
	Edit Personal Contact Dialog Box – Adding Entry	
	Edit Personal Contact Window – Deleting Entry	
	Edit Speed Dials Dialog Box – Adding Entry	
	Edit Speed Dials Dialog Box – Modifying Entry	
	Edit Speed Dials Dialog Box – Deleting Entry	
	Contact (IM) Subscribe Dialog Box	
	Contact (IM) Re-Subscribe Dialog Box	
	Edit Instant Message Contacts Dialog Box – Add Contact	
	Edit Instant Message Contacts Dialog Box – Modify Contact	
	Contact (IM) Unsubscribe Dialog Box	
	Contact (IM) Request Dialog Box	
	Instant Message Directory – Unified Presence State of Contacts	
	IM&P Contact with Chat button	
	Chat Window	
	Add Participants to Chat	
	Multiuser Chat	
	Managing Chat Sessions	
	Supervisors Panel	
	O Supervisor Favorites Dialog Box	
	1 Dashboard Pane (Agents)	
Figure 102	2 Select Queues Dialog Box	107
Figure 103	3 Select Fields Dialog Box	107



Figure 104	Dashboard - Options - Sort By	108
Figure 105	Agents Panel	109
Figure 106	Edit Monitored Agents Dialog Box	109
Figure 107	Agents Panel – Monitored Agents	110
Figure 108	Agents Panel - Contact with Queue Button	110
Figure 109	Agent Queue Membership Dialog Box	111
	Agents Panel - Agents with Phone and ACD State Displayed	
Figure 111	Agents Panel Entry Expanded	113
Figure 112	Agents Panel – Agent ACD State	113
Figure 113	Silently Monitored Call	114
Figure 114	Queued Calls Pane	117
Figure 115	Queued Calls - Options - Edit Queue Favorite Dialogue	119
	Edit Queue Favorites Dialog Box	
Figure 117	Queued Calls - Options - View	120
Figure 118	Queued Calls - Options - Group	121
Figure 119	Queued Calls - Options - Sort	121
Figure 120	Edit Queue Favorites Dialog Box	122
Figure 121	Ad Hoc Queue Transfer	124
	Reordering Queued Call	
Figure 123	Transferring Call to Top of Queue	125
	Dashboard	
•	Visual Indicators of Threshold Severity	
•	Dashboard – Hide Signed Out Agents Box	
	Dashboard – Select Columns to Display	
Figure 128	Dashboard – Navigate to Queue or Agent	130
	Queued Calls Pane – Quick Link Queue	
Figure 130	Main Interface (Top of Window)	131
	Report Window	
	Abandoned Call Report – Running Report	
Figure 133	Preferences – General	136
Figure 134	Abandoned Calls Report – Bar Chart	137
Figure 135	Abandoned Calls Report – Table (Fragment)	137
Figure 136	Report Window – Report List	138
Figure 137	Scheduling Report (Abandoned Call Report)	139
Figure 138	Scheduled Report – Daily Recurrence Pattern	140
Figure 139	Scheduled Report – Weekly Recurrence Pattern	140
Figure 140	Scheduled Report – Monthly Recurrence Pattern	140
Figure 141	Scheduled Report – Yearly Recurrence Pattern	141
Figure 142	Report Time for Nonrecurrent Report	141
Figure 143	Report Time for Recurrent Report	141
Figure 144	Scheduled Report – Recurrence Range	141
Figure 145	Report Timeframe for Nonrecurrent Report	142
Figure 146	Report Timeframe for Recurrent Report	142
Figure 147	Report Sampling and Output Format	142
	Scheduled Reports Dialog Box	
	Settings – General	
•	Account – Change Password	
•	Settings – Application (Agent)	
	Settings – Application (Supervisor)	
Figure 153	Settings – Services	151
Figure 154	Settings – Plugins	152
Figure 155	Settings – Messaging	157
Figure 156	Settings – Report	158



Figure 157	Settings – About	159
Figure 158	Security Settings – Internet Zone Dialog Box	161
Figure 159	Firefox – Content Tab	162
Figure 160	Firefox – Window Focus Settings	162
Figure 161	Settings – About (Launching Diagnostic Tool)	168
Figure 162	Diagnostic Tool – Session Tab	169
Figure 163	Diagnostic Tool – Long Polling Tab	170
Figure 164	Diagnostic Tool – Calls Tab	170
Figure 165	Diagnostic Tool – Service Tab	171
Figure 166	Diagnostic Tool – Monitoring Tab	171
•	Diagnostic Tool – Support Tab	



1 Summary of Changes

This section describes the changes to this document for each release and document version.

1.1 Changes for Release 20.0, Document Version 5

This version of the document includes the following changes:

- Updated section 13.4 View Agent's Details for EV 235015.
- Updated section 6.9.1 Set Your Outgoing Calling Line Identity (Premium Call Center) for EV 231329.
- Updated sections 6.3 View Calls and 15.3 Agent Information for EV 218533.
- Added Appendix B: Diagnostic Tool and updated sections 2.2 How This Guide is Organized and 17.7 Settings – About for the Client Side Diagnostic Tool For Thin Clients Feature (for EV 232627).

1.2 Changes for Release 20.0, Document Version 4

This version of the document includes the following changes:

- Revised indexing and updated Figure 154 Settings Report.
- Updated sections 11.2 Supervisor Phone States, 13.3 Agent Phone and ACD States, and 19.3 Phone States for EV 224630.

1.3 Changes for Release 20.0, Document Version 3

This version of the document includes the following changes:

■ Updated section 5.3.11 Outlook Panel for EV 216467.

1.4 Changes for Release 20.0, Document Version 2

This version of the document includes the following changes:

- Updated section 11 Monitor Supervisors (Agent) for EV 213354.
- Updated sections 4.10 Change Your Instant Messaging and Presence State, 10 Monitor IM&P Contacts and Chat with Contacts, 10.1.6 View Unified Presence State of Contacts, and 19.4 Unified Instant Messaging Presence States for the Thin Clients to Conform to Presence Rules Feature Description (EV 192594).

1.5 Changes for Release 20.0, Document Version 1

This version of the document includes the following changes:

- Updated document for Release 20.0.
- Updated section 9.2.1 Sort Contacts for EV 182669.
- Updated document for the Call Center Usability Enhancements Feature Description (EVs 181240 and 173610).
- Updated document for the Visual Security Classification for Active Call Feature Description (EV 174096).



- Updated sections 5.5.1 Call Action Buttons and 6.6 Record Calls for the Call Recording – Start/Stop/Pause/Resume User Control Feature Description (EV 171961).
- Updated sections 5.2.3 Current Calls, 6.3.2 View Incoming Call Details, and 17.1.4 Screen Pop for the Diversion Info Availability for Queued Calls Feature Description (EV 187126).
- Updated sections 4 Getting Started and 17.4.2 Microsoft Outlook for EV 192180.
- Updated sections 4 *Getting Started* and 17.1 *Settings General* for the *Flexible Seating Feature Description (EV 191552).*
- Removed section on theme for EV 194697.
- Updated sections 5 Explore Workspace and 17.1.7 Workspace for EV 175559.
- Updated section 17.4.5 Call Event Log for EV 196539.
- Updated section 6.8.5 End Call for EV 198717.
- Updated section 17.1.7 Workspace for EV 205434.

1.6 Changes for Release 19.0, Document Version 1

This version of the document includes the following changes:

- Updated section 17.2.3 Barge-In & Monitor (Supervisor).
- Updated document for the Web Pop URL Enhancement Call Center and Receptionist (Thin Clients) Feature Description (EVs 149945).
- Added section 12 Monitor Call Centers (Agent) and updated sections 3.1 Call Center

 Agent and 5 Explore Workspace for the Call Center Agent Client View Queue
 Status Feature Description (EV 149948).
- Updated section 16 Generate Reports for the Remove CCRS Feature Description (EV 154550) and for EV 172891.
- Updated the description of the *Unknown* phone state in sections 11.2 Supervisor Phone States, 13.3 Agent Phone and ACD States, and 19.3 Phone States.
- Updated section 14.2 Select Call Centers to Monitor and 14.4 Show or Hide Call Center Panels for EV 165300.
- Updated section 4.2 Sign in from Web Browser for EV 160535.
- Added section 4.4 Sign-in Restrictions for the Thin Client Single User Login Restrictions Feature Description (EV 163737).
- Updated sections 12 Monitor Call Centers (Agent) and 15 View Real-Time Statistics (Supervisor) for the CC Thresholds and Alerts Feature Description (EV 149950).
- Updated sections 13.4 View Agent's Details, 17.2.1 Queue Memberships (Agent), and Appendix A: Glossary and Definitions for the Call Center Skill-Based Routing Feature Description (EV 150771).
- Updated section 16.1.2 Schedule Report for the Schedule User Interface Improvements Feature Description (EV 165598).
- Added sections 4.10 Change Your Instant Messaging and Presence State and 10 Monitor IM&P Contacts and Chat with and updated section 9 Manage Contacts for the IM&P for Call Center and Receptionist Clients Feature Description (EV 150370).
- Updated section 6.12.1 Make Emergency Call for EV 175261.



1.7 Changes for Release 18.0, Document Version 2

This version of the document includes the following changes:

- Updated sections 3.2 Call Center Supervisor, 14.1 Queued Calls Pane, 14.2 Select Call Centers to Monitor, 14.9 Enable Night Service Override or Forced Forwarding (Premium Call Center), and 14.15 Change Position of Call in Queue and added section 14.3 Modify Number of Calls to Display to align document with changes in the application.
- Updated section 14.1 Queued Calls Pane for EV 159630. The position of the following information in the Queued Calls pane has changed, name and number of the remote party and the name and number of the DNIS/call center that took the call.

1.8 Changes for Release 18.0, Document Version 1

This version of the document includes the following changes:

- Added section 6.6 Record Calls for the Call Recording Thin Clients Feature Description (EVs 46939 and 141973).
- Updated sections 4 *Getting Started* and *17.4.2 Microsoft Outlook* for EV 153628.
- Updated section 17.6.3 Default Service-level Calculations for EV 141759.

1.9 Changes for Release 17.sp2, Document Version 6

This version of the document includes the following changes:

■ Updated section 14.7 Order Queued Calls for EV 142502.

1.10 Changes for Release 17.sp2, Document Version 5

This version of the document includes the following changes:

- Updated section 14 Manage Queued Calls (Supervisor) for EV 141300.
- Updated section 16.1.1 Run Report for EVs 141759 and 143506.
- Updated section 16.1.2 Schedule Report for EV 144204.
- Updated document for the usability enhancements.
- Updated sections 9.4 Manage Personal Contacts and 9.5 Manage Speed Dial Numbers for EV 145992.
- Removed the section about transferring calls to voice mail for EV 146029.
- Updated section 14.8 Monitor Next Call for EV 146021.
- Updated sections 11.2 Supervisor Phone States, 13.3 Agent Phone and ACD States, and 19.3 Phone States for EV 146017.
- Updated section 4.6 Sign Out with comments from testing.

1.11 Changes for Release 17.sp2, Document Version 4

This version of the document includes the following changes:

- Updated sections 14.1.1 Run Report and 14.1.9 Agent Utilization Report for EV 131031.
- Updated sections 4.6 Sign Out and 13.6 Silently Monitor Agent's Call for EV 131536.
- Updated sections 4.8 Change Your Password and 17.1.1 Account for EV 130633.
- Added Appendix C: Keyboard Shortcuts.



- Updated document with changes in the application.
- Updated section 14.2 Select Call Centers to Monitor for EV 141300.
- Updated Appendix C: Keyboard Shortcuts for EV 130778.
- Updated sections 6.3.2 View Incoming Call Details and 17.4.1 Notification for EV 131521.

1.12 Changes for Release 17.sp2, Document Version 3

This version of the document includes the following changes:

- Updated section 17.1.7 Workspace for EV 119881.
- Updated sections 6.3.2 View Incoming Call Details and 17.4.1 Notification for EV 118621.
- Updated document to align with changes in the interface.

1.13 Changes for Release 17.sp2, Document Version 2

This version of the document includes the following changes:

- Updated section 6.4.1 Assign Disposition Codes to Current Call to reflect changes in the interface.
- Updated section 6.3.2 View Incoming Call Details for EV 127533.
- Updated section 17 Configure Call Center for EV 126771.
- Updated section 5 Explore Workspace for EVs 127180 and 128936
- Updated sections 4.6 Sign Out and 17.7 Settings About to align document with changes in the interface.
- Updated section 5 Explore Workspace for EV 126451.

1.14 Changes for Release 17.sp2, Document Version 1

This is a new document.



2 About This Document

This user guide provides step-by-step procedures and reference information for using the BroadWorks Hosted Thin Call Center Release 20.0 client application.

2.1 Audience

This document is intended for Call Center agents and supervisors who use the BroadWorks Hosted Thin Call Center client.

2.2 How This Guide is Organized

The following table identifies the sections to refer to for information about the functionality provided by Call Center.

Section	Overview
Introduction to Call Center	This section provides an overview of Call Center and the functionality available to agents and supervisors.
Getting Started	This section describes how to sign in and out of Call Center, perform the initial setup, change a password, and obtain help.
Explore Workspace	This section provides an overview of the user interface.
Manage Calls	This section provides information on how to make and manage calls. This includes using your contacts to make calls or perform actions on existing calls.
Manage Call History	This section provides information on managing call logs.
E-mail Contacts	This section includes information on how to send e-mail messages to contacts.
Manage Contacts	This section provides information on managing contact directories and searching for contacts.
Monitor IM&P Contacts and Chat with Contacts	This section provides information about monitoring the presence state of your IM&P contacts and chatting with them.
Monitor Supervisors (Agent)	This section describes how agents can monitor the phone state of selected supervisors.
Monitor Call Centers (Agent)	This section describes the Dashboard panel available to agents. The Dashboard panel allows agents to view key indicators about selected call centers they are staffing.
Manage Agents (Supervisor)	This section describes how supervisors can use Call Center to manage agents under their supervision.
Manage Queued Calls (Supervisor)	This section provides information on managing queued calls.
View Real-Time Statistics (Supervisor)	This section describes the Dashboard that supervisors can use to monitor the state of selected call centers and agents.
Generate Reports	This section describes how to generate and schedule reports.
Configure Call Center	This section describes the settings you can configure to set up and customize Call Center for improved usability.
Appendix A: Glossary and Definitions	This appendix contains definitions of terms used in Call Center.



Section	Overview
Appendix B: Diagnostic Tool	This appendix describes a diagnostic tool available in some versions of Call Center used to troubleshoot performance problems with the help of support personnel.
Appendix C: Keyboard Shortcuts	This appendix describes the keyboard shortcuts available in Call Center.

2.3 Additional Resources

For more information on Call Center and on Application Server procedures used by group administrators, department administrators, and users, see the following BroadWorks guides:

- BroadWorks Hosted Thin Call Center Agent/Supervisor Configuration and Administration Guide
- BroadWorks Call Center Solution Guide
- BroadWorks Call Center Reports Guide
- BroadWorks Getting Started Web Interface Administration Guide
- BroadWorks Application Server User Web Interface Administration Guide



3 Introduction to Call Center

BroadWorks Call Center is a carrier-class, communications management product for Call Center agents and supervisors used with the BroadSoft® BroadWorks® telephony softswitch platform, on which call centers are hosted.

BroadWorks Call Center delivers the following real benefits to users:

- Efficient call handling and automatic call distribution (ACD) state management by Call Center agents
- Integration of online directories with Click-To-Dial capability
- Real-time monitoring of agent and queue activity by Call Center supervisors
- Historical reporting on agent and queue activity by Call Center supervisors

Along with this focus on design, BroadWorks Call Center employs the latest technology platforms and communications facilities.

The Hosted Thin Call Center, introduced in Release 17.sp2, is an SaaS Rich Internet Application (RIA) hosted on BroadWorks that allows you to manage call center activity from a web browser.

NOTE: For information about the web browsers supported by Call Center, see the *BroadWorks Hosted Thin Call Center Agent/Supervisor Configuration and Administration Guide* or ask your administrator.

This document describes the BroadWorks Hosted Thin Call Center client.

BroadWorks Hosted Thin Call Center client application herein is referred to as Call Center, Call Center client, Call Center application, or client.

The Call Center functionality available to you depends on your Call Center function (agent or supervisor), the types of queues you are staffing or monitoring (Standard or Premium), and your own services and settings. For more information about the capabilities and services assigned to you, ask your group or enterprise administrator.

The following sections provide an overview of Call Center – Agent and Call Center – Supervisor functions and refer you to other sections for more information.

NOTE: Call Center functionality available in specific contexts is identified throughout the document.



3.1 Call Center – Agent

The Call Center – Agent client is designed to support the needs of Call Center agents in any environment. It supports the full set of call handling functions, ACD state management, integration of multiple directories, Outlook integration, and other features required in large call centers.

Figure 1 shows the main interface of the Call Center – Agent.




Figure 1 Call Center – Agent Main Interface

The interface contains the following work areas:

- **Logo pane** The *Logo* pane displays information about you and contains links to other pages and functions.
- Call Console You use the Call Console to view and manage your current calls.
- Contacts pane The Contacts pane contains your contact directories, the list of your supervisors, and the list of the call centers to which you belong. It allows you to use your contacts to make and manage your calls.
- Dashboard pane The Dashboard pane provides real-time summary information about up to 50 call centers selected from the list of call centers to which you are assigned.
- Call History dialog box You use the Call History dialog box to view your past calls and make calls from history.
- Chat windows You use Chat windows to chat with your IM&P contacts.
- **Report window** You use the *Report* window, accessed via the Reporting link, to generate reports about your activity and performance in the call centers you are staffing.
- **Settings pages** You use the *Settings* pages, accessed via the Settings link, to configure various aspects of Call Center.

For more information about the Call Center user interface, see section 5 *Explore Workspace*.



Call Center functionality available to agents is described in the following sections:

- Getting Started
- Manage Calls
- Manage Call History
- E-mail Contacts
- Manage Contacts
- Monitor IM&P Contacts and Chat with Contacts
- Monitor Supervisors (Agent)
- Monitor Call Centers (Agent)
- Generate Reports
- Configure Call Center

3.2 Call Center - Supervisor

The Call Center – Supervisor client is designed to support the needs of call center supervisors in any environment. It supports agent monitoring, queue management, real-time and historical reporting, and other features required in large call centers.

Figure 2 shows the main interface of the Call Center – Supervisor.



Figure 2 Call Center - Supervisor Main Interface

The Call Center interface contains the following work areas:

- **Logo pane** The *Logo* pane displays information about you and contains links to other pages and functions.
- Call Console You use the Call Console to view and manage your current calls.
- **Contacts pane** The *Contacts* pane contains your contact directories and provides you with real-time call and ACD state of the agents you are monitoring.



- Queued Calls pane You use the Queued Calls pane to manage queued calls.
- Call History dialog box You use the Call History dialog box to view your past calls and make calls from history.
- Chat windows You use Chat windows to chat with your IM&P contacts.
- **Dashboard** The *Dashboard* provides real-time summary information for up to 50 queues and allows you to monitor key performance indicators for monitored call centers and supervised agents.
- Report window You use the Report window, accessed via the Reporting link, to generate reports about the activity and performance of call centers and agents you manage.
- **Settings pages** You use the *Settings* pages, accessed via the Settings link, to configure various aspects of Call Center.

For more information, see section 5 Explore Workspace.

For information on Call Center functions performed by supervisors, see the following sections:

- Manage Agents (Supervisor)
- Manage Queued Calls (Supervisor)
- View Real-Time Statistics (Supervisor)
- Generate Reports

In addition, for information about other functions available to you, see the following sections:

- Getting Started
- Manage Calls
- Manage Call History
- E-mail Contacts
- Manage Contacts
- Monitor IM&P Contacts and Chat with Contacts
- Configure Call Center



4 Getting Started

Call Center is hosted on BroadWorks and you access it over the network either from your web portal or from a web browser. The sign-in procedure is the same for agents and supervisors.

In addition, agents can sign in to Call Center using hot desk functionality, that is, sign in from any available desk configured for that purpose. Upon login, a desk's phone is associated with a certain agent and behaves as if it were the permanent phone of the agent for the duration of the login session. This allows agents to use a single login ID to perform their work independently of their location.

NOTE 1: The minimum screen resolution required for the Call Center is 1024 x 768 pixels.

NOTE 2: Call Center does not support logging in as different users from the same machine at the same time.

NOTE 3: When using the Outlook Integration feature with Microsoft Outlook 2010 or Outlook 2013 (32- or 64-bit edition), make sure Outlook is running before Call Center is launched; otherwise, the Outlook Integration functionality does not work.

4.1 Launch Call Center from Web Portal

BroadWorks has a Single Sign-On feature. When you access the Call Center client from the web portal, you do not need to provide your credentials since you are already logged in to the web portal.

To launch Call Center:

- Log in to your BroadWorks web portal.
- 2) From the *Launch* drop-down list at the top right-hand side of the BroadWorks logo pane, select the *Call Center* service.



Figure 3 BroadWorks Web Portal Logo Pane - Launching Call Center as Agent




Figure 4 BroadWorks Web Portal Logo Pane - Launching Call Center as Supervisor

Call Center starts and you are automatically signed in.



4.2 Sign in from Web Browser

To sign in to the Call Center client, use the same credentials that you use to connect to the web portal.

To sign in to Call Center:

1) In your web browser, enter the Uniform Resource Locator (URL) of the Call Center client. The *Call Center Sign-in* page appears.



Figure 5 Call Center Sign-in Page

- 2) Enter your BroadWorks user ID in user@domain format and enter your password.
 - If you are unsure of your user ID or password, contact your administrator.
 - You can also enter just the *user* part of your ID. The system then appends the default domain to it before authenticating you. However, if your domain is different from the default domain, you have to enter your user ID with the domain name.
 - Optionally, if your system has been configured to allow it, you can configure your domain name.
- 3) Check Stay signed in to instruct the client to automatically reconnect and sign in to the server when it detects a network connection.
 - This should generally be enabled to help mitigate intermittent internet connections. When disabled, the client signs out the user when the connection is lost.
- 4) To configure your domain name or the Call Center language, click **Show options**. The area expands, displaying advanced options.





Figure 6 Call Center Sign-in Dialog Box – Advanced Options

- 5) To configure your domain, in the *Append Domain* text box, enter your domain name. When you enter your user ID without a domain, the system appends the configured domain instead of the system-wide default domain.
- 6) To change the language, from the Language drop-down list, select a new language.
- To add a bookmark to this page in your browser, click Bookmark this page and follow the instructions of your browser.
- 8) Click Sign In.

Call Center starts and you are signed in.

NOTE: In some browser/operating system combinations, when you press ENTER instead of the **Sign In** button, a blank page appears instead of the Call Center main interface.

4.3 Hot Desk Sign-in

If you are a Call Center agent, you can automatically associate yourself with a Hoteling Host or Flexible Seating Host phone device when you sign in to the Call Center client. This is commonly used in a shared workspace environment where users working different shifts share a single computer and phone.

To use hot desk functionality, you must have your Hoteling Guest or Flexible Seating Guest service assigned. You turn on your Hoteling Guest or Flexible Seating Guest service using the BroadWorks web portal or voice portal.

To sign in to Call Center as a hot desk user:

- 1) At the assigned workstation, start a web browser and enter the URL of the Call Center client. The *Call Center Sign-in* page appears.
- Enter your BroadWorks user ID and password.
- 3) Click **Show options**. The area expands, displaying advanced options.
- 4) In the *Hotel/Flexible Seating Host* text box, enter the user ID of the Hoteling Host or Flexible Seating Host that corresponds to the desk/device you are using, for example, "station_224@acme.com".



- 5) To change the language of the user interface, from the *Language* drop-down list, select a new language.
- 6) Click Sign In.

You are signed in and Call Center associates that desk's phone with your user account for the duration of the session.

NOTE 1: When you sign out from the Call Center client, the guest session with the host device at the desk is terminated. After sign-out, the host user ID you entered is saved and can be reused on the next sign-in.

NOTE 2: The host/guest association can be configured with a time limit. If the association/session expires while you are signed in to the client, you are automatically signed out from the client. The association time limit can be specified both for hosts and for guests. You can configure your association time limit for your Hoteling Guest or Flexible Seating Guest service on the BroadWorks web portal. The host association time limit is usually configured by your administrator.

4.4 Sign-in Restrictions

You can only have one active Call Center session at a time. When you sign in from a second location, you are automatically signed out from the original location with the following message: "You have been signed out as you have signed in from another location."



Figure 7 Sign-in Dialog Box with Error Message



Figure 8 Main Interface (Top of Page) with Error Message

You may also be automatically signed out if you signed in from a Hoteling Host or Flexible Seating Host and your session expired.



Figure 9 Main Interface (Top of Page) with Information Message



4.5 Get Help

Call Center provides you with online access to a portable document format (PDF) version of this guide.



Figure 10 Logo Pane with Help Link

To access the document, click the **Help** link in the top right-hand side of the main interface.

4.6 Sign Out

1) To sign out of Call Center, click **Sign Out** at the top right-hand side of the main interface.

If you are the last agent to sign out of a call center, a message appears, providing the details of queues in which you are the last agent to sign out and asking you to confirm that you want to sign out.

NOTE: This functionality is not available when you close the application using the browser's Close button or when you refresh (F5) the browser.



Figure 11 Dialog Box - Signing Out Last

- 2) To stay signed in, click **No**. You are returned to the application.
 - To continue signing out, click Yes.

A message appears asking whether you would like to save your current workspace.



Figure 12 Dialog Box - Saving Workspace on Sign Out



 To save your current workspace, click Yes. This allows you to retain the same interface setup at your next session. For information about the elements of the Call Center workspace that can be customized and retained between sessions, see section 17.1.7 Workspace.

If you are signing out from a hot desk, your account is dissociated from the hot desk where you were signed in.

4.7 Set Up Call Center

When you sign in to Call Center for the first time, it is recommended that you configure the following settings:

If you are an agent:

- Configure the queues you want to join on sign-in.
- Configure your post sign-in and post call ACD states.
 For information, see section 17.2 Settings Application.
- Configure the supervisors whose call status you want to monitor. For information, see section 11.1 Select Supervisors to Monitor.
- Make sure that your web browser is set up to use all the features of Call Center. For information, see section 18 Configure Web Browser.

If you are a supervisor:

- Configure agents you want to monitor. For more information, see section 13.1 Select Agents to Monitor.
- Configure queues you want to monitor. For more information, see section 14.2 Select Call Centers to Monitor.

For more information about the settings you can configure in Call Center, see section 17 Configure Call Center.

4.8 Change Your Password

You can change your password when you are signed in to Call Center.

- To change your password, click the **Settings** link at the top right-hand side of the main page.
- Click the General tab and then click Change Password.



Figure 13 Changing Password

3) Enter your old and new password in the provided text boxes and click **Change Password**.

Note that the Reset button does not reset your password. It only clears the input boxes.



NOTE: This password is shared with your web portal and other client applications that share BroadWorks Single Sign-On feature. It must meet the password requirements set on BroadWorks.

4.9 Change Your ACD State (Agents)

When you sign in to Call Center, your ACD state is set to the post sign-in ACD state set on the *Settings* page.

To change your ACD state:

 At the top right-hand side of the main window, select your ACD state from the ACD drop-down list.




Figure 14 Logo Pane - ACD State Control

 If you selected *Unavailable* and your company requires you to provide a reason for your unavailability, select an *Unavailable Code* from the drop-down list.




Figure 15 Logo Pane - Unavailable Codes

4.10 Change Your Instant Messaging and Presence State

When you sign in to Call Center, Call Center connects to the Instant Messaging and Presence (IM&P) server and sets your presence state to *Available*.

Subsequently Call Center displays your unified instant messaging presence, which reflects your presence in various instant messaging clients when you are logged in through several devices and applications.

Your unified presence state can change either when you manually change it or when Call Center receives information about your presence state change from other clients.

The possible states are *Available*, *Busy*, *Away*, and *Offline*. When you are in *Available*, *Busy*, or *Away* state, you are considered to be online. For more information, see section 19.4 *Unified Instant Messaging Presence States*.

Call Center also allows you to provide a status message to display to your contacts.

IM&P capabilities are only available when you have an IM&P service assigned on BroadWorks and are online. For more information about the IM&P capabilities of Call Center, see section 10 Monitor IM&P Contacts and Chat with Contacts.

To change your IM&P state:

At the top right-hand side of the main window, select a new state from the *Presence* drop-down list. Your presence state is updated as soon as you select a new value.





Figure 16 IM&P State Drop-Down List

When you are online, you can also specify a status message to display to your contacts.

To set the status message:

1) Click the **Edit** button next to the *Presence* box. The *Set IM Status* dialog box appears.



Figure 17 Set IM Status Dialog Box

- 2) Enter your message and click **OK**.
- To see your message, move the mouse over the Edit button . A ToolTip with your presence massage appears.



Figure 18 IM&P Status Message in ToolTip

4.11 Enable or Disable Services

You can use the following services in Call Center: Call Waiting, Call Forwarding Always, and Do Not Disturb, provided that your administrator has assigned the services to you.

To enable or disable Call Waiting:

- 1) In the *Call Console*, click **Call Waiting**. The button changes to this indicate that the service is enabled.
- 2) To disable it, click the button again.

To enable or disable Do Not Disturb or Call Forwarding Always:

- 1) At the top right-hand corner of the main page, click **Settings**. The *Settings* page appears.
- 2) Click the Services tab.



- 3) On the *Services* page that appears, select the service you want to enable or disable, and check or uncheck the *is Active* box.
- 4) If you checked the *is Active* box for the Call Forwarding Always service, in the *Forward To* text box, enter the phone number to forward your call to.
- 5) Click Save.

For more information, see section 17 Configure Call Center.



5 Explore Workspace

When you sign in to Call Center, the main page appears where you perform most of your call management or monitoring tasks. In addition, the main page provides links to other pages and windows of Call Center, where you perform functions such as configuration and report generation.




Figure 19 Call Center – Agent Main Interface

Many visual aspects of the Call Center workspace are configurable. For example, you can change the size and placement of windows on the screen. You can then save your workspace and retrieve it the next time you sign in. For more information on saving your workspace settings, see section 17.1.7 Workspace.

To work in full screen mode, click the **Full Screen** link at the top-right corner of the main window. The link changes to *Exit Full Screen*, which you can click to exit full screen mode.

NOTE 1: To work in full screen mode, you can also click F11 when the main window is in focus.

NOTE 2: The Back, Forward, and Refresh operations of the web browser are not supported by Call Center, and if performed, the results are inconsistent.

NOTE 3: When a window is vertically resized, the panes do not always resize to fill the window. To resize a window, drag the window from the bottom right-hand corner or collapse and then expand the panes after resizing to adjust them to the window.

Most call center controls are context-based, which means that they appear only when the action they represent can be taken. Context-based controls that allow you to take actions on calls are called action buttons. For the list of controls available in Call Center, see section 5.5 Controls. The action buttons are described in section 5.5.1 Call Action Buttons.



The Call Center interface contains the following elements:

Interface Element	Description
Logo Pane	Located at the top of the main interface, the <i>Logo</i> pane displays global messages, information about the logged user, and links to other Call Center interface elements and functions.
Call Console	The Call Console is where you manage your current calls.
Contacts Pane	The <i>Contacts</i> pane contains your contact directories and allows you to manage your contacts and use contacts to make calls or take actions, such as transfer to contact or queue, on existing calls.
Queued Calls Pane (Supervisors)	The Queued Calls pane, available only to supervisors, allows you to manage queued calls for selected call centers that you supervise.
Chat Windows	You chat with your IM&P contacts using Chat windows.
Call History Window	The <i>Call History</i> window, accessible from the <i>Call Console</i> via the Call History button, displays your placed, received, and missed calls, and allows you to make calls from history and delete call logs.
Report Windows	The Report windows, accessible from the main page via the Reporting link, provide access to Enhanced Reporting, allowing you to generate, schedule, and view reports. Agents can only generate reports about themselves.
Dashboard (Supervisors)	The <i>Dashboard</i> , accessible from the main page via the Dashboard link, provides you with real-time summary information about the call centers and agents you supervise (up to 50).
Dashboard Pane (Agent)	The <i>Dashboard</i> pane allows you to view the current state of the monitored call centers.
Settings Pages	The Settings pages, accessible from the main page via the Settings link, allow you to configure various user-level and application settings.
Controls	You use controls, such as buttons and drop-down lists to execute actions on calls, contacts, queues, and so on.

This section describes the following elements of the Call Center interface:

- Logo Pane
- Call Console
- Contacts Pane
- Call History
- Controls

For information about other interface elements, see the following sections:

- Queued Calls pane Section 14.1 Queued Calls Pane
- Chat windows Section 10.2 Chat with IM&P Contacts.
- Report windows Section 16 Generate Reports
- Dashboard pane Section 12 Monitor Call Centers (Agent)
- Dashboard Section 15 View Real-Time Statistics (Supervisor)
- Settings pages Section 17 Configure Call Center



5.1 Logo Pane

The Call Center main window interface contains a logo pane that displays the Call Center client or company logo, global messages, links to other interface elements or Call Center functions, and information about the logged-in user.



Figure 20 Call Center Logo Pane

5.1.1 Global Message Area

The *Global Message Area*, that is, the center area of the *Logo* pane, is used by Call Center to display various information, warnings, and error messages to the user. A message is displayed for several seconds and then it disappears.

5.1.2 Links to Other Interface Elements and Functions

The *Logo* pane displays links to the *Report* windows, *Settings* pages, the *Dashboard* (Supervisors), and the Help and Sign Out links.

5.1.3 Logged User Information

Information about yourself, that is, your name, your availability to take calls, and your voice mail status, is displayed at the top right-hand side of the main interface.

Your current ACD state and presence state are displayed to the left of your name. You can change your ACD state or presence state by selecting a new state from the drop-down list.

- ACD state ACD: ACD: Available ▼
- Presence state Presence: Available ▼

In addition, information about the following services and features is provided:

- Do Not Disturb (DND)
- Call Forwarding Always (CFA)
- Busy phone state
- Voice Messaging ■

The information is presented in the form of icons to the left of your name in the following format:

<DND/CFA/Busy> <Voice Messaging>

The <DND/CFA/Busy> state is represented by one icon, where Do Not Disturb has precedence over Call Forwarding Always, which has precedence over your Busy Phone State. If none of the services is enabled and your phone state is *Idle*, the icon is not displayed.

The Voice Messaging icon is present only if you have outstanding voice messages.



5.2 Call Console

You use the *Call Console* to view and manage your current calls. For information on managing your calls, see section 6 *Manage Calls*.



Figure 21 Call Console

The Call Console contains the following areas:

- Header Bar
- Dialer
- Current Calls
- Conference Call



5.2.1 Header Bar

The header bar contains various controls that allow you to configure your services and perform call and service-related actions.




Figure 22 Call Console Header Bar

The header bar can contain the following controls:

- Disposition Code button This allows you to assign disposition codes to the last call. The button only appears when you are in *Wrap-Up* state.
- Trace Call button This allows you to attach a trace to the last call.
- Call History button
 This allows you to access the list of your previous calls.
- Auto Answer button This allows you to enable or disable the automatic answering of calls.
- Call Waiting button This allows you to enable or disable the Call Waiting service.

5.2.2 Dialer

The *Dialer*, located at the top of the *Call Console*, below the header bar, allows you to make ad hoc calls and set your outgoing calling line identity (CLID) for the next call.



Figure 23 Dialer

It contains the following elements:

- The Outbound CLID button which allows you to configure the number you want to use for outgoing calls.
- The Enter Number text box, which is where you enter the number to dial.
- Action buttons, which change depending on the context, and they allow you to perform operations on calls. For more information, see section 5.5.1 Call Action Buttons.



5.2.3 Current Calls

The *Call Console* displays your current calls, both direct and ACD, and allows you to take actions on them. Direct calls are calls placed from or received on your own phone number, whereas ACD calls are calls routed to you from a call center that you are staffing as an agent.

If you are involved in a conference call, its details are displayed in a separate area of the Call Console, called the *Conference Call* panel. The *Conference Call* panel is described in the following section.



Figure 24 Call Console - Current Calls

The following information is displayed for each call:

- Call State icon This is a visual representation of the current state of the call. For more information, see section 5.2.5 Call States and Actions.
- Remote CLID This is the name of the remote party (if available) and the phone number in parenthesis.
- Diversion CLID This is the name (if available) of the party who diverted (transferred, forwarded) the call before you received the call and the phone number is in parenthesis. If the call was diverted more than once, the last party who diverted the call is listed first; the second to last party is listed second; and so on.
- Call State name This is the display name of the "call" state the call is currently in.
- Call duration [Held duration] This is the duration of the call from the time the call was received from BroadWorks and it reflects how long the call has been present in the system. In addition, for held calls, the time a call has been on hold is displayed.
- Security Classification (if applicable) This is the security classification level of the call.

The call entry also displays action buttons for the operations that you can currently take on that call. The actions you can perform depend on the state of the call.

For the list of Call Center action buttons, see section 5.5.1 Call Action Buttons and for the list of actions that can be taken in each call state, see section 5.2.5 Call States and Actions.



5.2.4 Conference Call

The *Conference Call* panel displays your current conference and allows you to manage your conference calls.

NOTE: You can only be involved in one conference call at a time.




Figure 25 Call Console - Conference Call

The header bar contains various controls that allow you to manage the conference:

- End Conference button This allows you to end the current conference.
- Leave Conference button This allows you to leave the conference.
- Hold Conference button This allows you to place the conference on hold.
- Resume Conference button This allows you to resume the conference that you previously placed on hold.

The *Conference Call* panel, when expanded, lists the call legs that make up your current conference. Each two-way call is displayed on a separate line. The information displayed for each call leg is the same as the information displayed for two-way calls. For information, see section *5.2.3 Current Calls*.

For information on managing conferences, see section 6.13 Manage Conference Calls.

5.2.5 Call States and Actions

The following table lists the possible call states and actions that can be performed on calls in each state.

Call State	Display Name	Display Icon	Call Personality	Call Actions
Ringing In (Local)	Incoming Local	-	Click-To-Dial	Answer, End
Ringing In (Remote)	Incoming	•	Terminator	Answer, Conference, End
Ringing Out, Outgoing	Outgoing	4	Originator	Conference, End
Active	Active		Any	Transfer, Hold, End, Conference
On Hold	Held		Any	Transfer, Resume, End, Conference



Call State	Display Name	Display Icon	Call Personality	Call Actions
On Hold (Remote)	Remote Held		Any	Transfer, Hold, End, Conference
Active (In Conference)	Active	&	Conference	Transfer, Hold, End
Held (In Conference)	Held	Aii	Conference	Resume, Transfer, End
Ringing In (Recalled Call)	Call Recalled	-	Terminator	Answer, Conference, End

5.3 Contacts Pane

The *Contacts* pane contains your contact directories and allows you to use your contacts to make or manage calls. For information on using contacts to manage calls, see section 6 *Manage Calls*. For information about organizing and managing your contact directories, see section 9 *Manage Contacts*.



Figure 26 Contacts Pane



The Contacts pane contains the following panels:

- Search Panel
- Enterprise/Group Panel
- Common Panel
- Agents Panel (Supervisors)
- Supervisors Panel (Agents)
- Speed Dial Panel
- Queues Panel
- Custom Directories Panels
- Instant Message Panel
- Outlook Panel
- Directories Panel

The contact directories you have access to depend on your system configuration as well as the services assigned to you. For more information, contact your administrator.

The directories you see in the *Contacts* pane also depend on your setup. For information on selecting the directories to display in the *Contacts* pane, see section *9.1.1 Show or Hide Directories*.

When you click a contact, the entry expands and the contact's information, such as phone numbers and the action buttons for the operations that you can currently take on that contact appear.

You can only view the details of one contact per directory at a time. When you click another contact in the same directory, the details of the currently expanded contact are automatically hidden.



Figure 27 Group Panel – Contact in Focus with Action Buttons



For the list of Call Center action buttons, see section 5.5.1 Call Action Buttons.

5.3.1 Search Panel

You use the *Search* panel to look for specific contacts in your contacts' directories and, if available, in the configured *LDAP* directory. For information about performing contact searches, see section *9.3 Search for Contacts*.



Figure 28 Contacts Pane – Search Panel

5.3.2 Enterprise/Group Panel

The *Enterprise/Group* panel contains the contacts in your BroadWorks group directory (if your group is part of a service provider) or enterprise directory (if your group is part of an enterprise. However, if your enterprise administrator restricted your access to the enterprise directory, you can only see the contacts from your group.)



Figure 29 Contacts Pane - Group Panel

5.3.3 Common Panel

The *Common* directory contains the contacts in your group's common phone list configured by your administrator on BroadWorks.




Figure 30 Contacts Pane - Common Panel



5.3.4 Personal Panel

The *Personal* panel contains the contacts from your BroadWorks Personal Phone List. It displays the name/description and phone number of each contact.

For information about managing your personal contacts, see section *9.4 Manage Personal Contacts*.




Figure 31 Contacts Pane - Personal Panel

5.3.5 Agents Panel (Supervisors)

The *Agents* panel is used by supervisors to monitor and manage agents under their supervision. For more information, see section 13 Manage Agents (Supervisor).



Figure 32 Contacts Pane - Agents Panel

5.3.6 Supervisors Panel (Agents)

The *Supervisors* panel, available to agents, contains the list of your supervisors. The main purpose of this directory is to allow you to contact a supervisor quickly.




Figure 33 Contacts Pane - Supervisors Panel

Selected supervisors have their call status displayed. For more information, see section 11 *Monitor Supervisors*.



5.3.7 Speed Dial Panel

The *Speed Dial* panel allows you to manage your Speed Dial 8 and Speed Dial 100 contacts. It is available to users who have been assigned Speed Dial 8 and/or Speed Dial 100 services. If you only have one of these services, you only see the entries for that service in your *Speed Dial* directory.

For each configured speed dial number, Call Center displays the speed dial code and description. The description is what you entered when configuring the number.

For information about managing your *Speed Dial* directory in Call Center, see section *9.5 Manage Speed Dial Numbers*.




Figure 34 Contacts Pane - Speed Dial Panel

5.3.8 Queues Panel

The *Queues* panel is available to both agents and supervisors. It lists the call centers you are staffing as an agent or monitoring as a supervisor and the associated Dialed Number Identification Service (DNIS) numbers. The primary purpose of this panel is to provide you with a quick way to transfer calls to queues.




Figure 35 Contacts Pane - Queues Panel

5.3.9 Custom Directories Panels

If your administrator has configured custom contact directories for your group, you can access them from Call Center. A custom directory contains a subset of the contacts in your BroadWorks group or enterprise directory.

NOTE: A custom directory has the same properties as the *Group/Enterprise* directory.






Figure 36 Contacts Pane - Custom Panel

5.3.10 Instant Message Panel

The *Instant Message* panel displays IM&P contacts you are subscribed to and their presence state. You can chat with any contact that has an IM&P service assigned on BroadWorks, but you can only see the presence state of the contacts to which you are subscribed. For information on subscribing to and chatting with IM&P contacts, see section 10 Monitor IM&P Contacts and Chat with Contacts.




Figure 37 Contacts Pane – Instant Message Panel

The *Instant Message* panel appears only if you have been assigned an IM&P service on BroadWorks.

When your presence state is set to "Offline", this panel is empty. To change your IM&P presence state, see section 4.10 Change Your Instant Messaging and Presence State.

5.3.11 Outlook Panel

The Outlook panel contains your Outlook contacts.




Figure 38 Contacts Pane - Outlook Panel



5.3.12 Directories Panel

The *Directories* panel consolidates the contacts from the following directories: *Enterprise/Group*, *Custom*, *Personal*, *Outlook*, and *Speed Dial*. This panel is always visible. You can choose which directories to display in the *Directories* panel and you can collapse the panel, but you cannot close it.



Figure 39 Contacts Pane – Directories Panel

You can also place a copy of a directory below the *Call Console*. This allows you to view more than one directory at a time easily. For more information, see section 9 *Manage Contacts*.



5.4 Call History

The *Call History* dialog box, accessed from the *Call Console* via the Call History button, allows you to view your past calls. You can place a call to a number from Call History and manage call logs. For information on making calls from Call History, see section 6 *Manage Calls*, and for information on managing your call logs, see section 7 *Manage Call History*.




Figure 40 Call History Dialog Box

Each call log is displayed on a separate line. Call logs are grouped in three categories: Missed calls, Received calls, and Placed calls. The following information is displayed for each call log:

- The name and phone number of the remote party
- The date and time when the call was initiated

In addition, if you have Enhanced Call Logs service assigned, the following information is displayed, as applicable:

- Duration
- Outgoing DNIS
- Redirection Number
- Redirection Type

If you also have the Security Classification service assigned, the security classification of calls is displayed.

When you click a call log, the Call Action button appears, allowing you to place a call to the remote party.



Figure 41 Call History Dialog Box – Call Log with Call Action Button

For the list of action buttons available in Call Center, see section 5.5.1 Call Action Buttons.



5.5 Controls

Call Center controls are designed in a contextual manner, that is, most controls appear only when the action they represent can be taken. For example, when you enter a number or select a contact, a Dial button appears, allowing you to place a call. The contextual controls that correspond to call operations such as dialing, transferring calls, or putting calls on hold are called action buttons. They appear on the Dialer, in a call entry, in a directory entry (contact), in a call log, or on a queued call (Supervisors).

The following table lists the general controls used in Call Center and the controls displayed on the headers in the panels. For more information on the action buttons, see section 5.5.1 Call Action Buttons.

Name	Description		
Common Controls			
Options	This is located in the upper-right corner of a pane or page. When clicked, it displays a drop-down menu of options that control the display of information in that pane/page. The available options depend on the context.		
Expand/Collapse	This shows or hides the contents of a window or panel.		
Close	This closes an interface element, such as window, pane, or panel.		
Edit	This allows you to edit a list of items, such as agents to monitor or speed dials.		
Logo Bar, Dialer, Call Console, Di	rectories Panel, and Search Panel Controls		
Web Pop URL	This opens a page in your browser at the configured URL to provide additional information about the caller.		
Outbound CLID	This allows you to select the phone number to use as your Calling Line ID for the next outgoing call.		
Disposition Code	This allows you to apply one or more disposition codes to the last call when you are in <i>Wrap-Up</i> .		
Disposition :	This allows you to apply one or more disposition codes to the selected call.		
Trace Call	This allows you to attach a trace to the last call.		
ACD: & Available ACD State	This displays your current ACD state and allows you to change it.		
Presence: Available > Presence State	This displays your current IM&P presence state and allows you to change it using the drop-down list.		
Call History	This displays Call History.		
Auto Answer	This allows you to turn Auto Answering on or off.		



This allows you to turn Call Waiting on or off. It is available only if		
you have been assigned the Call Waiting service.		
This ends a conference call.		
This disconnects you from the conference while allowing other participants to continue the call.		
This holds the conference call.		
This resumes a held conference.		
This "un-mutes" your Silent Monitoring call, thereby establishing a Three-Way Conference.		
This places a selected directory below the Call Console.		
This opens a page in your browser at the configured URL to provide additional information about the caller.		
This saves the caller's phone number and personal information as a vCard in Microsoft Outlook. It appears only when Outlook is running.		
This places a call to your chat partner.		
This allows you to select users to add to the chat.		
This invites selected users to the chat.		
This takes a chat window out of the main interface and makes it a free-floating window.		
This anchors a free-floating chat window inside the main interface.		
This minimizes the chat window.		
This closes the chat window.		
Supervisors Panel (Agents)		
This makes an emergency call to a supervisor.		
This escalates a call to a supervisor.		
Queued Calls Pane – Call Center Queue Panel (Supervisors)		
This identifies and allows you to change the service mode of a supervised call center.		



Name	Description
Scheduled Reports Window	
Load Report	This loads a scheduled report, allowing you to view and modify it.
Delete Report	This deletes a scheduled report.

5.5.1 Call Action Buttons

Action buttons allow you to perform actions on calls, such as answering or transferring a call, or actions that result in a call being placed, such as dialing a number or contact. They appear on the Dialer, on a call line, in a call history log, in a directory entry, or (for supervisors) in a queued call entry.

Action buttons are contextual, that is, they appear on a line/entry when the corresponding action can be performed on that entry.

For example, when you click a contact in the *Group* directory, the contact expands and the Call button appears on the line for that contact, allowing you to call the contact. This is illustrated in *Figure 42*. Note that other buttons may appear on the line for a contact, depending on the call state and the contact's configuration.



Figure 42 Group Panel – Contact in Focus

The following table lists the action buttons available in Call Center.

Button	Description
Dial	This dials the number you entered in the <i>Dialer</i> .
CALL Call	This places a call to the selected contact or to a number from Call History.
Redial	This redials the last dialed number.
MOB Mobile	This dials the contact's mobile number.



Button	Description
E-mail	This brings up a new e-mail message window with the contact's e-mail address, allowing you to send a message to the contact.
Transfer Transfer	This transfers a call to an ad hoc number entered in the <i>Dialer</i> .
TXR	This transfers a call to a selected number or contact.
ANS Answer	This answers an incoming call, answers an unanswered call for a contact, or resumes a held call.
HOLD	This places a call on hold.
END	This ends a call.
TRACE Trace	This generates a call trace on a call.
CONF	This establishes a conference call or adds a call to a conference.
RECORD Record	Starts call recording or marks a call that is already being recorded to be kept.
PAUSE Pause	Pauses call recording.
RESUME Resume	Resumes call recording.
STOP Stop	Ends call recording.
CAMP Camp	This camps a call on a busy contact.
ESC Escalate Call	This escalates a call to a selected supervisor.
EMER Emergency Call	This places an emergency call to a selected supervisor.
CHAT Chat	This opens a chat window allowing you to chat with an IM&P contact.
Web Pop URL	This opens a page in your browser at the configured URL to provide additional information about the caller.
Delete Call Log	This deletes a call log from Call History.
For Supervisors Only	
QUEUE Queue	This allows the supervisor to make an agent join or leave queues.
SMN Monitor Next Call	This allows the supervisor to silently monitor the next call for a selected agent or call center.
SM Monitor	This allows the supervisor to silently monitor the current call for a selected agent with an active call.
ACD State	This allows the supervisor to change a selected agent's ACD state.



Button	Description
BARGE Barge In	This allows the supervisor to barge in on an agent's call, by establishing a Three-Way Call between the supervisor and the two parties involved in the call.
ANS	This answers an unanswered call for a monitored agent.
PROMOTE	This promotes a selected call to the next highest priority bucket within the queue.
RETRIEVE Retrieve	This retrieves a call from the queue to the supervisor's device. When a call is manually retrieved via this action, the call is reported as an <i>Incoming</i> call rather than an <i>ACD</i> call in the reports.
REORDER	This changes a call's position in the queue.



6 Manage Calls

This section describes the operations you can perform to make and manage calls.

Your current calls are displayed in the *Call Console* with the calls currently involved in a conference displayed in a separate panel called *Conference Call*.

NOTE: You can only be involved in one conference at a time.




Figure 43 Call Console

The following subsection provides a quick reference to call management operations. These operations are described in detail in the rest of this section.

NOTE: For operations on calls that involve a contact, you can drag the call onto the contact and click the button for that contact, which corresponds to the operation you want to perform. For information, see *6.2 Drag and Drop Call onto Contact*.



6.1 Call Management Operations Quick Reference

The following table provides a summary of the actions that you can take to manage calls. These actions (operations) are described in more detail in the following sections.

Function	Steps
Assign Disposition Code to Selected ACD Call	In the <i>Call Console</i> , click the target ACD call and select a code from the drop-down list that appears.
Assign Disposition Code while in Wrap-Up	In the <i>Call Console</i> , click the Disposition Code button and select a code from the list. The code is applied to the last released call.
Generate Call Trace for Selected Call	In the Call Console, click the Call Trace button for the target call.
Generate Call Trace for Last Released Call	In the Call Console, click the Call Trace button.
Answer Incoming Call	In the Call Console, click Answer for the target call.
Turn Auto Answer On	In the Call Console, click Auto Answer.
Open URL	In the Call Notification dialog box for an incoming call or on any call in the Call Console, click the Web Pop URL button.
Save a vCard	In the <i>Call Notification</i> dialog box for an incoming call, click the Add vCard button.
Place Call on Hold	In the Call Console, move the mouse over the call and click Hold .
Resume Held Call	In the Call Console, move the mouse over the call and click Retrieve.
Blind Transfer Call	Drag the call onto the target contact and click Transfer for that contact. Alternatively, enter the target number in the <i>Dialer</i> and click Transfer on the <i>Dialer</i> .
Transfer with Consultation	While on the call, enter a number in the <i>Dialer</i> or select a contact in the <i>Contacts</i> pane and click Dial. When the new call is connected, consult with the party. When ready to transfer, select the original call. Move the mouse over the new call that is not selected call and click Transfer .
Transfer to Queue	Drag the call onto the target queue in the <i>Queues</i> panel and click Transfer for that queue.
Make Emergency Call to Available Supervisor	In the <i>Call Console</i> , select the call to escalate and click the Emergency button in the <i>Supervisors</i> panel.
Make Emergency Call to Selected Supervisor	Drag the call to escalate onto an available supervisor in the <i>Supervisors</i> panel and click Emergency for that supervisor.
Blind Escalate Call	In the <i>Call Console</i> , select the call to escalate. In the <i>Supervisors</i> panel, click Escalate or click an available supervisor and click Escalate for that supervisor. In the <i>Call Console</i> , move the mouse over the call to the supervisor and click Transfer before the supervisor answers the call.
Escalate with Consultation	In the <i>Call Console</i> , select the call to escalate. In the <i>Supervisors</i> panel, click Escalate or click an available supervisor and click Escalate for that supervisor. Consult with the supervisor. When ready to transfer, in the <i>Call Console</i> , move the mouse over the call to the supervisor and click Transfer .



Function	Steps
Escalate with Conference	In the <i>Call Console</i> , select the call to escalate. In the <i>Supervisors</i> panel, click Escalate or click an available supervisor and click Escalate for that supervisor. In the <i>Call Console</i> , move the mouse over the new call and click Conference .
Start Three-Way Conference	In the <i>Call Console</i> , select a call. Move the mouse over a call that is not selected and click Conference .
Add Participant to Conference	In the Call Console, move the mouse over a call and click Conference.
Hold Conference	In the Conference Call panel, click Hold.
Resume Conference	In the Conference Call panel, click Resume.
Hold Conference Participant	In the Conference Call panel, select the call to put on hold and click Hold for that call.
Take Conference Participant Off Hold	In the Conference Call panel, select a held call and click Resume for that call.
Leave Conference	In the Conference Call panel, click Leave Conference.
End Participant	In the Conference Call panel, select the target call and click End.
End Conference	In the Conference Call panel, click End Conference.
Set Outbound CLID	In the <i>Dialer</i> , click the Outbound CLID button and select the number to use as your calling line identity for the next call from the list.
Dial Ad Hoc Number	In the Dialer, enter the number to call and click Dial.
Re-dial Recent Number	In the Dialer, click Redial and select a number from the list.
Dial Recent Number	In the <i>Dialer</i> , start entering the number to dial. A list of numbers starting with the entered digits appears. Select a number from the list and click Dial .
Dial Contact	In the <i>Contacts</i> pane, click the contact and then click Call for that contact.
Dial from History	In the <i>Call Console</i> , click the Call History button. Select <i>Missed calls</i> , <i>Received calls</i> , or <i>Dialed calls</i> from the drop-down list. In the <i>Call History</i> dialog box, move the mouse over a call log and click Call .
Dial from Search	In the Search panel, select a contact and click Dial .



6.2 Drag and Drop Call onto Contact

In Call Center, you can drag a call from the Call Console and drop it on a target contact in one of your contact directories. This provides you with a quick way to perform operations on calls that involve a contact.

As the call is dragged, a green icon is displayed. When the call is dropped onto a contact, no action is taken on the call. The target contact expands and you can select the action button for the operation you want to perform on that call.




Figure 44 Dragging Call and Dropping on Contact

6.3 View Calls

You can view your current calls and your past calls (Call History). For information about Call History, see section 7 *Manage Call History*.

6.3.1 View Current Calls

Your current calls are displayed in the *Call Console* with the calls involved in a conference displayed in a separate pane called *Conference Call*.





Figure 45 Call Console – View Current Calls

6.3.2 Group Calls

Your current calls can be grouped by the call center they come from. When calls are grouped, direct calls are placed in a separate category.



Figure 46 Call Console - Grouped Calls

To group or ungroup calls:

- 1) On the Call Console header bar, click Options
- 2) Select Group By and then Calls From.
- 3) To ungroup, repeat the operation by selecting None instead of Calls From.






Figure 47 Grouping Calls in Call Console

To view or hide calls in a group:

Click the **Show/Hide** button (\square) to the left of the group name.

6.3.3 View Incoming Call Details

When you receive a new call, the call appears in the Call Console. If calls are grouped and the corresponding grouping is collapsed, it is expanded to make the call visible.

When the Call Notification feature is enabled, a *Call Notification* pop-up window appears on top of the system tray when you receive an inbound call.

- For calls to your direct number or extension, the following information is displayed:
 - Calling party name
 - Calling party number



Figure 48 Call Notification Pop-up Window for Call That Is Not ACD Call

- For calls from a call center, the following information is displayed:
 - Calling party name
 - Calling party number
 - Call center name or DNIS name, followed by the time the call has been waiting in queue (wait time)
 - Number of calls in queue (queued calls)



Figure 49 Call Notification Pop-up Window for ACD Call

In addition, for diverted calls, that is, calls that were forwarded or transferred before being delivered to you, the diversion information is also displayed.






Figure 50 Call Notification Pop-up Window with Diversion Information

NOTE 1: You must have only one tab open in the browser running Call Center to receive call notifications.

NOTE 2: If calls come within eight seconds of each other, the *Call Notification* pop-up window only appears for the first call of that series.

6.4 Assign Disposition Codes (Premium Call Center)

Disposition codes are additional attributes that can be applied to ACD calls to tag calls with comments, results, and so on. More than one disposition code can be assigned to a call.

You can assign disposition codes to current ACD calls or to the latest released ACD call while you are in the *Wrap-Up* state.

6.4.1 Assign Disposition Codes to Current Call

To assign a disposition code to a current call:

1) From the *Call Console*, select the call and click it. The call line displays the *Disposition* drop-down list.



Figure 51 Call Console - Assigning Disposition Code to Active Call

2) From the list, select a code.

6.4.2 Assign Disposition Codes in Wrap-Up

While you are in Wrap-Up, you can assign disposition codes to the last released ACD call.

To assign a disposition code to the last released call:

- 1) In the Call Console, click **Disposition Code**
- 2) From the drop-down list that appears, select a code.






Figure 52 Call Console – Assigning Disposition Code in Wrap-Up



6.5 **Generate Call Trace**

Call Center allows you to generate a trace on active, held, released, or missed calls.

NOTE: You must be assigned the Customer Originated Trace service to use this capability.

A call trace contains the following information:

- The phone number of the user who initiated the trace. When the user does not have a phone number, the group phone number and the extension of the user is provided instead. For intra-group calls, only the caller's extension is used.
- The date and time the call was received.
- The identity (name and number) of the caller, if available.

Issuing more than one call trace request has no effect.

6.5.1 **Generate Call Trace for Selected Call**

To generate a trace for a selected call:

Click **Trace** TRACE for that call.

6.5.2 **Generate Call Trace for Last Released Call**

You can generate a trace for the most recently released or missed call.

To generate a trace for the last released or missed call:

In the Call Console, click **Trace**



6.6 **Record Calls**

To record calls, you have to have the Call Recording service assigned and configured. You can record calls manually or have the system automatically record your calls. Depending on your Call Recording mode, Call Center may allow you to manually start, pause, resume, or stop recording a call.

For information on configuring your services, see the BroadWorks Application Server User Web Interface Administration Guide.



Figure 53 Call in Call Console with Record Button

When a call is being recorded, the recording state, (which can be either Recording or Paused) appears on the line for the call.



Figure 54 Call Being Recorded



6.6.1 Start Call Recording

To manually record calls, you have to have your Call Recording service mode set to On Demand or On Demand with User Initiated Start.

To record a call, select the call in the Call Console and click Record



In the On Demand mode, the call is recorded from the beginning, and you have to request the recording before the end of the call to keep the recording. In the On Demand with User Initiated Start mode, the recording starts from the moment when you click the Record button.

6.6.2 Pause and Resume Call Recording

To pause and resume a recording, you have to have your Call Recording service mode set to On Demand, On Demand with User Initiated Start, or Always with Pause/Resume.

To pause a recording, select a call that is being recorded in the Call Console and click Pause Pause

The recording pauses until you resume it or the call ends.

To resume a paused recording, select a call whose recording has been paused in the Call Console and click Resume RESUME

When you pause and resume a recording, only one call recording is generated for the call.

6.6.3 Stop Call Recording

You can only stop recording a call if your Call Recording service mode is set to On Demand with User Initiated Start.

To stop recording a call, select the call that is being recorded (or whose recording has been paused) in the Call Console and click Stop

If you click Start after a call recording has been stopped, a separate recording is created.

6.7 **View and Change Security Classification of Calls**

Call Center displays the security classification level of your current calls and allows you to change your assigned security classification level if you have the Security Classification service assigned and your security classification level is not "Unclassified", which is the lowest level.

The security classification level of a call is the lowest security classification level for all call participants. Users who do not have a security level assigned are considered to have the security level of "Unclassified".





Figure 55 Security Classification of Calls

6.7.1 Change Security Classification

You can change your security classification, but only to a level lower than your assigned level, and you can only do so while in an active call. The security classification level of your calls is then recalculated.

The security classification of a call can also change when other participants change their security classification level or when participants join or leave the call. If the security classification level of a call changes, then the new level is displayed.

After all your calls end, your security classification level is reset to your assigned security classification level.



Figure 56 Security Classification Levels

To change your security classification:

From the Security Classification drop-down list, select a new security classification level.



6.8 Receive, Answer, and End Calls

You can answer calls manually or have your phone automatically answer incoming calls.

6.8.1 Answer Call

NOTE: When using the Remote Office service, the Answer button is disabled.

To answer a ringing call:

Click **Answer** ANS for that call.

To answer an incoming call from a Call Notification pop-up window:

Click anywhere on the text in the pop-up window.

6.8.2 Auto Answer Calls

This feature is typically used by agents who use headsets with their phones and take care of a high volume of calls. It may be enabled either by you in the client or configured in the system by your administrator.

NOTE: Auto Answer only works if your device is compliant with Advanced Call Control (ACC).

To answer calls automatically:

In the *Call Console*, click **Auto Answer**. The button changes to this indicate that Auto Answer is on.

When Auto Answer is enabled, your phone automatically goes off-hook when it is alerted. This applies to both inbound and Click-To-Dial calls.

The Auto Answer feature may be enabled manually in the Call Center client or by the administrator on BroadSoft.

NOTE: If this feature is enabled by your administrator, you must **not** enable the client-based Auto Answer using the Auto Answer button.

6.8.3 Open URL

For any current call, you can open a page in your browser that contains information about the calling party encoded in its URL. This can be done either from the *Call Notification* pop-up window that appears on top of the system tray for an incoming call or from the *Call Console* for any current call.

This feature is configured on the *Settings – General* configuration page. For more information, see section *17.1.4 Screen Pop*.

To open a URL for an incoming call:

In the ${\it Call Notification}$ pop-up window, click the ${\it Web Pop URL}$ button





To open a URL for any call:

In the Call Console, click the Web Pop URL button for the target cal

6.8.4 Save vCard

When you receive a call, a *Call Notification* pop-up window appears on top of the system tray. You can click a button in this window to save the caller's phone number and personal information as a vCard in Microsoft Outlook.

To save a vCard:

In the *Call Notification* pop-up window, click the **Add vCard** button Is only present when Outlook is running.

6.8.5 End Call

To end a call:



NOTE: If the call has not been answered yet, then the calling party continues to ring until there is no answer, until another applicable timer expires, or the user hangs up.

6.9 Make Outbound Calls

You can make calls to an ad hoc number, to a contact from any of your contacts' directories, or to a number from Call History. You can also specify the calling line identity to use for your outbound calls.

6.9.1 Set Your Outgoing Calling Line Identity (Premium Call Center)

As a Call Center agent, you can specify whether your direct number or a DNIS number assigned to one of your call centers should be used as your calling line identity when you make calls. This allows you to conduct outbound calling campaigns with an appropriate calling line identity presented to the called party.

To set your outgoing call identity for the next call:

In the *Dialer*, click the **Outbound CLID** button and select the number from the drop-down list. The number you select is displayed as your CLID when you make the next call.




Figure 57 Dialer - Setting Outbound CLID

For information on permanently setting your outbound CLID, see section 17.2.2 Agent Policies (Agent).



6.9.2 Dial Ad Hoc Number

You use the *Dialer*, located at the top of the *Call Console*, to place a call to an ad hoc number.



Figure 58 Dialer - Dialing Ad Hoc Number

To dial an ad hoc number:

In the *Dialer*, enter the phone number and click **Dial**. The client issues a Click-To-Dial attempt to the specified phone number and the call appears in the *Call Console*.

6.9.3 Redial Number

Call Center keeps up to ten most recently dialed numbers, which you can redial using the *Dialer*.

To redial one of the recently dialed numbers:

1) In the *Dialer*, place the cursor in the text box and start entering a number. A list of recently called numbers that start with the entered digits appears.




Figure 59 Dialer – Select Recently Dialed Number

2) Select the number to dial and click **Dial**

The client issues a Click-To-Dial attempt to the selected number.

Alternatively, click the **Redial** button and select the number from the list that appears.




Figure 60 Dialer – Redialing Number



6.9.4 Dial Contact

You can use any directory in the Contacts pane to dial a contact.

To dial a contact:

- 1) In the Contacts pane, expand the directory from which you want to dial a contact.
- 2) Click the target contact to expand it and click **Call** for that contact.



Figure 61 Group Panel - Expanded Contact with Action Buttons

Alternatively, to dial the contact's mobile number, click **Mobile**

The client issues a Click-To-Dial attempt to the specified phone number and the call appears in the *Call Console*.

6.9.5 Dial from Search

You use the *Search* panel in the *Contacts* pane to search for contacts in your contacts' directories. For more information, see section 9.3 *Search for Contacts*.

To dial a number from search:

- 1) Perform a search.
- 2) Click the target contact to expand it and then click **Call**



Figure 62 Dial From Search



6.9.6 Dial from History

You can dial any number that is available in Call History.

To dial from Call History:

1) In the Call Console, click Call History. The Call History dialog box appears.




Figure 63 Call History Dialog Box

- 2) From the Show drop-down list, select Missed Calls, Received Calls, or Placed Calls.
- 3) Click the call log from which you want to dial and then click the Call CALL button.

6.10 Place Calls on Hold, Resume, and Camp Calls

You can only put an active call on hold.

NOTE: When using the Remote Office service, the Hold/Resume buttons are disabled.

6.10.1 Place Call on Hold

To place a call on hold:

Click **Hold** for the target call.

6.10.2 Resume Held Call

To resume a held call:

Click **Answer** ANS for the target call.



6.10.3 Conduct Busy Camp On

Busy Camp On allows you to find a temporary parking place for a call by placing the call on hold for a busy contact. The call is automatically transferred to the destination when the contact becomes available. A call to camp must be active or held and the destination contact's phone state must be either *Busy* or *Ringing*.

If the camped call is not answered within the predefined time, then the call is recalled and it reappears in your *Call Console*.

Agents can camp calls on monitored contacts in their *Supervisors* directory and supervisors can camp calls on monitored contacts in their *Agents* directory. For information on monitoring supervisors, see section *11 Monitor Supervisors* (*Agent*). For information on monitoring agents, see section *13 Manage Agents* (*Supervisor*).

To camp a call on a busy contact:

- 1) From the Call Console, select an active or held call.
- In your Supervisors or Agents directory, select the contact to camp the call on. The contact's phone state must be Busy or Ringing.
- Move the mouse over the contact and click **Camp**

Once the call is camped, it is removed from the Call Console.

If the camped call timer expires before the call is answered, the call reappears in the *Call Console*.

6.11 Transfer Calls

There are a number of ways that you can transfer a call. You can transfer using blind transfer, transfer with consultation, or transfer to a queue.

6.11.1 Blind Transfer

Use this method to transfer a call to another number without providing an introduction to the destination party. Calls may be transferred this way while active, held, or ringing (in) on your phone. In the latter case, the system redirects the call before it is answered.

To blind transfer a call to an ad hoc number:

- 1) From the *Call Console*, select the call to transfer.
- 2) In the *Dialer*, enter the destination number and click **Transfer**. The call is transferred and removed from the *Call Console*.

To blind transfer a call to a contact:

- 1) From the Call Console, select the call to transfer.
- 2) In the Contacts pane, expand the directory from which you want to select a contact.
- 3) Click the destination contact and click **Transfer** for that contact. The call is transferred and removed from the *Call Console*.



6.11.2 Transfer with Consultation

Use this method to transfer a call with an introduction to the destination party. Calls may be transferred this way while active, held, or ringing (in) on your phone. In the latter case, the system redirects the call before it is answered.

To transfer a call with consultation:

- Make a call to the person to whom you want to transfer the call. If the first call was active, it is put on hold.
- 2) Wait until the called party accepts your call and speak to the party.
- 3) When ready to transfer, from the Call Console, select one of the two calls.
- 4) Move the mouse over the call that is not selected and click **Transfer**The calls are connected and removed from the *Call Console*.

6.11.3 Transfer to Queue

You can transfer a call back to a queue. A transferred call is placed at the bottom of the queue.

To transfer a call to a queue:

- 1) From the Call Console, select the call to transfer.
- 2) In the Contacts pane, expand the Queues panel.
- Click the destination queue and click **Transfer** for that queue.
 The call is transferred to the selected queue and removed from the *Call Console*.
 Alternatively, drag the call onto the target queue and click **Transfer** for that

6.12 Escalate Calls

You can escalate calls to the first available supervisor or to a specific supervisor. You can also make an emergency call, which quickly conferences an available supervisor into your call, without placing the remote party on hold.

You use the Supervisors panel located in the Contacts pane to escalate calls.

6.12.1 Make Emergency Call

queue.

Use this method to escalate a call to a supervisor in an emergency. When you make an emergency call, the caller is not placed on hold; instead, a supervisor is immediately conferenced in to the call. You can let Call Center select the supervisor or you can select the supervisor yourself.

NOTE: To make emergency calls, you must have the Three-Way Call or N-Way Call service assigned.

To make an emergency call to an available supervisor:

1) While on the call, click **Emergency** in the *Supervisors* panel.





Figure 64 Supervisors Panel – Making Emergency Calls

This places the call to the first available supervisor. When the supervisor answers the emergency call, a Three-Way call or an N-Way call is started, without putting the caller on hold.

 To transfer the call to the supervisor, click LEAVE in the Conference Call panel after the conference is established.




Figure 50 Conference Call Panel – Leave Conference

To make an emergency call to a specific supervisor:

- 1) While on a call, expand the Supervisors panel.
- 2) Click the target supervisor and click the **Emergency** button Make sure the supervisor you selected is available.

Alternatively, drag the call onto the target supervisor and click the **Emergency** button for that supervisor.

This places the call to the selected supervisor. When the supervisor answers the emergency call, a Three-Way call or an N-Way call is started, without putting the caller on hold.

 To transfer the call to the supervisor, click LEAVE in the Conference Call panel after the conference is established.

6.12.2 Blind Escalate Call

Use this method to escalate a call to a supervisor without consulting the supervisor. You can escalate a call to the first available supervisor or select the supervisor yourself.

To blind escalate a call:

- 1) In the *Supervisors* panel, click **Escalate** to let the system select a supervisor; or, to select the supervisor yourself, click an available supervisor and click the **Escalate** button for that supervisor. Your original call is placed on hold and a call to the supervisor is initiated.
- Without waiting for the supervisor to answer, in the Call Console, select the original call.



3) Move the mouse over the call to the supervisor and click **Transfer**



6.12.3 Escalate with Consultation

Use this method to escalate a call to a supervisor and provide an introduction beforehand. You can escalate the call to the first available supervisor or select the supervisor yourself.

To escalate a call with consultation:

- 1) In the *Supervisors* panel, click **Escalate** to let the system select a supervisor; or, to select the supervisor yourself, click an available supervisor and click **Escalate** for that supervisor.
- 2) Wait until the supervisor accepts your call and speak to the supervisor.
- 3) When ready to transfer the call, in the *Call Console*, select the original call.
- 4) Move the mouse over the call to the supervisor, and click **Transfer** \blacksquare

6.12.4 Escalate with Conference or Handover

Use this method to escalate a call to a supervisor through a conference call. You can then leave the call.

To escalate a call with conference or handover:

- 1) In the *Supervisors* panel, click **Escalate** to let the system select a supervisor; or, to select the supervisor yourself, click an available supervisor and click **Escalate** for that supervisor.
- 2) When the supervisor accepts your call, speak to the supervisor about the issue.
- 3) In the Call Console, select the original call.
- 4) Move the mouse over the call to the supervisor and click **Conference** . A conference call is established and the calls appear in the *Conference Call* panel.
- 5) To hand the call over to the supervisor, click **Leave Conference** in the *Conference Call* panel.

6.12.5 Escalate with Mid-Conference Hold

Use this method to escalate a call to a supervisor through a conference call and provide an opportunity for the customer to speak to the supervisor.

To escalate a call with mid-conference hold:

- 1) In the *Supervisors* panel, click **Escalate** to let the system select a supervisor; or, to select the supervisor yourself, click an available supervisor and click **Escalate** for that supervisor.
- 2) When the supervisor accepts your call, speak to the supervisor about the issue.
- 3) In the Call Console, select the original call.
- 4) Move the mouse over the call to the supervisor and click **Conference**



BROADWORKS HOSTED THIN CALL CENTER AGENT/SUPERVISOR USER GUIDE ©2014 BROADSOFT, INC.



A conference call is established and the calls appear in the Conference Call panel.

- 5) In the *Conference Call* panel, click **Hold Conference** This puts both calls on hold but allows the customer and the supervisor to continue their conversation.
- 6) To drop a specific party from the conference, select their call from the *Conference Call* panel and click **End**.
- 7) To leave the call, click **Leave Conference** in the *Conference Call* panel.

6.13 Manage Conference Calls

You manage conferences in the Call Console. You use the:

- Current calls area to establish a conference and add participants to it.
- Conference Call panel to manage or end an active conference call.

You can only have one active conference at a time.



Figure 65 Call Console - Conference Call Panel

NOTE: To start conference calls, you must have the Three-Way Call or N-Way Call service assigned.



6.13.1 Start Three-Way Conference

To start a conference call, you must have at least two current calls. The calls can be received or made by you. If required, make calls using any of the methods described in section 6.9 Make Outbound Calls.

To start a conference:

1) In the Call Console, select a call.



Figure 66 Call Console - Starting Conference Call

2) Move the mouse over a call that is not selected and click Conference Three-Way Conference is established and the connected calls appear in the Conference Call panel.




Figure 67 Conference Call Panel - Conference Call

6.13.2 Add Participant to Conference

NOTE: To add participants to a conference, you must have the N-Way Calling service assigned.

To add a participant to a conference:

- 1) If the call you want to add to the conference is not yet established, place the call.
- 2) In the *Call Console*, move the mouse over the call and click **Conference**. The call is added to the conference.



6.13.3 Hold Conference

To put an active conference on hold:

In the *Conference Call* panel, click **Hold Conference**This allows other conference participants to continue their conversation.

6.13.4 Resume Conference

To resume a conference call that you previously put on hold:

In the Conference Call panel, click Resume Conference ANS. All the calls in the conference become active.

6.13.5 Hold Participant

To put a specific conference participant on hold:

- 1) Expand the Conference Call panel.
- 2) Move the mouse over the target call and click **Hold**

6.13.6 Take Participant Off Hold

To resume a participant's held call:

- 1) Expand the Conference Call panel.
- 2) Move the mouse over the target call and click **Answer** ANS.

6.13.7 Leave Conference

To leave the conference:

In the *Conference Call* panel, click **Leave Conference**. The other parties continue their conversation.

NOTE: This function is only available for Three-Way Conferences.

6.13.8 End Participant

To end a selected call in a conference:

- 1) Expand the Conference Call panel.
- 2) Move the mouse over the call and click **End**

6.13.9 End Conference

To end the conference:

In the *Conference Call* panel, click **End Conference** This releases all the calls that participated in the conference.



7 Manage Call History

Call Center collects call logs for your placed, received, and missed calls. You can call any number available in Call History. For information on making calls from Call History, see section 6 *Manage Calls*.

This section explains how to view and delete call logs.

7.1 View Call History

You can view your placed, received, and missed calls.

To view your call history:

1) In the *Call Console*, click **Call History**. The *Call History* dialog box appears displaying your past calls. The calls are grouped into placed, received, and missed calls. By default, missed calls are displayed.




Figure 68 Call History Dialog Box

2) To show calls in a specific group, select that group from the *Show* drop-down list.

7.2 Delete Call History

You can delete a selected call log or all call logs from Call History.

To delete calls from Call History:

- 1) In the Call Console, click Call History . The Call History dialog box appears.
- 2) To delete all call logs, click **Delete All**
- 3) To delete a selected log, move the mouse over the log and click **Delete**



8 E-mail Contacts

Call Center allows you to send an e-mail message to a contact that has e-mail configured on the system. You must also have messaging enabled within Call Center settings. For information, see section 17.5 Settings – Messaging.

The **EMAIL** button appears when you select a contact that has an e-mail address configured.

8.1 Send E-mail Message to Contact

To send an e-mail message to a contact:

- 1) In the Group/Enterprise directory, move the mouse over a contact who has e-mail.
- 2) Click **EMAIL**. This brings up a new e-mail window for the configured Messaging service.
- 3) Write your message and click **Send**.



9 Manage Contacts

You use the *Contacts* pane to perform call and monitoring operations on your contacts as well as to manage your contacts' directories.



Figure 69 Contacts Pane

Call Center provides access to the contacts' directories listed in the following table.

Interface Element	Description	
Enterprise/Group	The <i>Enterprise/Group</i> directory contains the contacts in your BroadWorks group or enterprise directory.	
Common	The <i>Common</i> directory contains the contacts in the common phone list configured by your administrator on BroadWorks.	
Personal	The <i>Personal</i> directory contains all contacts in your Personal Phone List on BroadWorks.	
Supervisors (Agents)	The <i>Supervisors</i> directory, available only to agents, contains the list of your supervisors and allows you to view their phone state.	



Interface Element	Description	
Agents (Supervisors)	The <i>Agents</i> directory, available only to supervisors, contains the list of agents you supervise and allows you to manage them and view their phone and ACD state.	
Speed Dial	The Speed Dial directory contains the numbers configured for you or by you for your Speed Dial services (Speed Dial 8 and/or Speed Dial 100).	
Queues	The <i>Queues</i> directory lists the call centers and associated DNIS numbers for the call centers you are either supervising or staffing. It allows you to transfer calls to queues quickly.	
Custom	A <i>Custom</i> directory contains selected contacts from your BroadWorks group or enterprise directory. You can have access to zero, one, or several custom directories. Custom directories are configured by your administrator.	
Outlook	The Outlook directory contains your Outlook contacts.	
Instant Message	The Instant Message directory lists IM&P contacts to which you are subscribed.	
LDAP (Search Access Only)	Call Center provides search access to a configured <i>LDAP</i> directory. When you make a search on the <i>LDAP</i> directory and your search returns results, these results are displayed in the <i>Search</i> panel (in the <i>Contacts</i> pane). By default, no LDAP contacts are displayed in the <i>Contacts</i> pane.	

Access to certain directories depends on your permissions and the system setup. For information, contact your administrator.

The *Contacts* pane also contains the *Directories* panel, which consolidates the contacts from the following directories: *Enterprise/Group*, *Custom*, *Personal*, *Outlook*, and *Speed Dial*. The *Contacts* pane is always visible. You can choose which directories to display in the *Directories* panel and you can collapse the panel, but you cannot close it.

For information about the operations you perform to manage your contact directories, see the following sections:

- View Contacts
- Organize Contacts
- Search for Contacts
- Manage Personal Contacts
- Manage Speed Dial Numbers
- Monitor IM&P Contacts and Chat with Contacts

9.1 View Contacts

Call Center allows you to select directories to display in the *Contacts* pane and below the *Call Console*, show or hide directory contents, and select the order of appearance for information in certain directories.

9.1.1 Show or Hide Directories

You can decide which of the directories that you are allowed to access appear in the *Contacts* pane.

All directories can be displayed individually in the Contacts pane.

In addition, you can decide which directories to display in the *Directories* panel (on their own or with other directories), and below the *Call Console*.



To show or hide a directory in the Contacts pane:

- In the Contacts pane, click **Options**
- 2) Select *View*, *Directories*, and then select or unselect the directory to display/hide. To display all directories, select *All*.

To hide a directory, you can also click the **Close** button for that directory.

NOTE: You cannot close the Directories panel.




Figure 70 Contacts Pane - Show/Hide Contact Directories

To show a directory in the Directories panel:

In the *Directories* panel, select the directory to display from the drop-down list. To display all directories, select *Show all*.




Figure 71 Directories Panel – Selecting Directory to Display

9.1.2 Display Directory Below Call Console

To display a directory below the Call Console:

1) In the Directories panel, select Show all.






Figure 72 Directories Panel – Selecting Directory

2) Click the **Pullout Directory** button for the directory to display. The directory appears below the *Call Console*.




Figure 73 Custom Directory Displayed Below Call Console

To close the directory, click the **Close** button



9.1.3 Show or Hide Directory Content

By default, your directories are collapsed, with only the title bar visible. You can selectively expand the directories that you want to consult or use.

To show or hide contacts in a directory:

In the *Contact*s pane, click the **Expand/Collapse** button for that directory.



Figure 74 Group Panel Expanded

9.1.4 Show Contact Details

You can view the details of a contact in any directory.

To view contact details:

- 1) Expand the target directory.
- Click the contact. The entry expands, displaying the contact's details. The information depends on the target directory and includes the contact's phone numbers or IDs and action buttons.

Only one contact per directory can be expanded at a time. When you click a contact, the system automatically hides the details of the previously expanded contact.





Figure 75 Group Panel - Contact Details

9.1.5 Select Display Order

Contacts in the *Group/Enterprise*, *Agents*, and *Supervisors* directories can be displayed by either their first name or last name first. Your selection applies to all of these directories. You cannot specify the display order for each directory individually.

To specify the contacts' display order:

- 1) In the *Contacts* pane, click the **Options** button
- Select View, then Display Name, and then the order in which you want to display the contacts: Last Name, First Name -or- First Name, Last Name.




Figure 76 Contacts Pane - Displaying Contacts by First Name, Last Name

Figure 75 shows supervisors displayed by their last name followed by their first name.




Figure 77 Supervisors Panel – Supervisors Listed by First Name, Last Name



9.2 Organize Contacts

9.2.1 Sort Contacts

You can sort contacts in the following directories: *Group/Enterprise*, *Queues*, and *Agents*.

- To order contacts in a directory:
- 1) In the Contacts pane, click Options
- 2) Select *Sort*, followed by the name of the directory in which you want to sort contacts, and then the sorting option.




Figure 78 Contacts Pane – Sorting Contacts

Figure 77 shows a Group directory sorted by the contact's first name.




Figure 79 Group Panel - Contacts Sorted by First Name

NOTE: When agents are ordered by ACD state and there is a change in the ACD state of an agent, the agents are not automatically re-ordered.



9.3 Search for Contacts

Call Center provides you with a search function that allows you to search for specific contacts in your directories.

You use the Search panel in the Contacts pane to look for contacts.




Figure 80 Contacts Pane - Search Panel

9.3.1 Perform Contact Search

To search for contacts:

1) In the *Search* text box, enter the text you want to search for and press ENTER. You can enter partial information, such as part of a name or phone number.

For example, if you do not remember whether Mary's last name is spelled "Shelley" or "Shelly", you can enter "Shell", and either name is returned.

- To restrict the search to contacts that start with the entered text, check the Begins with box.
- 3) From the drop-down list, select the directories to search.
- 4) Press ENTER.

The text you enter is matched against all attributes of every entry in the selected directories.

NOTE: The search is not case-sensitive; the search for "Ann" and "ann" returns the same results.

Search results are displayed in the *Search* panel, each contact listed with the name of the directory where they were found.

BroadWorks directories are searched in the following order: Supervisors, Agents, Group/Enterprise. Duplicate search results in BroadWorks directories are not displayed; the first match for a given contact is displayed.

Duplicate search results in other directories are displayed.




Figure 81 Contacts Pane – Search Results



The search returns either all the contacts (in the selected directories) that contain the entered keyword or all the contacts that start with the entered keyword.

In the first case (*Contains*), entering "Ann" and selecting "First Name" from the *Keyword Search Filter* drop-down list returns all contacts with the first name "Ann", but it also returns all contacts with first names such as "Anne", "Marianne", "Marie Ann", "Ann Marie", and so on.

In the second case (*Starts With*), entering "Ann" and selecting "First Name" returns all contacts with first names such as "Ann", Anne", and Ann Marie", but not "Marianne" or "Mary Ann".

5) To clear the search results, click **Reset**

NOTE: Contact entries displayed in search results follow the same rules as if that entry was accessed in its own directory. This allows you to perform any operations directly from the search results.

9.4 Manage Personal Contacts

You can add or remove personal contacts via the web portal or in Call Center, and the updates appear in both places. However, the updates that you make via the web portal appear only in Call Center at the next sign-in.

To update personal contacts using the client, perform the following operations:

- Add Personal Contact
- Delete Personal Contact

You cannot modify a personal contact entry in Call Center. To modify information for a personal contact, delete the entry and add it again.

9.4.1 Add Personal Contact

To add a personal contact:

- 1) In the *Personal* panel, click **Edit** . The *Edit Personal Contact* dialog box appears.
- 2) Click **Add**. A new line is added below the existing entries, allowing you to define a new entry.






Figure 82 Edit Personal Contact Dialog Box – Adding Entry

- 3) In the *Name* text box, enter the contact's name or description, as you want it to appear on the contact's list.
- 4) In the *Number* text box, enter the phone number of the contact.
- 5) To save the entry, click anywhere in the dialog box outside the entry.

9.4.2 Delete Personal Contact

To delete a speed dial entry:

- 1) In the *Personal* panel, click **Edit** . The *Edit Personal Contact* dialog box appears.
- 2) Select the entry to delete and click **Delete**.




Figure 83 Edit Personal Contact Window – Deleting Entry



9.5 Manage Speed Dial Numbers

You can add or remove speed dial numbers via the web portal or in Call Center, and the updates appear in both places. However, the updates that you make via the web portal appear only in Call Center at the next sign-in.

To update speed dial entries using the client, perform the following operations:

- Add Speed Dial Entry
- Modify Speed Dial Entry
- Delete Speed Dial Entry

9.5.1 Add Speed Dial Entry

To add a speed dial entry:

- 1) In the Speed Dial panel, click **Edit** . The Edit Speed Dials dialog box appears.
- 2) Click **Add**. A new line is added below the existing entries, allowing you to define a new entry.




Figure 84 Edit Speed Dials Dialog Box – Adding Entry

- 3) From the Code drop-down list, select a speed dial code.
- 4) In the *Phone Number* text box, enter the phone number to assign to the code.
- 5) In the *Description* text box, enter a description that allows you to identify the entry.
- To save the changes, click anywhere in the dialog box outside the entry.

9.5.2 Modify Speed Dial Entry

To modify a speed dial entry:

- 1) In the Speed Dial panel, click **Edit** . The Edit Speed Dials dialog box appears.
- 2) Double-click the entry to modify. The entry becomes modifiable.






Figure 85 Edit Speed Dials Dialog Box – Modifying Entry

- Modify information as required.
- 4) To save the changes, click anywhere in the dialog box outside the entry.

9.5.3 Delete Speed Dial Entry

To delete a speed dial entry:

- 1) In the Speed Dial panel, click **Edit** . The Edit Speed Dials dialog box appears.
- 2) Select the entry to delete and click **Delete**.




Figure 86 Edit Speed Dials Dialog Box – Deleting Entry



10 Monitor IM&P Contacts and Chat with Contacts

When you have an IM&P service assigned on BroadWorks, you can chat with other IM&P users and see the unified presence state of selected IM&P users directly from Call Center. The unified presence of a contact is their presence state when they are logged in through multiple devices or applications, such as IM&P or BroadTouch Business Communicator.

IM&P capabilities are available only when you are online. For information on setting you IM&P presence state, see section *4.10 Change Your Instant Messaging and Presence State*.

10.1 Monitor IM&P Contacts

To view the presence state of an IM&P contact, you have to first subscribe to the contact. Otherwise, Call Center displays the contact's state as *Unsubscribed*. When you send a subscription request to a contact and you are waiting for their reply, Call Center displays the contact's state as *Pending Subscription*.

The following directories display the IM&P state of contacts: *Instant Message, Agent, Supervisor, Enterprise/Group, Custom, Search,* and *Directories*.

NOTE: The Instant Message panel does not include IM&P contacts in the *Unsubscribed* state.

You can subscribe to a contact either by sending a subscription request to the contact or by adding the contact to the *Instant Message* directory.

For information about the operations related to subscribing to contacts and viewing their presence state, see the following sections:

- Subscribe to Contact
- Add Contact to Instant Message Directory
- Modify Contact Name
- Unsubscribe from Contact
- Accept or Reject Subscription Request
- View Unified Presence State of Contacts

10.1.1 Subscribe to Contact

To send a subscription request to a contact:

1) Click the IM&P presence icon of an unsubscribed contact in any directory where the presence state of contacts is displayed. The *Contact (IM) Subscribe* dialog box appears.



Figure 87 Contact (IM) Subscribe Dialog Box



2) Click Yes.

A subscription request is sent to the contact, and the contact is added to the *Instant Message* directory. The contact's state is set to "Pending Subscription".

When the subscription is accepted, the contact's presence state is updated to their actual presence state.

3) To resend a subscription request at any time, click the contact's presence icon again and click **Resend** in the dialog box that appears.



Figure 88 Contact (IM) Re-Subscribe Dialog Box

10.1.2 Add Contact to Instant Message Directory

When you add a contact to the *Instant Message* directory, the system automatically sends a subscription request to the contact.

To add a contact to the Instant Message directory:

- 1) In the *Instant Message* panel, click **Edit** . The *Edit Instant Message Contacts* dialog box appears.
- 2) Click **Add**. A new line is added below the existing entries, allowing you to define a new entry.



Figure 89 Edit Instant Message Contacts Dialog Box – Add Contact

- 3) In the *Name* text box, enter the display name of the contact to add.
- 4) In the IM ID text box, enter a valid IM&P ID of the contact.
- 5) To save the changes, click anywhere in the dialog box outside the entry.

A subscription request is sent to the contact, the contact's presence state is set to "Pending Subscription", and the contact is added to the *Instant Message* panel.

When the subscription is accepted, the contact's presence state is updated to their actual presence state.



10.1.3 Modify Contact Name

You can modify the display name of an existing contact.

To modify the name of a contact:

- 1) In the *Instant Message* panel, click **Edit** . The *Edit Instant Message Contacts* dialog box appears.
- 2) Double-click the contact and enter the new name in the *Name* text box.
- 3) To save your changes, click anywhere in the dialog box outside the entry.




Figure 90 Edit Instant Message Contacts Dialog Box – Modify Contact

10.1.4 Unsubscribe from Contact

To stop monitoring a contact:

1) Click the presence icon of the contact. The *Contact (IM) Unsubscribe* dialog box appears.



Figure 91 Contact (IM) Unsubscribe Dialog Box

2) Click **Yes**. The contact is removed from the *Instant Message* directory and its presence status changes to *Unsubscribed* in other directories.



10.1.5 Accept or Reject Subscription Request

When you receive a request from another user, a dialog box appears allowing you to accept or deny the request.



Figure 92 Contact (IM) Request Dialog Box

To accept the request, click **Yes**. If the contact is not yet in your *Instant Message* directory, a request is sent automatically to add the user to the directory.

To reject the request, click No.

You can also close the dialog box and ignore the request. If you ignore the request, the dialog box will reappear the next time you go online.

10.1.6 View Unified Presence State of Contacts

You can view the unified presence state of IM&P contacts in the *Instant Message, Agent, Supervisor, Enterprise/Group, Custom, Directories,* and *Search* panels. The presence icon is displayed to the left of the contact's name.

Unified instant messaging presence states indicate your contacts' availability to communicate using client applications such as Hosted Thin Call Center, Hosted Thin Receptionist, BroadTouch Business Communicator Desktop, or BroadTouch Business Communicator Mobile.

The actual unified presence state of a contact is displayed only if you are subscribed to the contact. Otherwise, the contact's state is displayed as *Unsubscribed* or *Pending Subscription*.




Figure 93 Instant Message Directory – Unified Presence State of Contacts

The following table lists the possible unified presence states in Call Center:

IM&P State	Icon	Description		
Subscribed States				
Available		The contact is online, available on one or more devices, and not busy on any device.		
Busy		The contact is online, but currently busy on one or more devices. Do not disturb.		
Away	4	The contact is connected but away from one or more devices and not busy on any device.		



IM&P State	Icon	Description		
Offline		The contact is offline on all devices.		
Unsubscribed States				
Pending Subscription	3	You sent a subscribe request to the contact, but it has not yet been accepted. Clicking the icon resends the request.		
Not subscribed	\$ ⁷	The contact has the IM&P service but you are not subscribed to monitor their state. The contact does not appear in the <i>Instant Message</i> pane. Clicking this icon sends a subscription request to the contact.		

10.2 Chat with IM&P Contacts

You can have several concurrent one-on-one or multiuser instant messaging sessions open.

You can chat with more than one contact at the same time, either in one-on-one sessions or by participating in multiuser chats. Each session requires a separate window.

Chat windows appear at the bottom-right hand side of the Call Center main interface. Subsequent windows open to the left of the latest opened *Chat* window.

Chat windows can be taken out of the main interface and placed elsewhere on the screen.

The number of concurrently open *Chat* windows depends on the browser window size and screen resolution. The oldest *Chat* window is closed when there is no more room for a new *Chat* window to open. This only applies to *Chat* windows that are placed within the main interface.

You can start a chat session with a contact or accept a session request from another user. A one-on-one session can be converted into a multiuser chat by inviting more participants. You can also receive an invitation to a multiuser chat from another user.

When your IM&P contact is in your group/enterprise, you can also phone them directly from the *Chat* window.

The tasks related to instant messaging are described in the following sections:

- Start Instant Messaging Session
- Place Call from Chat Window
- Establish Multiuser Chat Session
- Manage Instant Messaging Sessions

10.2.1 Start Instant Messaging Session

You can start an instant messaging session with an IM&P contact from any of the following panels: *Instant Message, Agent, Supervisor, Enterprise/Group, Custom, Search,* and *Directories*.

To start an instant messaging session with a contact:

 In the Contacts pane, click the target contact. The entry expands displaying available action buttons.






Figure 94 IM&P Contact with Chat button

2) Click **Chat** CHAT on the line for the contact. A *Chat* window appears, displaying your contact's information on the title bar.



Figure 95 Chat Window

NOTE: A *Chat* window also appears when another IM&P user initiates a chat session with you.

Type your message in the text box at the bottom of the window and click ENTER. Your message is sent to your contact.

The messages you send and receive appear in the *Chat Logs* area at the top of the window, below the title bar. Up to 50 messages per contact are kept in the log for the duration of your IM&P session, even if you close the *Chat* window and later start exchanging messages again with the same contact. The messages are cleared when you go offline.



10.2.2 Place Call from Chat Window

If the user with whom you are chatting is also a contact in your *Group/Enterprise* directory, you can call them directly from the *Chat* window.

To place a call from the Chat window:

Click the **Call** button at the top-right of the *Chat* window.

The Call Center client issues a Click-To-Dial attempt to the contact's phone number and the call appears in the *Call Console*.

10.2.3 Establish Multiuser Chat Session

You can invite other contacts to your chat, thus converting your one-on-one chat to a multiuser chat. An incoming multiuser chat invitation opens a window for a new multiuser chat.

To add users to a chat session:

1) Click the **Add User to Chat** button in the *Chat* window. A drop-down list of available contacts appears.



Figure 96 Add Participants to Chat

2) Select the check box next to each contact to invite and click the **Invite** button. When a contact joins the chat, a notification appears in the *Chat Logs* area of the *Chat* window. The participants (other than you) are also listed at the top of the window.






Figure 97 Multiuser Chat

3) To leave the multiuser chat, close the *Chat* window.

10.2.4 Manage Instant Messaging Sessions

If a *Chat* window is not in focus and an incoming message is available for you to read, the color of the window is light brown as shown in the following figure. This changes to black as soon as the window is in focus.



Figure 98 Managing Chat Sessions

You can also close, minimize, or pop out a *Chat* window, that is, take the *Chat* window out of the Call Center main interface and place it elsewhere on the desktop.



To pop out a *Chat* window:

Click the **Pop-out** button at the top-right of the window.

The window is placed on the desktop outside of Call Center and the Pop-out button becomes the Pop-in button.

To place the window back within the Call Center main interface:

Click the **Pop-in** button at the top-right of the window.

To minimize or close a Chat window:

Click the **Minimize** or **Close** button at the top-right of the window. When a window is closed, the windows to the left (if present) shift to the right. This applies only to *Chat* windows that are placed within the Call Center main interface.



11 Monitor Supervisors (Agent)

Call Center allows you to monitor the phone state of selected supervisors (up to 50). This is useful when you are escalating a call and want to find a supervisor who is available to take a call guickly.

You use the *Supervisors* panel to view the phone state of selected supervisors and to select supervisors to monitor. Supervisors who are not monitored have their state set to "Unknown".




Figure 99 Supervisors Panel

NOTE: This capability is designed to monitor the supervisor's state related to normal calls. Conference calls are handled differently, and it may happen that the state of a supervisor who was in a conference call is temporarily not reflected properly. For example, if the supervisor is in a conference and then all other parties hang up, the supervisor's status shows as I*dle* even though their phone may still be off hook.

11.1 Select Supervisors to Monitor

The list of selected supervisors is saved when signing out as part of your workspace and is restored on subsequent logins.

To select the supervisors to monitor:

1) In the *Supervisors* panel, click **Edit** . The *Supervisor Favorites* dialog box appears.



Figure 100 Supervisor Favorites Dialog Box



2) Check the box next to each supervisor to monitor and click **Save**.

11.2 Supervisor Phone States

The following table lists the possible states for a supervisor's phone line:

Phone State	Icon	Description
Idle		Supervisor's phone is on-hook, which means the supervisor is not on a call.
Busy		Supervisor's phone is off-hook, which means that the supervisor is on a call.
Ringing		Supervisor's phone is in alerting state; a call is currently being delivered to the supervisor.
Do Not Disturb		Supervisor has enabled the Do Not Disturb service.
Private	A	Supervisor has enabled phone state privacy. NOTE: This terminates monitoring of the supervisor's phone state for the current login session. To be able to monitor their phone state again, you must sign out and then sign in after the supervisor has disabled their phone state privacy.
Call Forwarding Always	••	Supervisor has enabled the Call Forwarding Always service.
Unknown		Supervisor is currently not monitored.




12 Monitor Call Centers (Agent)

Call Center provides you with real-time information about monitored queues. This information is displayed in the *Dashboard* pane.

12.1 Dashboard Pane

The *Dashboard* pane lists the monitored call centers and provides key indicators for each. For information about selecting call centers to monitor, see section *12.2 Select Call Centers to Monitor*.

Some fields are color-coded to provide visual indicators of threshold severity. Threshold values are configured by your administrator. The visual Indicators of threshold severity are as follows:






Figure 101 Dashboard Pane (Agents)

The following information is provided for each monitored call center:

- Call center name The name of the call center.
- Service Mode (Premium call centers) The mode in which the call center currently operates. This field can have one of the following values:
 - Night Service The call center is processing calls according to the Night Service schedule and policy.



 Night Service Override – The call center has been manually forced to follow the Night Service policy.

NOTE: The *Night Service or Night Service Override* status appears only if the Night Service policy is triggered, either by the *Night Service* schedule or by a manual override, and if the action to apply to incoming calls is set either to "Perform busy treatment" or "Transfer to phone number/SIP-URI". Setting the action to "None" acts as if the Night Service policy was not triggered and the *Night Service/Night Service Override* status is not displayed in Call Center.

 Holiday Service – The call center is processing calls according to the Holiday Service schedule and policy.

NOTE: The *Holiday Service* status appears only if the *Holiday Service* policy is triggered and if the action to apply to incoming calls is set by a BroadWorks administrator to "Perform busy treatment" or "Transfer to phone number/SIP-URI". Setting the action to "None" acts as if the *Holiday Service* policy was not triggered and the *Holiday Service* status is not displayed in Call Center.

- Forced Forwarding All calls to this call center are forwarded to a specified destination.
- None Call center is in normal mode of operation; none of the above modes are enabled.

NOTE: When the call center is in Normal service mode, the *Service Mode* field displays "None".

- Current Calls in Queue This is the number of queued calls expressed as a ratio of the total queue capacity for that call center. For example, "6/10" means that there are six calls in the queue, which can queue a maximum of ten calls.
- Longest Waiting Call This is the waiting time of the call that has been in the queue the longest.
- EWT (Expected Waiting Time) This is the estimated time a caller has to wait in this queue before their call is answered.
- AHT (Average Handle Time) This is the average time it takes to process a call in this queue.
- ASA (Average Speed of Answer) This is the average time a caller spends in the queue before the call is offered to an agent.
- Staffed This is the number of agents that are in Sign-In, Available, Unavailable, or Wrap-Up ACD state, as a ratio of all agents assigned to this call center.

The fields that provide visual indicators are *Current Calls in Queue*, *Longest Waiting Call*, *EWT*, *AHT*, and *ASA*.



12.2 Select Call Centers to Monitor

You can select up to 50 call centers to monitor in the *Dashboard* pane. You can only monitor call centers to which you have been assigned.

To select call centers to monitor:

1) In the *Dashboard* pane, click **Options** and select the *Select Queues* option. The *Select Queues* dialog box appears.




Figure 102 Select Queues Dialog Box

2) Check the call centers you want to monitor and click **Save**.

12.3 Select Information to Display

You can select which performance indicators you want to display in the Dashboard pane.

To select information to display:

1) In the *Dashboard* pane, click **Options** and select the *Select Visible Fields* option. The *Select Fields* dialog box appears.




Figure 103 Select Fields Dialog Box



- 2) To display all performance indicators, check *Select All*. Alternatively, to show or hide some fields, check to uncheck the corresponding check boxes.
- 3) Click Save.

12.4 Order Call Centers

By default, call centers displayed in the *Dashboard* pane are ordered by name. You can change the order in which call centers are displayed.

To change the order of call centers:

- 1) In the *Dashboard* pane, click **Options**
- 2) Select Sort By and then select the ordering options you want.




Figure 104 Dashboard – Options – Sort By



13 Manage Agents (Supervisor)

You use the *Agents* panel to view the agents who you are supervising and to perform actions on them. You can also monitor the call and the ACD state of selected agents and make agents join or leave queues. For information on selecting agents to monitor, see section 13.1 Select Agents to Monitor. For information on making agents join queues, see section 13.2 Make Agents Join Queues.



Figure 105 Agents Panel

13.1 Select Agents to Monitor

Call Center allows you to monitor the call and the ACD state of selected agents, but agents are not automatically monitored. To monitor the state of an agent, you must select the agent.

To select agents to monitor:

1) In the Agents panel, click **Edit** . The Edit Monitored Agents dialog box appears.




Figure 106 Edit Monitored Agents Dialog Box



- Select the check box next to each agent to monitor. If an agent is staffing multiple call centers, by selecting that agent for monitoring in one call center, you are also selecting them for monitoring under all call centers that they are staffing.
- 3) Click Save.

The selected agents have their call and ACD state displayed. The state of agents who are not monitored appears as unknown (dimmed).



Figure 107 Agents Panel - Monitored Agents

The list is saved and is available during subsequent sessions.

13.2 Make Agents Join Queues

Call Center allows you to force an agent's join status in queues, effectively making the agent join or leave queues.



Figure 108 Agents Panel – Contact with Queue Button

To make an agent join or leave one or more queues:

- 1) In the *Agents* panel, click the target agent. The entry expands displaying available action buttons.
- Click the Queue button. The Agent Queue Membership dialog box appears listing the call centers to which the agent is assigned.






Figure 109 Agent Queue Membership Dialog Box

- 3) To make the agent join a queue, check the *Join* box in the row of the queue you want the agent to join.
- 4) To make the agent leave a queue, uncheck the *Join* box in the row of the queue you want the agent to leave.
- 5) Click Save.

13.3 Agent Phone and ACD States

Monitored agents have their phone and ACD state displayed. A single icon, to the left of the agent's name, represents the agent's combined phone and ACD state, which indicates the agent's ability to take calls. In addition, the agent's ACD state is also displayed in text following their name. If the agent's ACD state is set to "Unavailable", then the unavailable code is also displayed (if applicable).

Other agents have their state set to "Unknown".



Figure 110 Agents Panel - Agents with Phone and ACD State Displayed

The possible agent's phone and ACD states are as follows:

Phone State	ACD State	Icon	Description
Idle	Available		Agent's phone is on-hook and the agent is available to take ACD calls.
Ringing	Available		Agent's phone is ringing and the agent is available to take the call.
Any	Unavailable, Sign-In, Sign-Out		Agent is not available to take ACD calls.



Phone State	ACD State	Icon	Description
Idle, Ringing	Wrap-Up		Agent is performing post call work. They may or may not be available to take calls.
Busy	Available, Wrap-Up		Agent's phone is off-hook, which means that the agent is on a call. Calls may be delivered to agents depending on their call waiting settings and the call center's call waiting and wrap-up settings.
Do Not Disturb	Any		Agent has enabled the Do Not Disturb service. ACD calls are not delivered to agent in the <i>Do Not Disturb</i> call state. This state is not recommended for Call Center agents. Agents should use the <i>Unavailable ACD</i> state when they need to block new incoming calls temporarily.
Call Forwarding Always	Any	••	Agent has enabled the Call Forwarding Always service.
Private	Any		Agent has enabled phone state privacy. NOTE: This terminates monitoring of the agent's phone state for the current login session. To be able to monitor their phone state again, you must sign out and then sign in after the agent has disabled their phone state privacy.
Unknown	Any		Agent is currently not monitored.

13.4 View Agent's Details

Clicking an agent expands the entry to show all queues the agent is assigned to and all the agent's current calls, in order of arrival.

For each call, the following information is displayed:

- Call number
- Calling name (if available) and calling number (and for direct calls, extension), for example, "Joe Smith +12403645125"
- Call length in the following format: "MM:SS" (or "HH:MM:SS" if the call lasts longer than an hour), for example, "10:22"

For each queue, the following information is displayed:

- Call Center ID
- Whether the agent has joined the queue
- The agent's skill level in that queue, if applicable





Figure 111 Agents Panel Entry Expanded

13.5 Change Agent ACD State

You can force an ACD state change for an agent. This action can only be performed on monitored agents.

To change and agent's ACD state:

1) In the Agents panel, click the agent and then click the ACD State button



Figure 112 Agents Panel – Agent ACD State

Maldini, Paolo

- 2) From the drop-down list, select the new state.
- 3) If you selected *Unavailable*, you may have to select the reason for their unavailability.

orgin out



13.6 Silently Monitor Agent's Call

Call Center allows you to listen to monitored agents' calls without being heard. You can listen in on agents who you selected for phone and ACD state monitoring.

NOTE: This function is available if you have the Directed Call Pickup with Barge-in and Call Center Monitoring services assigned.

You can silently monitor one agent at a time, and the agent you monitor must have the Call Center – Premium service assigned.

You can choose to monitor the agent's current call or next incoming call. To monitor the current call, the agent must have exactly one active call.

To listen in on an agent's current call silently:

- 1) In the *Contacts* pane, expand the *Agents* panel and click the agent to monitor. The agent must have exactly one active call.
- Click Monitor for that agent.

A new call is created in the *Conference Call* panel. You are conferenced in to the call and muted (Silent Monitoring).

To listen in on an agent's next call silently:

- 1) In the Contacts pane, expand the Agents panel.
- 2) Click the target agent and click **Monitor Next Call** for that agent. A monitoring call is established for the selected agent.

When the next call is received and answered by the agent, you are conferenced in to the call and your call is muted. Both calls appear in the *Conference Call* panel.



Figure 113 Silently Monitored Call

To barge in on a call you are silently monitoring:

In the Conference Call panel, click Barge In BARGE . You are conferenced in to the call.

For information on operations that can be performed on conference calls, see section *6.13 Manage Conference Calls*.



13.7 Barge in on Agent's Call

Supervisor Barge-In allows you to barge in on an agent's call. This is useful when you want to enter an already established call between two other people. You can only barge in on agents who you selected for phone and ACD state monitoring.

NOTE: This functionality is only available if you have been assigned the Directed Call Pickup with Barge-in service.

To barge in on an agent's call:

- 1) In the *Contacts* pane, expand the *Agents* panel and select an agent. The agent must have exactly one active call.
- 2) Click the agent to expand the entry and click **Barge In**Conference is established.

 A Three-Way

For information on operations that can be performed on conference calls, see section *6.13 Manage Conference Calls*.

13.8 Pick Up Agent's Ringing Call

Call Pickup allows you to pick up an unanswered call on behalf of an agent. This is useful when the agent is away or busy.

NOTE 1: This functionality is only available if your group has been assigned the Call Pickup service.

NOTE 2: A call that is retrieved using Call Pickup is treated in the Call Center reports as a direct inbound call to the retrieving party and not as an ACD call, because it was not answered by the agent selected using the ACD process.

NOTE 3: Supervisor Call Pickup is only supported if the agent and supervisor are in the same group. In an enterprise, this function can be disabled.

To pick up an unanswered call for an agent:

- 1) In the Agents panel, select an agent whose phone is ringing.
- 2) Move the mouse over the agent and click **Answer** ANS.

 You are now answering the call, and the call appears in the *Call Console*.



14 Manage Queued Calls (Supervisor)

Call Center allows you to manage queued calls in the selected call centers (up to five) and to monitor calls in real time. You use the *Queued Calls* pane to manage queued calls under your supervision.

Section 14.1 Queued Calls Pane describes the Queued Calls pane. The rest of this section describes the operations you perform to manage queued calls:

- Select Call Centers to Monitor
- Show or Hide Call Center Panels
- View Queued Calls
- Group Queued Calls
- Order Queued Calls
- Monitor Next Call
- Enable Night Service Override or Forced Forwarding (Premium Call Center)
- Retrieve Call from Queue
- Promote Call in Queue (Premium Call Center)
- Transfer Call to Another Queue
- Transfer Call to Top of Queue (Premium Call Center)
- Transfer Call from Queue to Agent
- Transfer Call to Ad Hoc Number
- Change Position of Call in Queue

14.1 Queued Calls Pane

You use the Queued Calls pane to manage queued calls.

The Queued Calls pane displays the monitored call centers and lists the calls queued in each call center.

You can monitor up to five call center queues at a time, plus one special queue, called the Quick Link Queue, which does not count toward the maximum of the five-queue limit. The monitoring of a Quick Link Queue is triggered from the *Dashboard*.

For information about selecting call centers to monitor, see section *14.2 Select Call Centers to Monitor*.

For more information about selecting the Quick Link Queue, see section 15.5 Navigate to Agent in Agent Directory or Queue in Queued Calls Pane.

Each call center is displayed in a separate panel. The panel's header provides the following information and controls:

- Call center name The name of the call center.
- Call center number The primary phone number of the call center.





Figure 114 Queued Calls Pane

- Service Mode button
 This identifies the service mode of the supervised call center. Clicking the button launches the Edit Queued Calls Favorites dialog box and allows you to activate Night Service Override or Forced Forwarding. The call center can be in one if the following service modes:
 - Night Service The call center is processing calls according to the Night Service schedule and policy.
 - Night Service Override The call center has been manually forced to follow the Night Service policy.

NOTE: The *Night Service* or *Night Service Override* mode appears only if the Night Service policy is triggered. It is triggered either by the *Night Service* schedule or by a manual override, and if the action to apply to incoming calls is set by a BroadWorks administrator to either *Perform busy treatment* or *Transfer to phone number/SIP-URI*. Setting the action to "None" acts as if the Night Service policy was not triggered, and as a result, the *Night Service/Night Service Override* mode is not displayed.

 Holiday Service — The call center is processing calls according to the Holiday Service schedule and policy.

NOTE: The *Holiday Service* mode appears only if the Holiday Service policy is triggered and if the action to apply to incoming calls is set by a BroadWorks administrator to either *Perform busy treatment* or *Transfer to phone number/SIP-URI*. Setting the action to "None" acts as if the Holiday Service policy was not triggered, and as a result, the *Holiday Service* mode is not displayed.

- Forced Forwarding All calls to this call center are forwarded to a specified destination.
- Normal Call center is in normal mode of operation; none of the above modes is enabled.



- Message Waiting icon
 This icon is displayed if there is one or more outstanding voice messages left in the call center's voice mailbox. This icon performs the role of a message waiting indicator for the call center.
- Ratio of visible calls to display limit This is the number of calls in the queue that are currently displayed against the maximum number of calls that can be displayed for a queue.
- Ratio of queued calls to queue length This is the number of calls in queue against the queue length that is displayed.

When you expand the panel for a call center, the list of calls queued in that call center appears.

By default, calls are listed according to their position in the queue with the oldest call first. They can be grouped by the priority bucket. For more information, see section 14.6 Group Queued Calls.

The following information is provided for each call:

- Call Status icon A graphic representation of the state of the queued call:
 - Waiting The call is queued, waiting to be answered.
 - Announcement An entrance announcement or music is being played to the caller.
 - Reordered The position of the call in the queue has been changed.
 - Bounced The call has been bounced.
- Caller's identity The name (if available) and the phone number of the calling party.
- Call time –The total call time, including the time in the current queue (in parentheses).

Clicking a call expands the call to show additional data:

- Priority (Premium call center) The priority bucket of the call.
- Position The position of the call in the gueue.
- Destination The name (if available) and the phone number of the call center (or DNIS, when applicable) that was called.

When the call is expanded, the action buttons for actions that can be performed on the call appear. For the list of action buttons available in Call Center, see section 5.5.1 Call Action Buttons.



14.2 Select Call Centers to Monitor

You can select up to five call centers to monitor. You view the monitored call centers in the *Queued Calls* pane.

To select call centers to monitor:

1) In the Queued Calls pane, click **Options** and select the Edit Queue Favorite Dialog option.




Figure 115 Queued Calls - Options - Edit Queue Favorite Dialogue

The Edit Queue Favorites dialog box appears.




Figure 116 Edit Queue Favorites Dialog Box

- 2) Select the *Monitor* check boxes in the rows of the call centers to monitor. Note that the Quick Link Queue can only be selected for monitoring from the *Dashboard*.
 - If you select a queue that you are currently monitoring as the Quick Link Queue, the queue stops being monitored as the Quick Link Queue when you save your changes and it is monitored as a regular queue.
- 3) Click Save.

NOTE: Clicking the Close button in a call center panel in the *Queued Calls* pane, closes the panel but does not stop monitoring the call center.

To stop monitoring a call center, deselect the *Monitor* check box for the call center in the *Edit Queue Favorites* dialog box.



For information about showing or hiding a call center in the *Queued Calls* pane, see section 14.4 Show or Hide Call Center Panels.

14.3 Modify Number of Calls to Display

For each Standard call center that you are monitoring, you can modify the maximum number of calls to be displayed and for each Premium call center, you can modify the maximum number of calls that can be displayed in each priority bucket. The total number of calls to display for a call center cannot exceed 50.

- 1) In the Queued Calls pane, click **Options** and select the Edit Queue Favorite Dialog option. The Edit Queue Favorites dialog box appears.
- 2) For each Standard call center you are monitoring, set the total number of calls to display.
- 3) For each Premium call center you are monitoring, set the number of calls to display in each priority bucket. The total number of call in all priority buckets cannot exceed 50.

14.4 Show or Hide Call Center Panels

You can show or hide call center panels for monitored queues. This is not the same as selecting queues to be monitored. For more information, see section 12.2 Select Call Centers to Monitor.

To show/hide call center panels:

- 1) In the Queued Calls pane, click **Options**
- 2) Select *View* and then select or unselect the names of the call centers. To show or hide all centers, select or deselect *All*.



Figure 117 Queued Calls - Options - View

Alternatively, to hide a call center, click the **Close** button . The call center is removed from the display but it continues to be monitored.

NOTE: This does not apply to the Quick Link Queue. When you click the Close button for the Quick Link Queue, the queue is no longer monitored.



14.5 View Queued Calls

You can selectively expand or collapse call center panels to show or hide calls in the monitored call centers.

To view queued calls for a call center:

Click the *Expand* button for that call center.

To view call details of a selected call:

Click that call.

14.6 Group Queued Calls

You can group queued calls by their priority bucket.

To group or ungroup queued calls:

- 1) In the Queued Calls pane, click **Options**
- 2) From the drop-down list, select *Group*, and then select or deselect *Group by Priority*. This action applies to all monitored call centers.



Figure 118 Queued Calls - Options - Group

3) To ungroup calls, unselect the *Group by Priority* option.

14.7 Order Queued Calls

Queued calls can be ordered according to their total waiting time or their waiting time in the current priority bucket.

To order queued calls:

- 1) In the Queued Calls pane, click **Options**
- Select Sort and then the ordering option you want. This operation applies to all monitored call centers.




Figure 119 Queued Calls - Options - Sort



NOTE: The ordering does not work when calls are grouped. If required, first ungroup the calls.

14.8 Monitor Next Call

You can silently monitor the next call that is received by a call center.

NOTE: To use this feature, you must have the Call Center Monitoring service assigned.

To monitor the call center's next call:

- 1) In the *Contacts* pane, expand the *Queues* panel and click the target call center to expand it.
- 2) Click the **Monitor Next Call** button for that call center. A monitoring call is established for the selected call center.

When the next call is received and answered by an agent, you are conferenced in to the call and your call is muted. Both calls appear in the *Conference Call* panel.

To barge in on a call you are silently monitoring:

In the Conference Call panel, click Barge In BARGE . You are conferenced in to the call.

For information on operations that can be performed on conference calls, see section *6.13 Manage Conference Calls*.

14.9 Enable Night Service Override or Forced Forwarding (Premium Call Center)

Call Center allows you to manually override the current mode of operation and enable the Night Service and/or Forced Forwarding of calls for selected call centers.

To enable Night Service Override and/or Forced Forwarding:

1) In the *Queued Calls* pane, click the **Service Mode** button in the panel for one of the call centers. The *Edit Queue Favorites* dialog box appears.




Figure 120 Edit Queue Favorites Dialog Box



- For each call center for which you want to override the time schedule and manually initiate Night Service (including the Quick Link Queue if present), check the Night Service Override check box.
- 3) For each call center that you want to divert calls to a specified destination temporarily (including the Quick Link Queue if present), check the *Force Forwarding* box, and then enter the phone number to which to forward the calls in the *Enter Number* box.

NOTE: Night Service Override has precedence over Forced Forwarding.

14.10 Retrieve Call from Queue

You can retrieve queued calls from the queue to your phone device.

To retrieve a call from a queue:

Click the call in the Queued Calls pane and click Retrieve for that call.

Once you retrieve a call, the call appears in the *Call Console* and you treat it as any other call. For example, you can transfer it to an ad hoc number or to another queue. For more information, see section 6 *Manage Calls*.

14.11 Promote Call in Queue (Premium Call Center)

A priority is attached to an incoming call based on the DNIS number on which it is received. Calls are distributed to the agents staffing the queue based on this priority, with calls of the higher priority being exhausted before calls in the next priority are distributed.

You can manually promote calls from a lower priority bucket to a higher priority bucket. A manually promoted call ends up as the last call in the higher priority bucket with a wait time of zero seconds.

To promote a call, that is to change its priority:

- 1) In the Queued Calls pane, expand a Call Center panel.
- Click the call you want to promote and click **Promote** for that call.
 The queued call is promoted to the end of the next highest priority bucket.

14.12 Transfer Call to Another Queue

To transfer a queued call to another queue:

- 1) In the Queued Calls pane, select the call to transfer.
- 2) In the Contacts pane, expand the Queues panel.
- 3) Click the target queue and click **Transfer** for that queue.

 The call is transferred and removed from the queue.



14.13 Transfer Call from Queue to Agent

To transfer a call from a queue to an agent:

- 1) In the Queued Calls pane, select the call to transfer.
- 2) In the Contacts pane, expand the Agents panel.
- 3) Click the target agent and click **Transfer** for that agent. The call is transferred and removed from the queue.

14.14 Transfer Call to Ad Hoc Number

To transfer a call to an ad hoc number:

- 1) In the Queued Calls pane, select the queued call.
- 2) In the *Dialer*, enter the destination number and click **Transfer**



Figure 121 Ad Hoc Queue Transfer

The call is transferred and removed from the queue.

14.15 Change Position of Call in Queue

You can reorder a queued call in a Standard call center or in the "0" priority bucket in a Premium call center.

To change a call's position in a queue:

1) In the Queued Calls pane, click the target call to expand it.




Figure 122 Reordering Queued Call

2) Click **Reorder** and select the new position in the queue from the list that appears.

The call is placed in the new position.

NOTE 1: You cannot place a call ahead of a bounced call.

NOTE 2: The list can contain a maximum of 24 reorder positions, which you can choose from to reorder a call in queue, in addition to *Send to Back* and *Sent to Front* options.



14.16 Transfer Call to Top of Queue (Premium Call Center)

If your administrator has configured the call center with the Transfer to Top feature, follow this procedure to transfer the call to the top of the queue.

You can only transfer a call to the top of the highest priority bucket (bucket with priority "0").

There need to be at least two calls in the target queue.

- 1) In the Queued Calls pane, click the target call to expand it.
- c) Click **Reorder** REORDER and select Send to Front from the list that appears.



Figure 123 Transferring Call to Top of Queue



15 View Real-Time Statistics (Supervisor)

Call Center provides you with real-time information about supervised agents and queues. This information is displayed in the Dashboard. You can also navigate to a selected agent or a queue directly from the Dashboard.

15.1 Display Dashboard

To access the Dashboard:

Click the **Dashboard** link at the top right-hand side of the main interface window. The *Dashboard* is launched in a separate window and can be open at the same time as other Call Center windows.




Figure 124 Dashboard

The *Dashboard* is divided into two parts with queue information in the top half and agent information in the bottom half. The information is updated at a configurable refresh rate. The default is 5 seconds.

By default, information about agents is hidden.

To view agents staffing a call center:

Check the Show Agents check box in the row for that call center.

Some fields are color-coded to provide visual indicators of threshold severity. Threshold values are configured by your administrator.




Figure 125 Visual Indicators of Threshold Severity



15.2 Queue Information

The *Dashboard* displays each call center queue on a separate line and provides the following information about each queue:

- Name This is the name of the call center.
- Status (Premium call centers) This identifies the service mode in which the call center currently operates, which can be one of the following:
 - Night Service The call center is processing calls according to the Night Service schedule and policy.
 - Night Service Override The call center has been manually forced to follow the Night Service policy.

NOTE: The *Night Service or Night Service Override* status appears only if the Night Service policy is triggered, either by the *Night Service* schedule or by a manual override, and if the action to apply to incoming calls is set either to "Perform busy treatment" or "Transfer to phone number/SIP-URI". Setting the action to "None" acts as if the Night Service policy was not triggered and the *Night Service/Night Service Override* status is not displayed in Call Center.

 Holiday Service – The call center is processing calls according to the Holiday Service schedule and policy.

NOTE: The *Holiday Service* status appears only if the *Holiday Service* policy is triggered and if the action to apply to incoming calls is set by a BroadWorks administrator to either "Perform busy treatment" or "Transfer to phone number/SIP-URI". Setting the action to "None" acts as if the *Holiday Service* policy was not triggered and the *Holiday Service* status is not displayed in Call Center.

- Forced Forwarding All calls to this call center are forwarded to a specified destination.
- Normal Call center is in normal mode of operation; none of the above modes is enabled.

NOTE: When the call center is in Normal service mode, the *Status* field is empty.

- Calls in Queue This is the number of queued calls expressed as a ratio of the total queue capacity for that call center. For example, "6/10" means that there are six calls in the queue, which can queue a maximum of ten calls.
- Long Waiting Call This is the waiting time of the call that has been in the queue the longest.
- EWT (Expected Waiting Time) This is the expected waiting time of calls in the queue.
- AHT (Average Handle Time) This is the average handling time for calls in the queue.
- ASA (Average Speed of Answer) This is the average amount of time a caller spends in the queue before the call is offered to an agent.



- Staffed (Agents) This is the number of agents managed by you that are in Sign-In, Available, Unavailable, or Wrap-Up ACD state, as a ratio of all agents managed by you for this call center.
- Idle (Agents) This is the number of agents who are in the Available ACD state but presently not on a call.
- Unavailable This is the number of agents who are signed in to the call center but not available to take calls.
- Show Agents When this check box is selected, the agents who are joined in the call center are displayed in the *Agents* area of the *Dashboard*.

The fields that provide visual indicators are *Calls in Queue*, *Longest Waiting Time*, *EWT*, *AHT*, and *ASA*.

15.3 Agent Information

The Dashboard displays information about the agents for the selected queues.

To display agent information:

- 1) To select the queues for which you want to view agents' information, check the *Show Agents* box on the lines for the queues in the *Queues* area of the *Dashboard*.
- 2) To hide signed-out agents, check the *Hide Signed Out Agents* box at the top-right corner of the *Dashboard*.



Figure 126 Dashboard - Hide Signed Out Agents Box

The following information is provided for each displayed agent:

- Status This is the agent's combined phone and ACD state. For more information, see section 13.3 Agent Phone and ACD States.
 - Note that the *Status* column is only sorted by the ACD state and it ignores the phone state.
- Name This is the agent's name.
- Queues (total) This is the total number of queues to which the agent is assigned.
 This number is a link, which when clicked, opens a dialog box that lists the agent's queues.
- Sign-In Time This is the agent's most recent sign-in time.
- Sign-In Duration This is the amount of time that the agent has been signed in.
- Call State (Time) This is the call state and time on the current call. The call state can be *Idle*, *Ringing*, or *On a call*. If an agent is in multiple calls, the call time reflects the time of the longest running call. When a call is released, then the call time reflects the time on the remaining calls.
- Agent State (Time) This is the agent ACD state and time. If an agent is unavailable, the unavailable code is shown.
- % Available This is the time that the agent was available to take calls shown as a
 percentage of the duration of the current sign-in.



- Avg Busy In This is the average time spent by the agent on an incoming ACD call.
- Avg Busy Out This is the average time spent by the agent on an outgoing ACD call.
- *Avg Wrap-Up* This is the average time spent by the agent in a post call wrap-up.

Fields that provide visual indicators are Call State (Time), On Call, Idle, Agent State (Time), Unavailable, Avg Busy In, Avg Busy Out, and Avg Wrap-Up.

The *Dashboard* is designed to be used together with the *Queued Calls* pane and the *Agents* panel in the *Contacts* pane. The *Dashboard* provides you with a real-time view of agents and queues, while the *Agents* panel and *Queued Calls* pane allow you to take actions on monitored agents and ACD calls. For more information about the actions you can take to manage agents and queued calls, see sections *13 Manage Agents* (*Supervisor*) and *14 Manage Queued Calls* (*Supervisor*).

15.4 Select Information to Display

By default, Call Center displays information about call centers and agents as described in sections 15.2 Queue and 15.3 Agent. You may however modify what information you want to appear in the Dashboard.

To select information to display:

- 1) Right-click the first row in the queued calls or agents table.
- 2) From the menu that appears, select Columns.
- 3) From the list of available columns, uncheck the columns you want to hide and check the columns you want visible.




Figure 127 Dashboard - Select Columns to Display

4) When you are done, click anywhere in the *Dashboard* outside the menu.

15.5 Navigate to Agent in Agent Directory or Queue in Queued Calls Pane

Call Center allows you to navigate to a call center queue in the *Queued Calls* pane or to an agent in the *Agents* directory directly from the *Dashboard*.

If the selected queue is currently not monitored, the application starts monitoring the queue as a special queue, called Quick Link Queue, which does not count toward the maximum of five queues that can be monitored. You can perform normal call operations on calls in the Quick Link Queue.



- When you close the Quick Link Queue, Call Center stops monitoring the queue and the queue is removed from the Queue pane.
- When you click a non-monitored queue while there is already a queue monitored as Quick Link Queue, the new queue replaces the old queue as the Quick Link Queue and Call Center stops monitoring the old queue.




Figure 128 Dashboard - Navigate to Queue or Agent

 To navigate from the Dashboard to a call center queue in the Queued Calls pane, click the name of the queue. The main window is brought to the foreground and the selected queue is displayed with an expanded listing of calls in the queue. All other queues are collapsed.



Figure 129 Queued Calls Pane - Quick Link Queue

2) To navigate from the Dashboard to an agent in the Agents directory, make sure that the Show Agents check box (on the row for the queue the agent is staffing), is checked and then click the agent's name. The main window is brought to the foreground and the selected agent is displayed expanded in the Agents panel.



16 Generate Reports

Call Center provides reporting functions to agents and supervisors. Agents can only generate reports about their own activity whereas supervisors have access to reports on activity and performance of agents and call centers under their supervision.

The Reporting feature allows you to run reports and schedule reports to run in the future using predefined templates. Reports can be of type *Agent* or *Call Center*.

The report templates available to you depend on how your administrator has configured your system.

You use the Reporting link at the top of the main interface to access pages used to generate and schedule reports.



Figure 130 Main Interface (Top of Window)

This section provides an example of a report. For the list of canned report templates available on BroadWorks for report generation, see the *BroadWorks Call Center Reports Guide*.



16.1.1 Run Report

To run a report:

1) Click the **Reporting** link at the top right-hand side of the main window. A *Report* window appears.




Figure 131 Report Window

2) Select a report template from the drop-down list. The page displays the input parameters for the report.






Figure 132 Abandoned Call Report – Running Report

3) Fill in the required information. The input that you need to provide depends on the template you select and the report type. The following table explains the input parameters for all reports.

Input Field	Description	Allowed Value
Scope	For <i>Agent Reports</i> , it allows you to specify the agents to include in the report. You can check <i>All Agents</i> or <i>Agents</i> . If you check <i>Agents</i> , select agents from the drop-down list. NOTE : This parameter is disabled when an agent runs the report, since agents can only run reports about themselves.	All Agents, Agents
	For Call Center Reports, it specifies the call centers or DNIS numbers to include in the report. You can check All Call Centers, Call Center, or DNIS.	All Call Centers, Call Center, DNIS
	 If you check <i>Call Center</i>, select call centers from the drop-down list. If you select <i>DNIS</i>, select a call center and DNIS numbers from the drop-down lists. For <i>DNIS</i> you can also select <i>ALL DNIS</i>. 	



Input Field	Description	Allowed Value
Call Completion	This setting is used to count the number of ACD calls an agent has completed within a service level during the specified interval. The Call Completion service level can be set to "1" through "7200" seconds.	1 through 72000
Short Duration	This setting is used to count the number of ACD short duration calls completed by an agent during an interval. You can set the maximum length of a short duration call to "1" through "7200" seconds.	1 through 7200
Service Level	This setting allows you to provide up to five service levels, used to perform service-level calculations for each call center or DNIS. Each service level can be set to "1" through "7200" seconds.	1 through 7200
Service Level Options	These settings are used to determine whether certain types of calls should be included in the service-level calculations: Check Include overflow time transfers in service level to include calls transferred due to time overflow. Check Include other transfers in service level to include calls transferred for other reasons. Select one of the following options for abandoned calls: Exclude Abandoned Calls to exclude all abandoned calls Include All Abandoned Calls to include all abandoned calls Include All Abandoned Calls Except Before Entrance Completes to include calls abandoned after the entrance message has finished playing Include Abandoned Calls Except in Defined Interval to include calls abandoned after the time specified by the abandoned call interval parameter.	These options can be checked or unchecked.
Abandoned Call Interval	If you selected the <i>Include Abandoned Calls Except in Defined Interval</i> option, enter the desired interval in this text box in seconds.	1 through 7200
Service Level Percentage	This setting allows you to specify the service-level objective (expressed as a percentage of calls).	
Туре	 This can be checked as Historical or Real time. Historical reports show data from the assigned start date to the assigned end date. Real-time reports show data from the assigned start date to the present, with the current interval refreshed with real-time data. Real-time reports for individual agents contain data for each time interval, with the last interval reflecting real-time data, if requested (subject to the refresh rate). When the interval switches over, the final data for the last time period is captured and shown as historical data and real-time data is reflected in the new time interval. 	Historical or Real time
Start Date	This is the date when you want the report to start. It can be set by typing in the text box or clicking the Calendar icon. This is compulsory. The oldest historical date depends on the interval selected: 180 days of half-hour interval statistics 365 days of hourly interval statistics 730 days of daily interval statistics	MMM DD, YYYY
Start Time	This is the time when you want the report to start. You can select the hour format (A.M., P.M., or Military time) from the <i>Hour Selection Type</i> . Time is applicable for hourly and minute intervals only.	1:00 am through 12:59 am, 1:00 pm through 12:59 pm, or 0:00 through 23:59



Input Field	Description	Allowed Value
End Date	This is the date when you want the report to end. It can be set by typing in the text box or clicking the Calendar icon. This is required when a Historical report is selected.	MMM DD, YYYY
End Time	This is the time when you want the report to end. You can select the hour format (A.M., P.M., or Military time) from the <i>Hour Selection Type</i> . Time is applicable for hourly and minute intervals only. This is required when a Historical report is selected.	1:00 am through 12:59 am, 1:00 pm through 12:59 pm, or 0:00 through 23:59
Sampling	This sampling period is only applicable to interval-based report templates and determines how the report information is presented. For example, an hourly report displays information for each hour of the report time frame.	15 minutes, 30 minutes, Hourly, Daily, Weekly, Monthly
Output Format	This allows you to specify in what format you would like the report output to be generated. If you select Hypertext Markup Language (HTML) or PDF, the report in displayed in the <i>Report</i> window. If you select Excel File Format (XLS), a file is created that you can save on your computer.	PDF, XLS, HTML

4) Click Run Report.

The results of the report are displayed in the *Report Output* area of the window. See the following section for an example of a report.

NOTE: Adobe Reader 10.01 has a setting *Enable Protected Mode at startup*, which is enabled by default. If you select the PDF report format and are using Adobe Reader 10.01 or later, (that has this setting), you need to disable the setting; otherwise, report results are not displayed.

To disable the protected mode in Adobe Reader, perform the following steps.

- 1) Close all opened Internet Explorer and Adobe Reader instances.
- 2) Open Adobe Reader.
- 3) From the menu bar, select *Edit* and then *Preferences*. The *Preferences* dialog box appears.
- 4) From the Categories menu on the left, select General.






Figure 133 Preferences – General

- 5) Uncheck Enable Protected Mode at startup.
- 6) Click OK.
- 7) Close Adobe Reader.

16.1.1.1 Report Results (Example)

Depending on the report type, the report results can contain the following elements: A pie chart, a bar chart, a table, a high-water marks table, and a line chart.

If you select HTML or PDF report format when requesting a report, the report is displayed in the *Report* window. If you select XLS, a file is created that you can save on your computer.

This section provides an example of a report: Abandoned Calls Report. For more information on the reports available in Call Center, see the *BroadWorks Call Center Reports Guide*.

The results of the Abandoned Calls Report are presented in a bar chart and table.






Figure 134 Abandoned Calls Report - Bar Chart




Figure 135 Abandoned Calls Report – Table (Fragment)



16.1.2 Schedule Report

To schedule reports, your company (group or enterprise) must have Enhanced Reporting enabled. For more information, see your administrator.

To schedule a report:

1) Click the **Reporting** link at the top right-hand side of the main window. A *Report* window appears.




Figure 136 Report Window - Report List

2) Select a report template from the drop-down list. The page displays the input parameters for the report.






Figure 137 Scheduling Report (Abandoned Call Report)

- 3) For Type, select Scheduled.
- 4) Provide the name and the description of the report.



- 5) Specify the recurrence pattern of the report. From the *Recurs* drop-down list, select one of the following options: *Never*, *Daily*, *Weekly*, *Monthly*, or *Yearly*. *Never* signifies that this is a one-time report.
 - If you selected Daily, enter the frequency of recurrence in days.



Figure 138 Scheduled Report - Daily Recurrence Pattern

 If you selected Weekly, enter the frequency of occurrence in weeks and select the day of the week when you want the report to be generated.




Figure 139 Scheduled Report – Weekly Recurrence Pattern

- If you selected *Monthly*, enter the frequency of occurrence in months and specify the day when you want the report to be generated. Select one of the following options:
 - To schedule the report on a specific day of the month, for example, the twenty-seventh, check Day <X> of the month and enter the day.
 - To schedule the report on a specific day of the week within the month, for example the second Monday of the month, check *The <X> <Day of week>* of the month and select *X* and *Day of week* from the drop-down lists.



Figure 140 Scheduled Report – Monthly Recurrence Pattern

- If you selected Yearly, specify the frequency of occurrence in years, for example every two years, and specify the day for the recurrence of the report. Select one of the following options:
 - To schedule the report on a specific day of the year, check Day <X> of <Month> and select the day and the month.
 - To schedule the report on a specific day of the week and month, for example, the first Sunday of January, check The <X> <Day of week> of <Month> and select X, Day of week, and Month from the drop-down lists.






Figure 141 Scheduled Report – Yearly Recurrence Pattern

- 6) Specify when the report should run.
 - For a nonrecurrent report, specify the actual date and time to generate the report.



Figure 142 Report Time for Nonrecurrent Report

 For a recurrent report, specify when the report should be generated for the first time.



Figure 143 Report Time for Recurrent Report

NOTE: The start date and run time (and for weekly reports the day of the week) determine when the report is generated for the first time. The subsequent times are determined by the recurrence pattern and range.

- 7) For a recurrent report, specify when the reporting should end. For *Recurrence Range*, select from the following options:
 - Never
 - After <X> occurrences, and enter the number of occurrences
 - Date, and select a date from the calendar



Figure 144 Scheduled Report – Recurrence Range



- 8) Specify the report time frame, that is, the period for which you are requesting the report.
 - For a nonrecurrent report, enter the actual dates and times.




Figure 145 Report Timeframe for Nonrecurrent Report

 For a recurrent report, select the time frame relative to the report generation time, for example, the previous month, previous five days, and so on.



Figure 146 Report Timeframe for Recurrent Report

NOTE: A report time frame always has a beginning date and time and an end date and time. For a recurring report, the relative time frame is converted to the actual dates and times at the moment that the report is run.

The actual time frame always starts at the top of the hour, day, week, month, or year and is based on the selected time zone and day of the week. For example, if a report is scheduled to run every day at 5:45 P.M. for the previous two hours, then the actual time frame of the report is from 3:00 P.M. to 5:00 P.M. of the day when the report is run

- 9) Specify the sampling frequency. From the *Sampling* drop-down list, select a frequency.
- 10) Specify the output format of the report. From the *Output Format* drop-down list, select a format, for example, PDF.



Figure 147 Report Sampling and Output Format

- 11) Enter the e-mail addresses of the recipients of the report.
- 12) Enter the remaining parameters, as required. For the description of the remaining parameters, see section 16.1.1 Run Report.
- 13) Click Schedule Report.

The report is scheduled. It is run at the specified times and sent to the recipients configured in the report schedule.



16.1.3 Manage Scheduled Reports

You can list, modify, and delete scheduled reports.

To manage scheduled reports:

- 1) Click the **Reporting** link at the top right-hand side of the main window. A *Report* window appears.
- 2) From the drop-down list, select *Scheduled Reports*. A *Scheduled Reports* dialog box appears, listing the reports that you have scheduled.




Figure 148 Scheduled Reports Dialog Box

- 3) To edit a report, click the **Load** button in the row for the report, and modify the report as required.
- 4) To delete a report, click the **Delete** button in the row for the report.



17 Configure Call Center

You use the Settings page, accessed via the Settings link at the top right-hand side of the main page to configure various aspects of the Call Center application.

To return to the main interface, click the **Back To Application** link.

NOTE: Do **not** use the internet browser's Back button to return to the main interface.

This section provides information about the options that you can use to configure Call Center.

- Settings General
- Settings Application
- Settings Services
- Settings Plug-ins
- Settings Messaging
- Settings Report
- Settings About

NOTE: Depending on your system configuration, some settings may not be available.



17.1 Settings - General

You use the General tab to configure miscellaneous settings that improve the usability of Call Center.




Figure 149 Settings – General

The following subsections describe the settings that can be configured on this page.

17.1.1 Account

You use this area to change your BroadWorks password.

Call Center shares logon credentials with BroadWorks. So when you change your password in Call Center, remember to use this new password when accessing your web portal.

NOTE: The password you enter must meet the password requirements set on BroadWorks.

To change your password:

 Click the Change Password link. The section expands, allowing you to change your password.






Figure 150 Account - Change Password

2) Enter your current and new password and click **Change Password**.

Note that the Passt button does not reset your password. It only clears the

Note that the *Reset* button does not reset your password. It only clears the input boxes.

17.1.2 Hotel/Flexible Seating Host

This setting allows you to configure the Hoteling Host or Flexible Seating Host, which is required when you use Call Center from a hot desk/device. This way you do not need to enter this information every time you sign in to Call Center if you use the same Hoteling or Flexible Seating device.

In the text box, enter the user name of the Hoteling Host or Flexible Seating Host that corresponds to the desk/device you are using, for example, "station 224@acme.com".

17.1.3 Language

The language settings allow you select the language of the Call Center user interface.

- The drop-down list lists the languages available in your edition of Call Center. To change the language, select a new language from the list.
- Synchronize language to my profile This box, when checked, synchronizes the Call Center language with your BroadWorks profile and ignores the language selection on this page.

17.1.4 Screen Pop

You use the screen pop settings to configure the URL that may be launched on incoming calls.

- Enter URL This text box allows you to enter the URL address of the web page that Call Center opens using the default browser when you click the Web Pop URL button in the Call Notification pop-up window.
- Auto pop for incoming calls When this option is checked, Call Center launches the Web Pop URL without your having to click the Web Pop URL button in the Call Notification pop-up window for each incoming call.

BroadSoft Professional Services is available to design web applications that can interface with different databases.

The URL can point to any URL address, but typically points to a web application that parses optional call parameters and passes them to a Customer Relationship Management (CRM) application or other database. For example:

http://www.mysite.com/webapp.php?remoteNumber=__REMOTE_PHONE__&sp=__S ERVICE_PROVIDER__



This URL passes the incoming calling number and the service provider ID to the web application at www.mysite.com. The web application formats the data for the applicable database and launches the web page on your PC.

There are a number of optional parameters that the client can pass to the browser. The following list summarizes these parameters:

- __USER__: The user's BroadWorks ID (Note that in this case the "user" is the BroadWorks subscriber.)
- __FIRST__: The first name of the user
- LAST : The last name of the user
- EMAIL : The e-mail address of the user
- __GROUP__: The name of the BroadWorks group to which the user belongs
- __SERVICE_PROVIDER__: The name of the BroadWorks service provider to which the user belongs
- __PHONE__: The phone number of the user
- __REMOTE_PHONE__: The phone number of the remote party
- __REMOTE_NAME__: The name of the remote party (when available)
- __CALL_TYPE__: "Incoming", "Outgoing", or "Alerting"
- __DNIS_NAME__: The name of the DNIS on which the call was received
- DNIS PHONE : The phone number of the DNIS on which the call was received
- __REDIRECTED_NAME_1__, __REDIRECTED_NAME_2__, and so on: The name of a party to whom the call was redirected prior to being delivered to you, from the most recent to the least recent
- __REDIRECTED_PHONE_1__, __REDIRECTED_PHONE_1__, and so on: The phone number of a party to whom the call was redirected prior to being delivered to you, from the most recent to the least recent
- __REDIRECTED_USERID_1__, __REDIRECTED_USERID_1__, and so on: The
 user ID of a party to whom the call was redirected prior to being delivered to you, from
 the most recent to the least recent

NOTE: The maximum number of redirections that can be displayed on a *Web Pop URL* page is configured by your administrator.

17.1.5 Date Format

This setting allows you to select the format for displaying dates in reports. The format is used for all dates that are included in generated reports. The possible options are:

- MM/DD/YYYY
- DD/MM/YYYY

17.1.6 Time Format

This setting allows you to select the format for displaying time in reports. It is used for all times that are included in generated reports. The selected time format is also used to display the time in the chat logs. The possible options are:



- AM/PM
- 24 hours

Note that this setting does not impact the format in which event duration is reported in generated reports. It is always *DD:HH:MM:SS*.

17.1.7 Workspace

Call Center allows you to customize elements of your workspace, such as the size and placement of windows on the desktop. The system remembers the setup between sessions.

The following elements can be customized:

- The size and position of the web browser window in which the main interface is displayed
- The size of the panes (Call Console, Contacts, and Queued Calls)
- The size and position of the Dashboard window
- The size and position of any Report window

NOTE 1: This functionality does not work in Internet Explorer, due to a technical limitation of Internet Explorer. Moreover, Firefox 7 and later does not provide a standard API to re-size a window without opening a new window. Therefore, saving workspace settings for the main application window size does not work in Firefox 7 and or later.

NOTE 2: The browser window running Call Center should be at least 1024 x 768 pixels in size.

NOTE 3: When a window is vertically resized, the panes do not always resize to fill the window. To resize a window, drag the window from the bottom right-hand corner or collapse and then expand the panes after resizing to adjust them to the window.

- Save Workspace This button, when clicked, saves the current workspace.
- Load Workspace This button, when clicked, arranges your workspace according to the last saved configuration.
- Restore To Default This button, when clicked, restores the workspace to the system default configuration.
- Always save workspace on signout When you sign out from the client, Call Center asks you whether you want to save your current workspace. To save your workspace automatically when signing out, without being asked, check the Always save workspace on signout box.

To customize your workspace:

- 1) Arrange the windows the way you like.
- Click the Save Workspace button to save the current configuration. To restore the system default, click Restore To Default.
- At any time to return to the last saved configuration, click the Load Workspace button.



17.2 Settings - Application

You use the Application tab to configure your application settings. The settings are different for agents and supervisors. They are described in the following subsections.




Figure 151 Settings – Application (Agent)

17.2.1 Queue Memberships (Agent)

These settings allow you to select the call center queues you wish to join. The table also displays your skill level in each queue (for more information, see section 19.2 Agent Skill Levels (Premium Call Centers).

- 1) To join a call center queue, select the check box on the line for the call center.
- 2) To join all queues, select the check box in the header.

NOTE: If you are not allowed to join/leave a queue, the line for the queue is dimmed and you can only view your join status in the queue. To change your join status in a queue, if you are not allowed to do it yourself, contact your administrator.

17.2.2 Agent Policies (Agent)

You use agent policies settings to specify your post sign-in ACD state, post call ACD state, wrap-up timer, and outbound CLID:

 Post Sign-In ACD State – To configure your post sign-in ACD state, select a state from the Sign-In State drop-down list. Your ACD state is automatically set to the selected state when you sign in to Call Center.

If you selected *Unavailable* and unavailable codes are enabled for your organization, select an unavailable code from the drop-down menu.



- Post Call ACD State To configure your post call ACD state, that is your ACD state upon completion of a call, select a state from the Post Call State list.
 - If you selected *Unavailable* and unavailable codes are enabled for your organization, select an unavailable code from the drop-down menu.
 - In most cases, when you select *Wrap-Up*, you must also configure your wrap-up timer.
- Set Wrap-Up Timer to To set your post call wrap-up timer, check the Set Wrap-Up Timer to <mm:ss> for queues without a policy box and enter the time in minutes and seconds. Your ACD state automatically changes from Wrap-Up to Available after the specified period.

NOTE: Your post call wrap-up timer setting may be overridden if your administrator sets the timer to a smaller value on BroadWorks.

- Outgoing calls as call center Check this box to display a call center CLID instead of your phone number when you make a call.
- Outbound Caller ID If you checked Make outgoing calls as call center, select the number to use from the drop-down menu.

17.2.3 Barge-In & Monitor (Supervisor)

The following options only apply if you have the Directed Call Pickup with Barge-in and/or Call Center Monitoring services assigned. If the Call Center Monitoring service is not assigned, then the *Monitor* option is not visible.




Figure 152 Settings – Application (Supervisor)

Use warning tone when:

- Barging In When this option is set, the agent hears a warning tone when you barge in on their call.
- Monitoring When this option is checked, the agent hears a warning tone when you start silently monitoring their call.



17.3 Settings - Services

You use the Services tab to configure various services assigned to you by your administrator on BroadWorks, which are integrated with Call Center. These settings are only available if you have been assigned such services. For more information, see your administrator.

The services are grouped into two categories: Active and Inactive.




Figure 153 Settings – Services

The services that you can configure (if you have been assigned the services) are:

- Do Not Disturb When you activate this service, you are not available to take calls, and all your calls are automatically sent to your voice mail.
- Call Forwarding Always When you activate this service, you must provide the phone number to forward your calls to. When the service is active, all your calls are forwarded to the specified number.

To activate a service:

- 1) Select the service and check the *Is Active* box. The service is moved from the *Inactive* to *Active* category.
- If you enabled the Call Forwarding Always service, in the Forward To box that appears, enter the number to forward your calls to.
- 3) To generate a ring splash for incoming calls, check the *RingSplash* option.
- To save your changes, click Save.



17.4 Settings - Plug-ins

You use the Plugins tab to configure the plug-in software used by Call Center to provide functionality such call notification, program shortcuts, and call log.




Figure 154 Settings - Plugins

17.4.1 Notification

These options control when and how call notifications are displayed. The options you can set are as follows:

 Focus window for incoming calls – When this option is checked and the browser window that is running Call Center is minimized, Call Center automatically restores the window on incoming calls.

This does not work in Firefox. In Internet Explorer, you must have only one tab open in the web browser running Call Center.



Show notification for calls – When this option is checked, Call Center displays the Call Notification pop-up window on top of other applications' windows when you receive a call. When you check this box, you need to select an option from the drop-down list to specify the condition under which notifications are displayed.

This does not work if other tabs are open in the same web browser window as Call Center. In addition, if calls come within eight seconds of each other, the *Call Notification* pop-up window appears only for the first call of that series.

17.4.2 Microsoft Outlook

The Microsoft Outlook options control Outlook integration with Call Center. They are only visible if Outlook integration is enabled in Call Center.

The options you can set are as follows:

- Enable/Disable Outlook Integration This determines whether Call Center integrates with Outlook to provide you with access to your Outlook contacts. If Outlook integration is disabled, the corresponding desktop plug-in software components are not downloaded from BroadWorks.
- Retrieve contacts from This option allows you to specify where to look for your Outlook contacts.
- Use Outlook contacts as preferred CLID lookup When this option is checked, Call Center uses Outlook to try to identify a caller, when the caller ID is unknown.

NOTE: The Outlook Integration feature provides the following functionality: CLID lookup, saving vCards, and accessing and searching Outlook contacts. When using Microsoft Outlook 2010 or 2013 (32- or 64-bit edition), Outlook must be running before Call Center is launched for these functions to work.

17.4.3 LDAP v3

LDAP settings allow you integrate an LDAP directory with Call Center. These options are only visible if LDAP integration is enabled in Call Center. If you do not know the appropriate settings, contact your system administrator.

Make sure you have correctly imported a valid certificate in the Java Keystore (JKS) with the keytool.

To import a certificate:

- 1) Click **Start** and then select *Run...*
- 2) Type "cmd" and click **OK**.
- 3) Type "<Java Runtime Path>\bin\keytool -import -alias <aliasname> -file <path><certificate file name> -keystore %JAVA_HOME%\jre\lib\security\cacerts".

To verify the certificate:

- 1) Click **Start** and select *Run...*
- 2) Type "cmd" and click OK.
- 3) Type "<Java Runtime Path>\bin\keytool -printcert -file <path><certificate file name>".



The LDAP directory options are as follows:

- Enable/Disable LDAP Integration This determines whether Call Center provides LDAP directory lookup services. Clicking the **Enable LDAP Integration** button enables the controls for LDAP settings.
- LDAP Hostname This is the network address of the LDAP server.
- LDAP Port This is the port number for the LDAP server. This is compulsory and can be obtained from your system administrator.
- Search Base:
 - The text box determines the location in the LDAP server tree that Call Center looks in when executing a search.
 - The check box, when checked, searches all sub-trees within the search base until the specifications are found.
- Encrypt Connection This option determines whether Call Center uses encryption when connecting to the LDAP server. Note that if encryption is enabled, you may have to use of a different port.
- ("cn=__Search__Text") This option specifies an additional search filter to apply to all directory searches. For example, to include the search criteria in the filter you must include (cn=*__SEARCH_TEXT__*). Alternatively, in another example, (telephoneNumber=*) restricts search results to users who have a telephone number assigned.
- Attribute Mapping This table controls the way that Call Center maps attributes
 returned from the directory server to columns displayed on the list of search results.
 - In each row of the table, enter an LDAP attribute in the *Remote Attribute* column. In the *Local Attribute* column, enter a corresponding local attribute. Typical Remote Attribute values are "cn", "sn", "telephoneNumber", "mobile", "homePhone", and "mail".
- Authentication Required When this box is checked, Call Center must provide a user name and password to the directory server to conduct searches.
- DN This is the user name Call Center uses when connecting to the LDAP server when Authentication Required is checked.
- Password This is the password that corresponds to the authentication DN.

17.4.4 Program Shortcuts

You use the program shortcuts settings to create call center shortcuts on your desktop for convenient access to Call Center.

The program shortcuts plug-in allows for the creation of desktop shortcuts on a Windows platform, which when clicked, launches the applications in your default web browser.

- Add Shortcut This button, when clicked, creates a call center shortcut on your desktop.
- Remove Shortcut This button, when clicked, removes the previously created Call Center shortcut. If you did not create a shortcut using the Add Shortcut button, the Remove Shortcut button has no effect.



17.4.5 Call Event Log

This plug-in software provides the ability to store call event statistics content locally on your computer.

- Enable/Disable Call Event Log Integration This double-action button allows you to enable or disable call log archives on your computer.
- Rotate Log This parameter allows you to specify the frequency with which the call log is rotated. You select the frequency from the drop-down list.
- Open Log Location Click this link to go to the place on your computer where the log is stored.

The log is saved at the desired interval as a comma-separated value (CSV) file in the following path:

<Drive>:\Documents and Settings\<Windows_Username>\Application
Data\BroadSoft\BW Call Center\profiles\<BW_User_ID>\statistics

where:

- Drive is the drive letter where your profile is stored (typically C)
- Windows_Username is your Windows user name
- BW_User_ID is your BroadWorks user ID

The following events are captured based on activity that occurs on the Agent/Supervisor client (irrespective of ACD or direct inbound or outbound calls).

Statistic	Description	Allowed Values	Example Value
BroadWorks User ID	BroadWorks user ID	String	jsmith@abc.net
Call Center ID	Call Center ID for inbound ACD calls only	String, null	ABCSales
Availability	Agent's joined state	Joined, Not Joined, null	Joined
ACD State	Agent's ACD state	Sign-On, Available, Unavailable, Wrap- Up, Sign-Out, null	Null
Call ID	ID of the call	String, null	192.168.1.5:1
Call State	State of the call	Idle, Incoming, Outgoing, Active, Held, Remote Held, Detached, Released, null	Incoming
Personality	The personality of the call. It indicates whether the user originated this call or whether the call was placed to the user.	Integer (0, 1, 2): • 0 = BroadWorks Originator • 1 = Originator • 2 = Terminator	0
Remote Name	External caller name	String or null	Null
Remote Number	External caller number	String or null	5555551234
Last Redirected Name	Last redirected name	String or null	Jane Doe



Statistic	Description	Allowed Values	Example Value
Last Redirected Number	Last redirected number	String or null	Null
Time	Date stamp of record	Long Date/Time Format	2008-04-03 12:08:17.859

NOTE: Each row in the log file records a *single* event change and as such, columns like *Availability*, *ACD State*, and *Call State* may contain null values since an alternate column value caused the event change. For example, *Wrap-Up* is stored in the ACD State while the Call State (and other columns) store null.



17.5 Settings - Messaging

The Messaging tab allows you to configure various messaging options for Call Center. Currently, e-mail messaging and instant messaging are supported.




Figure 155 Settings – Messaging

17.5.1 E-mail Messaging

These options allow you to specify the mail client you use for sending e-mail messages.

From the drop-down list, select the mail client to use for e-mails.

If you selected the custom Simple Mail Transfer Protocol (SMTP) option, you also need to configure the following options:

- Display Name This is the name that is displayed in the From field.
- Reply-to Address This is the address where reply messages can be sent.
- Default Subject This is the subject that appears when you generate an e-mail message in Call Center.
- SMTP Host This is the IP address of the SMTP host.
- *SMTP Port* This is the port of the SMTP host.
- Outgoing SMTP Server requires Authentication When this option is set, authentication is required to send e-mails.
- Username This is the name you must enter to authenticate yourself.
- Password This is the password part of your authentication credentials.
- Mail Type This is the type of mail to use.
- *Mail Template* This is the mail template to use.

17.5.2 Instant Messaging and Presence

Check this option if you want the *Chat* windows that appear when you receive an instant message to appear in minimized format.



17.6 Settings – Report

You use the *Report* tab to configure values to be used as default input parameters for generating reports. If you do not provide any values, system defaults are used. You can change these values as required when generating reports.




Figure 156 Settings - Report

17.6.1 Default Thresholds

These settings allow you to configure the thresholds that are used by default when you generate reports that require you to provide thresholds. This is useful, if you often use the same threshold values. You can always change a default value, when required.

- Call Completion This setting is used to count the number of ACD calls an agent has completed within a service level during the specified interval. The Call Completion service level can be set to "1" through "7200" seconds.
- Short Duration Call This setting is used to count the number of ACD short duration calls completed by an agent during an interval. You can set the maximum length of a short duration call to "1" through "7200" seconds.

17.6.2 Default Start of the Week

The following setting allows you to configure the day of the week to start reports.

■ Default Start Day of Week – This setting applies to interval-based reports, when the selected sampling period is "Weekly". It can be set to any day of the week.



17.6.3 Default Service-level Calculations

The following settings allow you to configure default settings used to make service-level calculations.

- Include Overflow Time Transferred Calls Check this box to include calls transferred due to time overflow in service-level calculations.
- Include All Other Transfers Check this box to include calls transferred for other reasons that overflow in service-level calculations.
- Exclude Abandoned Calls Check this box to exclude all abandoned calls from service-level calculations.
- Include all abandoned calls Check this box to include all abandoned calls in service-level calculations.
- Include all abandoned calls except before entrance completes Check this box to include calls abandoned after the entrance message has finished playing in servicelevel calculations.
- Include Abandoned Calls except in Defined Interval Check this box to include calls abandoned after the time specified by the interval for abandoned calls parameter in service-level calculations.
- Defined Interval for Abandoned Calls If you checked Include Abandoned Calls except in Defined Interval, enter the desired interval in this text box in seconds. The Defined Interval for Abandoned Calls can be set to "1" through "7200" seconds.

17.7 Settings – About

You use the About tab to view the information about Call Center.




Figure 157 Settings - About

The following information is provided on this page:

Version – This is the name and software version of BroadWorks Call Center client.



- *Profile* This is the Call Center client profile used.
- *Disclaimer* This is the Call Center copyright information.
- *Diagnostics* This allows you to access the Diagnostic Tool, available in some versions of Call Center. If the tool is not available, this information does not appear. For more information about the tool, see *Appendix B: Diagnostic Tool*.



18 Configure Web Browser

18.1 Internet Explorer Settings for Full Screen Mode

For the supported versions of Internet Explorer, see the *BroadWorks Hosted Thin Call Center Agent/Supervisor Configuration and Administration Guide.*

Internet Explorer needs to be configured as follows to enable the Full Screen link in Call Center. Otherwise, the link has no effect; Call Center is not displayed in full-screen mode when the Full Screen link is clicked and no error message is displayed to the user.

- 1) On the Internet Explorer *Menu* bar, select the *Tools* menu and then click **Internet Options**.
- 2) In the *Internet Options* dialog box, click the **Security** tab and then click the **Custom level...** button.




Figure 158 Security Settings – Internet Zone Dialog Box

- 3) In the Security Settings Internet Zone dialog box, scroll down to Initialize and script ActiveX controls not marked as safe for scripting setting in the ActiveX controls and plug-ins section.
- 4) Select Enable or Prompt.
- 5) Restart Internet Explorer.



18.2 Firefox Settings Quick Link Navigation

The following settings are required in Firefox for quick link navigation to work. If these settings are not configured, Call Center does not change focus from the Dashboard to the main application window when the user clicks on a quick link.

- 1) On the Firefox *Menu* bar, select the *Tool*s menu, and then click **Options**.
- 2) In the *Options* dialog box, click the **Content** tab.
- 3) Click the **Advanced** button, to the right of the to *Enable JavaScript* check box.




Figure 159 Firefox - Content Tab

 In the Advanced JavaScript Settings dialog box, check the Raise or lower windows box.




Figure 160 Firefox - Window Focus Settings

5) Restart Firefox.



19 Appendix A: Glossary and Definitions

19.1 ACD States

ACD states specify the agent's availability to take calls. The possible call states are those listed in the following table. An agent can be in one of the ACD states.

ACD State	Icon	Description
Available	&	Agent is available to receive ACD calls. (Agent can also receive direct calls.) This is the primary ACD state of an agent during the workday. It indicates that the agent is at their workstation and either ready to take a call or on an active call. ACD calls may be delivered to an agent who is in an <i>Available</i> state. BroadWorks uses both the ACD state and the phone state of the agent to determine whether to route a call to the agent. By default, agents receive calls when they are available and their phone is <i>Idle</i> . However, this behavior can be overridden if Call Waiting on agents is enabled for the call center, which allows for new calls when the agent is available and on an active call.
Unavailable	&	Agent is unavailable to receive ACD calls. (Agent can still receive direct calls.) The <i>Unavailable</i> state should be used when the agent is away from their workstation and not available to take calls. ACD calls are not delivered to agents in an <i>Unavailable</i> state. This state should be used when the agent is at lunch, on a break, in a meeting, or engaged in some other activity while they are at work, but unavailable to take calls.
Wrap-Up	8	Agent is performing post call work. This state is designed to allow the agent to complete paperwork or other post call procedures associated with the last call. Calls may be delivered to agents in <i>Wrap-Up</i> state depending on the call center configuration. By default, calls are not routed to agents in <i>Wrap-Up</i> state, except when the call center is configured to enable calls to agents in the <i>Wrap-Up</i> state.
Sign-In		The <i>Sign-In</i> state is equivalent to a "clock in", which means that the agent is at their work location but not yet ready to accept incoming calls. Calls are not delivered to the agent in this state. Sign-In is a transitional state and agents do not remain in this state; rather they transition to their post sign-in state. It is recommended that agents only be in this state between the time they arrive at work and the time they become available to accept calls.
Sign-Out		The Sign-Out state is equivalent to a "clock out", which means that the agent's workday or shift is completed and they are leaving. Calls are not delivered to the agent in this state. It is recommended not to use this state when agents leave for lunch or breaks during the day. The Unavailable state should be used for that.

In Call Center, an agent can only set their ACD state to "Available", "Unavailable", or "Wrap-Up". A supervisor can set the ACD state of an agent to "Available", Unavailable", Wrap-Up", or Sign-Out".

The Sign-In state can only be assigned to an agent through the web portal.



19.2 Agent Skill Levels (Premium Call Centers)

Agent skill levels are used to rate the ability of an agent to handle calls in call centers with skill-based routing.

- An agent skill level is an integer between 1 and 20, where 1 indicates the highest skill level.
- A skill level is assigned to an agent for each call center with skill-based routing to which the agent is assigned.
- A skill level is shown as "N/A" for Standard call centers and for call centers with priority-based routing.

19.3 Phone States

Phone states show the state of the monitored agent's telephone line or the supervisor's telephone line.

For supervisors, the phone states are displayed as follows:

Phone State	Icon	Description
Idle		Supervisor's phone is on-hook, which means the supervisor is not on a call.
Busy		Supervisor's phone is off-hook, which means that the supervisor is on a call.
Ringing		Supervisor's phone is in <i>alerting</i> state; a call is currently being delivered to the supervisor.
Do Not Disturb		Supervisor has enabled the Do Not Disturb service.
Private	A	Supervisor has enabled phone status privacy. NOTE: This terminates monitoring of the supervisor's phone state for the current login session. To be able to monitor their phone state again, you must sign out and then sign in after the supervisor has disabled their phone state privacy.
Call Forwarding Always	••	Supervisor has enabled the Call Forwarding Always service.
Unknown		Supervisor is currently not monitored.

For agents, the phone states are combined with their ACD states and are displayed as follows:

Phone State	ACD State	Icon	Description
Idle	Available		Agent's phone is on-hook and the agent is available to take ACD calls.
Ringing	Available	<u></u>	Agent's phone is ringing and the agent is available to take the call.
Any	Unavailable, Sign-In, Sign- Out		Agent is not available to take ACD calls.
Idle, Ringing	Wrap-Up		Agent is performing post call work. They may or may not be available to take calls.



Phone State	ACD State	lcon	Description
Busy	Available, Wrap-Up		Agent's phone is off-hook, which means that the agent is on a call. Calls may be delivered to agents depending on their call waiting settings and the call center's call waiting and wrap-up settings.
Do Not Disturb	Any		Agent has enabled the Do Not Disturb service. ACD calls are not delivered to an agent in the Do Not Disturb call state. This state is not recommended for Call Center agents. Agents should use the Unavailable ACD state when they need to block new incoming calls temporarily.
Call Forwarding Always	Any	••	Agent has enabled the Call Forwarding Always service.
Private	Any	A	Agent has enabled phone status privacy. NOTE: This terminates monitoring of the agent's phone state for the current login session. To be able to monitor their phone state again, you must sign out and then sign in after the agent has disabled their phone state privacy.
Unknown	Any		Agent is currently not monitored.

19.4 Unified Instant Messaging Presence States

Unified instant messaging presence states indicate you or your contacts' availability to communicate using client applications such as Hosted Thin Call Center, Hosted Thin Receptionist, BTBC Desktop, or BCBT Mobile. The possible states are as follows:

• •	• '	•		
IM&P State	Icon	Description		
Subscribed Sta	Subscribed States			
Available	-	The contact is online, available on one or more devices, and not busy on any device.		
Busy	(The contact is online, but currently busy on one or more devices. Do not disturb.		
Away	4	The contact is connected but away from one or more devices and not busy on any device.		
Offline		The contact if offline on all devices. If you are offline, you do not receive any presence updates or instant messages. In addition, your Instant Message pane is empty and the presence state of your contacts in other <i>Contact</i> panels is set to "Offline".		
Unsubscribed States				
Pending Subscription	3	You sent a subscribe request to the contact, but it has not yet been accepted. Clicking the icon resends the request.		
Not subscribed	5	The contact has IM&P but you are not subscribed to monitor their state. The contact is not listed in the <i>Instant Message</i> directory. Clicking this icon sends a subscription request to the contact.		



19.5 Call States

Call states are the states that your current calls can be in. They are as follows:

Call State	Display Name	Display Icon	Call Personality	Call Actions
Ringing In (Local)	Incoming Local	-	Click To Dial	Answer, End
Ringing In (Remote)	Incoming	•	Terminator	Answer, Conference, End
Ringing Out, Outgoing	Outgoing	4	Originator	Conference, End
Active	Active		Any	Transfer, Hold, End, Conference
On Hold	Held		Any	Transfer, Resume, End, Conference
On Hold (Remote)	Held		Any	Transfer, Hold, End, Conference
Active (In Conference)	Active	A	Conference	Transfer, Hold, End
On Hold (In Conference)	Held	Ai	Conference	Resume, Transfer, End
Ringing In (Recalled Call)	Call Recalled	→	Terminator	Answer, Conference, End

19.6 Call Types

This section defines different types of calls measured in call center statistics.

Name	Description
ACD Call	This is a call delivered to a call center pilot number that is directed to an agent via the ACD function.
Inbound Call	This is a direct call to an agent. Other calls treated as inbound calls include: Calls that a supervisor retrieves from a queue Calls that an agent receives due to a transfer from another agent (Note that they may have originated as ACD calls.)
Outbound Call	This is an outbound call made by an agent.
Held Call	This is an ACD call that was placed on hold by an agent. Each time an agent places a call on hold, it is counted as a held call.
Transferred Call	This is an ACD call that was transferred to another number. Transfers can be the result of manual transfers by agents, transfers to voice mail because the calls were timed out, and transfers by supervisors to alternate queues. NOTE: A timed-out call is a call that is transferred due to exceeding the maximum wait time in a queue.
Answered Call	This is an ACD call that was answered by an agent.



Name	Description
Abandoned Call	This is an ACD call that entered the queue, but the caller hung up before the call was answered or transferred.
Received Call	This is an ACD call that was received and either answered or abandoned. Overflowed calls are not included.
Overflowed Call	This is an ACD call that was received, but immediately transferred to another destination due to the queue's exceeding the configured maximum queue size or the configured maximum wait time.
Queued Call	This is an ACD call that is not immediately diverted using the Night Service, Holiday Service, Forced Forwarding, or Overflow, and goes to a queue to be distributed to an agent or to wait for an available agent.
Bounced Call	This is a call that has been transferred back to queue because it was not answered by an agent in the specified time.
Stranded Call	This is a call that is in a queue after all agents assigned to the queue have moved to the Sign-Out ACD state.



20 Appendix B: Diagnostic Tool

The Diagnostic Tool provides client-side performance measurements for the Call Center client to help troubleshoot client application performance problems. It should only be used when performance problems occur and with the assistance of a support person.

NOTE: The Diagnostic Tool is available in Release 20.0.30 or later, and only if enabled by the service provider.

20.1 Launching Diagnostic Tool

To start the Diagnostic Tool, go to the *Settings – About* page and click the **Run Client Diagnostics** link.




Figure 161 Settings – About (Launching Diagnostic Tool)

20.2 Diagnostic Tool GUI

The Diagnostic Tool runs in a separate browser window. Its user interface consists of six tabs: Session, Long Polling, Calls, Service, Monitoring, and Support. Each tab is described in a separate subsection.

20.2.1 Session Tab

The Session tab displays session information stored for the user on BroadWorks. It provides information about the logged user, connection, and subscriptions.

- The user information includes your name, user ID, phone number, extension, and the list of services assigned to you.
- The connection information includes the session ID for the current session, the channel ID for the OCI-C channel, and the address of the Xtended Services Platform the client is running on.



■ The subscription table shows all active subscriptions for the logged-in user and is updated in real-time.




Figure 162 Diagnostic Tool – Session Tab

20.2.2 Long Polling Tab

The Long Polling tab shows, in real-time, statistics on long polls performed by the client. The Polls table lists long polls and includes the request timestamp, response timestamp, status, and poll time of each long poll.

By default, the number of long polls retained in the Polls table is "10".

To change the number of displayed long polls, click the drop-down arrow in the *Polls* combo box, and select a new number from the drop-down list.

The *Data* column of the Polls table indicates whether the long poll contains data or not. If the icon in the *Data* column is a green icon, then the corresponding long poll contains data. Clicking on the row for the long poll displays detailed data in the Poll Details table at the bottom of the page.

The Poll Details table displays the feature data that is contained in the update as well as the event type and event ID that triggered the data update.

To clear the tab and start fresh captures of the long polls, click the **Clear** button.






Figure 163 Diagnostic Tool - Long Polling Tab

20.2.3 Calls Tab

The Calls tab shows call statistics for calls placed through the dialer. For each call, the following information is displayed: the called destination, the call ID of the outbound call, the time the number was dialed, the time the client received the incoming alerting call update, the client answer time (if the call was answered from the client), and the time the client received the outgoing call update.




Figure 164 Diagnostic Tool – Calls Tab



20.2.4 Service Tab

The Service tab measures the time for enabling/disabling the DND service from the client. It is only shown if you have the DND service assigned.

For each service action, the tool displays the command that was invoked (DND On or DND Off), the time the command was invoked from the client, the time the command response was received by the client, and the time difference in milliseconds between the request time and the response time.




Figure 165 Diagnostic Tool – Service Tab

20.2.5 Monitoring Tab

The Monitoring tab displays statistics on monitored agents (if you are a supervisor) or supervisors (if you are an agent). The *Target* column displays the user ID of the agents or supervisors being monitored.



Figure 166 Diagnostic Tool – Monitoring Tab



20.2.6 Support Tab

The Support tab is a textual representation of all data contained in the other tabs. The text in this tab should be copied and pasted into the body of the e-mail that you send to the technical support of your service provider.

The Email Support link in the upper right-hand corner of the Diagnostic Tool can be used to open the default e-mail client on your machine. If the "To" address is not preconfigured by the service provider, the support person should provide it to you.




Figure 167 Diagnostic Tool - Support Tab

20.3 Known Issues

If you are using the Chrome browser to run Call Center, and you click the Diagnostic Tool *Email Support* link, an untitled tab opens in the Call Center window, in addition to the new message window of your default e-mail application. The issue can occur if the Chrome browser attempts to process the request with a different mail protocol than the one defined on your computer.



21 Appendix C: Keyboard Shortcuts

When using keyboard shortcuts, make sure that the main interface window is in focus.

Key	Equivalent Mouse Action	Description
ESC	Click the Close button in a dialog box.	This closes the open dialog box.
ESC	Cancel the changes.	This exits the currently selected editable item, such as a text box.
1	Click the <i>Dialer</i> text box.	This places the cursor in the <i>Dialer</i> text box; it retains the currently selected item (if applicable). NOTE : In Internet Explorer 8, the "/" shortcut key does not always work. Pressing the key clears the default <i>Enter Number</i> text, but does not place the cursor in the input box.
?	Click the Search text box.	This places the cursor in the Search text box; it retains the currently selected item (if applicable).
ARROW DOWN	Click the scroll bar or the next item on a list.	This selects the next item in the Call Console or the Queued Calls pane.
ARROW UP	Click the scroll bar or the previous item in a list.	This selects the previous item in the <i>Call Console</i> or the <i>Queued Calls</i> pane.
PAGE DOWN	Scroll down one page.	This goes to the next page in the Call Console or the Queued Calls pane.
PAGE UP	Scroll up one page.	This goes to the previous page in the <i>Call Console</i> or the <i>Queued Calls</i> pane.
19	Select a call in the Call Console.	Pressing 1 selects the first call, pressing 2 selects the second call, and so on.
SPACEBAR	Click Answer on the selected incoming call in the <i>Call Console</i> .	This answers the selected incoming call or if no call is selected, the incoming call that has been waiting the longest. Pressing the SPACEBAR again answers the next longest waiting incoming call, which puts the previously answered call on hold.
<period></period>	Click End on the selected call in the <i>Call Console</i> .	This ends the selected call.
ENTER	Click Dial .	If the cursor is placed in the <i>Enter Number</i> text box in the <i>Dialer</i> , the entered digits are dialed.
ENTER	Click Search .	If the cursor is placed in the Search text box, a search is performed.
+	Click Transfer in the <i>Dialer</i> .	This transfers the selected call to the ad hoc number entered in the <i>Dialer</i> .
SHIFT+19	Select a ringing call and click Answer .	Pressing SHIFT+1 selects and answers the first ringing call, pressing SHIFT+2 selects and answers the second ringing call, and so on.
SHIFT+19	Select an active call and click Hold .	Pressing SHIFT+1 selects and places on hold the first active call, pressing SHIFT+2 selects and answers the second active call, and so on.
SHIFT+19	Select a held call and click Retrieve.	Pressing SHIFT+1 selects and retrieves the first held call, pressing SHIFT+2 selects and retrieves



Key	Equivalent Mouse Action	Description
S or s	Click the Settings link.	This goes from the main page to the Settings page.
B or b	Click the Back to Application link.	This goes back from the <i>Settings</i> page to the main page.
Rorr	Click the Call History button.	This opens the Call History dialog box.
H or h	Click the Help link.	This opens this guide in a PDF format.
D or d	Click the Dashboard link (Supervisor)	This opens the <i>Dashboard</i> or brings the <i>Dashboard</i> to the front if it is already open.
SHIFT+L or SHIFT+I	Click the Sign Out link.	This signs the user out of the application.
SHIFT+A	Select Available (Agent).	This sets the agent's ACD state to "Available".
SHIFT+U	Select <i>Unavailable</i> (Agent).	This sets the agent's ACD state to "Unavailable".
SHIFT+W	Select Wrap-Up (Agent).	This sets the agent's ACD state to "Wrap-Up".



Index

About Call Center, 159	Configuring, 144, 145
Accepting IM&P subscription requests, 97	Getting started, 28
ACD states	Launching, 28
Changing, 34, 113	Overview, 24
Listing, 111, 163	Setting up, 33
Actions on calls, 43	Signing in
	From hot desk, 30
Ad hoc numbers, dialing, 70	From web browser, 29
Adding	Supervisor, 26
Conference participants, 78	Call centers
Contacts	Agent membership, configuring, 149
IM&P, 95	Monitoring
Personal, 90	By agent, 105, 107
Speed dial, 92	By supervisor, 119
Users to chat sessions, 100	Ordering in agent's Dashboard, 108
Additional resources, 23	Real-time statistics about, 127
Agents	Showing in Queued Calls pane, 120
ACD states	Call Console, 40
Changing by, 34	Conference Call panel, 43
Changing for, 113	Current calls, 42
Listing, 111, 163	Dialer, 41
Answering calls for, 115	Header bar, 41
Barging in on, 115	Call Forwarding Always, configuring, 151
Call center membership, configuring, 149	Call history, 51
Calls, managing, 57	Deleting, 80
Dashboard, 105	Dialing from, 72
Directory, 47	Managing, 80
Joining queues	Viewing, 80
By agent, 149	Call Pickup, 115
Forced by supervisor, 110	Calling line ID, configuring, 69
Managing calls, 57 Monitoring by supervisor, 109	Calls
Password, changing, 33	Actions
Phone states, definition, 111, 164	Buttons, 54
Policies, configuring, 149	Permitted in call states, 43
Real-time statistics about, 128	Answering, 68
Selecting call centers to monitor, 107	Assigning disposition codes to, 63
Selecting information to display, 107	Auto answering, 68
Silently monitoring calls for, 114	Blind
Skill levels, 164	Escalating, 75
Viewing details on, 112	Transferring, 73
Answering calls, 68	Camping, 73
Assigning disposition codes, 63	Current, viewing, 60
Current call, 63	Dialing
Wrap-Up, 63	Ad hoc number, 70
	Contacts, 71
Auto answering calls, 68	History, from, 72
Barging in	Search, from, 71
Agent calls, on, 115	Dragging and dropping, 60
Enabling or disabling warning for, 150	Emergency escalating, 74
Blind	Ending, 69
Escalating calls, 75	Escalating, 74
Transferring calls, 73	Blind, 75
Busy Camp On, 73	Conference and handover, with, 76
Call Center application	Consultation, with, 76
Agent 25	Emergency, 74



Mid-conference, 76	Barging in and monitoring, 150
Event log, configuring, 155	Call Center application, 144
Generating trace, 65	Call event log, 155
Incoming, viewing, 62	E-mail messaging, 157
Making outbound, 69	Firefox, 162
Managing	Flexible Seating Host, 146
By agent, 57	General settings, 145
By supervisor, 116	Hoteling Host, 146
Opening URL for, 68	IM&P messaging, 157
Operations, quick reference, 58	Internet Explorer, 161
Placing on hold, 72	Language, 146
Queued	LDAP, 153
Moving to top of queue, 125	Messaging, 157
Reordering, 124	Notification of calls, 152
Received, placed, and missed, viewing, 51	Outlook, 153
Recording, 65	Plug-ins, 152
Redialing, 70	Policies, agent, 149
Resuming held, 72	Program shortcuts, 154
Saving vCard, 69	Queue membership, agent, 149
Security classification, assigning, 66	Reports default settings, 158
Silently monitoring	Date format, 147
For agents, 114	Service-level calculations, 159
Next in queue, 122	Start day of week, 158
States, 43, 166	Thresholds, 158
Trace, generating, 65	Time format, 147
Transferring, 73	Services, 151
Blind, 73	Web browser, 161
By supervisor only, 123, 124	Web Pop URL, 146
From Call Console to queue, 74	Workspace settings, 148
With consultation, 74	Consultation
Types, 166	Escalating calls with, 76
Viewing, 60	Transferring calls with, 74
Camping calls on busy contacts, 73	Contacts
Changing	Agents, 47
ACD states, 34	Calling, 71
IM&P presence, 34	Common, 46
Password, 33, 145	Custom, 48
Security classification of calls, 67	Details, viewing, 86
Chatting	Dialing, 71
Contacts, with, 94	Directories
Multiuser, 100	Overview, 44
One-on-one, 98	Viewing, 83, 86
Classification, security level of calls, 66	Display order, selecting, 87
Common directory, 46	E-mailing, 81
	Enterprise, 46
Conference Call panel, 43	Group, 46
Conferences	IM&P, 49
Ending, 79	Accepting subscription requests, 97
Escalating calls with, 76	Adding, 95
Holding, 79	Chatting with, 98
Leaving, 79	Subscribing to, 94
Managing, 77	Unsubscribing from, 96
Participants	Viewing presence of, 97
Adding, 78	Managing, 82
Ending, 79	Organizing, 88
Holding, 79	Outlook, 49
Resuming, 79	Pane, 44
Resuming, 79	Personal, 47
Starting, 78	Searching, 46, 89
Configuring	Sorting, 88
Agent policies, 149	Speed dial numbers, 48



Supervisors, 47	Contacts, 81
Controls	Emergency escalating calls to supervisor, 74
Action buttons, 54	Enabling
Call Center, 52	Call Forwarding Always, 35, 151
Current calls	Call Waiting, 35
Details, 42	Do Not Disturb, 35, 151
Viewing, 60	Forced Forwarding, 122
Custom directory panel, 48	Night Service Override, 122
Customer Originated Trace, 65	Ending
Dashboard	Calls, 69
Agent, 105	Conference participants, 79 Conferences, 79
Supervisor, 126	•
Date format in reports, configuring, 147	Enterprise directory, 46
Definitions, 163	Escalating calls, 74 Blind, 75
ACD states, 111, 163	Conference and handover, with, 76
Call states, 166	Consultation, with, 76
Call types, 166	Emergency, in, 74
IM&P states, 165 Phone states	Mid-conference, 76
Agents, 111, 164	Exploring workspace, 37
Supervisors, 104, 164	Flexible Seating Host, configuring, 146
Deleting	Forced Forwarding, enabling, 122
Calls from history, 80	General settings, configuring, 145
Contacts	Generating
Personal, 91	Call trace, 65
Speed dial, 93	Reports, 131, 132
Diagnostic Tool, 168	Global Message Area, 39
Dialer, 41	Glossary, 163
Dialing	Group directory, 46
Ad hoc number, 70	Grouping, queued calls, 121
Contacts, 71	Handover, escalating calls with, 76
From chat window, 100	Header bar, 41
History, from, 72	Help, getting, 32
Search, from, 71	
Directories Agents, 47	History of calls, 51
Custom, 48	Holding Calls, 72
Displaying below Call Console, 84	Conference participants, 79
Enterprise, 46	Conferences, 79
Group, 46	Hot desk sign in, 30
Instant Message, 49	Hoteling host, configuring, 146
Ordering, 88	IM&P
Outlook, 49	Accepting subscription requests, 97
Panel, 50 Personal, 47, 90	Chatting, 98
Queues, 48	Multiuser, 100
Searching, 46, 89	One-on-one, 98
Showing or hiding, 83, 86	Configuring chat windows, 101, 157
Speed Dial, 48, 92	Contacts
Supervisors, 47	Adding, 95
Viewing, 83, 86	Chatting with, 98 Directory, 49
Disabling services, 35, 122, 151, See also Enabling	Editing, 96
Displaying directories below Call Console, 84	Presence, 94
Disposition codes, assigning to calls, 63	Subscribing to, 94
Do Not Disturb, enabling and disabling, 151	Unsubscribing from, 96
Dragging and dropping calls, 60	Presence
E-mailing	Changing, 34
Configuring, 157	States, listing, 165
	Viewing for contacts, 97



Incoming calls, viewing details, 62	Agents, 47
Instant messaging. See IM&P	Conference Call, 43
Joining queues, 149	Custom, 48
- •	Directories, 50
Keyboard shortcuts, 173	Enterprise, 46
Language, configuring, 146	Group, 46
Launching Call Center, 28	Instant Message, 49
LDAP, configuring, 153	Outlook, 49
	Personal, 47
Leaving conferences, 79	Queues, 48
Logged user information, 39	Search, 46
Logo pane, 39	Speed Dial, 48
Global Message Area, 39	Supervisors, 47
Links, 39	Panes
Logged user information, 39	
Making outbound calls, 69	Call Console, 40
Managing	Contacts, 44
Agents, 109	Queued Calls, 116
Call history, 80	Parking calls on busy contacts, 73
Calls, 57	Participants, conference
Chat sessions, 101	Adding, 78
,	Ending call for, 79
Conference calls, 77 Contacts, 82	Holding, 79
	Leaving, 79
IM&P, 94	Resuming held, 79
Ordering, 88	Password, changing, 33, 145
Personal, 90	Pausing call recording, 66
Searching, 89	_
Setting visibility, 83	Personal contacts
Speed dial numbers, 92	Adding, 90
Queued calls, 116	Deleting, 91
Promoting, 123	Directory, 47
Reordering, 124, 125	Managing, 90
Retrieving, 123	Phone states
Transferring, 123, 124	Definition
Speed dial numbers, 92	Agents, 111, 164
Messaging, configuring, 157	Supervisors, 104, 164
Modifying contacts	Monitoring
IM&P, 96	Agents, 111
Speed dial, 92	Supervisors, 103
Monitoring	Picking up agent's calls, 115
Call centers by agent, 105	Placing calls on hold, 72
IM&P contacts' presence, 94	_
Phone state of	Plug-ins settings, configuring, 152
Agents, 111	Pop-up notification, 62
Supervisors, 103	Presence
Silently	IM&P contacts, viewing, 97
Agent's call, 114	States, definition, 165
· ·	Program shortcuts, configuring, 154
Next queued call, 122	Promoting, calls in queues, 123
Multiuser chat, starting, 100	- · · · · · · · · · · · · · · · · · · ·
Night Service Override, enabling, 122	Pulling out directories, 84
Notification of calls, configuring, 152	Queued calls
Number of queued calls to display, 120	Grouping, 121
Ordering	Managing, 116
Call centers in agent's Dashboard, 108	Maximum allowed to display, 120
	Monitoring, 122
Queued calls, 121	Moving to top of queue, 125
Outgoing CLID, configuring, 69	Ordering, 121
Outlook	Pane, 116
Configuring, 153	Promoting, 123
Directory, 49	Reordering, 124, 125
Panels	Retrieving, 123



Selecting to monitor by supervisor, 119 Showing and hiding call centers, 120	Agents only Policies, 149
Transferring	Queue membership, 149
Between queues, 123	Application, 149
To ad hoc number, 124	E-mail messaging, 157 General, 145
To agents, 124 Viewing details, 121	Hoteling/Flexible Seating Host, 146
Queues. See Call centers and Queued calls	Instant Messaging and Presence, 157
	Language, 146
Queues directory, 48	Messaging, 157
Quick reference, call operations, 58	Outgoing CLID, 69
Real-time statistics. See also Statistics	Plug-ins, 152
Agent, 105	Call event log, 155
Supervisor, 126	LDAP, 153
Recording calls, 65	Notification, 152
Pausing, 66	Outlook, 153
Starting, 66	Program shortcuts, 154
Stopping, 66	Reports, 158
Redialing recent number, 70	Date format, 147
Rejecting IM&P subscription requests, 97	Service-level calculations, 159
Reordering, calls in queue, 124, 125	Start day of week, 158
Reports	Thresholds, 158
Configuring default settings, 158	Time format, 147
Date format, 147	Services, 151
Service-level calculations, 159	Supervisor only, barging in and monitoring, 150
Start day of week, 158	Web Pop URL, 146
Thresholds, 158	Workspace, 148
Time format, 147	Shortcuts, keyboard, 173
Example, 136	Signing in
Generating, 131	From web browser, 29
Requests, managing, 143	Hot desk, 30
Running, 132	Restrictions, 31
Scheduling, 138	Signing out, 32
Resources, additional, 23	Silent monitoring, 114
Resuming	Skill levels, agents, 164
Call recording, 66	Sorting, contacts, 88
Conference participants, 79	Speed dial numbers
Conferences, 79	Adding, 92
Held calls, 72	Deleting, 93
Retrieving calls from queues, 123	Directory, 48
Scheduling reports, 138	Managing, 92
Screen Pop. See Web Pop URL	Modifying, 92
Search	Start day of week, in reports, 158
Dialing from, 71	Starting
Panel, 46	Call recording, 66
Performing on contacts, 89	Chat sessions, 98
Selecting	Multiuser chats, 100
Agents to monitor, 109, 110	Three-Way conferences, 78
Call centers to monitor	States
By agent, 107	ACD, 163
By supervisor, 119	Calls, 166
Information to display, 107	Phone line, 164
Supervisors to monitor, 103	Presence, 165
Service-level calculations, configuring defaults, 159	Statistics
Services	Agent
Configuring, 151	Configuring information to display, 107
Enabling or disabling, 35	Dashboard, 105
Settings About 159	Ordering call centers, 108 Real-time, 105
ADDIII 139	1 1001 1110, 100



Selecting call centers to monitor, 107	Common panel, 46
Supervisor	Conference Call panel, 43
Agents, about, 128	Contacts pane, 44
Call centers, about, 127	Controls, 52
Dashboard, 126	Custom directories panels, 48
Navigating to agent, 129	Dashboard
Real-time, 126	Agent, 105
Selecting information to display, 129	Supervisor, 126
Stopping call recording, 66	Dialer, 41
	Directories panel, 50
Subscription requests, IM&P contacts	Enterprise panel, 46
Accepting or rejecting, 97	Group panel, 46
Issuing, 94	Header bar, 41
Supervisors	Instant Message panel, 49
Actions on agents	Logged user state, 39
Answering calls for, 115	Outlook panel, 49
Barging in on, 115	Personal panel, 47
Changing ACD state for, 113	Queued Calls pane, 116
Forcing to join queues, 110	Queues panel, 48
Monitoring, 109	Search panel, 46
Silently monitoring, 114	Speed Dial panel, 48
Viewing details, 112	
Barging in on agent calls, 115	Supervisors panel, 47
Call centers to monitor, selecting, 119	vCard, saving, 69
Changing agent's ACD state, 113	Viewing
Dashboard, 126	Agent details, 112
Directory, 47	Call history, 80
Monitoring phone state of, 103	Calls, 60
Phone states, 104, 164	Contacts, 83
Queues, managing, 116	Current calls, 60
Selecting to monitor by agent, 103	Directory, 83
Statistics, viewing	IM&P presence state, 97
Agents, 128	Incoming calls details, 62
Call centers, 127	Queued calls details, 121
Thresholds, configuring in reports, 158	Web browser
- · · · · · · · · · · · · · · · · · · ·	Configuring, 161
Time format in reports, configuring, 147	Firefox, 162
Trace, generating for calls, 65	Internet Explorer, 161
Transferring calls, 73	Signing in from, 29
Blind, 73	
Supervisor only	Web Pop URL
From queue to ad hoc number, 124	Configuring, 146
From queue to agent, 124	Opening for calls, 68
Queues, between, 123	Workspace
To queues, 74	Call Console, 40
With consultation, 74	Call history, 51
Unsubscribing from IM&P contact, 96	Configuring settings, 148
URL	Contacts pane, 44
	Controls, 52
Configuring, 146	Dashboard
Opening for calls, 68	Agent, 105
User interface	Supervisor, 126
Action buttons, 54	Exploring, 37
Agents panel, 47	Logo pane, 39
Call Console, 40	Queued Calls pane, 116
Call history, 51	1 ,