Avaliação 6 - Rede de Roteadores

Aluno: Beatriz Vidal Freire, P8 de informática IFCE Campus Fortaleza

- **ETAPA 1:**



R1
192.168.30.0/24 via 192.168.10.2
192.168.40.0/24 via 192.168.20.2
192.168.60.0/24 via 192.168.10.2
192.168.60.0/24 via 192.168.20.2

R2
192.168.20.0/24 via 192.168.10.1
192.168.40.0/24 via 192.168.30.2
192.168.50.0/24 via 192.168.10.1
192.168.60.0/24 via 192.168.30.2

R3
192.168.10.0/24 via 192.168.20.1
192.168.30.0/24 via 192.168.40.2
192.168.60.0/24 via 192.168.40.2
192.168.50.0/24 via 192.168.20.1

4
192.168.10.0/24 via 192.168.30.1
192.168.20.0/24 via 192.168.40.1
192.168.50.0/24 via 192.168.30.1
192.168.50.0/24 via 192.168.40.1

- **ETAPA 2:**

Roteador 1

```
Router#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#hostname R1
R1(config)#enable secret class
R1(config)#line console 0
R1(config-line)#password cisco
R1(config-line)#exit
R1(config)#exit
R1(config)#line console 0
R1(config-line)#password cisco
R1(config-line)#login
R1(config-line)#exit
R1(config)#line vty 0 4
R1(config-line)#password cisco
R1(config-line)#login
R1(config-line)#exit
R1(config)#interface fastEthernet 0/0
R1(config-if)#description Enlace R1-R2 192.168.10.0
R1(config-if)#ip address 192.168.10.1 255.255.255.0
R1(config-if)#no shutdown
R1(config-if)#exit

R1(config)#interface fastEthernet 1/0
R1(config-if)#description Enlace R1-R3
R1(config-if)#ip address 192.168.20.1 255.255.255.0
R1(config-if)#no shutdown
R1(config-if)#exit
R1(config)#interface f
R1(config)#interface fastEthernet 6/0
R1(config-if)#description Enlace LAN 192.168.50.0
R1(config-if)#ip address 192.168.50.1 255.255.255.0
R1(config-if)#no shutdown
R1(config-if)#exit
```

ROTEADOR 2

```
Router>enable
Router#config terminal
Enter configuration commands, one per line.  End with
Router(config)#hostname R2
R2(config)#enable secret class
R2(config)#line console 02
                        ^
% Invalid input detected at '^' marker.

R2(config)#line console 0
R2(config-line)#password cisco
R2(config-line)#login
R2(config-line)#exit
R2(config)#line vty 0 4
R2(config-line)#password cisco
R2(config-line)#login
R2(config-line)#exit
R2(config)#interface fa
R2(config)#interface fastEthernet 0/0
R2(config-if)#description Enlace R2-R1 192.168.10.0
R2(config-if)#ip address 192.168.10.2 255.255.255.0
R2(config-if)#no shutdown
R2(config-if)#exit
R2(config)#interface f
R2(config)#interface fastEthernet 1/0
R2(config-if)#description Enlace R2-R4
R2(config-if)#ip address 192.168.30.1 255.255.255.0
R2(config-if)#no shutdown
R2(config-if)#exit
```

ROTEADOR 3

```
Router>ENABLE
Router#config terminal
Enter configuration commands, one per line.  End with
Router(config)#hostname R3
R3(config)#enable secret class
R3(config)#line console 0
R3(config-line)#password cisco
R3(config-line)#login
R3(config-line)#exit
R3(config)#line vty 0 4
R3(config-line)#password cisco
R3(config-line)#login
R3(config-line)#exit
R3(config)#interface fast
R3(config)#interface fastEthernet 0/0
R3(config-if)#description Enlace R3-R1 192.168.20.0
R3(config-if)#ip address 192.168.20.2 255.255.255.0
R3(config-if)#no shutdown
R3(config-if)#exit
R3(config)#interface fas
R3(config)#interface fastEthernet 1/0
R3(config-if)#description Enlace R3-R4
R3(config-if)#ip address 192.168.40.1 255.255.255.0
R3(config-if)#no shutdown
R3(config-if)#exit
R3(config)#
```

ROTEADOR 4

```
Router(config)#hostname R4
R4(config)#enable secret class
R4(config)#line console 0
R4(config-line)#password cisco
R4(config-line)#login
R4(config-line)#line vty 0 4
R4(config-line)#password cisco
R4(config-line)#login
R4(config-line)#exit
R4(config)#line vty 0 4
R4(config-line)#password cisco
R4(config-line)#login
R4(config-line)#exit
R4(config)#interface fas
R4(config)#interface fastEthernet 0/0
R4(config-if)#description Enlace R4-R2 192.168.10.0
R4(config-if)#ip address 192.168.30.2 255.255.255.0
R4(config-if)#no shutdown
R4(config-if)#exit
R4(config)#interface fas
R4(config)#interface fastEthernet 1/0
R4(config-if)#description Enlace R4-R3
R4(config-if)#ip address 192.168.40.2 255.255.255.0
R4(config-if)#no shutdown
R4(config-if)#exit
R4(config)#interface fas
R4(config)#interface fastEthernet 6/0
R4(config-if)#description Enlace LAN 192.168.60.0
R4(config-if)#ip address 192.168.60.1 255.255.255.0
R4(config-if)#no shutdown
R4(config-if)#exit
```

- **ETAPA 3**

  Roteador 1

```
Password:
R1#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#ip route 192.168.30.0 255.255.255.0 192.168.10.2
R1(config)#ip route 192.168.40.0 255.255.255.0 192.168.20.2
R1(config)#ip route 192.168.60.0 255.255.255.0 192.168.10.2
R1(config)#ip route 192.168.60.0 255.255.255.0 192.168.20.2
R1(config)#exit
R1#
%SYS-5-CONFIG_I: Configured from console by console

R1#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

C    192.168.10.0/24 is directly connected, FastEthernet0/0
C    192.168.20.0/24 is directly connected, FastEthernet1/0
S    192.168.30.0/24 [1/0] via 192.168.10.2
S    192.168.40.0/24 [1/0] via 192.168.20.2
C    192.168.50.0/24 is directly connected, FastEthernet6/0
S    192.168.60.0/24 [1/0] via 192.168.10.2
                     [1/0] via 192.168.20.2

R1#copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]
R1#
```

Roteador 2

```
R2#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R2(config)#ip route 192.168.20.0 255.255.255.0 192.168.10.1
R2(config)#ip route 192.168.40.0 255.255.255.0 192.168.30.2
R2(config)#ip route 192.168.50.0 255.255.255.0 192.168.10.1
R2(config)#ip route 192.168.60.0 255.255.255.0 192.168.30.2
R2(config)#exit
R2#
%SYS-5-CONFIG_I: Configured from console by console

R2#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

C    192.168.10.0/24 is directly connected, FastEthernet0/0
S    192.168.20.0/24 [1/0] via 192.168.10.1
C    192.168.30.0/24 is directly connected, FastEthernet1/0
S    192.168.40.0/24 [1/0] via 192.168.30.2
S    192.168.50.0/24 [1/0] via 192.168.10.1
S    192.168.60.0/24 [1/0] via 192.168.30.2

R2#copy run
R2#copy running-config st
R2#copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]
R2#
```

Roteador 3

```
R3#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R3(config)#ip route 192.168.10.0 255.255.255.0 192.168.20.1
R3(config)#ip route 192.168.30.0 255.255.255.0 192.168.40.2
R3(config)#ip route 192.168.50.0 255.255.255.0 192.168.20.1
R3(config)#ip route 192.168.60.0 255.255.255.0 192.168.40.2
R3(config)#exit
R3#
%SYS-5-CONFIG_I: Configured from console by console
show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

S    192.168.10.0/24 [1/0] via 192.168.20.1
C    192.168.20.0/24 is directly connected, FastEthernet0/0
S    192.168.30.0/24 [1/0] via 192.168.40.2
C    192.168.40.0/24 is directly connected, FastEthernet1/0
S    192.168.50.0/24 [1/0] via 192.168.20.1
S    192.168.60.0/24 [1/0] via 192.168.40.2

R3#copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]
R3#
```

Roteador 4

```
R4#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R4(config)#ip route 192.168.10.0 255.255.255.0 192.168.30.1
R4(config)#ip route 192.168.20.0 255.255.255.0 192.168.40.1
R4(config)#ip route 192.168.50.0 255.255.255.0 192.168.30.1
R4(config)#ip route 192.168.50.0 255.255.255.0 192.168.40.1

R4#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

S    192.168.10.0/24 [1/0] via 192.168.30.1
S    192.168.20.0/24 [1/0] via 192.168.40.1
C    192.168.30.0/24 is directly connected, FastEthernet0/0
C    192.168.40.0/24 is directly connected, FastEthernet1/0
S    192.168.50.0/24 [1/0] via 192.168.30.1
                     [1/0] via 192.168.40.1
C    192.168.60.0/24 is directly connected, FastEthernet6/0

R4#copy run
R4#copy running-config st
R4#copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]
R4#
```

Teste de PINGS

```
C:\>ping 192.168.50.1

Pinging 192.168.50.1 with 32 bytes of data:

Reply from 192.168.50.1: bytes=32 time=72ms TTL=255
Reply from 192.168.50.1: bytes=32 time<1ms TTL=255
Reply from 192.168.50.1: bytes=32 time<1ms TTL=255
Reply from 192.168.50.1: bytes=32 time<1ms TTL=255

Ping statistics for 192.168.50.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 72ms, Average = 18ms
```

```
C:\>ping 192.168.10.2

Pinging 192.168.10.2 with 32 bytes of data:

Request timed out.
Reply from 192.168.10.2: bytes=32 time=11ms TTL=254
Reply from 192.168.10.2: bytes=32 time<1ms TTL=254
Reply from 192.168.10.2: bytes=32 time=1ms TTL=254

Ping statistics for 192.168.10.2:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 11ms, Average = 4ms
```

```
C:\>ping 192.168.20.2

Pinging 192.168.20.2 with 32 bytes of data:

Reply from 192.168.20.2: bytes=32 time<1ms TTL=254
Reply from 192.168.20.2: bytes=32 time<1ms TTL=254
Reply from 192.168.20.2: bytes=32 time<1ms TTL=254
Reply from 192.168.20.2: bytes=32 time=1ms TTL=254

Ping statistics for 192.168.20.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 1ms, Average = 0ms

C:\>ping 192.168.40.2

Pinging 192.168.40.2 with 32 bytes of data:

Reply from 192.168.40.2: bytes=32 time<1ms TTL=253
Reply from 192.168.40.2: bytes=32 time<1ms TTL=253
Reply from 192.168.40.2: bytes=32 time<1ms TTL=253
Reply from 192.168.40.2: bytes=32 time<1ms TTL=253

Ping statistics for 192.168.40.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 0ms, Average = 0ms
```

```
C:\>ping 192.168.30.2

Pinging 192.168.30.2 with 32 bytes of data:

Reply from 192.168.30.2: bytes=32 time<1ms TTL=253
Reply from 192.168.30.2: bytes=32 time=13ms TTL=253
Reply from 192.168.30.2: bytes=32 time<1ms TTL=253
Reply from 192.168.30.2: bytes=32 time<1ms TTL=253

Ping statistics for 192.168.30.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 13ms, Average = 3ms

C:\>ping 192.168.60.2

Pinging 192.168.60.2 with 32 bytes of data:

Request timed out.
Reply from 192.168.60.2: bytes=32 time<1ms TTL=125
Reply from 192.168.60.2: bytes=32 time<1ms TTL=125
Reply from 192.168.60.2: bytes=32 time<1ms TTL=125

Ping statistics for 192.168.60.2:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 0ms, Average = 0ms
```

```
C:\>ping 192.168.60.3

Pinging 192.168.60.3 with 32 bytes of data:

Request timed out.
Reply from 192.168.60.3: bytes=32 time<1ms TTL=125
Reply from 192.168.60.3: bytes=32 time<1ms TTL=125
Reply from 192.168.60.3: bytes=32 time<1ms TTL=125

Ping statistics for 192.168.60.3:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>ping 192.168.60.4

Pinging 192.168.60.4 with 32 bytes of data:

Request timed out.
Reply from 192.168.60.4: bytes=32 time=3ms TTL=125
Reply from 192.168.60.4: bytes=32 time=11ms TTL=125
Reply from 192.168.60.4: bytes=32 time<1ms TTL=125

Ping statistics for 192.168.60.4:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 11ms, Average = 4ms
```

```
C:\>ping 192.168.60.5

Pinging 192.168.60.5 with 32 bytes of data:

Request timed out.
Reply from 192.168.60.5: bytes=32 time=1ms TTL=125
Reply from 192.168.60.5: bytes=32 time<1ms TTL=125
Reply from 192.168.60.5: bytes=32 time<1ms TTL=125

Ping statistics for 192.168.60.5:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 1ms, Average = 0ms
```

- **ETAPA 4:**






PC1
Physical
Config
Desktop
Programming
Attributes
Web Browser
URL
http://192.168.60.2
Go
Cisco Packet Tracer
Welcome to Cisco Packet Tracer. Opening doors to new opportunities. Mind Wide Open.
Quick Links:
A small page
Copyrights
Image page
Image


PC1
Physical
Config
Desktop
Programming
Attributes
Web Browser
URL
http://www.lambda.com
Go
Cisco Packet Tracer
Welcome to Cisco Packet Tracer. Opening doors to new opportunities. Mind Wide Open.
Quick Links:
A small page
Copyrights
Image page
Image


Server2
Physical
Config
Services
Desktop
Programming
Attributes
SERVICES
HTTP
DHCP
DHCPv6
TFTP
DNS
SYSLOG
AAA
NTP
EMAIL
FTP
IoT
VM Management
Radius EAP
DHCP
Interface
FastEthernet0
Service
On
Off
Pool Name
serverPool2
Default Gateway
192.168.50.1
DNS Server
192.168.60.5
Start IP Address :
192
168
50
3
Subnet Mask:
255
255
255
0
Maximum Number of Users :
252
TFTP Server:
0.0.0.0
WLC Address:
0.0.0.0
Add
Save
Remove
Pool Name
Default Gateway
DNS Server
Start IP Address
Subnet Mask
Max User
TFTP Server
WLC Address
serverPool2
192.168...
192.168...
192.168...
255.255...
252
0.0.0.0
0.0.0.0
serverPool
0.0.0.0
0.0.0.0
192.168...
255.255...
512
0.0.0.0
0.0.0.0

```
R1(config)#interface fastEthernet 6/0
R1(config-if)#ip helper-address 192.168.60.3
R1(config-if)#end
```

```
C:\>ping 192.168.60.2

Pinging 192.168.60.2 with 32 bytes of data:

Reply from 192.168.60.2: bytes=32 time=1ms TTL=125
Reply from 192.168.60.2: bytes=32 time=14ms TTL=125
Reply from 192.168.60.2: bytes=32 time=1ms TTL=125
Reply from 192.168.60.2: bytes=32 time=10ms TTL=125

Ping statistics for 192.168.60.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 1ms, Maximum = 14ms, Average = 6ms
```

PC0

Physical | Config | Desktop | Programming | Attributes

IP Configuration

Interface: FastEthernet0

IP Configuration

- (•) DHCP
- ( ) Static

IPv4 Address	192.168.50.4
Subnet Mask	255.255.255.0
Default Gateway	192.168.50.1
DNS Server	192.168.60.5

Server3

Physical | Config | Services | Desktop | Programming | Attributes

SERVICES
- HTTP
- DHCP
- DHCPv6
- TFTP
- DNS
- SYSLOG
- AAA
- NTP
- EMAIL
- FTP
- IoT
- VM Management
- Radius EAP

FTP

Service: (•) On ( ) Off

User Setup

Username: _____ Password: _____

[ ] Write [ ] Read [ ] Delete [ ] Rename [ ] List

	Username	Password	Permission
1	cisco	cisco	RWDNL
2	xico	1234	RWDNL

Add

Save

PC0

Physical | Config | Desktop | Programming | Attributes

Command Prompt

```
ftp ftp.lambda.com
Trying to connect...ftp.lambda.com
Connected to ftp.lambda.com
220- Welcome to PT Ftp server
Username:xico
331- Username ok, need password
Password:
230- Logged in
(passive mode On)
ftp>dir

Listing /ftp directory from ftp.lambda.com:
0    : asa842-k8.bin                                5571584
1    : asa923-k8.bin                                30468096
2    : c1841-advipservicesk9-mz.124-15.T1.bin       33591768
3    : c1841-ipbase-mz.123-14.T7.bin                13832032
4    : c1841-ipbasek9-mz.124-12.bin                 16599160
5    : c1900-universalk9-mz.SPA.155-3.M4a.bin       33591768
6    : c2600-advipservicesk9-mz.124-15.T1.bin       33591768
7    : c2600-i-mz.122-28.bin                        5571584
8    : c2600-ipbasek9-mz.124-8.bin                  13169700
9    : c2800nm-advipservicesk9-mz.124-15.T1.bin     50938004
10   : c2800nm-advipservicesk9-mz.151-4.M4.bin      33591768
11   : c2800nm-ipbase-mz.123-14.T7.bin              5571584
12   : c2800nm-ipbasek9-mz.124-8.bin                15522644
13   : c2900-universalk9-mz.SPA.155-3.M4a.bin       33591768
14   : c2950-i6q412-mz.121-22.EA4.bin               3058048
15   : c2950-i6q412-mz.121-22.EA8.bin               3117390
16   : c2960-lanbase-mz.122-25.FX.bin               4414921
17   : c2960-lanbase-mz.122-25.SEE1.bin             4670455
18   : c2960-lanbasek9-mz.150-2.SE4.bin             4670455
19   : c3560-advipservicesk9-mz.122-37.SE1.bin      8662192
20   : c3560-advipservicesk9-mz.122-46.SE.bin       10713279
21   : c800-universalk9-mz.SPA.152-4.M4.bin         33591768
22   : c800-universalk9-mz.SPA.154-3.M6a.bin        83029236
23   : cat3k_caa-universalk9.16.03.02.SPA.bin       505532849
```

```
23   : cat3k_caa-universalk9.16.03.02.SPA.bin       505532849
24   : cgr1000-universalk9-mz.SPA.154-2.CG          159487552
25   : cgr1000-universalk9-mz.SPA.156-3.CG          184530138
26   : ir800-universalk9-bundle.SPA.156-3.M.bin     160968869
27   : ir800-universalk9-mz.SPA.155-3.M             61750062
28   : ir800-universalk9-mz.SPA.156-3.M             63753767
29   : ir800_yocto-1.7.2.tar                        2877440
30   : ir800_yocto-1.7.2_python-2.7.3.tar           6912000
31   : pt1000-i-mz.122-28.bin                       5571584
32   : pt3000-i6q412-mz.121-22.EA4.bin              3117390
ftp>help
         ?
         cd
         delete
         dir
         get
         help
         passive
         put
         pwd
         quit
         rename
ftp>
```